Enterprise Message API C# Edition 3.4.0.L2

ENTERPRISE MESSAGE API DEVELOPERS GUIDE

Document Version: 3.4.0.L2 Date of issue: May 2025

Document ID: EMACSharp340UM.250



Legal			

© LSEG 2023 - 2025. All rights reserved.

Republication or redistribution of LSEG Data & Analytics content, including by framing or similar means, is prohibited without the prior written consent of LSEG Data & Analytics. 'LSEG Data & Analytics' and the LSEG Data & Analytics logo are registered trademarks and trademarks of LSEG Data & Analytics.

Any software, including but not limited to: the code, screen, structure, sequence, and organization thereof, and its documentation are protected by national copyright laws and international treaty provisions. This manual is subject to U.S. and other national export regulations.

LSEG Data & Analytics, by publishing this document, does not guarantee that any information contained herein is and will remain accurate or that use of the information will ensure correct and faultless operation of the relevant service or equipment. LSEG Data & Analytics, its agents, and its employees, shall not be held liable to or through any user for any loss or damage whatsoever resulting from reliance on the information contained herein.

Contents

1		Introduction	1
	1.1	About this Manual	1
	1.2	Audience	1
	1.3	Programming Languages	1
	1.4	Acronyms and Abbreviations	
	1.5	References	
	1.6	Documentation Feedback	
	1.7	Document Conventions	
2		Product Overview	4
_	2.1	Enterprise Message API Product Description	
	2.2	Product Documentation and Learning Enterprise Message API	
	2.2.1	Consumer Examples	
	2.2.2	Provider Examples	
	2.2.2	Product Architecture	
	2.3.1	Enterprise Message API Consumer Architecture	
	2.3.7	Enterprise Message API Provider Architecture	
	2.3.2	Enterprise Message API Codec Architecture	
	2.3.4	Enterprise Message API Error Handling	
	-		
3		OMM Containers and Messages	
	3.1	Overview	
	3.2	Classes	
	3.2.1	DataType Class	
	3.2.2	DataCode ENUM	
	3.2.3	Data Class	_
	3.2.4	Msg Class	
	3.2.5	OmmError Class	
	3.3	Working with OMM Containers	
	3.3.1	Example: Populating a FieldList Class	
	3.3.2	Example: Extracting Information from a FieldList Class	
	3.3.3	Example: Extracting FieldList information using a Downcast operation	
	3.4	Working with OMM Messages	
	3.4.1	Example: Populating the GenericMsg with an ElementList Payload	
	3.4.2	Example: Extracting Information from the GenericMsg class	14
4		Consumer Classes	15
	4.1	OmmConsumer Class	15
	4.1.1	Connecting to a Server and Opening Items	15
	4.1.2	Opening Items Immediately After OmmConsumer Object Instantiation	15
	4.1.3	Destroying the OmmConsumer Object	
	4.1.4	Example: Working with the OmmConsumer Class	16
	4.1.5	Working with Items	
	4.1.6	Example: Working with Items	
	4.2	IOmmConsumerClient Class	
	4.2.1	IOmmConsumerClient Description	
	4.2.2	Example: OmmConsumerClient	
	4.3	OmmConsumerConfig Class	
	4.3.1	OmmConsumerConfig Description	
	4.3.2	Encrypted Connections	

5		Provider Classes	20
	5.1	OmmProvider Class	20
	5.1.1	Submitting Items	20
	5.1.2	Non-Interactive Providers: Post OmmProvider Object Instantiation	21
	5.1.3	Interactive Providers: Post OmmProvider Object Instantiation	21
	5.1.4	Uninitialize the OmmProvider Object	
	5.1.5	Non-Interactive Example: Working with the OmmProvider Class	
	5.1.6	Interactive Provider Example: Working with the OmmProvider Class	
	5.1.7	Interactive Provider Example: Handling a Post Message	
	5.1.8	Interactive Provider Example: Handling RTT Responses from Consumer	
	5.1.9	Working with Items	
	5.1.10	Packing with Providers	26
	5.2	IOmmProviderClient Class	29
	5.2.1	IOmmProviderClient Description	29
	5.2.2	Non-Interactive Example: IOmmProviderClient	29
	5.2.3	Interactive Provider Example: IOmmProviderClient	31
	5.3	OmmNiProviderConfig and OmmIProviderConfig Classes	32
6		Consuming Data from the Cloud	33
•	6.1	Workflows Overview	
	6.2	Encrypted Connections	
	6.3	Credential Management	
	6.4	Version 2 Authentication Using OAuth Client Credentials	
	6.4.1	Configuring and Managing Version 2 Credentials	
	6.4.2	Version 2 OAuth Client Credentials Token Lifespan	
	6.5	Service Discovery	
	6.6	Consuming Market Data	
	6.7	HTTP Error Handling for Reactor Token Reissues	
	6.8	Cloud Connection Use Cases	
	6.8.1	Session Management Use Case	
	6.8.2	Explicit Service Discovery Use Case	
	6.9	Logging of Authentication and Service Discovery Interaction	38
	6.9.1	Logged Request Information	
	6.9.2	Logged Response Information	38
7		Request Routing	39
	7.1	Administrative Domains Behaviors	
	7.1.1	Login Request Timer Handling and Login Response Aggregation	
	7.1.2	Aggregated Login Elements	
	7.1.3	Scenarios for Receiving Aggregated Login Stream	
	7.1.4	Directory Request Timer Handling and Directory Response Aggregation	41
	7.1.5	Dictionary Request Timer Handling	42
	7.2	Service List	42
	7.3	Item Request Routing and Recovery	43
	7.4	Posting Messages	
	7.5	Sending Generic Message	
	7.6	Session Channel Information from OmmConsumer and IOmmConsumerEvent	44
8		Troubleshooting and Debugging	45
	8.1	EMA Logger Usage	
	8.2	OMM Error Client Class	
	8.2.1	IOmmConsumerErrorClient and IOmmProviderErrorClient Descriptions	45
	8.2.2	Example: IOmmConsumerErrorClient	45
	8.3	OmmException Class	

1 Introduction

1.1 About this Manual

This document is authored by Enterprise Message API architects and programmers. Several of its authors have designed, developed, and maintained the Enterprise Message API product and other LSEG products which leverage it.

This guide documents the functionality and capabilities of the Enterprise Message API C# Edition. The Enterprise Message API can also connect to and leverage many different LSEG and customer components. If you want the Enterprise Message API to interact with other components, consult that specific component's documentation to determine the best way to configure for optimal interaction.

1.2 Audience

This document provides detailed yet supplemental information for application developers writing to the Enterprise Message API.

1.3 Programming Languages

The Enterprise Message API is written using the C# programming language taking advantage of the object oriented approach to design and development of API and applications.

1.4 Acronyms and Abbreviations

ACRONYM / TERM	MEANING
ADH	LSEG Real-Time Advanced Distribution Hub is the horizontally scalable service component within the LSEG Real-Time Distribution System providing high availability for publication and contribution messaging, subscription management with optional persistence, conflation and delay capabilities.
ADS	LSEG Real-Time Advanced Distribution Server is the horizontally scalable distribution component within the LSEG Real-Time Distribution System providing highly available services for tailored streaming and snapshot data, publication and contribution messaging with optional persistence, conflation and delay capabilities.
API	Application Programming Interface
ASCII	American Standard Code for Information Interchange
Enterprise Message API	The Enterprise Message API (EMA) is an ease of use, open source, Open Message Model API. EMA is designed to provide clients rapid development of applications, minimizing lines of code and providing a broad range of flexibility. It provides flexible configuration with default values to simplify use and deployment. EMA is written on top of the Enterprise Transport API (ETA) utilizing the Value Added Reactor and Watchlist features of ETA.
Enterprise Transport API (ETA)	Enterprise Transport API is a high performance, low latency, foundation of the LSEG Real-Time SDK. It consists of transport, buffer management, compression, fragmentation and packing over each transport and encoders and decoders that implement the Open Message Model. Applications written to this layer achieve the highest throughput, lowest latency, low memory utilization, and low CPU utilization using a binary Rssl Wire Format when publishing or consuming content to/from LSEG Real-Time Distribution Systems.
HTTP	Hypertext Transfer Protocol
HTTPS	Hypertext Transfer Protocol (Secure)

Table 1: Acronyms and Abbreviations

ACRONYM / TERM	MEANING
JWK	JSON Web Key. Defined by RFC 7517, a JWK is a JSON formatted public or private key.
JWKS	JSON Web Key Set, This is a set of JWK, placed in a JSON array.
JWT	JSON Web Token. Defined by RFC 7519, JWT allows users to create a signed claim token that can be used to validate a user.
OMM	Open Message Model
QoS	Quality of Service
RDM	Domain Model
DP	Delivery Platform: this platform is used for REST interactions. In the context of Real-Time APIs, an API gets authentication tokens and/or queries Service Discovery to get a list of Real-Time - Optimized endpoints using DP.
LSEG Real-Time Distribution System	LSEG Real-Time Distribution System is LSEG's financial market data distribution platform. It consists of the LSEG Real-Time Advanced Distribution Server and LSEG Real-Time Advanced Distribution Hub. Applications written to the LSEG Real-Time SDK can connect to this distribution system.
Reactor	The Reactor is a low-level, open-source, easy-to-use layer above the Enterprise Transport API. It offers heartbeat management, connection and item recovery, and many other features to help simplify application code for users.
RMTES	A multi-lingual text encoding standard
RSSL	Source Sink Library
RTT	Round Trip Time, this definition is used for round trip latency monitoring feature.
RWF	Rssl Wire Format, an LSEG proprietary binary format for data representation.

Table 1: Acronyms and Abbreviations

1.5 References

- Enterprise Message API C# Edition LSEG Domain Model Usage Guide
- API Concepts Guide
- Enterprise Message API C# Edition Configuration Guide
- Enterprise Message API C# Edition Developers Guide
- The LSEG Developer Community

1.6 Documentation Feedback

While we make every effort to ensure the documentation is accurate and up-to-date, if you notice any errors, or would like to see more details on a particular topic, you have the following options:

- Send us your comments via email at ProductDocumentation@lseg.com.
- Add your comments to the PDF using Adobe's **Comment** feature. After adding your comments, submit the entire PDF to LSEG by clicking **Send File** in the **File** menu. Use the <u>ProductDocumentation@lseg.com</u> address.

1.7 Document Conventions

This document uses the following types of conventions:

- C# classes, methods, in-line code snippets, and types are shown in Courier New font.
- Parameters, filenames, tools, utilities, and directories are shown in Bold font.
- Document titles and variable values are shown in italics.
- When initially introduced, concepts are shown in Bold, Italics.
- Longer code examples are shown in Courier New font against a gray background. For example:

2 Product Overview

2.1 Enterprise Message API Product Description

The Enterprise Message API is a data-neutral, multi-threaded, ease-of-use API providing access to OMM and RWF data. As part of the LSEG Real-Time Software Development Kit, or RTSDK, the Enterprise Message API allows applications to consume and provide OMM data at the message level of the API stack. The message level is set on top of the transport level which is handled by the Enterprise Transport API.

The Enterprise Message API:

- Provides a set of easy-to-use and intuitive interfaces and features intended to aid in message-level application development. These interfaces simplify the setting of information in and getting information from OMM containers and messages. Other interfaces abstract the behavior of consumer-type and provider-type applications.
- Enables applications to source market data from, and provide it to, different components that support OMM and/or RWF (e.g. Real-Time, LSEG Real-Time Distribution System, LSEG Real-Time Advanced Transformation Server, Data Feed Direct, etc).
- Leaves a minimal code footprint in applications written to it. The design of the Enterprise Message API and its interfaces allows application development to focus more on the application business logic than on the usage of the Enterprise Message API.
- Includes training applications that provide basic, yet still functional, examples of Enterprise Message API applications.
- Presents applications with simplified access to OMM messages and containers while providing all necessary transport level functionalities. Generally, Enterprise Message API applications are meant to process market data items (e.g. open and receive item data or provide item data).
- Abstracts and hides all the transport level functionality minimizing application involvement to just optional transport level configuration and server address specification.
- Provides simple accessor functionality to populate and read OMM containers and messages. Enterprise Message API takes
 advantage of fluent interface design, which users can leverage to set disparate values of the same message or container by stringing
 respective interface methods together, one after the other. Fluent interfaces provide the means for visual code simplification which helps
 in understanding and debugging applications.

Transport level functionality is abstracted, specialized, and encapsulated by the Enterprise Message API in a few classes whose functionality is implied by their class name.

2.2 Product Documentation and Learning Enterprise Message API

When learning the Enterprise Message API, LSEG recommends you set up a sandbox environment where developers can experiment with various iterations of Enterprise Message API applications. Enterprise Message API is designed to facilitate a hands-on (experiment-based) learning experience (versus a documentation-based methodology). To support a hands-on learning methodology, the Enterprise Message API package provides a set of training examples which showcase the usage of Enterprise Message API interfaces in increasing levels of complexity and sophistication. While coding and debugging applications, developers are encouraged to refer to the *Enterprise Message API C# Edition Reference Manual* and/or to the features provided by their IDE (e.g., VisualStudio).

NOTE: Enterprise Message API application developers should already be familiar with OMM and Market Data distribution systems.

2.2.1 Consumer Examples

The complexity of a consumer example is reflected in its series number as follows:

- 100-series examples simply open an item and print its received content to the screen (using the Data.ToString() method).
 Applications in this series illustrate Enterprise Message API support for stringification, containers, and primitives. Though useful for learning, debugging, and writing display applications, stringification by itself is not sufficient to develop more sophisticated applications.
- The 200-series examples illustrate how to extract information from OMM containers and messages in native data formats, (e.g., int, String, and Buffer).
- The 300- and 400- series examples depict usage of particular Enterprise Message API features such as posting, generic message, programmatic configuration, and etc.

2.2.2 Provider Examples

The complexity of an example is reflected in its series number. Each provider type (i.e., non-interactive versus interactive) has its own directory structure in the product package:

- 100-series examples simply create streaming items and submit their refreshes and updates. Applications in this series use the hardcoded Enterprise Message API configuration.
- The 200-series examples showcase the submission of multiple, streaming items from different market domains. Applications in this series use the EmaConfig.xml file to modify its configuration.
- The 300- and 400- series examples depict usage of particular Enterprise Message API features such as user control of the source directory domain, login streaming, connection recovery, programmatic configuration, etc.

2.3 Product Architecture

2.3.1 Enterprise Message API Consumer Architecture

The Enterprise Message API incorporates the ValueAdded Reactor component (called the Transport API VA Reactor) from the Transport API, which provides the watchlist and transport-level functionality. The Enterprise Message API wraps up the reactor component in its own class of <code>OmmConsumer</code>. <code>OmmConsumer</code> provides interfaces to open, modify, and close market items or instruments, as well as submit Post and Generic messages. To complete the set of consumer application functionalities, the <code>OmmConsumer</code> class provides the <code>Dispatch()</code> method. Depending on its design and configuration, an application might need to call this method to dispatch received messages. The <code>OmmConsumerConfig</code> class configures the reactor and <code>OmmConsumer</code>.

The IOmmConsumerClient class provides the callback mechanism for Enterprise Message API to send incoming messages to the application. The application needs to implement a class inheriting from the IOmmConsumerClient class to receive and process messages. By default, IOmmConsumerClient callback methods are executed in Enterprise Message API's thread of control. However, you can use the OmmConsumerConfig.OperationModel() interface to execute callback methods on the application thread. If you choose to execute callback methods in this manner, the application must also call the OmmConsumer.Dispatch() method to dispatch received messages.

The Enterprise Message API consumer will always have at least one thread, which is implemented by the VA Reactor and runs the internal, VA Reactor logic. For details on this thread, refer to the *Transport API C# Edition Value Added Component Developers Guide*. Additionally, you can configure the Enterprise Message API to create a second, internal thread to dispatch received messages. To create a second thread, set the <code>OmmConsumerConfig</code> operation model to <code>OmmConsumerConfig</code>. <code>OperationModelMode.API_DISPATCH</code>. If the <code>OmmConsumerConfig</code> operation model is set to the <code>OmmConsumerConfig</code>. <code>OperationModelMode.USER_DISPATCH</code>, the Enterprise Message API will not run a second thread. Without running a second thread, the application is responsible for calling the <code>Ommconsumer.Dispatch()</code> method to dispatch all received messages.



WARNING! If the application delays in dispatching messages, it can result in slow consumer behavior.

2.3.2 Enterprise Message API Provider Architecture

The Enterprise Message API provider incorporates the Value Added (VA) Reactor component from the Enterprise Transport API, which provides transport-level functionality. The Enterprise Message API wraps the reactor component in its own class of <code>OmmProvider</code>. <code>OmmProvider</code> provides interfaces to submit item messages as well as handling login, directory, and dictionary domains (depending on Enterprise Message API's specific provider role). To complete the set of provider functionalities, the <code>OmmProvider</code> class provides the <code>Dispatch()</code> method. Depending on its design and configuration, an application might need to call this method to dispatch received messages. The provider configuration class (i.e., <code>OmmNiProviderConfig</code> or <code>OmmIProviderConfig</code>) class configures both the reactor and <code>OmmProvider</code>.

Enterprise Message API sends incoming messages to the application using the <code>IOmmProviderClient</code> callback mechanism. To receive and process messages, the application needs to implement a class that inherits from the <code>IOmmProviderClient</code> class. By default, <code>IOmmProviderClient</code> callback methods are executed in Enterprise Message API's thread of control. However, you can use either the <code>OmmNiProviderConfig.OperationModel()</code> or <code>OmmIProviderConfig.OperationModel()</code> interface to execute callback methods on the application's thread, in which case the application must also call the <code>OmmProvider.Dispatch()</code> method to dispatch received messages.

An Enterprise Message API provider must always have at least one thread, which is implemented by the VA Reactor and runs the internal, VA Reactor logic. For details on this thread, refer to the *Transport API C# Edition Value Added Component Developers Guide*. Additionally, you can configure Enterprise Message API to create a second internal thread over which to dispatch received messages:

- For non-interactive providers, set the OmmNiProviderConfig operation model to
 OmmNiProviderConfig.OperationModel.API_DISPATCH. If the operation model is set to
 OmmNiProviderConfig.OperationModel.USER DISPATCH, Enterprise Message API will not run a second thread.
- For interactive providers, set the OmmIProviderConfig operation model to
 OmmIProviderConfig.OperationModel.API_DISPATCH. If the operation model is set to
 OmmIProviderConfig.OperationModel.USER DISPATCH, Enterprise Message API will not run a second thread.

Without running a second thread, the application is responsible for calling the OmmProvider.Dispatch() method to dispatch all received messages.

The Enterprise Message API provider includes an internal, hard-coded, and configurable initial source directory refresh message. The application can either use the internal hard-coded source directory, configure its own internal one via the **EmaConfig.xml** file, or programmatically create one and/or disable the internal one. To disable the internal source directory message:

- When running Enterprise Message API as a non-interactive provider: the application must set
 OmmNiProviderConfig.AdminControl.USER_CONTROL through the OmmNiProviderConfig.AdminControlDirectory() method.
- When running Enterprise Message API as an interactive provider: the application must set
 OmmIProviderConfig.AdminControl.USER_CONTROL through the OmmIProviderConfig.AdminControlDirectory()
 method. Additionally, you can configure the ability to disable internal dictionary responses by setting
 OmmIProviderConfig.AdminControl.USER_CONTROL through the OmmIProviderConfig.AdminControlDictionary()
 method

NOTE: If the user control is enabled, the application is responsible for sending the response messages.

An Enterprise Message API provider also supports the programmatic configuration of a source directory refresh of dictionary information, which overrides any configuration in **EmaConfig.xml**. To programmatically configure a source directory refresh:

- When running Enterprise Message API as a non-interactive provider: the application must set
 OmmNiProviderConfig.AdminControl.API_CONTROL through the
 OmmNiProviderConfig.AdminControlDirectory() method. An Enterprise Message API non-interactive provider does not support programmatically configuring dictionary information.
- When running Enterprise Message API as an interactive provider: the application must set
 OmmIProviderConfig.AdminControl.API_CONTROL through the OmmIProviderConfig.AdminControlDirectory()
 method. Additionally, you can programmatically configure dictionary information, which overrides any dictionary information defined
 from EmaConfig.xml. To programmatically configure dictionary information, set
 OmmIProviderConfig.AdminControl.API_CONTROL through the OmmIProviderConfig.AdminControlDictionary()
 method.

2.3.3 Enterprise Message API Codec Architecture

The Enterprise Message API Codec uses the Enterprise Transport API decoding and encoding functions to read and populate OMM containers and messages. Each OMM container and message is represented by a respective Enterprise Message API interface class, which provides relevant methods for setting information on, and accessing information from, these containers and messages. All classes representing OMM containers, messages, and primitives inherit from the common parent class of **Data**. Through such inheritance, classes provide the same basic, common, and easy to use functionality that applications might expect from them (e.g., printing contained data using **ToString()**).

2.3.4 Enterprise Message API Error Handling

The Enterprise Message API interfaces are designed to throw exceptions when encountering error scenarios: OmmConsumer and OmmProvider classes throw an OmmException. For details on exception types, refer to Section 8.3. For which exceptions are thrown by each class, refer to the Reference Manual.

The Enterprise Message API application must catch exceptions and take appropriate actions. Notably, exceptions related to decoding or encoding content must be caught with appropriate try and catch blocks in callbacks or wherever decoding or encoding takes place. Decoding methods to retrieve content may result in exceptions if the content is not present within the message. It is best practice to check for a field's existence prior to accessing content.

While the OmmConsumer and OmmProvider classes throw an OmmException to report an error condition, the IOmmConsumerErrorClient class provides an alternate reporting mechanism via callbacks. To use the alternate error reporting, pass the IOmmConsumerErrorClient on the constructor of the OmmConsumer class, which switches the error reporting from exception throwing to callbacks. Similarly, passing in IOmmProviderErrorClient on the constructor of the OmmProvider class switches reporting error to the callbacks. Refer to Section 8.2.2 for sample code to set error callbacks such as OnInvalidHandle, OnInvalidUsage, etc. When using API dispatch, the recommendation is to use callbacks for receiving errors by passing in ErrorClient. In addition to its error reporting mechanisms, Enterprise Message API provides a logger mechanism which is useful in monitoring Enterprise Message API behavior and debugging any issues that might arise.

3 OMM Containers and Messages

3.1 Overview

Enterprise Message API supports a full set of OMM containers, messages, and primitives (e.g. **FieldList**, **Map**, **RefreshMsg**, **int**). For simplicity, Enterprise Message API uses:

- . The "set / add" type of functionality to populate OMM containers, messages, and primitives
 - Set functionality is used to specify variables that occur once in an OMM container or message.
 - Add functionality is used to populate entries in OMM containers.
 - Set and add type methods return a reference to the modified object (for fluid interface usage).
- Iterators are used to iterate over every OMM container.

Depending on the container type, the entry may contain:

- Its own identity (e.g., field id)
- An action to be applied to the received data (e.g., add action)
- Permission information associated with the received data
- An entry's load and its data type.

The Enterprise Message API has two different ways of extracting an entry's load:

- Use ease-of-use interfaces to return references to contained objects (with reference type being based on the load's data type)
- Use the Load interface to return a reference to the base Data class. The Load interface enables more advanced applications to use the
 down-cast operation (if desired).

For details on ease of use interfaces and the down-cast operation, refer to Section 3.3.

To provide compile time-type safety on the set-type interfaces, Enterprise Message API provides the following, deeper inheritance structure:

- All classes representing primitive / intrinsic data types inherit from the Data class (e.g. OmmInt, OmmBuffer, OmmRmtes, etc.).
- OmmArray class inherits from the Data class. The OmmArray is treated as a primitive instead of a container, because it represents a set
 of primitives.
- OmmError class inherits from the Data class. OmmError class is not an OMM data type.
- All classes representing OMM containers (except OmmArray) inherit from the ComplexType class, which in turn inherits from the Data class (e.g., OmmXml, OmmOpaque, Map, Series, or Vector).
- All classes representing OMM messages inherit from the Msg class, which in turn inherits from the ComplexType class (e.g., RefreshMsg, GenericMsg, or PostMsg).

3.2 Classes

3.2.1 DataType Class

The <code>DataType</code> class provides the set of enumeration values that represent each and every supported OMM data type, including all OMM containers, messages, and primitives. Each class representing OMM data identifies itself with an appropriate <code>DataType</code> enumeration value (e.g., <code>DataType.Dat</code>

The **DataType** class list of enumeration values contains two special enumeration values, which can only be received when reading or extracting information from OMM containers or messages:

- DataType.DataTypes.ERROR, which indicates an error condition was detected. For more details, refer to Section 3.2.5.
- DataType.DataTypes.NO DATA, which signifies a lack of data on the summary of a container, message payload, or attribute.

3.2.2 DataCode ENUM

The DataCode enum provides two enumeration values that indicate the data's state:

- The DataCode.NO CODE indicates that the received data is valid and application may use it.
- The DataCode . BLANK indicates that the data is not present and application needs to blank the respective data fields.

3.2.3 Data Class

The **Data** class is a parent abstract class from which all OMM containers, messages, and primitives inherit. **Data** provides interfaces common across all its children, which in turn enables down-casting operations. The **Data** class and all classes that inherit from it are optimized for efficiency and built so that data can be easily accessed.



WARNING! The **Data** class and all classes that inherit from it are designed as temporary and short-lived objects. For this reason, do not use them as storage or caching devices.

3.2.4 Msg Class

The Msq class is a parent class for all the message classes. It defines all the interfaces that are common across all message classes.

3.2.5 OmmError Class

The OmmError class is a special purpose class. It is a read only class implemented in the Enterprise Message API to notify applications about errors detected while processing received data. This class enables applications to learn what error condition was detected. Additionally it provides the AsHex() method to obtain binary data associated with the detected error condition. The sole purpose of this class is to aid in debugging efforts.

The following code snippet presents usage of the OmmError class while processing ElementList.

```
void Decode(ElementList elementList)
{
    foreach (ElementEntry elementEntry in elementList)
    {
        if (Data.DataCode.BLANK == elementEntry.Code)
            Console.WriteLine(" blank");
        else
```

```
switch (elementEntry.LoadType)
{
    case DataTypes.REAL:
        Console.WriteLine(elementEntry.OmmRealValue().AsDouble());
        break;
    case DataTypes.ERROR:
        Console.WriteLine(elementEntry.OmmErrorValue().ErrorCode + " (" + elementEntry.OmmErrorValue().ErrorCodeAsString() + ")");
        break;
    default:
        Console.WriteLine();
        break;
}
```

3.3 Working with OMM Containers

Enterprise Message API supports the following OMM containers: ElementList, FieldList, FilterList, Map, Series, and Vector.

Each of these classes implements the IEnumerable interface and provides set type interfaces for container header information (e.g., dictionary id, element list number, and the add-type interfaces for adding entries). You must set the container header and optional summary before adding the first entry.

Though it is treated as an OMM primitive, the **OmmArray** acts like a container and therefore provides add-type interfaces for adding primitive entries.

NOTE: OMM Container classes do perform some validation of their usage. If a usage error is detected, an appropriate **OmmException** will be thrown.

3.3.1 Example: Populating a FieldList Class

The following example illustrates how to populate a FieldList class with fluid interfaces.

```
fieldList fieldList = new FieldList();

fieldList.Info(1, 1);
fieldList.AddUInt(1, 64);
fieldList.AddReal(6, 11, OmmReal.MagnitudeTypes.EXPONENT_NEG_2);
fieldList.AddDime(16, 2023, 10, 23);
fieldList.AddTime(19, 02, 03, 04, 005);
fieldList.Complete();
}
catch (OmmException excp)
{
    Console.WriteLine(excp);
}
```

3.3.2 Example: Extracting Information from a FieldList Class

In the following example illustrates how to extract information from the **FieldList** class by iterating over the class. The following code extracts information about all entries.

```
break;
}
}
}
```

3.3.3 Example: Extracting FieldList information using a Downcast operation

The following example illustrates how to extract information from a FieldList object using the down-cast operation.

```
void DecodeFieldList(FieldList fieldList)
   if (fieldList.HasInfo)
       Console.WriteLine("FieldListNum: " + fieldList.InfoFieldListNum() + " DictionaryId: " +
   fieldList.InfoDictionaryId());
    foreach (FieldEntry fieldEntry in fieldList)
        Console.WriteLine("Load");
        Decode(fieldEntry.Load!);
void Decode(Data data)
    if (Data.DataCode.BLANK == data.Code)
        Console.WriteLine("Blank data");
   else
        switch (data.DataType)
        {
            case DataType.DataTypes.REFRESH MSG:
                DecodeRefreshMsg((RefreshMsg)data);
                break;
            case DataType.DataTypes.UPDATE MSG:
                DecodeUpdateMsg((UpdateMsg)data);
                break;
            case DataType.DataTypes.STATUS MSG:
                    DecodeStatusMsg((StatusMsg)data);
                break;
            case DataType.DataTypes.FIELD LIST:
                    DecodeFieldList((FieldList)data);
                break:
            case DataType.DataTypes.MAP:
```

```
DecodeMap((Map)data);
        break;
   case DataType.DataTypes.NO_DATA:
       Console.WriteLine("NoData");
        break;
   case DataType.DataTypes.TIME:
        Console.WriteLine("OmmTime: " + ((OmmTime)data).ToString());
       break;
   case DataType.DataTypes.DATE:
       Console.WriteLine("OmmDate: " + ((OmmDate) data).ToString());
       break;
   case DataType.DataTypes.REAL:
       Console.WriteLine("OmmReal::asDouble: " + ((OmmReal) data).AsDouble());
       break;
   case DataType.DataTypes.INT:
       Console.WriteLine("OmmInt: " + ((OmmInt)data).Value);
       break;
   case DataType.DataTypes.UINT:
       Console.WriteLine("OmmUInt: " + ((OmmUInt)data).Value);
       break;
   case DataType.DataTypes.ENUM:
       Console.WriteLine("OmmEnum: " + ((OmmEnum)data).Value);
       break;
   case DataType.DataTypes.ASCII:
       Console.WriteLine("OmmAscii: " + ((OmmAscii)data).Value);
       break;
   case DataType.DataTypes.RMTES:
       Console.WriteLine("OmmRmtes: " + ((OmmRmtes)data).Value);
       break;
   case DataType.DataTypes.ERROR:
       Console.WriteLine("Decoding error: " + ((OmmError)data).ErrorCodeAsString());
       break;
   default:
       break;
}
```

3.4 Working with OMM Messages

Enterprise Message API supports the following OMM messages: RefreshMsg, UpdateMsg, StatusMsg, AckMsg, PostMsg and GenericMsg. As appropriate, each of these classes provide set and get type interfaces for the message header, permission, key, attribute, and payload information.

3.4.1 Example: Populating the GenericMsg with an ElementList Payload

The following example illustrates how to populate a GenericMsg with a payload consisting of an ElementList.

```
GenericMsg genMsg = new GenericMsg();

FieldList nestedFieldList = new FieldList();
nestedFieldList.AddReal(22, 34, OmmReal.MagnitudeTypes.EXPONENT_POS_1);

genMsg.DomainType(200).Name("TRI.N").ServiceId(234).Payload(nestedFieldList);
```

3.4.2 Example: Extracting Information from the Generic Msg class

The following example illustrates how to extract information from the GenericMsg class.

```
void Decode(GenericMsg genMsg)
{
    if (genMsg.HasServiceId)
        Console.WriteLine("ServiceId: " + genMsg.ServiceId());

    if (genMsg.HasPartNum)
        Console.WriteLine("PartNum: " + genMsg.PartNum());

    if (genMsg.HasSeqNum)
        Console.WriteLine("SeqNum: " + genMsg.SeqNum());

    switch (genMsg.Payload().DataType)
    {
        case DataTypes.FIELD_LIST:
            Decode(genMsg.Payload().FieldList());
            break;
    }
}
```

4 Consumer Classes

4.1 OmmConsumer Class

The **OmmConsumer** class is the main consumer application interface to the Enterprise Message API. This class encapsulates watchlist functionality and transport level connectivity. It provides all the interfaces a consumer-type application needs to open, close, and modify items, as well as submit messages to the connected server (both **PostMsg** and **GenericMsg**). The **OmmConsumer** class provides configurable admin domain message processing (i.e., login, directory, and dictionary requests).

4.1.1 Connecting to a Server and Opening Items

Applications observe the following steps to connect to a server and open items:

- (Optional) Specify a configuration using the EmaConfig.xml file.
 This step is optional because the Enterprise Message API provides a default configuration which is usually sufficient in simple application cases.
- Create OmmConsumerConfig object (for details, refer to Section 4.3).
- (Optional) Change Enterprise Message API configuration using methods on the OmmConsumerConfig class.
 If an EmaConfig.xml file is not used, then at a minimum, applications might need to modify the default host address and port.
- Implement an application callback client class that inherits from the **IOmmConsumerClient** class (for details, refer to Section 4.2).

 An application needs to override the default implementation of callback methods and provide its own business logic.
- (Optional) Implement an application error client class that inherits from the IOmmConsumerErrorClient class (for details, refer to Section 8.2).
 - The application needs to override default error call back methods to be effectively notified about error conditions.
- Create an OmmConsumer object and pass the OmmConsumerConfig object (and if needed, also pass in the application error client object), and optionally register for Login events by passing in an application callback client class.
- Open items of interest using the OmmConsumer.RegisterClient() method.
- Process received messages.
- (Optional) Submit PostMsg and GenericMsg messages and modify / close items using appropriate OmmConsumer class methods.
- Exit by calling OmmConsumer.Uninitialize().

4.1.2 Opening Items Immediately After OmmConsumer Object Instantiation

To allow applications to open items immediately after creating the **OmmConsumer** object, the Enterprise Message API performs the following steps when creating and initializing the **OmmConsumer** object:

- · Create an internal item watchlist.
- · Establish connectivity to a configured server / host.
- Log into the server and obtain source directory information.
- Obtain dictionaries (if configured to do so).

4.1.3 Destroying the OmmConsumer Object

Calling **Uninitialize()** on an **OmmConsumer** object causes the application to log out and disconnect from the connected server, at which time all items are closed.

4.1.4 Example: Working with the OmmConsumer Class

The following example illustrates the simplest application managing the OmmConsumer Class.

4.1.5 Working with Items

The Enterprise Message API assigns all opened items or instruments a unique numeric identifier (e.g. long), called a handle, which is returned by the OmmConsumer.RegisterClient() call. A handle is valid as long as its associated item stays open. Holding onto these handles is important only to applications that want to modify or close particular items, or use the items' streams for sending PostMsg or GenericMsg messages to the connected server. Applications that just open and watch several items until they exit do not need to store item handles.

While opening an item, on the call to the **OmmConsumer.RegisterClient()** method, an application can pass an item closure or an application-assigned numeric value. The Enterprise Message API will maintain the association of the item to its closure as long as the item stays open.

Respective closures and handles are returned to the application in an IOmmConsumerEvent object on each item callback method.

4.1.6 Example: Working with Items

The following example illustrates using the item handle while modifying an item's priority and posting modified content.

```
public void OnRefreshMsq(RefreshMsq refreshMsq, IOmmConsumerEvent consumerEvent)
        Console.WriteLine(refreshMsg);
public static void Main()
        OmmConsumer? consumer = null;
        try
        {
            consumer = new(new OmmConsumerConfig().Host("localhost:14002").UserName("user"));
            consumer.RegisterClient(new RequestMsg().ServiceName("DIRECT FEED").Name("IBM.N")
               .Qos(RequestMsq.Timeliness.REALTIME, RequestMsg.Rate.TICK BY TICK).Priority(2, 1), new
   AppClient());
            Thread.Sleep(60000); // API calls OnRefreshMsq(), OnUpdateMsq() and OnStatusMsq()
        catch (OmmException ommException)
            Console.WriteLine(ommException.Message);
        finally
            consumer?.Uninitialize();
    }
```

In the code snippet above, when submitting a message, specifically **PostMsg**, **RefreshMsg**, **StatusMsg**, or **UpdateMsg**, application may specify original publisher information using the Visible Publisher Identifier (VPI) feature. This is set using **publisherId** by setting **UserId** and **UserAddress**. For an explanation of the VPI feature, refer to the *Enterprise Transport API Developers Guide* for an explanation of VPI feature. For more usage information, refer to the Reference Manual.

4.2 IOmmConsumerClient Class

4.2.1 IOmmConsumerClient Description

The IOmmConsumerClient class provides a callback mechanism through which applications receive OMM messages on items for which they subscribe. The IOmmConsumerClient is a parent class that implements empty, default callback methods. Applications must implement their own class (inheriting from IOmmConsumerClient), and override the methods they are interested in processing. Applications can implement many specialized client-type classes; each according to their business needs and design. Instances of client-type classes are associated with individual items while applications register item interests.

The IOmmConsumerClient class provides default implementation for the processing of RefreshMsg, UpdateMsg, StatusMsg, AckMsg and GenericMsg messages. These messages are processed by their respectively named methods: OnRefreshMsg(), OnUpdateMsg(), OnStatusMsg(), OnAckMsg(), and OnGenericMsg(). The OnAllMsg() method processes any of these messages. Applications only need to override methods for messages they want to process.

4.2.2 Example: OmmConsumerClient

The following example illustrates an application client-type class, depicting OnRefreshMsq() method implementation.

```
public void OnRefreshMsg(RefreshMsg refreshMsg, IOmmConsumerEvent @ommConsumerEvent)
{
    Console.WriteLine("Item Name: " + (refreshMsg.HasName ? refreshMsg.Name() : "<not set>"));
    Console.WriteLine("Service Name: " + (refreshMsg.HasServiceName ? refreshMsg.ServiceName() :
"<not set>"));

Console.WriteLine("Item State: " + refreshMsg.State());

if (refreshMsg.Payload().DataType != DataTypes.No_DATA)
    Decode(refreshMsg.Payload().Data);
}
```

4.3 OmmConsumerConfig Class

4.3.1 OmmConsumerConfig Description

You can use the **OmmConsumerConfig** class to customize the functionality of the **OmmConsumer** class. The default behavior of **OmmConsumer** is hard coded in the **OmmConsumerConfig** class. You can configure **OmmConsumer** in any of the following ways:

- Using the EmaConfig.xml file
- Using interface methods on the OmmConsumerConfig class

For more details on using the **OmmConsumerConfig** class and associated configuration parameters, refer to the *Enterprise Message API Configuration Guide*.

4.3.2 Encrypted Connections

The Enterprise Message API supports encrypted TCP connections for **Consumer** via a **ChannelType** of **RSSL_ENCRYPTED** (i.e., **ChannelType::RSSL_ENCRYPTED**).

You configure connection types in the Enterprise Message API configuration file. After configuring the file with the appropriate encrypted connection type, to connect the application via a proxy, call the **ProxyHost()** and **ProxyPort()** functions on the **OmmconsumerConfig** class.

Clients can use the **OmmConsumerConfig** class to call **EncryptionProtocol()** to set a cryptographic protocol. Enterprise Message API uses the default value of **TLS** (the operating system chooses the best protocol to use and blocks protocols that are not secure).

An encrypted connection might use proxy devices as it tunnels through the Internet. Client can configure some proxy servers to authenticate client applications before they pass through the proxy. The Enterprise Message API supports Basic authentication schemes. You also use the OmmConsumerConfig class to set credential parameters such as ProxyUsername(), ProxyPassword() for Proxy Authentication. The Enterprise Message API package provides an encrypted connection training example that showcases the usage of the Enterprise Message API's OmmConsumerConfig interface configured for encrypted connection (i.e., ChannelType::RSSL ENCRYPTED).

5 Provider Classes

5.1 OmmProvider Class

The **OmmProvider** class is the main provider application interface to the Enterprise Message API. This class encapsulates transport-level connectivity. It provides all the interfaces a provider-type application needs to submit item messages (i.e., refresh, update, status, generic) as well as handle the login, directory, and dictionary domains (depending upon whether or not the application is an interactive provider). The **OmmProvider** class provides configurable admin domain message processing (i.e., login, directory, and dictionary).

5.1.1 Submitting Items

In the following process, the value for ProviderType is dependent on the type of provider with which you are dealing:

- For non-interactive providers, ProviderType is NiProvider.
- For interactive providers, *ProviderType* is **IProvider**.

To establish a connection and submit items:

1. (Optional) Specify a configuration using the EmaConfig.xml file.

Specifying a configuration in **EmaConfig.xml** is optional because the Enterprise Message API provides a default configuration which is usually sufficient in simple application cases.

- Create the appropriate OmmProviderTypeConfig object (for details, refer to Section 5.3):
 - For a non-interactive provider, create an OmmNiProviderConfig object.
 - For an interactive provider, create an OmmIProviderConfig object
- 3. (Optional) Change the Enterprise Message API configuration using methods on the OmmProviderTypeConfig class.

If **EmaConfig.xml** file is not used, then at a minimum:

- Non-interactive provider applications might need to modify both the default host address and port.
- Interactive provider applications might need to modify the default port.
- (Conditional) Implement an application callback client class that inherits from the IOmmProviderClient class (for details, refer to Section 5.2).

An application might need to override the default callback implementation and provide its own business logic. Not all methods need to be overridden: only those that require the application's business logic.

- For non-interactive providers, this step is optional because the application may choose not to open login or dictionary items. In such cases, the provider application will not receive return messages.
- For interactive providers, this step is required, because at a minimum, the application needs to handle all inbound login domain and item request messages.
- 5. (Optional) Implement an application error client class that inherits from the IOmmProviderErrorClient class (for details, refer to Section 5.2).

To be effectively notified about error conditions, the application needs to override any default, error callback methods.

- Create an OmmProvider object and pass the OmmProviderTypeConfig object (and if needed, also pass in the application error client object), and optionally in NiProvider only, register for Login events by passing in an application callback client class.
- 7. (Optional) For non-interactive providers, open login and dictionary items using the OmmProvider.RegisterClient() method.
- 8. Process received messages.
- Create, populate, and submit item messages (refresh, update, status).
 - · For non-interactive providers, the application needs to associate each item with a handle that uniquely identifies the item.
 - For interactive providers, the application needs to use the handle from the OMMProviderEvent.

- 10. (Optional) Submit GenericMsg messages using the appropriate OmmProvider class methods.
- 11. Exit.

5.1.2 Non-Interactive Providers: Post OmmProvider Object Instantiation

After creating an **OmmProvider** object, the Enterprise Message API performs the following steps when creating and initializing the **OmmProvider** object so that applications can begin submitting items:

- Establish connectivity to a configured server / host
- · Log into ADH and submit source directory information

5.1.3 Interactive Providers: Post OmmProvider Object Instantiation

Before an interactive provider can start submitting items, the application must first accept a login request. Though the Enterprise Message API accepts connections, it is the responsibility of the application to send the login response. Subsequently, the consumer will request the source directory, and the Enterprise Message API will respond by submitting the source directory.

After creating an **OmmProvider** object, the Enterprise Message API observes the following process when creating and initializing the **OmmProvider** object so that applications can begin submitting items:

- · Accept the connection request from a consumer
- Accept the login
- Submit the source directory information

5.1.4 Uninitialize the OmmProvider Object

For non-interactive providers, causes the application to log out and disconnect from the connected ADH, at which time all items are closed. For interactive providers, causes Enterprise Message API to close all consumer connections.

5.1.5 Non-Interactive Example: Working with the OmmProvider Class

The following example illustrates the simplest non-interactive application managing the OmmProvider class.

```
map.SummaryData(summary.Complete());
entryLoad.AddRealFromDouble(3427, 7.76, OmmReal.MagnitudeTypes.EXPONENT NEG 2);
entryLoad.AddRealFromDouble(3429, 9600);
entryLoad.AddEnumValue(3428, 2);
entryLoad.AddRmtes(212, new EmaBuffer(Encoding.ASCII.GetBytes("Market Maker")));
map.AddKeyAscii("100", MapAction.ADD, entryLoad.Complete());
provider.Submit(new RefreshMsg().DomainType(EmaRdm.MMT MARKET BY ORDER)
        .ServiceName("TEST NI PUB").Name("AAO.V")
   .State(OmmState.StreamStates.OPEN, OmmState.DataStates.OK, OmmState.StatusCodes.NONE,
        "UnSolicited Refresh Completed")
   .Payload(map.Complete()).Complete(true),
   aaoHandle);
summary.Clear();
summary.AddEnumValue(15, 840);
summary.AddEnumValue(53, 1);
summary.AddEnumValue(3423, 1);
summary.AddEnumValue(1709, 2);
map.Clear();
map.SummaryData(summary.Complete());
entryLoad.Clear();
entryLoad.AddRealFromDouble(3427, 9.92, OmmReal.MagnitudeTypes.EXPONENT NEG 2);
entryLoad.AddRealFromDouble(3429, 1200);
entryLoad.AddEnumValue(3428, 2);
entryLoad.AddRmtes(212, new EmaBuffer(Encoding.ASCII.GetBytes("Market Maker")));
map.AddKeyAscii("222", MapAction.ADD, entryLoad.Complete());
provider.Submit(new RefreshMsg().DomainType(EmaRdm.MMT MARKET BY ORDER)
    .ServiceName("TEST NI PUB").Name("AGG.V")
  .State(OmmState.StreamStates.OPEN, OmmState.DataStates.OK, OmmState.StatusCodes.NONE,
     "UnSolicited Refresh Completed")
  .Payload(map.Complete()).Complete(true),
  aggHandle);
Thread.Sleep(1000);
for (int i = 0; i < 60; i++)
    entryLoad.Clear();
```

```
entryLoad.AddRealFromDouble(3427, 7.76 + i * 0.1, OmmReal.MagnitudeTypes
                   .EXPONENT NEG 2);
              entryLoad.AddRealFromDouble(3429, 9600);
              entryLoad.AddEnumValue(3428, 2);
              entryLoad.AddRmtes(212, new EmaBuffer(Encoding.ASCII.GetBytes("Market Maker")));
              map.Clear();
              map.AddKeyAscii("100", MapAction.UPDATE, entryLoad.Complete());
              provider.Submit(new
UpdateMsg().DomainType(EmaRdm.MMT MARKET BY ORDER).ServiceName("TEST NI PUB").Name("AAO.V")
                  .Payload(map.Complete()), aaoHandle);
              entryLoad.Clear();
              entryLoad.AddRealFromDouble(3427, 9.92 + i * 0.1,
OmmReal.MagnitudeTypes.EXPONENT NEG 2);
              entryLoad.AddRealFromDouble(3429, 1200);
              entryLoad.AddEnumValue(3428, 2);
              entryLoad.AddRmtes(212, new EmaBuffer(Encoding.ASCII.GetBytes("Market Maker")));
              map.Clear();
              map.AddKeyAscii("222", MapAction.UPDATE, entryLoad.Complete());
              provider.Submit(new
UpdateMsg().DomainType(EmaRdm.MMT MARKET BY ORDER).ServiceName("TEST NI PUB").Name("AGG.V")
                  .Payload(map.Complete()), aggHandle);
              Thread.Sleep(1000);
        }
    }
    catch (OmmException excp)
         Console.WriteLine(excp.Message);
    finally
    {
        provider?.Uninitialize();
    }
```

5.1.6 Interactive Provider Example: Working with the OmmProvider Class

The following example illustrates the simplest interactive application managing the OmmProvider class.

```
OmmProvider? provider = null;
try
        AppClient appClient = new AppClient();
        FieldList fieldList = new FieldList();
        Map map = new Map();
        OmmIProviderConfig config = new OmmIProviderConfig();
        provider = new OmmProvider(config.Port("14002"), appClient);
        while (appClient.ItemHandle == 0)
        Thread.Sleep (1000);
        for (int i = 0; i < 60; i++)
            fieldList.AddRealFromDouble(3427, 7.76 + i * 0.1, OmmReal.MagnitudeTypes.EXPONENT NEG 2);
            fieldList.AddRealFromDouble(3429, 9600);
            fieldList.AddEnumValue(3428, 2);
            fieldList.AddRmtes(212, new EmaBuffer(Encoding.ASCII.GetBytes("Market Maker")));
            map.AddKeyAscii(appClient.OrderNr, Access.MapAction.ADD, fieldList.Complete());
            provider.Submit(new UpdateMsg().DomainType(EmaRdm.MMT MARKET BY ORDER)
                .Payload(map.Complete()), appClient.ItemHandle);
            map.Clear();
            fieldList.Clear();
            Thread.Sleep(1000);
        Thread.Sleep(60 000);
    catch (OmmException excp)
        Console.WriteLine(excp.Message);
    finally
        provider?.Uninitialize();
    }
```

5.1.7 Interactive Provider Example: Handling a Post Message

The following example illustrates the **OmmProvider** sending an **AckMsg** in response to a **PostMsg**. For further details on post message support by the provider, refer to the *Transport API C# Edition Developers Guide*.

```
public void OnPostMsg(PostMsg postMsg, IOmmProviderEvent providerEvent)
{
    Console.WriteLine("Received PostMsg with id: " + postMsg.PostId());
    Console.WriteLine(postMsg);

    if (postMsg.SolicitAck())
    {
        AckMsg ackMsg = new AckMsg();
        if (postMsg.HasSeqNum)
        {
             ackMsg.SeqNum(postMsg.SeqNum());
        }
        if (postMsg.HasName)
        {
             ackMsg.Name(postMsg.Name());
        }
        if (postMsg.HasServiceId)
        {
             ackMsg.ServiceId(postMsg.ServiceId());
        }
        ackMsg.AckId(postMsg.PostId())
            .DomainType(postMsg.DomainType());
        providerEvent.Provider.Submit(ackMsg, providerEvent.Handle);
    }
}
```

5.1.8 Interactive Provider Example: Handling RTT Responses from Consumer

The following example implements a provider's callback for Generic messages. The example illustrates how the provider can identify and process consumer responses to RTT requests. For further information on RTT messages and RTT monitoring, refer to the *Transport API C# Edition RDM Usage Guide*.

5.1.9 Working with Items

The application assigns unique numeric identifiers, called handles (e.g., long) to all open items it is providing. Application must pass this identifier along with an item message on the call to **Submit()**. The handles are used to manage item stream ids. To reassign a handle to a different item, application must first close the item previously associated with the given handle.

5.1.10 Packing with Providers

Provider applications can use the **PackedMsg** object to send multiple messages packed together in a single packet. Applications can designate the bounds of the **PackedMsg** by setting its limit for messages packed, the byte limit of data it can send, and then pack messages before sending them together.

The following sections provide packing examples for an Interactive Provider and a Non-interactive Provider.

5.1.10.1 Interactive Example of Packing

The following example illustrates an Interactive Provider application setting up a basic **PackedMsg** object and packing messages together before submitting **PackedMsg**.

```
public void SendPackedMessagesExample(OmmProvider provider, long clientHandle, long itemHandle)
        FieldList fieldList = new FieldList(); // Field list used for message payload
        PackedMsg packedMsg = new PackedMsg(provider);
        packedMsg.InitBuffer(clientHandle); // Initialize buffer using client handle and default
            size of 6000. See reference manual for other uses of InitBuffer().
        UpdateMsg updateMsg = new UpdateMsg();
        for (int i = 0; i < 10; i++) // Send 10 packed messages every second
            for (int j = 0; j < 10; j++) // Pack 10 messages
                fieldList.Clear();
                fieldList.AddReal(22, 3991 + j, OmmReal.MagnitudeTypes.EXPONENT NEG 2);
                fieldList.AddReal(30, 10 + j, OmmReal.MagnitudeTypes.EXPONENT 0);
                updateMsg.Clear();
                updateMsg.ServiceName("NI PUB").Name("IBM.N").Payload(fieldList.Complete());
                try
                {
                    packedMsg.AddMsg( msg, itemHandle ); // Add message with its item handle
```

```
catch ( OmmInvalidUsageException excp )
                 //The API was unable to add the current message into the packed buffer.
                 //If messages have been successfully added to the packed buffer, submit them, get a
                 //new packed buffer, and add the current message into that new buffer.
                 //and add the current message into that new buffer.
                 if ( excp.errorCode() == OmmInvalidUsageException.ErrorCode.BUFFER TOO SMALL)
                     if (packedMsg.packedMsgCount() > 0) // Packed message has some data
                         // Submit the messages we've already packed, get a new packed buffer, and
add the current message.
                         provider.submit(packedMsg);// Submit packed message on OmmProvider
                         packedMsg.initBuffer(clientHandle); // Re-initialize buffer for next set of
packed messages.
                         packedMsg.addMsg(msg, itemHandle); // Add missed message with its item
handle
                     }
                     else
                         //Packed buffer too small to add even first message.
                         //Consider initializing the buffer to a higher value than the default 6000
bytes if needed.
                         //See initBuffer() methods for more details
                 }
                 else
                     // Handle other exceptions from addMsg() here
             }
        if (packedMsg.packedMsgCount() > 0)
             provider.submit(packedMsg);// Submit packed message on OmmProvider
             packedMsg.initBuffer(clientHandle); // Re-initialize buffer for next set of packed
messages.
         else
             // Nothing to submit because packed message is empty.
        Thread.sleep(1000);
    }
}
```

5.1.10.2 Non-interactive Example of Packing

The following example illustrates a Non-interactive Provider application setting up a basic **PackedMsg** object and packing messages together before submitting the **PackedMsg**.

```
public void SendPackedMessagesExample(OmmProvider provider, long itemHandle)
        FieldList fieldList = new FieldList();
        PackedMsg packedMsg = new PackedMsg(provider);
        packedMsg.InitBuffer();
        UpdateMsg updateMsg = new UpdateMsg();
        for (int i = 0; i < 60; i++)
             for (int j = 0; j < 10; j++)
                  fieldList.Clear();
                  fieldList.AddReal(22, 3991 + j, OmmReal.MagnitudeTypes.EXPONENT NEG 2);
                  fieldList.AddReal(30, 10 + j, OmmReal.MagnitudeTypes.EXPONENT 0);
                  updateMsq.Clear();
                  updateMsg.ServiceName("NI PUB").Name("IBM.N").Payload(fieldList.Complete());
                  try
                       packedMsq.AddMsq(updateMsq, itemHandle);
                  catch (OmmInvalidUsageException excp)
                       //The API was unable to add the current message into the packed buffer.
                       //If messages have been successfully added to the packed buffer, submit them, get
                       //a new packed buffer, and add the current message into that new buffer.
                       if (excp.ErrorCode == OmmInvalidUsageException.ErrorCodes.BUFFER TOO SMALL)
                            if (packedMsg.PackedMsgCount() > 0) // Packed message has some data.
                                 // Submit the messages we've already packed, get a new packed buffer,
                                 //and add the current message.
                                 provider.Submit(packedMsg); // Submit packed message on OmmProvider
                                 packedMsq.InitBuffer(); // Re-initialize buffer for next set of packed
                                 packedMsg.AddMsg(updateMsg, itemHandle); // Add missed message with
                                      its item handle.
                       else
                       {
                            //Packed buffer too small to add even first message.
                            //Consider initializing the buffer to a higher value than the default 6000
                                 bytes if needed.
                            //See InitBuffer() methods for more details.
```

5.2 IOmmProviderClient Class

5.2.1 IOmmProviderClient Description

The IOmmProviderClient class provides a callback mechanism through which applications receive OMM messages on items for which they subscribe. The IOmmProviderClient is a parent class that implements empty, default callback methods. Applications must implement their own class (inheriting from IOmmProviderClient), and override the methods they are interested in processing. Applications can implement many specialized client-type classes; each according to their business needs and design. Instances of client-type classes are associated with individual items while applications register item interests. The IOmmProviderClient class provides default implementation for the processing of RefreshMsg, StatusMsg, and GenericMsg messages. These messages are processed by their respectively named methods: OnRefreshMsg(), OnStatusMsg(), OnGenericMsg(), OnRequest()¹, OnReIssue()¹, OnClose()¹, and OnPost()¹. Applications only need to override methods for messages they want to process.

5.2.2 Non-Interactive Example: IOmmProviderClient

The following example illustrates an application client-type class, depicting OnRefreshMsg () method implementation.

```
class AppClient : IOmmProviderClient
{
   bool m_connectionUp;

   public bool IsConnectionUp()
   {
      return m_connectionUp;
   }
}
```

1. Interactive Provider Only

```
public void OnRefreshMsg(RefreshMsg refreshMsg, IOmmProviderEvent evt)
     Console.WriteLine("Received Refresh. Item Handle: " + evt.Handle + " Closure: " + evt.Closure);
     Console.WriteLine("Item Name: " + (refreshMsg.HasName ? refreshMsg.Name() : "<not set>"));
     Console.WriteLine("Service Name: " + (refreshMsg.HasServiceName ? refreshMsg.ServiceName() :
          "<not set>"));
     Console.WriteLine("Item State: " + refreshMsg.State());
     if (refreshMsg.State().StreamState == OmmState.StreamStates.OPEN)
     {
          if (refreshMsg.State().DataState == OmmState.DataStates.OK)
               m connectionUp = true;
          else
               m_connectionUp = false;
     else
         m connectionUp = false;
public void OnStatusMsg(StatusMsg statusMsg, IOmmProviderEvent evt)
     Console.WriteLine("Received Status. Item Handle: " + evt.Handle + " Closure: " + evt.Closure);
     Console.WriteLine("Item Name: " + (statusMsg.HasName ? statusMsg.Name() : "<not set>"));
     Console.WriteLine("Service Name: " + (statusMsg.HasServiceName ? statusMsg.ServiceName() :
          "<not set>"));
     if (statusMsg.HasState)
          Console.WriteLine("Item State: " + statusMsg.State());
          if (statusMsg.State().StreamState == OmmState.StreamStates.OPEN)
          {
               if (statusMsg.State().DataState == OmmState.DataStates.OK)
                    m connectionUp = true;
               else
               {
                    m connectionUp = false;
          }
          else
               m_connectionUp = false;
```

5.2.3 Interactive Provider Example: IOmmProviderClient

```
class AppClient : IOmmProviderClient
   public long ItemHandle = 0;
   public string OrderNr = "100";
   public void OnReqMsg(RequestMsg reqMsg, IOmmProviderEvent providerEvent)
         switch (reqMsg.DomainType())
              case EmaRdm.MMT LOGIN:
                   ProcessLoginRequest(reqMsg, providerEvent);
                   break;
              case EmaRdm.MMT MARKET BY ORDER:
                   ProcessMarketByOrderRequest(reqMsg, providerEvent);
              default:
                   ProcessInvalidItemRequest(reqMsg, providerEvent);
                   break;
   void ProcessLoginRequest(RequestMsg reqMsg, IOmmProviderEvent providerEvent)
        providerEvent.Provider.Submit(new RefreshMsg().DomainType(EmaRdm.MMT LOGIN)
              .Name(reqMsg.Name()).NameType(EmaRdm.USER NAME)
              .Complete(true).Solicited(true)
              .State(OmmState.StreamStates.OPEN, OmmState.DataStates.OK, OmmState.StatusCodes.NONE,
              "Login accepted"),
              providerEvent.Handle);
   void ProcessMarketByOrderRequest(RequestMsq reqMsq, IOmmProviderEvent providerEvent)
         if (ItemHandle != 0)
              ProcessInvalidItemRequest(reqMsg, providerEvent);
              return;
         FieldList mapSummaryData = new FieldList();
        mapSummaryData.AddEnumValue(15, 840);
         mapSummaryData.AddEnumValue(53, 1);
        mapSummaryData.AddEnumValue(3423, 1);
         mapSummaryData.AddEnumValue(1709, 2);
         FieldList entryData = new FieldList();
         entryData.AddRealFromDouble(3427, 7.76, OmmReal.MagnitudeTypes.EXPONENT NEG 2);
         entryData.AddRealFromDouble(3429, 9600);
```

```
entryData.AddEnumValue(3428, 2);
     entryData.AddRmtes(212, new EmaBuffer(Encoding.ASCII.GetBytes("Market Maker")));
    Map map = new Map();
    map.SummaryData(mapSummaryData.Complete());
    map.AddKeyAscii(OrderNr, Access.MapAction.ADD, entryData.Complete());
     providerEvent.Provider.Submit(new RefreshMsq().DomainType(EmaRdm.MMT MARKET BY ORDER)
          .Name(reqMsg.Name()).ServiceName(reqMsg.ServiceName()).Solicited(true)
          .State(OmmState.StreamStates.OPEN, OmmState.DataStates.OK, OmmState.StatusCodes.NONE,
               "Refresh Completed")
          .Payload(map.Complete()).Complete(true),
          providerEvent.Handle);
     ItemHandle = providerEvent.Handle;
}
void ProcessInvalidItemRequest(RequestMsq reqMsq, IOmmProviderEvent providerEvent)
    providerEvent.Provider.Submit(new StatusMsg()
          .Name(regMsg.Name()).ServiceName(regMsg.ServiceName())
          .State(OmmState.StreamStates.CLOSED, OmmState.DataStates.SUSPECT, OmmState
               .StatusCodes.NOT FOUND, "Item not found"),
          providerEvent.Handle);
```

5.3 OmmNiProviderConfig and OmmlProviderConfig Classes

In the following, the value for **ProviderType** is dependent on the type of provider with which you are dealing, thus:

- For non-interactive providers, ProviderType is NiProvider.
- For interactive providers, **ProviderType** is **IProvider**.

You can use the OmmProviderTypeConfig class to customize the functionality of the OmmProvider class. The default behavior of OmmProvider is hard coded in the OmmProviderTypeConfig class. You can configure OmmProvider in any of the following ways:

- Using the EmaConfig.xml file
- Using interface methods on the OmmProviderTypeConfig class

For more details on using the **OmmProviderTypeConfig** class and associated configuration parameters, refer to the *Enterprise Message API Configuration Guide*.

6 Consuming Data from the Cloud

6.1 Workflows Overview

You can use the Enterprise Message API to consume data from a cloud-based LSEG Real-Time Advanced Distribution Server. The API interacts with cloud-based servers using the following workflows:

- Credential Management (for details, refer to Section 6.3)
- Service Discovery (for details, refer to Section 6.5)
- Consuming Market Data (for details, refer to Section 6.6)

There are two versions of login credentials for the Delivery Platform:

Version 2 Authentication, also known as "V2 auth", "OAuthClientCredentials" or "V2 Client Credentials", uses OAuth2.0 Client Credentials grant to obtain an access token. Requires a Service Account consisting of client ID and client Secret. For details, refer to Section 6.4.

The Enterprise Transport API will determine which authentication version to use based on the inputs. By default, for cloud connections the Enterprise Message API connects to a server in the **us-east-1** cloud location.

For further details on Real-Time as it functions in the cloud, refer to the *Real-Time — Optimized: Installation and Configuration for Client Use.* For details on the parameters you use to configure cloud connections, refer to the *EMA C# Edition Configuration Guide.*

6.2 Encrypted Connections

When connecting to an LSEG Real-Time Advanced Distribution Server in the cloud, you must use a **ChannelType** of **RSSL_ENCRYPTED** (for details on **ChannelType**, refer to the *Enterprise Message API C# Configuration Guide*).

6.3 Credential Management

By default, the Enterprise Message API will store all credential information. In order to use secure credential storage, a callback function can be specified by the user. If a callback function is specified, credentials are not stored in API; instead, application is called back whenever credentials are required.

If an IOmmOAuth2ConsumerClient is specified when creating the OmmConsumer object, the API will callback IOmmOAuth2ConsumerClient.OnOAuth2CredentialRenewal whenever credentials are required. This call back must call OmmConsumer.RenewOAuthCredentials to provide the updated credentials.

NOTE: OmmConsumer.RenewOAuthCredentials can only be called during the callback.

6.4 Version 2 Authentication Using OAuth Client Credentials

Version 2 authentication is available with two types of accounts:

- OAuth Client Credentials which requires a client ID and client secret.
- OAuth Client Credentials with JWT which requires client ID and private JWK for JWT.

Version 2 will generate an Access Token. Once connected to Real-Time — Optimized RTC, the login session to the LSEG Real-Time Connector (RTC) will remain valid until the consumer disconnects or is disconnected from Real-Time — Optimized. The API will only rerequest an Access Token in the following cases:

- When the consumer disconnects and goes into a reconnection state.
- If the Channel stays in reconnection long enough to get close to the expiry time of the Access Token.

Due to the above changes, credentials are managed independently per reactor channel. Channels do not share credentials.

6.4.1 Configuring and Managing Version 2 Credentials

The client ID and client secret or private JWK must be set on the **OmmConsumer** object as described in Section of the *Enterprise Transport API C# Edition Value Added Developers Guide*. The **IOmmOAuth2ConsumerClient** will handle the credentials the same way as Version 1, with an **IOmmOAuth2ConsumerClient** callback for credentials if the user does not wish for the **IOmmOAuth2ConsumerClient** to store them.

6.4.1.1 JWT Credentials Handling

Version 2 OAuth Client Credentials with JWT requires a JWK public/private pair to be generated and registered with LSEG via the Platform Admin UI. The API will use a private JWK to create and sign a JWT request, which will be sent to retrieve an access token. The JWK will be handled by the API the exact same way as a client secret above. For more information about the Platform Admin UI, refer to the Real-Time — Optimized documentation in the LSEG Developers portal.

NOTE: Follow best practices for securely storing and retrieving JWK.

6.4.2 Version 2 OAuth Client Credentials Token Lifespan

Version 2 will produce a single Access Token, which will be valid for the length of the entire **expires_in** field in the token. This Access Token is used by the API to perform service discovery, and to connect to Real-Time — Optimized.

Once connected, the API does not need to periodically renew a token.

The API will re-request a token on reconnect, and will use that token for all reconnect attempts until a short time prior to expiry. At that time, the API will get a new token for reconnection use.


6.5 Service Discovery

After obtaining a token (for details, refer to Section 6.4), the Enterprise Message API can perform a service discovery against the Delivery Platform to obtain connection details for the Real-Time — Optimized. To discover endpoints, application may rely either on file or programmatic configuration. This is accomplished by making a REST query to the Service Discovery service. EMA API may be configured to perform this query and choose an endpoint (host and port) in a specified region. Or, EMA application may interact with a pre-defined service discovery object (see **ServiceEndpointDiscovery**) to customize choosing endpoint(s).

For service discovery performed by API, see Cons113 example. For service discovery performed in application, see Cons450 example.

In response to a service discovery, the Delivery Platform returns transport and data format protocols and a list of hosts and associated ports for the requested service(s) (i.e., an LSEG Real-Time Advanced Distribution Server running in the cloud or endpoint). LSEG provides multiple cloud locations based on region, which is significant in how the Enterprise Message API chooses the IP address and port to use when connecting to the cloud.

From the list sent by the Delivery Platform, the Enterprise Message API identifies a Real-Time — Optimized endpoint with built-in resiliency whose regional location matches the API's location setting in **ChannelGroup** (for details, refer to Section 3.2.2 "Universal Channel Entry Parameters" of the *Enterprise Message API C# Edition Configuration Guide*). If you do not specify a location, the Enterprise Message API defaults to the **us-east-1** cloud location. An endpoint with built-in resiliency lists multiple locations in its location field (e.g., **location:** [us-east-la, us-east-lb]). If multiple endpoints are configured for failover, the Enterprise Message API chooses to connect to the first endpoint listed.




^{*:} An RTSDK API can be a consuming application written to EMA or ETA in C/C++, Java or C#.

Figure 1. Service Discovery

6.6 Consuming Market Data

After obtaining its login token (for details, refer to Section 6.4) and running a service discovery (for details, refer to Section 6.5), the API can connect to the LSEG Real-Time Advanced Distribution Server in the cloud and obtain market data.



6.7 HTTP Error Handling for Reactor Token Reissues

The Enterprise Message API supports handling for the following HTTP error codes from the API gateway:

- 300 Errors:
 - Perform URL redirect for 301, 302, 307 and 308 error codes
 - · Retry the request to the API gateway for all other error codes
- 400 Errors:
 - Stop retry the request for error codes 403, 404, 410, and 451
 - · Retry the request to the API gateway for all other error codes
- 500 Errors:
 - · Retry the request to the API gateway for all error codes

6.8 Cloud Connection Use Cases

You can connect to the cloud and consume data according to the following use cases:

- Start to finish session management (for details, refer to Section 6.8.1)
- Explicit service discovery option for applications (for details, refer to Section 6.8.2)

6.8.1 Session Management Use Case

In this use case, the Enterprise Message API manages the entire connection from start to finish. To use session management, you need to configure the API to enable session management. To do so, in the ChannelGroup, set the Channel entry parameter **EnableSessionManagement**).

The API exhibits the following behavior for this use case:

- 1. Obtains a token (according to the details in Section 6.4).
- 2. Queries service discovery (according to the details in Section 6.5).
- 3. Consumes market data (according to the details in Section 6.6).

Enterprise Message API's Consumer example (113__MarketPrice__SessionManagement example) provides sample source to illustrate session management.

With session management enabled, application may specify a host and port in ChannelGroup parameters. In this case, the Enterprise Message API exhibits the same behavior listed above, but ignores the endpoints it receives from the service discovery and connects to the specified host and port.

6.8.2 Explicit Service Discovery Use Case

Application has the option to do a service discovery, parse the results, and choose an endpoint to pass into API. The API exhibits the following behavior when application does an explicit service discovery:

- 1. Obtains a token (according to the details in Section 6.4).
- 2. Queries service discovery (according to the details in Section 6.5).

Enterprise Message API's **Consumer** example (**450__MarketPrice__QueryServiceDiscovery**) provides sample source that discovers an endpoint using the service discovery feature and establishes an encrypted connection to consume data.

6.9 Logging of Authentication and Service Discovery Interaction

If needed, you can log interactions with the Delivery Platform. To enable logging, use the parameters **RestEnableLog** and **RestLogFileName** in the EMA configuration file or programmatic configuration in the Consumer Group. If Service Discovery is done from the application, logging may be enabled only via function call configuration. For details on these parameters, refer to the *Enterprise Message API C# Configuration Guide*.

6.9.1 Logged Request Information

With logging turned on in the fashion mentioned in , the Enterprise Message API writes the following request information in the log:

Request:

- Time stamp
- The Name of the class and method that made the request
- Request method
- URI
- Request headers
- Proxy information (if used)
- Body of request as set of pairs parameter_name: parameter_value

NOTE: If the request contains the **client_secret** parameter, the Enterprise Message API uses a placeholder instead of the real value of the respective parameter (thus indicating that the value was present).

6.9.2 Logged Response Information

With logging turned on in the fashion mentioned in , the Enterprise Message API writes the following response information in the log:

Response:

- Time stamp
- The Name of the class and method that received the response
- Response status code
- Response headers
- Body of response in string format

7 Request Routing

The Request Routing feature, a client-side feature, provides the application the capability to route market data item requests to multiple connections depending on the availability of services of each connection. EMA routes item requests by matching the quality of service and capabilities of the requested concrete service or service list name in order to submit the request messages. EMA manages multiple connections, aggregates login responses and concrete services on behalf of application. The same concrete service name of each connection must have the same quality of service list, item list and support QoS range attributes otherwise the subsequent connection is closed and removed at OmmConsumer creation. Application can define a service list which contains a list of concrete service names for requesting market data items using the service list name which requests are routed to the first qualifying service on the service list. For item recovery, EMA recovers items from the concrete services in the consumer session which matches with the requested concrete service name or one of concrete service in the specified service list and the service is ready to accept requests.

For details, see the following sections:

- Administrative Domains Behaviors
- Service List
- <u>Item Request Routing and Recovery</u>
- Posting Messages
- Sending Generic Message
- Session Channel Information from OmmConsumer and IOmmConsumerEvent

7.1 Administrative Domains Behaviors

In order to create a consumer session for request routing, multiple connections must be aggregated. Handling administrative domains for aggregating multiple connections has some specific behaviors.

For details, see the following sections:

- Login Request Timer Handling and Login Response Aggregation
- Aggregated Login Elements
- Scenarios for Receiving Aggregated Login Stream
- <u>Directory Request Timer Handling and Directory Response Aggregation</u>
- Dictionary Request Timer Handling

7.1.1 Login Request Timer Handling and Login Response Aggregation

The **LoginRequestTimeOut** parameter is configured in ConsumerGroup to control how long would EMA waits to receive login response for all configured session channels during OmmConsumer initialization. The following are scenarios for handling multiple connections for a consumer session.

SCENARIOS FOR LOGIN REQUEST TIMEOUT	LOGIN INITIALIZATION BEHAVIOR	
No connections come up or EMA does not receive any login response within timeout.	 Initialization fails at timeout. Application must re-create the OmmConsumer object. The OmmConsumer object will not be created. 	
Only some connections are up and sent login response, the login timer fires.	 Initialization succeeds with the login domain at timeout. NOTE: Initialization succeeds with the login domain at timeout. Channels that did not come up will be closed: if application wants to route to channels that did NOT come up in time, application must re-create OmmConsumer. Application is notified of which connections are up/down upon timeout via login stream. Requests are routed in the ordered list of connections in the Consumer's SessionChannelSet configuration. 	
EMA receives login denied status message for a connection.	Enterprise Message API closes the connection and removes the channel from the session channel list.	
All configured connections come up before the login timeout fires.	 Initialization succeeds with the login domain immediately upon all connections up. Application is notified of which connections are up/down upon all connections up. Requests are routed in the ordered list of connections in the Consumer's SessionChannelSet configuration. 	

Table 2: Scenarios for Login Request Timeout

7.1.2 Aggregated Login Elements

Enterprise Message API aggregates all login responses from all connections and presents to application as a login response once login domain handling is completed. Login aggregation takes the login element attributes that are present across all of the connections.

The following is the list of aggregated login elements. For each element, all connections must support login aggregation, otherwise it will not be supported.

- ProvidePermissionProfile
- ProvidePermissionExpressions
- SupportBatchRequests
- SupportOptimizedPauseResume
- SupportPauseResume
- SupportOMMPost
- SupportEnhancedSymbolList
- SupportViewRequests
- RoundTripLatency

NOTE: SingleOpen and AllowSuspect attributes are always turned on for the Request Routing feature.

7.1.3 Scenarios for Receiving Aggregated Login Stream

Applications can register to receive an aggregated login stream and channel information via login stream for each session channels in order to receive notification of channel events. The aggregated login message's **OmmState** is used to represent the entire consumer session as described in the following table.

AGGREGATED LOGIN STREAM SCENARIOS	MESSAGE TYPE	STREAM STATE	DATA STATE	DESCRIPTION
EMA tries to establish a connection with all session channels for a consumer session within the timeout.	StatusMsg	Open	Suspect	Application receives channel information for each session channel via login stream event so that application get notified which session channel is up or down or down reconnecting. This should only be sent once for each underlying reactor channel, upon initialization of the reactor channel.
EMA receives a "login accepted" status message from at least one session channel in a consumer session and login timeout fires.	RefreshMsg	Open	Ok	Enterprise Message API is successfully establishing a login stream for an OmmConsumer . Enterprise Message API notified application with aggregated login response.
EMA receives a "login closed" status message from a session channel, but others login stream is still open.	StatusMsg	Open	Ok	There is no change to the aggregated login stream and application receives channel down event for the session channel.
EMA receives a "login closed" status message from every session channel.	StatusMsg	Closed	Suspect	EMA notifies application with a Login Status with OmmState of Closed/Suspect upon detecting that all channels in a SessionChannelSet are down either due to receiving a Login Status Closed/Suspect or channel down event. See the previous row for behavior if only some of the session channels are closed. In this case, OmmConsumer is in terminal state and application should uninitialize it.
EMA receives a channel down event from every session channel.	StatusMsg	Closed	Suspect	EMA notifies application with a Login Status with OmmState of Closed/Suspect indicating channel down upon detecting that all channels in a SessionChannelSet are down either due to receiving a Login Status Closed/Suspect or channel down event. See two rows for behavior if only some of the session channels are closed. In this case, OmmConsumer is in terminal state and application should uninitialize it.

Table 3: Aggregated Login Stream Scenarios

7.1.4 Directory Request Timer Handling and Directory Response Aggregation

The **DirectoryRequestTimeOut** parameter in **ConsumerGroup** is used to control how long would Enterprise Message API waits to receive directory response for all configured session channels during **OmmConsumer** initialization. Initialization fails at timeout when Enterprise Message API does not receive at least one source directory valid response from a channel.

For source directory aggregation, Enterprise Message API generates a unique service ID for each particular service in order to aggregate particular services with the same name from multiple connections, Applications can register with the source directory domain to receive source directory response for aggregated services in order to retrieve source directory information including the generated service ID. Enterprise Message API aggregates and caches for particular services only for INFO and STATE filters for routing user's requests.

For each particular service name, the following element attributes must match.

- List of supported quality of service (QoS)
- Item List name
- Support QoS range

NOTE: If element attributes do not match the service name during OmmConsumer creation, Enterprise Message APIremoves and closes the subsequent connection based on the order of the session channel list. Afterward, it ignores source directory update with mismatched attributes for the service.

For service's state aggregation of a particular service:

- ServiceState is UP (1) unless the service of all connections is in the DOWN (0) state.
- AcceptingRequests is UP (1) unless the service of all connections in the DOWN (0) state.

7.1.5 Dictionary Request Timer Handling

The **DictionaryRequestTimeOut** parameter in **ConsumerGroup** is used to control how long would Enterprise Message API waits to receive dictionary response for the **ChannelDictionary** type from a channel during **OmmConsumer** initialization. Initialization fails at the timeout when Enterprise Message API does not receive a dictionary response from a session channel which provides the first available service for downloading data dictionary.

NOTE: Enterprise Message API supports single data dictionary version per **OmmConsumer**, so all services of all session channels must support the same version.

7.2 Service List

A Service List is a named grouping of particular service names in order to request items using service list name. The **ServiceList** class is used to create a service list, and applications have to add **ServiceList** instances to an instance of **OmmConsumerConfig** before creating **OmmConsumer**.

NOTE: The concrete services in a service list must have the same quality of service.

The following example illustrates the creation of a service list and adding it to OmmConsumer.

```
/* Create a service list which can subscribe data using any concrete services in this list */
ServiceList serviceList = new("SVG1");

serviceList.ConcreteServiceList.Add("DIRECT_FEED");
serviceList.ConcreteServiceList.Add("DIRECT_FEED_2");

consumer = new OmmConsumer(new OmmConsumerConfig().AddServiceList(serviceList), appClient);

consumer.RegisterClient(new RequestMsg().ServiceListName("SVG1").Name("LSEG.L"), appClient);
```

NOTE: When making a request using the service list name, the response messages will utilize the name and ID of the service list name instead of the concrete service name and ID.

7.3 Item Request Routing and Recovery

Applications can set an item request using a concrete service name, service ID, or service list name in a **RequestMsg** instance and register it using the **RegisterClient()** method of **OmmConsumer**. For specifying service name/ID, Enterprise Message API tries to match the specified concrete service with a session channel according to the ordered list of connections in the **OmmConsumer**. For service list name, Enterprise Message API tries to match between the ordered list of concrete service names and the ordered list of connections in the **OmmConsumer**.

The following diagram illustrates the request matching workflow for a concrete service and a session channel.




Figure 2. Item Request Matching Workflow

Enterprise Message API conducts automatic item recovery for all streaming item requests initiated by the client, with the exception of private item streams. The situations that lead to an item's data becoming stale include loss of connection, service outages, and the provider transmitting the CLOSED_RECOVER stream state to the consumer, among others. The process of item recovery involves recovering items from a stale condition by closing the existing item stream and utilizing the item request matching workflow to identify a session channel for re-requesting the item. Request Routing also works with the WarmStandby feature which has its own fallback mechanism to receive data from a standby server when the active server or service is unavailable. Items that cannot be retrieved due to the unavailability of a service for data requests will be placed in a recovery queue for future retrieval at an appropriate time. The items that are in the CLOSED stream state will be recovered in others session channel until there is no other channel, then the closed status message will be sent to application.

NOTE: The **SessionEnhancedItemRecovery** parameter is set to true by default to recovery items to others session channels when the session channel is temporary down due to connection loss. Users can override this behavior by setting the parameter to false to let Enterprise Message API wait until the connection is recovered and request data with the requested service name.

7.4 Posting Messages

In order to perform off-stream posting, the aggregated login refresh for all session channels must support the OMM post feature, otherwise the **OmmInvalidUsageException** is thrown to application. The service name or service ID specified in a **PostMsg** will be translated into the underlying session channel's service ID. The **AckMsg** will be transmitted through the session channel which it was received.

For off-stream posting, Enterprise Message API will distribute the **PosMsg** to all connected session channels that are compatible with the designated service. Enterprise Message API will discard the **PostMsg** from any session channel that does not support the specified service name or ID.

For on-stream posting, Enterprise Message API will submit the **PostMsg** to the session channel of the requested stream that supports the specified service. The **OmmInvalidUsageException** will be raised to the application if the specified service name or ID is not present on the requested stream.

7.5 Sending Generic Message

The application is capable of submitting a **GenericMsg** on both the login and item streams. In this process, the specified service ID within the **GenericMsg** will be converted into the service ID of the underlying session channel. However, if the service ID is unknown, this will not trigger an **OmmInvalidUsageException**, and the unknown service ID will be transmitted as it is.

For sending a **GenericMsg** on login stream, Enterprise Message API will distribute the GenericMsg to all connected channels without regard to the validity of the specified ID.

7.6 Session Channel Information from OmmConsumer and IOmmConsumerEvent

Application can get a list of session channels from the SessionChannelInfo() method from either OmmConsumer class and IOmmConsumerEvent interfaces. This would help application to get a list of active session channels in order to keep track each session's channel state. The session channel will be removed from the list once it is closed by Enterprise Message API, or the channel is completely down. Users must specify a List of ChannelInformation in order to return the current session information per function call. The following is the sample code how to iterator through the list of ChannelInformation from the function.

```
List<ChannelInformation> channelInList = new();

consumerEvent.SessionChannelInfo(channelInList);

foreach (ChannelInformation channelInfo in channelInList)
{
    Console.WriteLine(channelInfo);
}
```

NOTE: The SessionChannelInfo() method returns an empty list if request routing is not enabled.

Moreover, the **ChannelInformation** class can also get a channel name and session channel name using the **ChannelName()** and **SessionChannelName()** method respectively.

8 Troubleshooting and Debugging

8.1 EMA Logger Usage

The Enterprise Message API provides a logging mechanism useful for debugging runtime issues. In the default configuration, Enterprise Message API is set to log significant events encountered during runtime and direct logging output to a file. If needed, you can turn off logging, or direct its output to stdout. Additionally, applications can configure the logging level at which the Enterprise Message API logs event (to log every event, only error events, or nothing). For further details on managing and configuring the EMA logging function, refer to the Enterprise Message API C# Edition Configuration Guide.

8.2 OMM Error Client Class

8.2.1 IOmmConsumerErrorClient and IOmmProviderErrorClient Descriptions

Enterprise Message API has two Error Client classes: **IOmmConsumerErrorClient** and **IOmmProviderErrorClient**. These two classes are an alternate error notification mechanism in the Enterprise Message API, which you can use instead of the default error notification mechanism (i.e., **OmmException**, for details, refer to Section 8.3). To use Error Client, applications need to implement their own error client class, override the default implementation of each method, and pass this Error Client class on the constructor to **OmmConsumer** and **OmmProvider**.

8.2.2 Example: IOmmConsumerErrorClient

The following example illustrates an application error client and depicts simple processing of the OnInvalidHandle() method.

```
class AppErrorClient : IOmmConsumerErrorClient
{
    public void OnInvalidHandle(long handle, String text)
    {
        Console.WriteLine("onInvalidHandle callback function" + "\nInvalid handle: " + handle + "\nError text: " + text);
    }
    public void OnInvalidUsage(String text, int errorCode) {
        Console.WriteLine("onInvalidUsage callback function" + "\nError text: " + text +" , Error code: " + errorCode);
    }
    public void OnDispatchError(String text, int errorCode) {
        Console.WriteLine("OnDispatchError callback function" + "\nError text: " + text + " , Error code: " + errorCode);
    }
}
```

8.3 OmmException Class

If the Enterprise Message API detects an error condition, the Enterprise Message API might throw an exception. All exceptions in the Enterprise Message API inherit from the parent class **OmmException**, which provides functionality and methods common across all **OmmException** types.



TIP: LSEG recommends you use **try** and **catch** blocks during application development and QA to quickly detect and fix any Enterprise Message API usage or application design errors.

The Enterprise Message API supports the following exception types:

- OmmInvalidConfigurationException: Thrown when the Enterprise Message API detects an unrecoverable configuration error.
- OmmInvalidHandleException: Thrown when an invalid / unrecognized item handle is passed in on OmmConsumer or OmmProvider class methods.
- OmmInvalidUsageException: Thrown when the Enterprise Message API detects invalid interface usage.
- OmmOutOfRangeException: Thrown when a passed-in parameter lies outside the valid range.
- OmmUnsupportedDomainTypeException: Thrown if domain type specified on a message is not supported.

8.4 Creating a DACSLOCK for Publishing Permission Data

Provider applications can create a DACSLocks and publish it to permission data on the LSEG Real-Time Distribution System. A DACSLock controls access to data by users. For further details on the DACSLock API, refer to the *Enterprise Message API C# Edition DACSLock Library*.

The following example code illustrates how to create a DACSLock.

```
List<uint> peList = new() { 1001 };
AuthorizationLock authLock = new(serviceID: 261, AuthorizationLock.OperatorEnum.OR, peList);
AuthorizationLockData lockData = new();
AuthorizationLockStatus retStatus = new();
LockResultEnum result = authLock.GetLock(lockData, retStatus);
if (result == LockResultEnum.LOCK_SUCCESS)
{
    Console.WriteLine("Success - GetLock()");
}
else
{
    Console.WriteLine("Failure - GetLock()");
}
```

 $\hfill \odot$ LSEG 2023 - 2025. All rights reserved.

Republication or redistribution of LSEG Data & Analytics content, including by framing or similar means, is prohibited without the prior written consent of LSEG Data & Analytics. 'LSEG Data & Analytics' and the LSEG Data & Analytics logo are registered trademarks and trademarks of LSEG Data & Analytics.

Any third party names or marks are the trademarks or registered trademarks of the relevant third party.

Document ID: EMACSharp340UM.250

Date of issue: May 2025

