The STklos Virtual Machine

Jeronimo Pellegrini

Table of Contents

1. The bytecode	2
2. Value register	3
3. Stack	6
4. Local variables	7
5. Deep variables	9
6. Global variables	11
7. Operations	12
7.1. Arithmetic	12
7.2. Increment and decrement val	14
7.3. Comparisons	14
7.4. Constructors.	15
7.5. Structure references	17
8. Control flow	19
9. Closures, let, and related	20
9.1. let	20
10. Miscelannea	22
10.1. Creating closures and procedures	23
10.2. Procedure calls	25
44 No dula	0.7

This is the documentation for the opcodes of the STklos virtual machine. The VM implementation is contained in the files src/vm.h and src/vm.c.

The VM has a stack, which in the source code is accessed using the C functions push(elt) and pop(). Each VM thread also has:

- STk_instr *pc, the program counter
- SCM *fp, the frame pointer
- SCM *sp, the Scheme stack pointer
- SCM *stack, the Scheme stack
- int stack_len, the length of the stack
- SCM val, a register for the current value
- SCM vals[], a register for multiple values
- int valc, the number of multiple values
- SCM r1, r2 two registers
- SCM env, the current environment
- SCM current_module, the current module
- SCM iport, oport, eport, the current input, output and error ports
- SCM scheme thread, the Scheme thread associated with this thread

Of these, only a few are relevant to understanding the bytecode – these are the value registers and the stack.

Chapter 1. The bytecode

STklos bytecode is a sequence of 16-bit integers. You can see the opcodes of a compiled thunk with

```
(disassemble (lambda () ...))
```

and the opcodes of an expression with

```
(disassemble-expr 'expr)
```

With an extra #t argument, dissasemble-proc will show constants:

```
(disassemble-expr "abc")
```

```
000: CONSTANT 0
002:
```

```
(disassemble-expr "abc" #t)
```

```
000: CONSTANT 0
002:

Constants:
0: "abc"
```

When we make a closure with the lambda, we'll always see a RETURN at the end of the output:

```
stklos> (disassemble (lambda () '() ))
```

```
000: IM-NIL
001: RETURN
```

In the above example, one opcode loads the NIL value to the register and another opcode `RETURN`s. This return is from the lambda.

Chapter 2. Value register

The simpler opcodes are those that carry with them an immediate value. These operations will copy their value to the val register in the VM.

```
IM_FALSE
IM_TRUE
IM_NIL
IM_MINUS1
IM_ZERO
IM_ONE
IM_VOID
```

Examples:

```
(disassemble-expr 1)
000: IM-ONE
(disassemble (lambda () #f 1) )
000: IM-FALSE
001: IM-ONE
002: RETURN
```

Opcodes for small integers and constants do the same, but they take a little longer to execute, since they need to perform some small operations.

```
SMALL_INT
CONSTANT
```

```
(disassemble-expr 5)
```

000: SMALL-INT 5 Small integers are *not* the same as fixnums! A small integer is an integer number that fits in 16 bits (that is, in one bytecode element). The fixnum range depends on the size of long in the platform being used.

Suppose STklos has been compiled on a 64 bit system and also ona 32 bit system. The ranges for small ints and fixnums are:

```
small integer (on both): [ -2^15, +2^15 - 1 ]
fixnum (long is 32-bit): [ -2^29, +2^29 - 1 ]
fixnum (long is 64-bit): [ -2^61, +2^61 - 1 ]
```

The expression above, 5, is compiled into the bytes

```
00 08 00 05
```

where 00 08 is the opcode for 'small int'', and '00 05 is the argument (the small integer, 5).

Small integers are compiled *into* the bytecode. Fixnums, bignums, strings are stored *outside* of the bytecode, and the instruction CONSTANT takes as argument an index into the constants vector.

The expression 50000 is not a small integer, so it is compiled as a constant:

```
(disassemble-expr 50000 #t)
000: CONSTANT 0
002:

Constants:
0: 50000
```

Zero is the index of 50000 in the constants vector.

The above code is compiled into bytecode as

```
00 09 00 00
```

where 00 09 means CONSTANT and 00 00 is the index into the constants vector.

Another clarifying example:

(disassemble-expr '(values 50000 ``abc") #t)

```
000: PREPARE-CALL
001: CONSTANT-PUSH
                         0
003: CONSTANT-PUSH
                         1
                        2 2
005: GREF-INVOKE
008:
Constants:
0: 50000
1: "abc"
2: values
```

The bytecode is

```
37 85 0 85 1 86 2 2
```

Here,

- 85 0 is CONSTANT-PUSH 0 (0 = first element of the vector)
- 85 1 is CONSTANT-PUSH 1 (1 = second element)
- 86 2 2 is GREF-INVOKE 2 2 (2 = number, arg to `values, next 2 = third element of vector)

Chapter 3. Stack

The following opcodes are similar to the immediate-value ones, except that, instead of copying their values to the val register, they push the value on the stack.

```
FALSE_PUSH
TRUE_PUSH
NIL_PUSH
MINUS1_PUSH
ZERO_PUSH
ONE_PUSH
VOID_PUSH

INT_PUSH
CONSTANT_PUSH
```

The POP and PUSH move objects between stack and value register.

```
POP ; move top of stack to val register
PUSH ; store val register on top of stack
```

Chapter 4. Local variables

The LOCAL_REF opcodes will load the values of variables from the current environment (the `local'' variables) on the 'val register.

```
LOCAL_REF0
LOCAL_REF1
LOCAL_REF2
LOCAL_REF3
LOCAL_REF4
LOCAL_REF
```

Examples:

```
(disassemble (lambda (a) a))
```

000: LOCAL-REF0 001: RETURN

```
(disassemble (lambda (a b) a))
```

```
000: LOCAL-REF1
     RETURN
001:
```

There are opcodes for five fixed positions only, so after that another opcode, LOCAL_REF, needs an argument:

```
(disassemble (lambda (a b c d e f) a))
```

```
000: LOCAL-REF
                          5
002: RETURN
```

The following opcodes are similar to the local reference ones, except that, instead of copying their values to the val register, they push the value on the stack.

```
LOCAL_REF0_PUSH
LOCAL_REF1_PUSH
LOCAL_REF2_PUSH
LOCAL_REF3_PUSH
LOCAL_REF4_PUSH
```

The following opcodes are analogous to the local reference ones, but instead of loading values, they store the value of the $\ensuremath{\text{val}}$ register on the local variables

```
LOCAL_SET0
LOCAL_SET1
LOCAL_SET2
LOCAL_SET3
LOCAL_SET4
LOCAL_SET
```

Chapter 5. Deep variables

Variables which are visible but not in the immediately accessible environment are accessed with the **DEEP** opcodes.

```
DEEP_LOCAL_REF
DEEP_LOCAL_SET
DEEP_LOC_REF_PUSH
```

Examples:

```
(disassemble
(let ((a 10))
   (lambda () a)))
```

```
000: DEEP-LOCAL-REF
                          256
002: RETURN
```

```
(disassemble
(let ((a 10))
  (lambda ()
     (set! a 20))))
```

```
000: SMALL-INT
                          20
002: DEEP-LOCAL-SET
                          256
004: RETURN
```

In the following example, the value of a is fetched from a deep environment and pushed onto the stack, so it can be used by the comparison opcode IN-NUMEQ:

```
(disassemble
(let ((a 10))
   (lambda ()
     (= a 20)))
```

004: IN-NUMEQ 005: RETURN

Chapter 6. Global variables

Global variables can be read and set with the following opcodes:

```
GLOBAL-REF
GLOBAL-SET
```

Examples:

```
(disassemble-expr 'my-cool-global-variable) #t)
```

000: GLOBAL-REF

Constants:

0: my-cool-global-variable

(disassemble-expr '(set! my-cool-global-variable #f) #t)

000: IM-FALSE

001: GLOBAL-SET

Constants:

0: my-cool-global-variable

Chapter 7. Operations

7.1. Arithmetic

The operations take the top of stack and val as operands, and leave the result on val.

```
IN_ADD2
IN_SUB2
IN_MUL2
IN_DIV2
```

```
(disassemble-expr '(+ a 3) #t)
```

```
000: GLOBAL-REF 0
002: IN-SINT-ADD2 3

Constants:
0: a
```

First the value of a (which is the zero-th local variable) is pushed onto the stack. Then, DEEP-LOCAL-REF brings the value of x, and IM-ADD2 adds the two values, leaving the result on the local variable register.

For fixnums, the analogous opcodes are:

```
IN_FXADD2
IN_FXSUB2
IN_FXMUL2
IN_FXDIV2
```

```
(disassemble-expr '(fx+ v 3))
```

```
000: GLOBAL-REF   0
002: IN-SINT-FXADD2   3

Constants:
0: v
```

The following variant of those opcodes do not use the stack. They operate on val and an argument:

```
IN_SINT_ADD2
IN_SINT_SUB2
IN_SINT_MUL2
IN_SINT_DIV2
```

Example:

```
(disassemble-expr '(+ a 2))
```

```
000: GLOBAL-REF     0
002: IN-SINT-ADD2     2

Constants:
0: a
```

With a as a local variable:

```
(disassemble (lambda (a) (+ a 2)))
```

```
000: LOCAL-REF0
001: IN-SINT-ADD2 2
003: RETURN
```

First, the value of a is put on val; then it is summed with 2, which comes as an argument to the opcode IN-SINT-ADD2.

These also have fixnum variants:

```
IN_SINT_FXADD2
IN_SINT_FXSUB2
IN_SINT_FXMUL2
IN_SINT_FXDIV2
```

Example:

(disassemble-expr '(fx+ a 2))

```
000: GLOBAL-REF    0
002: IN-SINT-FXADD2    2

Constants:
0: a
```

7.2. Increment and decrement val

```
IN_INCR
IN_DECR
```

7.3. Comparisons

These compare the top of stack with val, and leave a boolean on val.

Example:

```
(disassemble-expr ' (>= a 2))
```

```
000: GLOBAL-REF-PUSH 0
002: SMALL-INT 2
004: IN-NUMGE

Constants:
0: a
```

There are also opcodes for equal?, eqv? and eq?:

```
IN_EQUAL
IN_EQV
IN_EQ
```

Example:

```
(disassemble-expr '(eq? a 2))
```

```
000: GLOBAL-REF-PUSH 0
002: SMALL-INT 2
004: IN-EQ

Constants:
0: a
```

The dissassemble procedures will not, however, show the names of symbols or values of strings (disassemble-expr does, when passed the extra #t argument).

```
(disassemble (lambda (a) (eq? a 'hello-i-am-a-symbol)))
```

```
000: LOCAL-REF0-PUSH
001: CONSTANT 0
003: IN-EQ
004: RETURN
```

```
(disassemble-expr '(eq? a 'hello-i-am-a-symbol) #t)
```

7.4. Constructors

These will build structures with the value in val and store the structure (that is, the tagged word representing it) again on val.

```
IN_CONS
IN_CAR
IN_CDR
IN_LIST
```

Examples:

```
(disassemble-expr '(cons "a" "b") #t)
                             0
  000: CONSTANT-PUSH
  002: CONSTANT
                             1
  004: IN-CONS
  005:
 Constants:
  0: "a"
  1: "b"
  (disassemble (lambda (a b) (cons a b)))
  000: LOCAL-REF1-PUSH
  001: LOCAL-REF0
  002: IN-CONS
  003: RETURN
The element to be consed is pushed on the stack; then the second element is loaded on val, and then
IN-CONS is called.
  (disassemble (lambda (a) (list a)))
  000: LOCAL-REF0-PUSH
                             1
  001: IN-LIST
  003: RETURN
  (disassemble-expr '(car a) #t)
                             0
  000: GLOBAL-REF
```

002: IN-CAR

Constants:

003:

0: a

7.5. Structure references

The following opcodes access and set elements of strings and vectors.

```
IN_VREF
IN_SREF
IN_VSET
IN_SSET
```

V stands for vector, S stands for string; then, REF and SET mean reference' and set".

The instructions will use the object in the stack and the index from the val register.

Examples

```
(disassemble (let ((a #(0 1 2 3))) (lambda () (vector-ref a 2))))

000: DEEP-LOC-REF-PUSH 256
```

000: DEEP-LOC-REF-PUSH 256
002: SMALL-INT 2
004: IN-VREF
005: RETURN

In the following example, the CONSTANT-PUSH is including a reference to the string on the stack.

```
(disassemble-expr '(string-ref "abcde" 3) #t)
```

```
000: CONSTANT-PUSH   0
002: SMALL-INT    3
004: IN-SREF
005:
Constants:
0: "abcde"
```

When setting a value, the reference to the vector or string and the index go on the stack (index below the reference to the object – the index is popped first), and the value goes on val, then the setting opcode is used:

```
(disassemble
  (let ((v (vector #\a #\b #\c)))
      (lambda () (vector-set! v 2 10))))
```

000: DEEP-LOC-REF-PUSH 256 ; push ref. to vector

002: INT-PUSH 2 ; push index

004: SMALL-INT 10 ; put new value in val

006: IN-VSET ; set it!

007: RETURN

Chapter 8. Control flow

The following opcodes have an argument, which is the offset to be added to the program counter.

```
GOTO
                 ; unconditionally jump
JUMP_TRUE
                 ; jump if val is true
                 ; jump if val is false
JUMP FALSE
JUMP_NUMDIFF
                 ; jump if ! pop() = val (for numbers)
JUMP_NUMEQ
                 ; jump if pop() = val (for numbers)
JUMP NUMLT
                 ; jump of pop() < val
JUMP_NUMLE ; jump of pop() <= val
JUMP_NUMGT ; jump of pop() > val

JUMP_NUMGE ; jump of pop() >= val

JUMP_NOT_EQ ; jump if pop() not eq? val
JUMP_NOT_EQV ; jump if pop() not eqv? val
JUMP_NOT_EQUAL ; jump if pop() not equal? val
```

Example:

```
(disassemble
 (lambda () (if #t 2 4)))
```

```
000: IM-TRUE
001: JUMP-FALSE
                         3 ;; ==> 006
003: SMALL-INT
005: RETURN
006: SMALL-INT
                         4
008: RETURN
```

STklos' disassemble is nice enough to tell you the line number where a jump goes!

Chapter 9. Closures, let, and related

9.1. let

The opcodes for 'entering 'let0' create new environments and push them on the stack, but do not update activation records, since there is no procedure call happening. Then, the 'LEAVE_LET opcode removes the environment from the stack.

```
ENTER_LET
ENTER_LET_STAR
ENTER_TAIL_LET
ENTER_TAIL_LET_STAR
LEAVE_LET
```

Examples:

When the let is in tail position, then the opcode used is the ordinary ENTER_TAIL_LET, and no LEAVE_LET is needed:

```
(disassemble
  (lambda ()
      (let ((x 1))
      x)))
```

000: PREPARE-CALL

001: INT-PUSH 4 002: ENTER-TAIL-LET 1

004: LOCAL-REF0 005: RETURN

Chapter 10. Miscelannea

The following opcode does nothing:

```
NOP
```

The following sets the docstring and the formal parameter list documentation for a procedure:

```
DOCSTRG
FORMALS
```

Examples:

```
(disassemble-expr '(define (f) "A well-documented function" 5) #t)
```

```
000: CREATE-CLOSURE
                         4 0 ;; ==> 006
003: SMALL-INT
005: RETURN
006: DOCSTRG
                          0
008: DEFINE-SYMBOL
                         1
010:
Constants:
0: "A well-documented function"
1: f
```

```
(disassemble
(lambda ()
  (define (f) "A well-documented function" 5)
  10))
```

```
000: PREPARE-CALL
001: FALSE-PUSH
002: ENTER-TAIL-LET
004: CREATE-CLOSURE
                         4 0 ;; ==> 010
007: SMALL-INT
009: RETURN
010: DOCSTRG
                         0
012: LOCAL-SET0
013: SMALL-INT
                         10
015: RETURN
```

Here, DOCSTRG seems to have a zero argument because it uses a constant string, and disassemble does not show values of strings and symbol names.

The FORMALS opcode is similar to DOCSTRG, except that it expects a list instead of a string.

```
((in-module STKLOS-COMPILER compiler:generate-signature) #t)
(disassemble-expr '(define (f a b . c)
                     "A well-documented function"
                     (* a 3))
                  #t)
```

```
5 -3;; ==> 007
000: CREATE-CLOSURE
003: LOCAL-REF2
004: IN-SINT-MUL2
                         3
006: RETURN
007: FORMALS
                         0
009: DOCSTRG
                         1
011: DEFINE-SYMBOL
013:
Constants:
0: (a b . c)
1: "A well-documented function"
2: f
```

10.1. Creating closures and procedures

The following opcode creates a closure.

```
CREATE_CLOSURE
```

This opcode fetches two parameters:

- the number of instructions ahead that the VM needs to jump to (because what follows is the code of a closure being created, and it should *not* be executed, so the VM wull jump over it)
- the closure arity.

Examples:

```
(disassemble
(lambda ()
  (lambda () "Hello")))
000: CREATE-CLOSURE
                          4 0 ;; ==> 006
003: CONSTANT
                          0
005: RETURN
006: RETURN
(disassemble
(lambda ()
  (lambda (x) (* 2 x))))
000: CREATE-CLOSURE
                          5 1 ;; ==> 007
003: LOCAL-REF0
004: IN-SINT-MUL2
                          2
006: RETURN
007: RETURN
(disassemble
(lambda ()
  (define (g a b c) 10)
  g))
000: PREPARE-CALL
001: FALSE-PUSH
002: ENTER-TAIL-LET
                          4 3 ;; ==> 010
004: CREATE-CLOSURE
007: SMALL-INT
                          10
009: RETURN
010: LOCAL-SET0
011: LOCAL-REF0
012: RETURN
```

10.2. Procedure calls

The following opcodes are used to make procedure calls:

```
PREPARE-CALL
INVOKE
TAIL_INVOKE
GREF-INVOKE
GREF-TAIL-INVOKE
```

PREPARE_CALL pushes an activation record on the stack. The INVOKE opcodes call procedures – local or global; in tail position or not.

```
(disassemble (lambda () (f)))
```

```
PREPARE-CALL
000:
001: GREF-TAIL-INVOKE
                          0 0
```

004: RETURN

```
(disassemble (lambda () (f 3)))
```

```
000: PREPARE-CALL
                         3
001: INT-PUSH
003: GREF-TAIL-INVOKE
                         0 1
006: RETURN
```

```
(disassemble (lambda () (+ 2 (f))))
```

```
000: PREPARE-CALL
001: GREF-INVOKE
                          0 0
004: IN-SINT-ADD2
                          2
006: RETURN
```

In the next example, GREF-INVOKE is called with arguments 0 and 2. The value 2 is the address of the procedure in the stack. The IN-SINT-ADD2 procedure is called afterwards to sum 1 with the return from f.

```
(disassemble
(lambda (x)
   (+ 1 (f x #f)))
```

```
000: PREPARE-CALL
001: LOCAL-REF0-PUSH
002: FALSE-PUSH
003: GREF-INVOKE
                        0 2
006: IN-SINT-ADD2
                         1
008: RETURN
```

Now the next example shows how INVOKE is used to call a procedure that is non-global (it is in the local environment):

```
(let ((f (lambda (x) x)))
 (disassemble
  (lambda ()
    (+ 1 (f x #f)))))
```

```
000: PREPARE-CALL
001: GLOBAL-REF-PUSH
                         0
003: FALSE-PUSH
                         256
004: DEEP-LOCAL-REF
006: INVOKE
                         2
                         1
008: IN-SINT-ADD2
010: RETURN
```

Chapter 11. Modules

The following opcode enters a given module.

```
SET_CUR_MOD
```

An SCM object of type module must be in the val resgister.

Example:

```
(disassemble-expr '(select-module m) #t)
```

In the above example, the constants were two symbols: m and find-module. The find-module procedure, which is called, will leave module m in the val register, which is then used by SET_CUR_MOD.

The following opcode defines a variable in a module.

```
DEFINE_SYMBOL
```

It will define a variable with name set as symbol fetched after the opcode, and value in the val register.

```
(disassemble-expr '(define a "abc") #t)
```

(disassemble-expr '(define a #f) #t)

000: IM-FALSE

001: DEFINE-SYMBOL 0

003:

Constants:

0: a