Lost Messages

There are a number of reasons that messages may be lost:

7

7

Failure is more common in inter-machine communication

How can we tell if a message is lost?

- Each message can be responded to by the receiver with an acknowledge (or "ack") message
- If the sender does not receive an acknowledge within a certain period of time, it retransmits the message
 - We can keep doing this until we receive the "ack"

Problems with Retransmission

The same message may be sent more than once due to retransmission in two cases:



7

This leads to the same message being sent more than once.

- If the message was a request to perform an *idempotent* operation (an operation that if executed twice will produce no ill side-effects) then there is no problem
- A non-idempotent operation request is one where executing the operation more than once does cause a problem

Problems with Retransmission


- We can deal with retransmission problems by assigning each message packet a number in a predetermined sequence
 - Receiver discards any packet whose number matches one that has already been received from same sender
- Provide an "at-most-once" IPC operation for nonidempotent operations
 - \blacksquare Reply received? \rightarrow
 - \nearrow No reply received? \rightarrow
- We also may have to deal with orphaned requests (ones with no waiting client). We can do this by:
 - extermination, expiration, or reincarnation

Remote Procedure Call

RPC is a way to simplify IPC by modeling communication as procedure calls.

Consider calling a local procedure:

- When process A makes a call to the local subroutine X, it passes the parameters to X and the result from X is returned
- To make this into a remote procedure call:
 - Replace X with a "stub" procedure that packages up the parameters and sends them to the RPC server on remote machine
 - RPC server then calls X on the remote machine and packages up the return value and transmits it back to A



- 1. local routine calls procedure (stub) X.
- 2. stub X packs up the arguments, and sends them to the communication process.
- 3. communication process transfers the arguments to the communication process on the remote machine.
- 4. remote communications process "replies" the request to RPC server.
- 5. RPC server calls procedure X (the real one, not the stub).
- 6. Procedure X returns to RPC server.
- 7. RPC server sends the results back to the remote communication process.
- 8. remote communication process transfers results back to the local communication process.
- 9. local communication process "replies" the result to the stub X.
- 10. stub X unpacks the results and returns them to the local routine.

Problems with RPC

- Parameters must be passed using strictly machineindependent data structures
- Passing pointers is a big problem because machines do not typically share memory address space
 - Pointer value is meaningless on remote machine!


Some possible solutions to this:

- Copy the data pointed to by the pointer, and restore the new data on return
- Disallow passing of pointers for RPC calls
- Have standardized external memory address space representation

Administrator Model of IPC


If we have many clients sending requests to a server, then we can run into a problem if the server is doing blocking operations, or other long operations. In this case the clients will possibly have to wait a long while for a response.

Solution: use worker processes to do the blocking and/ or long operations



Administrator Model of IPC

- The server communicates with the workers using Send/Receive/Reply style IPC
- Server cannot "send" to a worker as that would make the server block until a reply was received. Instead:



- Server "replies" to worker, and worker "sends" results of the operation, and/or an indication of readiness
- Worker blocks until server "replies" with more work to do


Administrator Model of IPC

- The administrator (server) can create new workers as needed to handle the load, or destroy workers if they are no longer needed (to save resources)
- Typically, the administrator runs the following:

Client-Server Communication: Sockets

- A socket is defined as an endpoint for communication
- Concatenation of IP address and port
- The socket 161.25.19.8:1625 refers to port 1625 on host 161.25.19.8
- Communication consists between a pair of sockets

Socket Communication




Client-Server Communication: Pipes

- Acts as a conduit allowing two processes to
 communicate basically a form of IPC
- Issues underlying system creates pipeline
 - Is communication unidirectional or bidirectional?
 - In the case of two-way communication, is it half or full-duplex?
 - Must there exist a relationship (i.e. parent-child) between the communicating processes?
 - Can the pipes be used over a network?

Ordinary Pipes

- Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
- Consumer reads from the other end (the read-end of the pipe
- Ordinary pipes are unidirectional
- Requires parent-child relationship between communicating processes

Ordinary Pipes



Named Pipes

- Named Pipes are more powerful than ordinary pipes
- Communication is bidirectional
- No parent-child relationship is necessary between the communicating processes
- Several processes can use the named pipe for communication
- Provided on both UNIX and Windows systems