# For FHICT Reports That Actually Look Good

A Typst Template to Save Your Sanity - Version 1.1.3

O RLY?

# Contents

1.	Intro	duction	3					
2.	Licen	License 3						
3.	Versi	sioning						
4.	Impo	mporting 3						
5.	Requ	Requirements						
6.	Main	Function	4					
	6.1.	title	4					
	6.2.	subtitle	4					
	6.3.	language	4					
	6.4.	available-languages						
	6.5.	date						
	6.6.	authors-title	5					
	6.7.	authors	5					
	6.8.	assessors-title	6					
	6.9.	assessors						
		version-history						
		glossary-terms						
		glossary-front						
		bibliography-file						
		citation-style						
		toc-depth						
		disable-toc						
		disable-chapter-numbering						
		disable-version-on-cover						
		chapter-on-new-page						
		pre-toc						
		table-of-figures						
		table-of-listings						
		table-of-tables						
		appendix						
		watermark						
		censored						
		line-numbering						
		line-numbering-scope						
		print-extra-white-page						
		secondary-organisation-color						
		secondary-organisation-logo						
		enable-index						
		index-columns						
7.	-	er functions						
		hlink						
	7.2.	sensitive						
	7.3.	ftable						
	7.4.	set-code-line-nr						
	7.5.	text-box						
	7.6.	lined-box	16					

## 1. Introduction

Welcome to the FHICT Typst Document Template manual. This manual is designed to help you understand and utilize the features of the Typst document template tailored for FHICT (Fontys Hogeschool ICT). Whether you are a student or faculty member, this template will assist you in creating professional-looking documents with ease.

In this manual, you will find detailed explanations of the template's features, instructions on how to customize it to your needs, and examples to guide you through the process. The goal is to make document creation as straightforward and efficient as possible, allowing you to focus on your content rather than formatting.

We hope you find this manual helpful and that it enhances your document creation experience with Typst.

## 2. License

This document template is licensed under the MIT License. You are free to use, modify, and distribute this template, provided that the original copyright notice and this permission notice are included in all copies or substantial portions of the template.

For more details, refer to the LICENSE file included in the repository.

# 3. Versioning

This template follows semantic versioning. The version number is composed of three parts: major, minor, and patch. For example, in version 1.2.3:

- The first number (1) is the major version, which changes when there are significant updates that may include breaking changes.
- The second number (2) is the minor version, which changes when updates are added in a backward-compatible manner.
- The third number (3) is the patch version, which changes when backward-compatible bug fixes or small updates to documentation are made.

# 4. Importing

To use the FHICT Typst Document Template, you need to import it into your Typst document. You can do this by including the following line at the beginning of your document:

```
1 #import "@preview/unofficial-fhict-document-template:version": *
I Typst
```

It is also possible to download the template from the GitHub repository and import it locally. In that case the import statement would look like this:

```
1 #import "path/to/lib.typ": *

    Typst
```

# 5. Requirements

To use the FHICT Typst Document Template, you need the Roboto font installed on your system. This font is used for the text in the document.

## 6. Main Function

The template can be used by calling the main function. This is done by calling the fhict-doc function with the desired parameters.

```
Example code
1 #show: fhict-doc.with(
2 ...
3 )
```

Afterwards you can add the content of the document.

```
Example code
1 #show: fhict-doc.with(
2 ...
3 )
4
5 My amazing content
```

#### 6.1. title

The title parameter is used to set the title of the document. If it is set to <u>none</u>, the title will not be displayed.

```
Example code

1 title: "FHICT Typst Document Template Manual"
```

#### 6.2. subtitle

```
⟨→ Type: string or none (*) Default: none
```

The subtitle parameter is used to set the subtitle of the document. If it is set to <u>none</u>, the subtitle will not be displayed.

```
Example code

1 subtitle: "A Detailed Guide to Typst Template"
```

## 6.3. language

```
√Type: string [**] Default: "en"
```

The language parameter is used to set the language of the document. It determines the language of the text and formatting used in the document.

```
Example code

1 language: "nl"
```

# 6.4. available-languages

```
⟨/⟩Type: array of string or none [**]Default: none
```

The available-languages parameter is used to specify the languages in which the document is available. It is an array of strings representing the language codes. If more than one language is specified, a language indicator will be displayed on the cover page to indicate the available languages. If it is set to <u>none</u>, the language indicator will not be displayed.

```
Example code
1 available-languages: ("en", "nl")
```

#### 6.5. date

```
⟨→Type: string or none (*)Default: none
```

The date parameter is used to set the date of the document. If it is set to <u>none</u>, the date will be automatically generated based on the current date.

```
Example code

1 date: "2022-01-01"
```

#### 6.6. authors-title

The authors-title parameter is used to set the title of the authors section. If it is set to <u>none</u>, the authors section will not have a title.

```
Example code

1 authors-title: "Authors"
```

#### 6.7. authors

```
⟨⟩Type: (array of (string or content) and string) or none [**]Default: none
```

The authors parameter is used to specify the authors of the document. It is an array of strings or content blocks representing the authors' names and emails. If the array is set, the names are required, and emails are optional. If it is set to none, the authors section will not be displayed.

#### 6.8. assessors-title

```
√>Type: string or none [**]Default: none
```

The assessors-title parameter is used to set the title of the assessors section. If it is set to none, the assessors section will not have a title.

```
Example code

1 assessors-title: "Helpful People"
```

#### 6.9. assessors

```
⟨¬⟩Type: (array of (string or content) and string) or none (**)Default: none
```

The assessors parameter is used to specify the assessors of the document. It is an array of strings or content blocks representing the assessors' names and emails. If the array is set, the names are required, and emails are optional. If it is set to <u>none</u>, the assessors section will not be displayed.

# 6.10. version-history

```
⟨⟩ Type: (array of 4 × (string or content)) or none [**] Default: none
```

The version-history parameter is used to specify the version history of the document. It is an array of strings or content blocks representing the version number, data, author, and changes for each version. If the array is set, all four fields are required. If it is set to <u>none</u>, the version history section will not be displayed.

The top entry is the array is the oldest version, and the bottom entry is the newest version. The version number of the most recent version will be displayed on the cover page if Section 6.18 is set to true.

```
Example code - strings

1 version-history: (
2  (
3   version: "1.0.0",
4   date: "2022-01-01",
5   author: "John Doe",
6   changes: "Initial release",
7  ),
```

```
Example code - content

1 version-history: (
2  (
3  version: [1.0.0],
4  date: [2022-01-01],
5  author: [John Doe],
6  changes: [Initial release],
7  ),
```

# 6.11. glossary-terms

```
√>Type: dictionary or none (**)Default: none
```

The glossary-terms parameter is used to specify the glossary terms for the document. It should follow the format dictated by <u>Glossarium</u>.

```
Typst
Example code
1 glossary-terms: term-list
                                                                              Typst
Example code - terms list
   #let term-list = (
2
3
       key: "fhict",
4
       short: [FHICT],
5
       long: [Fontys Hogeschool ICT],
6
       description: [Fontys University of Applied Sciences],
7
       plural: [FHICTs],
8
       longplural: [Fontys Hogescholen ICT],
9
       group: [Education],
10
11 )
```

# 6.12. glossary-front

```
√Type: bool {*}Default: false
```

The glossary-front parameter is used to specify whether the glossary should be displayed at the front of the document. If set to true, the glossary will be displayed at the beginning of the document, else it will be displayed at the end.

```
Example code

1 glossary-front: true
```

# 6.13. bibliography-file

```
√ Type: bibliography or none [**] Default: none
```

The bibliography-file parameter is used to specify the bibliography file for the document. This should be done using the built in <u>bibliography</u> function. The file itself should be a <u>BibTeX</u> file.

```
Example code
1 bibliography-file: bibliography("my-sources.bib")
```

# 6.14. citation-style

⟨→⟩Type: string (\*\*)Default: "ieee"

The citation-style parameter is used to specify the citation style for the document. It determines the format in which citations are displayed.



# 6.15. toc-depth

√ Type: int (\*) Default: 3

The toc-depth parameter is used to specify the depth of the table of contents (TOC) in the document. It determines how many levels of headings are included in the TOC.



## 6.16. disable-toc

✓ Type: bool [\*\*] Default: false

The disable-toc parameter is used to specify whether the table of contents (TOC) should be disabled in the document. If set to true, the TOC will not be generated.



# 6.17. disable-chapter-numbering

✓ Type: bool {\*}Default: false

The disable-chapter-numbering parameter is used to specify whether chapter numbering should be disabled in the document. If set to true, chapters will not be numbered.



#### 6.18. disable-version-on-cover

✓ Type: bool {\*}Default: false

The disable-version-on-cover parameter is used to specify whether the version number should be displayed on the cover page. If set to true, the version number will not be displayed.



# 6.19. chapter-on-new-page

```
✓ Type: bool [**] Default: false
```

The chapter-on-new-page parameter is used to specify whether each top level chapter should start on a new page. If set to true, each chapter will begin on a new page.



## 6.20. pre-toc

```
⟨/⟩Type: content or none (*)Default: none
```

The pre-toc parameter is used to specify content that should be displayed before the table of contents (TOC) in the document. It can be used to add introductory content or other information. The chapters that are added to the pre-toc will not be included in the TOC.

```
Example code
1 pre-toc: [
2 = Introduction
3
4 This is the introduction to the document.
5 ]
```

# 6.21. table-of-figures

```
√Type: bool {*}Default: false
```

The table-of-figures parameter is used to specify whether a table of figures should be generated in the document. If set to true, a list of figures will be included in the document.

```
Example code

1 table-of-figures: true
```

#### 6.22. table-of-listings

```
√Type: bool {*}Default: false
```

The table-of-listings parameter is used to specify whether a table of listings should be generated in the document. If set to true, a list of code listings will be included in the document.



# 6.23. table-of-tables

✓ Type: bool [\*\*] Default: false


The table-of-tables parameter is used to specify whether a table of tables should be generated in the document. If set to true, a list of tables will be included in the document.



# 6.24. appendix

⟨→⟩Type: content or none (\*)Default: none

The appendix parameter is used to specify content that should be included in the appendix of the document. It can be used to add additional information, references, or other content. The chapters that are added to the appendix will be included in the TOC under the appendix section.



#### 6.25. watermark

⟨⟩Type: string or none (\*)Default: none

The watermark parameter is used to set a watermark text that will be displayed on each page of the document. If it is set to <u>none</u>, no watermark will be displayed.



#### 6.26. censored

√ Type: int [\*\*] Default: 0

The censored parameter is used to specify wether the sensitive (Section 7.2) should be censored in the document. If set to 1, the sensitive content will be censored.



# 6.27. line-numbering

✓ Type: bool [\*\*] Default: false

The line-numbering parameter is used to specify whether line numbering should be enabled in the document. If set to true, line numbers will be displayed in the document.



# 6.28. line-numbering-scope

√>Type: string [\*\*]Default: "page"

The line-numbering-scope parameter is used to specify the scope of line numbering in the document. It determines where the count is reset.

Options are:

- "page": Line numbers are reset on each page.
- "document": Line numbers are continuous throughout the document.

For more (and more up to date) information on the options, see the <u>Typst documentation</u>.



# 6.29. print-extra-white-page

The print-extra-white-page parameter is used to specify whether an extra white page should be added at the end of a chapter¹ to make sure each chapter starts facing the reader in the case of a printed document.

This feature is mostly intended for documents that will be printed and bound.



# 6.30. secondary-organisation-color

⟨→Type: color or none (\*\*)Default: none

The secondary-organisation-color parameter is used to set the color of an organisation's logo or other elements in the document that is not Fontys. It will be used on the cover page.

```
Example code
1 secondary-organisation-color: rgb("FF0000")
```

<sup>&</sup>lt;sup>1</sup>Currently only at the end of each section added by the template. Such as the table of contents, list of figures, etc.

# 6.31. secondary-organisation-logo

⟨/⟩Type: <u>image</u> or <u>none</u> [\*\*]Default: none

The secondary-organisation-logo parameter is used to set the logo of an organisation that is not Fontys. It will be displayed on the cover page.

Example code
1 secondary-organisation-logo: image("secondary-logo.png", width: 100px)

#### 6.32. enable-index

The enable-index parameter is used to specify whether an index should be generated in the document. If set to true, an index will be included in the document.

The index entries should be set using the index and index-main functions from In Dexter.

Example code

1 enable-index: true

#### 6.33. index-columns

√Type: int [\*\*] Default: 2

The index-columns parameter is used to specify the number of columns in the index. It determines how the index entries are displayed.

Example code

1 index-columns: 3

# 7. Helper functions

# 7.1. hlink

Parameters: string(url), content(text)

This function is used to create a styled hyperlink. The url parameter specifies the URL to link to, and the text parameter specifies the text to display as the link.

```
Example code
1 #hlink("https://typst.app/", content: [Typst])
```

Which will look like this:

<u>Typst</u>

#### 7.2. sensitive

⟨→Parameters: string(text)

This function is used to mark content as sensitive. The content will be censored if the censored parameter is set to 1.

```
Example code

1 #sensitive("This is sensitive content")
```

If the censored parameter is set to 0, the content will not be censored. It will end up looking like this:

This is sensitive content

If the censored parameter is set to 1, the content will be censored. It will end up looking like this:

#### 7.3. ftable

```
Parameters: <u>int(style)</u>, <u>array(columns)</u>, <u>content(content)</u>
```

The ftable function is the same as a normal table function, except it only takes 2 parameters and one custom parameter. The ftable parameter takes the columns and content parameters, just like the normal table function. The style parameter is used to set the style of the table. The available styles are 1 through 7.

```
Example code
1 #ftable(
2 columns: (auto, auto, auto, 1fr),
3 [Header 1], [Header 2], [Header 3], [Header 4],
4 [Cell 1], [Cell 2], [Cell 3], [Cell 4],
5 [Cell 1], [Cell 2], [], [Cell 4],
6 ),
```

Which will look like this:

Header 1	Header 2	Header 3	Header 4
Cell 1	Cell 2	Cell 3	Cell 4
Cell 1	Cell 2		Cell 4

#### 7.4. set-code-line-nr

```
\(\sigma\) Parameters: <u>int</u>(line)
```

This function is a helper function for the codly function. It is intended to simplify the process of setting the line number for code blocks.

```
Example code
1 #set-code-line-nr(start: 5)

Which will look like this:
5 #set-code-line-nr(5)

I Typst
```

You *will* need to call this function again if you want to change the line number. It does not reset the line number for the next code block.

#### 7.5. text-box

Parameters: <a href="mailto:color">color</a>(background-color), <a href="mailto:color">color</a>(stroke-color), <a href="mailto:color">color</a>(text-color), <a href="mailto:content">color</a>(content)

All values except for the content parameter are optional.

The text-box function is used to create a styled text box. The background-color parameter specifies the background color of the box, the stroke-color parameter specifies the color of the box's border, and the text-color parameter specifies the color of the text inside the box.



Which will look like this:

Hi there

#### 7.6. lined-box

Parameters: string(title), content(body), color(line-color)

The lined-box function is used to create a styled box with a title and body. The title parameter specifies the title of the box, the body parameter specifies the content of the box, and the line-color parameter specifies the color of the line surrounding the box, as well as the text color.

