# **Kernel Pwn Cheat Sheet**

- Kernel version
- · Kernel config
- Process management
  - task struct
  - current
- Syscall
- · Memory allocator
  - kmem cache
  - kmem cache create
  - kmalloc
  - kfree
- Physmem
- Paging
- <u>Usercopy</u>
- Symbol
- Snippet
- Structures
  - Idt struct
  - shm file data
  - seq operations
  - msg msg, msg msgseg
  - subprocess info
  - timerfd ctx
  - pipe buffer
  - tty struct
  - setxattr
  - sk buff
- Variables
  - modprobe path
  - core pattern
  - poweroff cmd
  - n tty ops

#### **Kernel version**

commit 09688c0166e76ce2fb85e86b9d99be8b0084cdf9 (HEAD -> master, tag: v5.17-rc8, origin/master, origin/HEAD)

Author: Linus Torvalds <torvalds@linux-foundation.org>

Date: Sun Mar 13 13:23:37 2022 -0700

Linux 5.17-rc8

# **Kernel config**

| config          | path                           |  |
|-----------------|--------------------------------|--|
| CONFIG_KALLSYMS | /proc/sys/kernel/kptr_restrict |  |

| CONFIG_USERFAULTFD            | /proc/sys/vm/unprivileged_userfaultfd      |
|-------------------------------|--|
| CONFIG_STATIC_USERMODEHELPER  |  |
| CONFIG_SLUB                   |  |
| CONFIG_SLAB                   |  |
| CONFIG_SLAB_FREELIST_RANDOM   |  |
| CONFIG_SLAB_FREELIST_HARDENED |  |
| CONFIG_HAVE_STACKPROTECTOR    |  |
| CONFIG_RANDOMIZE_BASE         |  |
| CONFIG_HARDENED_USERCOPY      |  |
| CONFIG_SMP                    |  |
| CONFIG_BPF                    | /proc/sys/kernel/unprivileged_bpf_disabled |
| CONFIG_FG_KASLR               |  |

# **Process management**

### task\_struct

- task struct
  - thread info
    - syscall\_work
  - cred
  - tasks
    - init task
      - init cred
  - comm
    - prctl(PR\_SET\_NAME, name);
  - thread struct
- start kernel
  - cred init
  - fork init
    - task struct whitelist
      - arch thread struct whitelist
        - fpu thread struct whitelist

#### current

- current
  - get current
    - current task
      - DECLARE PER CPU
        - DECLARE PER CPU SECTION

- PCPU ATTRS
  - case CONFIG\_SMP
    - PER CPU BASE SECTION
- this cpu read stable
  - pcpu size call return
    - this cpu read stable 8
      - percpu stable op
        - case CONFIG SMP
          - movq %%gs:%P[var], %[val] where var = &current\_task

- start\_kernel
  - setup per cpu areas
    - case CONFIG\_SMP
      - per cpu offset
      - per\_cpu\_offset[cpu] = pcpu\_base\_addr \_\_per\_cpu\_start +
        pcpu\_unit\_offsets[cpu]
    - switch to new gdt
      - load percpu segment
        - cpu kernelmode gs base
          - fixed percpu data
            - DECLARE PER CPU FIRST
            - fixed percpu data
          - per cpu
            - case CONFIG\_SMP
              - per cpu ptr
                - SHIFT PERCPU PTR
                  - RELOC HIDE
          - case CONFIG\_SMP
            - gs = &fixed\_percpu\_data.gs\_base +
              \_\_per\_cpu\_offset[cpu]

## **Syscall**

- entry SYSCALL 64
  - pt regs
    - pt\_regs may be use for stack pivoting
  - o do syscall 64
    - add\_random\_kstack\_offset();
    - syscall enter from user mode
      - syscall enter from user work
        - syscall trace enter
          - SYSCALL\_WORK\_SECCOMP

- do syscall x64
- swapgs restore regs and return to usermode

# **Memory allocator**

#### kmem\_cache

- case CONFIG SLUB
  - kmem\_cache
    - kmem cache cpu
      - freelist
      - <u>slab</u>
        - slab\_cache
        - freelist
    - offset
    - random
    - kmem cache node
- case CONFIG\_SLAB
  - kmem cache
    - array cache
      - entry
    - kmem cache node
      - shared

### kmem\_cache\_create

- kmem cache create
  - useroffset = 0
  - usersize = 0
  - kmem cache create usercopy
    - create cache
      - case CONFIG\_SLUB
        - kmem cache create
          - kmem cache open
            - calculate order
              - calculate sizes
                - <u>oo make</u>
                  - order objects
      - case CONFIG\_SLAB
        - kmem cache create
          - set objfreelist slab cache
            - calculate slab order
- start kernel
  - mm init
    - kmem cache init

- useroffset = 0
- usersize = kmalloc\_info[INDEX\_NODE].size
- create kmalloc cache
  - create boot cache
    - \_\_kmem\_cache\_create

#### kmalloc

- kmalloc
  - kmalloc index
    - kmalloc index
      - case CONFIG\_SLUB
        - #define KMALLOC\_MIN\_SIZE 8
      - case CONFIG\_SLAB
        - #define KMALLOC\_MIN\_SIZE 32
  - kmalloc caches
  - kmalloc type
    - #define GFP\_KERNEL\_ACCOUNT (GFP\_KERNEL | \_\_GFP\_ACCOUNT)
    - GFP\_KERNEL → KMALLOC\_NORMAL
    - GFP\_KERNEL\_ACCOUNT → KMALLOC\_CGROUP
  - case CONFIG\_SLUB
    - kmem cache alloc trace
      - slab alloc
        - slab alloc node
          - slab alloc
            - slab alloc
              - slab = c->slab =
                slub\_percpu\_partial(c);
              - new slab
                - <u>allocate slab</u>
                  - alloc slab page
                  - shuffle freelist
          - get\_freepointer\_safe
            - freelist ptr
              - swab
                - swab
                  - swab64
                    - constant swab64

- case CONFIG\_SLAB
  - kmem cache alloc trace
    - slab alloc
      - do cache alloc
        - cache alloc
          - cache alloc refill

- cache alloc node
  - cache grow begin
    - kmem\_getpages
      - alloc pages node
    - cache init objs
      - shuffle freelist

#### kfree

- case CONFIG\_SLUB
  - kfree
    - virt to folio
      - virt to page
        - pa
          - phys\_addr
            - phys addr nodebug
              - x \_\_START\_KERNEL\_map +
                \_\_START\_KERNEL\_map PAGE\_OFFSET
              - PAGE OFFSET
                - case

CONFIG\_DYNAMIC\_MEMORY\_LAYOUT

- PAGE OFFSET
  - page\_offset\_base
- pfn\_to\_page
  - pfn to page
    - vmemmap
      - VMEMMAP START
        - vmemmap\_base
- page\_folio
  - compound head
    - pageflags
- folio slab
- slab\_free
  - do slab free
    - likely(slab == c->slab) → likely(slab == slab->slab\_cache->cpu\_slab->slab)
    - set\_freepointer
      - BUG\_ON(object == fp);
    - slab free
      - put\_cpu\_partial(s, slab, 1);
- case CONFIG\_SLAB
  - kfree

- cache free
  - cache flusharray
  - free one
    - WARN\_ON\_ONCE(ac->avail > 0 && ac->entry[ac->avail 1] == objp)

## **Physmem**

- page tables
  - page\_offset\_base
    - heap base address (by kmalloc) and it is mapped to /dev/mem
    - secondary\_startup\_64 can be found at page\_offset\_base + offset
  - vmalloc\_base
  - vmemmap\_base
    - base address of <u>pages</u>

## **Paging**

- CR3 , Page Global Directory , Page Upper Directory , Page Middle Directory , Page Table Entry are used
- each register or variable holds an encoded pointer, not a raw pointer
- the 12~51 bits of each register or valiable indicates the base address of the next directory
- see <u>5.3.3 4-Kbyte Page Translation / AMD64 Architecture Programmer's Manual, Volume 2</u> for details
- last byte of Page Global Directory(PML4E) often be 0x67(0b01100111)

#### **Usercopy**

- · copy from user
  - check copy size
    - case CONFIG\_HARDENED\_USERCOPY
      - check object size
        - check object size
          - check heap object
            - case CONFIG\_HARDENED\_USERCOPY
              - case CONFIG SLUB
                - check heap object
              - case CONFIG\_SLAB
                - check heap object
            - otherwise
              - check heap object
            - check page span
    - otherwise
      - check object size
- · copy to user
  - check\_copy\_size

# **Symbol**

- EXPORT SYMBOL
  - EXPORT SYMBOL
    - EXPORT SYMBOL
      - cond export sym
        - cond export sym
          - cond export sym 1
            - EXPORT SYMBOL
              - KSYMTAB ENTRY
                - RO\_DATA
- kernel symbol value
  - offset to ptr

## **Snippet**

- · gain root privileges
  - (kernel) commit\_creds(prepare\_kernel\_cred(NULL));
- break out of namespaces
  - (kernel) switch\_task\_namespaces(find\_task\_by\_vpid(1), init\_nsproxy);
  - (user) setns(open("/proc/1/ns/mnt", O\_RDONLY), 0);
  - o (user) setns(open("/proc/1/ns/pid", 0\_RDONLY), 0);
  - o (user) setns(open("/proc/1/ns/net", 0\_RDONLY), 0);

### **Structures**

| structure       | size          | flag (v5.14+)      | memo                    |
|-----------------|---------------|--------------------|-------------------------|
| ldt_struct      | 16            | GFP_KERNEL_ACCOUNT |                         |
| shm_file_data   | 32            | GFP_KERNEL         |                         |
| seq_operations  | 32            | GFP_KERNEL_ACCOUNT | /proc/self/stat         |
| msg_msg         | 48 ~ 4096     | GFP_KERNEL_ACCOUNT |                         |
| msg_msgseg      | 8 ~ 4096      | GFP_KERNEL_ACCOUNT |                         |
| subprocess_info | 96            | GFP_KERNEL         | socket(22, AF_INET, 0); |
| timerfd_ctx     | 216           | GFP_KERNEL         |                         |
| pipe_buffer     | 640 = 40 x 16 | GFP_KERNEL_ACCOUNT |                         |
| tty_struct      | 696           | GFP_KERNEL         | /dev/ptmx               |
| setxattr        | 0 ~           | GFP_KERNEL         |                         |
| sk_buff         | 320 ~         | GFP_KERNEL_ACCOUNT |                         |

#### **Idt\_struct**

- modify\_ldt
  - write ldt
    - #define LDT\_ENTRIES 8192
    - #define LDT\_ENTRY\_SIZE 8
    - alloc ldt struct
  - read\_ldt
    - desc\_struct
    - copy\_to\_user
      - copy\_to\_user won't panic the kernel when accessing wrong address

#### shm file data

- shmat
  - do shmat

#### seq\_operations

- proc stat init
  - stat proc ops
- stat open
  - single open size
    - single open
- seq read iter
  - m->op->start

#### msg msg, msg msgseg

- msg\_queue
  - $\circ$  q\_messages  $\rightarrow$  msg\_msg
- msgsnd
  - ksys msgsnd
    - do msgsnd
      - load msg
        - alloc msg
- msgrcv
  - ksys msgrcv
    - msg\_handler = do\_msg\_fill
    - do msgrcv
      - find msg
        - testmsg
      - #define MSG\_COPY 040000
      - copy msg
      - do msg fill
        - store msg

### subprocess\_info

- socket
  - sys socket
    - sock\_create
      - sock create
        - request\_module
          - call modprobe
            - call usermodehelper setup

#### timerfd\_ctx

- timerfd create
- · timerfd release
  - kfree\_rcu

### pipe\_buffer

- pipe, pipe2
  - do\_pipe2
    - do pipe flags
      - create pipe files
        - get\_pipe\_inode
          - alloc pipe info
            - #define PIPE\_DEF\_BUFFERS 16
        - pipefifo\_fops
- pipe write
  - o buf->ops = &anon\_pipe\_buf\_ops;
- pipe\_release
  - put pipe info
    - free pipe info
      - pipe buf release
        - ops->release

#### tty\_struct

- unix98 pty\_init
  - tty\_default\_fops
    - tty\_fops
- ptmx\_open
  - tty init dev
    - alloc tty struct
- tty\_ioctl
  - tty paranoia check
    - #define TTY\_MAGIC 0x5401
  - tty pair get tty
  - tty->ops->ioctl

#### setxattr

- <u>setxattr</u>
  - path\_setxattr
    - setxattr
      - vfs\_setxattr may fail, but kvmalloc and kvfree complete successfully

#### sk\_buff

- socketpair
  - sys socketpair
    - sock create
      - sock create
        - case PF UNIX
          - unix family ops
            - unix create
              - case SOCK\_DGRAM
                - unix dgram ops
              - unix\_create1
                - sk->sk\_allocation =
                  GFP\_KERNEL\_ACCOUNT;
- unix dgram sendmsg
  - sock alloc send pskb
    - alloc skb with frags
      - alloc skb
        - alloc skb
          - struct skb\_shared\_info is at the end of data

## **Variables**

| variable      | memo                          |
|---------------|-------------------------------|
| modprobe_path | /proc/sys/kernel/modprobe     |
| core_pattern  | /proc/sys/kernel/core_pattern |
| poweroff_cmd  |                               |
| n_tty_ops     | (read) scanf, (ioctl) fgets   |

### modprobe\_path

- <u>execve</u>
  - do\_execve
    - do execveat common
      - <u>bprm\_execve</u>
        - exec\_binprm

- search\_binary\_handler
  - request module
    - call modprobe
      - call usermodehelper setup
      - call usermodehelper exec

### core\_pattern

- do coredump
  - format corename
  - <u>call\_usermodehelper\_setup</u>
  - call usermodehelper exec

#### poweroff\_cmd

- orderly poweroff
  - poweroff work func
    - orderly poweroff
      - run cmd
        - <u>call\_usermodehelper</u>
          - call usermodehelper setup
          - call\_usermodehelper\_exec

### n\_tty\_ops

- tty struct
  - tty\_ldisc
- n tty init
  - tty register Idisc