

Lab – NETCONF w/Python: Device Configuration

Objectives

Part 1: Retrieve the IOS XE VMs' existing running configuration

Part 2: Update the device's configuration

Background / Scenario

In this lab, you will learn how to use the NETCONF ncclient to retrieve the device's configuration, update and create new interface configuration. You will also learn why the transactional support of NETCONF is important for getting consistent network changes.

Required Resources

- Access to a router with the IOS XE operating system version 16.6 or higher
- Python 3.x environment


Part 1: Retrieve the IOS XE VMs' existing running configuration

In this part, you will use the ncclient module to retrieve the device's running configuration. The data are returned back in XML form that in the following steps is being transformed into more human readable format.


Step 1: Use ncclient to retrieve the device's running configuration.

The ncclient module provides a "manager" class with "connect()" function to setup the remote NETCONF connection. After a successful connection, the returned object represents the NETCONF connection to the remote device.

a. In Python IDLE, create a new Python script file:



b. In the new Python script file editor, import the "manager" class from the ncclient module:



c. Setup an m connection object using the manager.connect() function to the IOS XE device.

```
m = manager.connect(
    host="192.168.56.101",
    port=830,
    username="cisco",
    password="cisco123!",
    hostkey_verify=False
)
```

The parameters of the manager.connect() function are:

- host the address (host or IP) of the remote device (adjust the IP address to match the router's current address)
- port the remote port of the ssh service
- username remote ssh username (in this lab "cisco" for that was setup in the IOS XE VM)
- password remote ssh password (in this lab "cisco123!" for that was setup in the IOS XE VM)
- hostkey_verify whether to verify the ssh fingerprint (in lab it is safe to set to False, in production environments you should always verify the ssh fingerprints)
- d. After a successful NETCONF connection, using the "get_config()" function of the "m" NETCONF session object retrieve and print the device's running configuration. The get_config() function expects a "source" string parameter that defines the source NETCONF data-store.

```
netconf_reply = m.get_config(source="running")
print(netconf reply)
```


e. Execute the Python script and explore the output:

```
Python 3.6.5 Shell
                                                                           File Edit Shell Debug Options Window Help
Python 3.6.5 (v3.6.5:f59c0932b4, Mar 28 2018, 17:00:18) [MSC v.1900 64 bit (AMD6 ^
4)] on win32
Type "copyright", "credits" or "license()" for more information.
 RESTART: B:/DevNetAcad PS-E/Workshops/ETW3 Model Driven Programmability/Python
Files with Solutions/idle/lab 2.6.pv
<?xml version="1.0" encoding="UTF-8"?>
 <rpc-reply xmlns="urn:ietf:params:xml:ns:netconf:base:1.0" message-id="urn:uuid:</pre>
81113496-5a8d-4b28-be4e-8018302ef71f" xmlns:nc="urn:ietf:params:xml:ns:netconf:b
ase:1.0"><data><native xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native"><ver
sion>16.6/version><boot-start-marker/><boot-end-marker/><service><timestamps><d
ebug><datetime><msec></msec></datetime></debug><log><datetime><msec/></datetime>
</log></timestamps></service><platform><console xmlns="http://cisco.com/ns/yang/
Cisco-IOS-XE-platform"><output>virtual</output></console></platform><hostname>CS
R1kv</hostname><username><name>cisco</name><privilege>15</privilege><password><e
ls><routing-protocol><type>static</type><name>l</name></routing-protocol></routi
ng-protocols></routing-instance></routing></data></rpc-reply>
                                                                         Ln: 6 Col: 6545
```

Step 2: Use CodeBeautfiy.com to evaluate the response

Code Beautify maintains a website for viewing code in a more human readable format. The XML viewer URL is https://codebeautify.org/xmlviewer

- f. Copy the XML from IDLE to XML Viewer.
- g. Click Tree View or Beautify / Format to render the raw XML output into a more human readable format.



To simplify the view, close the XML elements that are under the rpc-reply/data structure:

```
₾ 🔀
                      Result: Beautify XML
 1 <?xml version="1.0" encoding="UTF-8"?>
 2 * <rpc-reply
        xmlns="urn:ietf:params:xml:ns:netconf:base:1.0" message-id="urn:uuid
 3
           :81113496-5a8d-4b28-be4e-8018302ef71f"
       xmlns:nc="urn:ietf:params:xml:ns:netconf:base:1.0">
 4
 5 +
       <data>
 61
           <native <pre>
186
           <interfaces <=> /interfaces>
289
           <network-instances</pre>
350
           <interfaces <pre>
398
           <routing</pre>
412
        </data>
413 </rpc-reply>
```

i. Note that the rpc-reply/data/native element when opened, it contains an attribute xmlns that points to "Cisco-IOS-XE-native" YANG model. That means this part of the configuration is Cisco Native for IOS XE.

j. Also note that there are two "interfaces" elements – one with xmlns pointing to "http://openconfig.net/yang/interfaces" YANG model, while the other pointing to "ietf-interfaces" YANG model.

. . .

```
<interfaces</pre>
350 *
                  xmlns="urn:ietf:params:xml:ns:yang:ietf-interfaces">
351
352 *
                  <interface>
353
                      <name>GigabitEthernet1</name>
354 ₹
                       <type
                           xmlns:ianaift="urn:ietf:params:xml:ns:yang:iana
355
                               -if-type">ianaift:ethernetCsmacd
356
                       </type>
                      <enabled>true</enabled>
357
```

Both are used to describe the configuration of the interfaces, with a difference that the openconfig.net YANG model does support sub-interfaces, while the ietf-interfaces YANG model does not.

Step 3: Use toprettyxml() function to prettify the output.

- a. Python has built in support to work with XML files. The "xml.dom.minidom" module can be used to prettify the output with the toprettyxml() function.
- b. Import the "xml.dom.minidom" module:

```
import xml.dom.minidom
```

c. Replace the simple print function "print (netconf_reply)" with a version that prints prettified XML output:

```
print( xml.dom.minidom.parseString(netconf_reply.xml).toprettyxml() )
```

d. Execute the updated Python script and explore the output.

Step 4: Use filters to retrieve a configuration defined by a specific YANG model

- a. NETCONF has support to return only data that are defined in a filter element.
- b. Create the following netconf_filter variable that contains an XML NETCONF filter element to only retrieve data defined by the Cisco IOS XE Native YANG model:

c. Include the netconf filter variable in the get_config() call using the "filter" parameter:

```
netconf_reply = m.get_config(source="running", filter=netconf_filter)
print(xml.dom.minidom.parseString(netconf_reply.xml).toprettyxml())
```

e. Execute the updated Python script and explore the output:

```
RESTART: B:/DevNetAcad PS-E/Workshops/ETW3 Model Driven Programmability/Python
Files with Solutions/idle/lab 2.6.py
<?xml version="1.0" ?>
<rpc-reply message-id="urn:uuid:7a860e08-0447-4482-9ce6-7ed0efe2f24a" xmlns="urn</pre>
:ietf:params:xml:ns:netconf:base:1.0" xmlns:nc="urn:ietf:params:xml:ns:netconf:b
ase:1.0">
       <data>
                <native xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native">
                       <version>16.6
                       <boot-start-marker/>
                       <boot-end-marker/>
                       <service>
                                <timestamps>
                                       <debug>
                                               <datetime>
                                                       <msec/>
                                               </datetime>
                                       </debug>
                                       <log>
                                                <datetime>
                                                       <msec/>
                                               </datetime>
                                       </log>
                               </timestamps>
                        </service>
```

```
<vty>
                                         <first>5</first>
                                         <last>15</last>
                                         <login>
                                                 <local/>
                                         </login>
                                </vty>
                        </line>
                        <diagnostic xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE</pre>
-diagnostics">
                                        <level>minimal</level>
                                </bootup>
                        </diagnostic>
               </native>
        </data>
</rpc-reply>
>>>
```

Part 2: Update the device's configuration

Step 1: Create a new Python script file

- a. In IDLE create a new Python script file
- b. Import the required modules and setup the NETCONF session:

Step 2: Change the hostname

f. In order to update an existing setting in the configuration, you can extract the setting location from the configuration retrieved in Step 1:

```
1 <?xml version="1.0" encoding="UTF-8"?>
3
           :uuid:ffad8001-6b82-4094-acc4-6f456ba9e088"
       xmlns:nc="urn:ietf:params:xml:ns:netconf:base:1.0">
       <data>
           <native
              xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native">
8
               <version>16.6</version>
              <boot-start-marker/>
               <boot-end-marker/>
10
11 -
               <service>
12 -
                  <timestamps>
13 *
                     <debug>
14 =
                         <datetime>
15
                             <msec></msec>
                         </datetime>
16
17
                      </debug>
18 -
                      <log>
                         <datetime>
19 +
20
                         </datetime>
21
                      </log>
                  </timestamps>
              </service>
24
              <platform>
                  <console
                     xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE
27
                         -platform"
28
                     <output>virtual</output>
                  </console>
29
               </platform>
              khostname>CSR1kv</hostname>
31
```

- g. The configuration update is always enclosed in a "config" XML element that includes a tree of XML elements that require update.
- h. Create a netconf_data variable that holds a configuration update for the hostname element as defined in the Cisco IOS XE Native YANG Model:

** ** **

- i. Edit the existing device configuration with the "edit_config()" function of the "m" NETCONF session object. The edit config() function expects two parameters:
 - target the target netconf data-store to be updated
 - config the configuration update

The <code>edit_config()</code> function returns an XML object containing information about the change success. After editing the configuration, print the returned value:

```
netconf_reply = m.edit_config(target="running", config=netconf_data)
print(xml.dom.minidom.parseString(netconf reply.xml).toprettyxml())
```

- Before executing the new Python script, check the current hostname by connecting to the console of the IOS XE VM.
- k. Execute the Python script and explore the output:

```
>>>
RESTART: B:/DevNetAcad PS-E/Workshops/ETW3 Model Driven Programmability/Python
Files with Solutions/idle/lab 2.6 part 2.py
<?xml version="1.0" ?>
<rpc-reply message-id="urn:uuid:a622edaf-f506-4863-abbe-42ce0994e32a" xmlns="urn
:ietf:params:xml:ns:netconf:base:1.0" xmlns:nc="urn:ietf:params:xml:ns:netconf:b
ase:1.0">
</krec-reply>
>>> |
```

 After executing the Python script, if the reply contained the <ok/> element, verify whether current hostname has been changed by connecting to the console of the IOS XE VM.

Step 3: Create a loopback interface

m. Update the netconf_data variable to hold a configuration update that creates a new loopback 100 interface with the IP address 100.100.100.100/24:

```
netconf data = """
<config>
 <native xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native">
  <interface>
   <Loopback>
    <name>100</name>
    <description>TEST1</description>
    <qi>>
     <address>
      cprimary>
       <address>100.100.100</address>
       \mbox{<mask>255.255.255.0</mask>}
      </primary>
     </address>
    </ip>
   </Loopback>
  </interface>
 </native>
</config>
** ** **
```

n. Add the new loopback 100 interface by editing the existing device configuration using the "edit config()" function:

```
netconf_reply = m.edit_config(target="running", config=netconf_data)
print(xml.dom.minidom.parseString(netconf reply.xml).toprettyxml())
```

- o. Before executing the updated Python script, check using "show ip int brief" and "show int desc" the existing loopback interface by connecting to the console of the IOS XE VM. Take a screenshot of the result.
- p. Execute the Python script and explore the output:

```
>>>
RESTART: B:/DevNetAcad PS-E/Workshops/ETW3 Model Driven Programmability/Python
Files with Solutions/idle/lab 2.6 part 2.py
<?xml version="1.0" ?>
```

q. After executing the Python script, if the reply contained the <ok/> element, verify whether current loopback interfaces have changed by connecting to the console of the IOS XE VM. Check using "show ip int brief" command. Take a screenshot of the result.

```
ETW-CSR1000v [Running] - Oracle VM VirtualBox
                                                                                  ×
 File Machine View Input Devices Help
SR1kv>
*May 16 03:58:16.782: %DMI-5-AUTH_PASSED: R0/0: dmiauthd: User 'cisco' authentic
ated successfully from 10.128.207.104\!:\!56037 and was authorized for \mathsf{netconf} over
ssh. External groups: PRIV15
*May 16 03:58:17.095: %DMI-5-CONFIG_I: R0/0: nesd: Configured from NETCONF/RESTC
ONF by cisco, transaction-id 194
NEWHOSTNAME>
NEWHOSTNAME>
NEWHOSTNAME>
*May 16 04:02:27.468: %DMI-5-AUTH_PASSED: RO/0: dmiauthd: User 'cisco' authentic
ated successfully from 10.128.207.104\!:\!56266 and was authorized for \mathsf{netconf} over
ssh. External groups: PRIV15
*May 16 04:02:28.129: %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback10
O, changed state to up
*May 16 04:02:28.136: %DMI-5-CONFIG_I: R0/0: nesd: Configured from NETCONF/RESTC
ONF by cisco, transaction-id 201
NEWHOSTNAME>
NEWHOSTNAME>
NEWHOSTNAME>sh ip int br
                         IP-Address
Interface
                                         OK? Method Status
                                                                             Protocol
GigabitEthernet1
                        10.128.207.132
                                         YES DHCP
                                                                             up
Loopback1
                        2.2.2.2
                                         YES manual up
                                                                             սթ
Loopback2
                        unassigned
                                         YES unset
                                                     up
                                                                             սթ
Loopback100
                        100.100.100.100 YES other
                                                     up
                                                                             up
NEWHOSTNAME>
                                                       🔯 💽 🔁 🥟 🥅 🗐 🚰 🔯 🚫 🕓 Right Ctrl
```

Step 4: Attempt to create a new loopback interface with a conflicting IP address


a. Update the netconf_data variable to hold a configuration update that creates a new loopback 111 interface with the same IP address as on loopback 100: 100.100.100.100/32:

```
netconf data = """
<config>
 <native xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native">
  <interface>
   <Loopback>
    <name>111</name>
    <description>TEST1</description>
    <ip>>
     <address>
      <primary>
       <address>100.100.100</address>
       \mbox{<mask>255.255.255.0</mask>}
      </primary>
     </address>
    </ip>
   </Loopback>
  </interface>
 </native>
</config>
```

b. Attempt to add the new loopback 111 interface by editing the existing device configuration using the "edit config()" function:

```
netconf_reply = m.edit_config(target="running", config=netconf_data)
print(xml.dom.minidom.parseString(netconf reply.xml).toprettyxml())
```

c. Before executing the updated Python script, check using "show ip int brief" and "show int desc" the existing loopback interface by connecting to the console of the IOS XE VM. Take a screenshot of the



d. Execute the Python script and explore the output:

```
>>>
RESTART: B:/DevNetAcad PS-E/Workshops/ETW3 Model Driven Programmability/Python
Files with Solutions/idle/lab 2.6 part 2.py
Traceback (most recent call last):
File "B:/DevNetAcad PS-E/Workshops/ETW3 Model Driven Programmability/Python Fi
les with Solutions/idle/lab 2.6 part 2.py", line 42, in <module>
    netconf_reply = m.edit_config(target="running", config=netconf_data)
    File "C:\Users\jjanitor\AppData\Local\Programs\Python\Python36\lib\site-packag
es\ncclient\manager.py", line 216, in execute
    raise_mode=self. raise_mode).request(*args, **kwds)
File "C:\Users\jjanitor\AppData\Local\Programs\Python\Python36\lib\site-packag
es\ncclient\operations\edit.py", line 67, in request
    return self._request(node)
ncclient.operations.rpc.RPCError: inconsistent value: Device refused one or more
commands
>>>
```

The device has refused one or more configuration settings. With NETCONF, thanks to the transactional behavior, no partial configuration change has been applied but the whole transaction was canceled.

e. After executing the Python script, verify that no configuration changes, not even partial have been applied: Check using "show ip int brief" and "show int desc" Take a screenshot of your result.

