Package 'prinvars'

January 5, 2022

Type Package
Title Principal Variables
Version 0.1.0
Description This package provides methods for reducing the number of features within a data set.
License MIT + file LICENSE
Imports methods, Rdpack
RdMacros Rdpack
Encoding UTF-8
LazyData true
<pre>URL https://github.com/Ronho/prinvars</pre>
BugReports https://github.com/Ronho/prinvars/issues
RoxygenNote 7.1.2
Collate 'block.R' 'cor.R' 'explained-variance.R' 'get-blocks.R' 'thresholding.R' 'scale.R' 'utils.R' 'pla.R' 'prinvars-package.R' Suggests testthat (>= 3.0.0) Config/testthat/edition 3
Block-class
pla
pla.drop_blocks
pla.keep_blocks
pla.show
print.pla
str,Block-method
Index 9

2 pla

ck-class	Block

Description

Class used within the package to keep the structure and information about the generated blocks.

Slots

features a vector of numeric which contains the indices of the block.

explained_varaiance a numeric which contains the variance explained of the blocks variables based on the whole data set.

is_valid a logical which indicates if the block structure is valid.

pla

Principal Loading Analysis

Description

This function performs a principal loading analysis on the given data matrix and returns the results as an object of class pla.

Usage

```
pla(
    x,
    cor = FALSE,
    scaled_ev = FALSE,
    thresholds = 0.33,
    threshold_mode = "cutoff",
    expvar = "approx",
    check = "rnc",
    ...
)
```

threshold value.

Arguments

X	a numeric matrix or data frame which provides the data for the principal loading analysis.
cor	a logical value indicating whether the calculation should use the correlation or the covariance matrix.
scaled_ev	a logical value indicating whether the eigenvectors should be scaled.
thresholds	a numeric value or list of numeric values used to determine "small" values inside the eigenvectors. If multiple values are given, a list of pla results will be returned.
threshold_mode	a character string indicating how the threshold is determined and used. cutoff indicates the usage of a threshold value. percentage indicates that the cutoff value is determined by the maximum element of each vector multiplied with the

pla 3

expvar a character string indicating the method used for calculating the explained vari-

ance. approx uses the explained variance of each eigenvector i.e. its eigenvalue.

exact uses the variance of each variable.

check a character string indicating if only rows or rows as well as columns are used to

detect the underlying block structure. rows checks if the rows fulfill the required

structure. rnc checks if rows and columns fulfill the required structure.

. . . further arguments passed to or from other methods.

Value

single or list of pla class containing the following attributes:

x a numeric matrix or data frame which equals the input of x.

c a numeric matrix or data frame which is the covariance or correlation matrix

based on the input of cov.

loadings a matrix of variable loadings (i.e. a matrix containing the eigenvectors of the

dispersion matrix).

threshold a numeric value which equals the input of thresholds.

threshold_mode a character string which equals the input of threshold_mode.

blocks a list of blocks which are identified by principal loading analysis.

See https://www.sciencedirect.com/science/article/pii/S0047259X21000324 and https://dl.acm.org/doi/10.1145/3475827.3475832 for more information.

```
## Not run:
require(AER)
data("OECDGrowth")
## the scales in OECDGrowth differ hence using the
## correlation matrix is highly recommended
pla(OECDGrowth, thresholds = 0.5) ## not recommended
pla(OECDGrowth,cor=TRUE,thresholds = 0.5)
## we obtain three blocks: (randd), (gdp85,gdp60) and
## (invest, school, popgrowth). Block 1, i.e. the 1x1 block
## (randd), explains only 5.76% of the overall variance.
## Hence, discarding this block seems appropriate.
pla_obj = pla(OECDGrowth,cor=TRUE,thresholds = 0.5)
pla.drop_blocks(pla_obj, c(1)) ## drop block 1
## Sometimes, considering the blocks we keep rather than
## the blocks we want to discard might be more convenient.
pla.keep_blocks(pla_obj, c(2,3)) ## keep block 2 and block 3
## End(Not run)
```

4 pla.drop_blocks

pla.drop_blo	cks
--------------	-----

Drop Blocks

Description

Used to pass the indices of the blocks we want to discard.

Usage

```
pla.drop_blocks(object, blocks, ...)
```

Arguments

object a pla object.

blocks a list of numeric values indicating the indices of the blocks that should be re-

moved.

... further arguments passed to or from other methods.

Value

list of the following attributes:

x a numeric matrix or data frame containing the reduced set of original variables.

cc_matrix a numeric matrix or data frame which contains the conditional dispersion matrix.

Depending on the pla procedure, this is either the conditional covariance matrix

or the conditional correlation matrix.

```
## Not run:
require(AER)
data("OECDGrowth")

pla(OECDGrowth,cor=TRUE,thresholds = 0.5)

## we obtain three blocks: (randd), (gdp85,gdp60) and
## (invest, school, popgrowth). Block 1, i.e. the 1x1 block
## (randd), explains only 5.76% of the overall variance.
## Hence, discarding this block seems appropriate.

pla_obj = pla(OECDGrowth,cor=TRUE,thresholds = 0.5)
pla.drop_blocks(pla_obj, c(1)) ## drop block 1

## End(Not run)
```

pla.keep_blocks 5

Description

Used to pass the indices of the blocks we want to keep (i.e. which we do no want to be discarded).

Usage

```
pla.keep_blocks(object, blocks, ...)
```

Arguments

object a pla object.

blocks a list of numeric values indicating the indices of the blocks that should be kept.

... further arguments passed to or from other methods.

Value

list of the following attributes:

x a numeric matrix or data frame containing the reduced set of original variables.

cc_matrix a numeric matrix or data frame which contains the conditional dispersion matrix.

Depending on the pla procedure, this is either the conditional covariance matrix

or the conditional correlation matrix.

```
## Not run:
require(AER)
data("OECDGrowth")

pla(OECDGrowth,cor=TRUE,thresholds = 0.5)

## we obtain three blocks: (randd), (gdp85,gdp60) and
## (invest, school, popgrowth). Block 1, i.e. the 1x1 block
## (randd), explains only 5.76% of the overall variance.
## Hence, discarding this block seems appropriate. Therefore,
## we keep block 2 and block 3

pla.keep_blocks(pla_obj, c(2,3)) ## keep block 2 and block 3

## End(Not run)
```

6 print.pla

pla.show

Show Function for pla S3

Description

Shows the blocks, threshold, threshold_mode and the loadings.

Usage

```
pla.show(x, ...)
```

Arguments

x a pla object.

... further arguments passed to or from other methods.

Examples

```
## Not run:
require(AER)
data("OECDGrowth")

pla_obj = pla(OECDGrowth, cor=TRUE, thresholds = 0.5)
show(pla_obj)
## End(Not run)
```

print.pla

Print Function for pla S3

Description

Prints the blocks, threshold, threshold_mode and the loadings.

Usage

```
## S3 method for class 'pla'
print(x, ...)
```

Arguments

```
x a pla object.
```

... further arguments passed to or from other methods.

show,Block-method 7

Examples

```
## Not run:
require(AER)
data("OECDGrowth")

pla_obj = pla(OECDGrowth,cor=TRUE,thresholds = 0.5)
print(pla_obj)
## End(Not run)
```

show, Block-method

Block - Show Prints the blocks structure.

Description

Block - Show

Prints the blocks structure.

Usage

```
## S4 method for signature 'Block'
show(object)
```

Arguments

object

block.

Examples

```
block <- new("Block", features = c(2, 5), explained_variance = 0.03)
print(block)</pre>
```

str,Block-method

Block - str Generic function to create a string out of the blocks structure

Description

Block - str

Generic function to create a string out of the blocks structure.

Usage

```
## S4 method for signature 'Block'
str(object)
```

Arguments

object

block.

8 str,Block-method

```
block <- new("Block", features = c(2, 5), explained_variance = 0.03)
str(block)</pre>
```

Index

```
Block-class, 2

pla, 2

pla.drop_blocks, 4

pla.keep_blocks, 5

pla.show, 6

print.pla, 6

show,Block-method, 7

str,Block-method, 7
```