

# **CSC/CPE 138 - Computer Network Fundamentals**

### Transport Layer


The presentation was adapted from the textbook: *Computer Networking: A Top-Down Approach* 8<sup>th</sup> edition Jim Kurose, Keith Ross, Pearson, 2020



- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control



Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?




receiver protocol stack



Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

https://www.youtube.com/watch?v=6n9ESFJTnHs

https://www.youtube.com/watch?v=K3axU2b0dDk





receiver protocol stack



Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket buffers








Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

#### -flow control


receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast



receiver protocol stack



- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow




TCP receiver-side buffering



- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept




TCP segment format

#### TCP connection management



before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
Socket clientSocket =
  newSocket("hostname", "port number");
```

```
application

connection state: ESTAB
connection Variables:
  seq # client-to-server
      server-to-client
  rcvBuffer size
  at server,client


network
```


```
Socket connectionSocket =
welcomeSocket.accept();
```

### Agreeing to establish a connection



#### 2-way handshake:






- Q: will 2-way handshake always work in network?
- variable delays
- retransmitted messages (e.g. req\_conn(x)) due to message loss
- message reordering
- can't "see" other side

### 2-way handshake scenarios









### 2-way handshake scenarios





### 2-way handshake scenarios





### TCP 3-way handshake



#### Client state

clientSocket = socket(AF INET, SOCK STREAM) LISTEN clientSocket.connect((serverName, serverPort) choose init seq num, x send TCP SYN msq **SYNSFNT** SYNbit=1, Seq=x send TCP SYNACK msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y)

#### Server state

serverSocket = socket(AF INET, SOCK STREAM) serverSocket.bind(('', serverPort)) serverSocket.listen(1) connectionSocket, addr = serverSocket.accept() LISTEN choose init seq num, y SYN RCVD indicates client is live **ESTAB** 

### Closing a TCP connection



- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

#### Chapter 3: roadmap



- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



### Principles of congestion control



#### Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!



congestion control: too many senders, sending too fast

flow control: one sender too fast for one receiver



#### Simplest scenario:

- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed


original data: \(\lambda\_{\text{in}}\)

Host A


infinite shared output link buffers

Host B

Q: What happens as arrival rate  $\lambda_{in}$  approaches R/2?




maximum per-connection throughput: R/2



large delays as arrival rate  $\lambda_{\text{in}}$  approaches capacity




- one router, finite buffers
- sender retransmits lost, timed-out packet
  - application-layer input = application-layer output:  $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes retransmissions :  $\lambda'_{in} \ge \lambda_{in}$






#### Idealization: perfect knowledge

sender sends only when router buffers available








#### Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost






#### Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost






**R/2** 


 $\lambda_{in}$ 



#### Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered








#### Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered




#### "costs" of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
  - decreasing maximum achievable throughput





- four senders
- multi-hop paths
- timeout/retransmit

- $\underline{Q}$ : what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?
- A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow$  0










#### another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


### Causes/costs of congestion: insights





- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream












#### Approaches towards congestion control



#### End-end congestion control:

- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



#### Approaches towards congestion control



## Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols

