1. What is locality of reference?

oms Locality of reference refers to the tendency of a Priogram to access a receively small Portion of its address.

Space at any given time. It can be temporal (repeating access to the same memory) on spatial (accessing memory) locations near trecently accessed ones).

2. What is UPE?

one & NPC (micreoprogram Counter) holds the address of the nent microinstruction to be ene cuted in a control memory during microprogrammed control.

- 3. What 15 the Use of womfc control signal?

  are womfc (wait for memory function complete) is

  a control signal used to Pacise the CPU until the memory completes the requested operation; ensuring synchromization between CPU and memory.
- 4. What is difference between memory access and memory cycle time?
- taken to access douta from a memory location.

time required between two successive memory operations (accesses), usually longer than access time.

S-two appless

Sec-Bo 41 smit novie you to so oge

to Physical address:

ans: The Virtual address generated by the CPO 15 translated to a Physical address using a memory management Unit (mmu). The most common method is Paging where the Virtual address is divided into a Page number of mapped to a frame number is the Page number is the Page table, and the Physical address is formed by combining the frame number and offset.

2. Emphain the main memorry address forment in direct, associative of set associative mapping:

· Direct mapping:

Physical Address = (Tag + Line Number + World)

Each block maps to only one cache line

## · Assosiative mapping:

Physical Address = (Tag+ World) any block can be Placed in any Couche line. This guld out box - outrosyn

Cache Stories tags and securicines all times lines in parallel.

· Set - Associative, mapping: 225min promon

Physical Address= (Tag + Set Number + World)

9013 + 19 . 19 . 5

couche is divided into sets; each set Contains several lines. A block maps to a specific set but any line in that set.

Sec-c

1. Differentiate between write through and write back policies with enample:

		memory updated later.
Conomple	protesting 5 to X:	Fostore as memory whites are treduced whites are treduced whiting 5 to 1 Updates only cache, RAM is updated on book replacement.
(3)		

2. ADD (R3), R1 - Descreibe the machine instruction using one-bus organization, with diagram:

Instruction: ADD (R3), R1 meaning: Add the value at the memorry Location Pointed to by R3 to R1.


Sequence (one bus Origanization):

a. MAR = R3 (Place address from R3 into memory Address Registera).

b. Read memory > mDR (memory) Duta Register) 200 i2100 on bobarb of suborg

c. TEMP MOR (Temporcary registor Storces memory value)

Derestonal.



## Step Action 1. PCour, MARIO, Read, Schect 4, Add, Zing 2. Zout, PCin, Winfe 3. MDRout, IRin 4. R3out, MARIO, Read 5. R1out, Yin, Winfe 6. MAMMOR Quir, Schect Y, Add, Zin

Zout, RIm, End