INScore OSC Messages Reference v.1.07

D. Fober
GRAME
Centre national de création musicale
<fober@grame.fr>

May 22, 2014

INScore makes use of the following technologies:

The GUIDOEngine http://guidolib.sf.net
The IRCAM Gesture Follower http://imtr.ircam.fr/imtr/Gesture_Follower
The Qt5 cross-platform application and UI framework
The V8 JavaScript Engine http://qt-project.org/qt5
https://code.google.com/p/v8/

INScore was initiated in the Interlude project, funded by the French National Research Agency [ANR-08-CORD-010].

Contents

1	Gen	eral format	1
	1.1	Parameters	2
	1.2	Address space	2
	1.3	Aliases	3
•			
2		nmon messages	4
	2.1	Positioning	5
		2.1.1 Absolute positioning	6
		2.1.2 Relative positioning	7
		2.1.3 Components origin	7
	2.2	Components transformations	8
	2.3	Color messages	8
		2.3.1 Absolute color messages	9
		2.3.2 The color messages	10
		2.3.3 The hsb messages	10
		2.3.4 Relative color messages	10
	2.4	The 'effect' messages	11
		2.4.1 The blur effect	11
		2.4.2 The colorize effect	12
		2.4.3 The shadow effect	12
_			
3	Tim	e management messages	13
4	The	'set' message	15
	4.1	Inline components	15
	4.2	File based components	17
5	The	'get' messages	19
6	Тур	e specific messages	20
	6.1	Pen control	20
	6.2	Brush control	21
	6.3	Width and height control	22
	6.4	Symbolic score management	23
	6.5	The 'grid' object	24

	6.6	The 'layer' object					
	6.7	The 'debug' nodes					
7	App	Application messages 26					
	7.1	Application management					
	7.2	Ports management					
	7.3	Messages forwarding					
	7.4	Application level queries					
	7.5	Application static nodes					
		7.5.1 The 'stats' nodes					
		7.5.2 The 'debug' nodes					
		7.5.3 The 'log' nodes					
8	Scen	e messages 31					
9	Laye	ers 33					
		Layers generalization					
10	Map	ping graphic space to time space 34					
	_	The 'map' message					
		The 'map+' message					
		Mapping files					
		Symbolic score mappings					
11	Synchronization 38						
	11.1	Synchronization modes					
		11.1.1 Using the master date					
		11.1.2 Synchronizing an object duration					
		11.1.3 Controlling the slave y position					
12	Sign	als and graphic signals 42					
	12.1	The 'signal' static node					
		12.1.1 Signal messages					
		12.1.2 Composing signals in parallel					
		12.1.3 Distributing data to signals in parallel					
	12.2	Graphic signals					
		12.2.1 Graphic signal default values					
		12.2.2 Parallel graphic signals					
13	Ever	its and Interaction 48					
	13.1	Events					
		13.1.1 UI events					
		13.1.2 Time events					
		13.1.3 Miscellaneous events					
	13.2	Variables					
		13.2.1 Position variables					

		13.2.2 Time variables	52
			52
		13.2.4 Message based variables	53
			53
	13.3		53
			54
14	Scri	pting	55
	14.1	Statements	55
	14.2	Messages	55
	14.3	Types	56
	14.4	Variables	56
	14.5	Message based parameters	57
	14.6	Languages	57
		14.6.1 The Javascript object	58
15	Plug		59
	15.1	1 0	59
			59
			60
	15.2		60
		1 1	60
		ϵ	61
		č	62
			63
		15.2.5 Gesture Follower Appearance	64
16	Ann	endices	65
10			65
			67
	10.2	Ecaleul tokens	01
17	Cha	inges list	69
	17.1	Differences to version 1.05	69
	17.2	Differences to version 1.03	69
	17.3	Differences to version 1.0	69
	17.4	Differences to version 0.98	70
	17.5	Differences to version 0.97	70
	17.6	Differences to version 0.96	71
	17.7	Differences to version 0.95	71
	17.8	Differences to version 0.92	71
	17.9	Differences to version 0.91	71
	17.10	Differences to version 0.90	71
	17.1	1 Differences to version 0.82	71
	17.12	2Differences to version 0.81	72
	17.13	3Differences to version 0.80	72
	17.14	4Differences to version 0.79	72

17.15 Differences to version 0.78	72
17.16Differences to version 0.77	72
17.17 Differences to version 0.76	73
17.18 Differences to version 0.75	73
17.19Differences to version 0.74	73
17.20Differences to version 0.63	73
17.21 Differences to version 0.60	74
17.22 Differences to version 0.55	74
17.23 Differences to version 0.53	75
17.24Differences to version 0.50	75
17.25 Differences to version 0.42	75

General format

An OSC message is made of an OSC address, followed by a message string, followed by zero to n parameters. The message string could be viewed as the method name of the object identified by the OSC address. The OSC address could be string or a regular expression matching several objects.

OSCMessage



EXAMPLE

/ITL/scene/score x 0.5

sends the message x to the object which address is /ITL/scene/score with 0.5 as parameter.

The address is similar to a Unix path and supports regular expressions as defined by the OSC specification.


NOTE A valid address always starts with /ITL that is the application address and that is also used as a discriminant for incoming messages.

OSCAddress



Identifiers may include letters, hyphen, underscore and numbers apart at first position (see lexical definition section 16.2 p.67).

identifier



Some specific nodes (like signals - see section 12.1.1) accept OSC messages without message string:

OSCMessage



1.1 Parameters

Message parameters types are the OSC types *int32*, *float32* and *OSC-string*. In the remainder of this document, they are used as terminal symbols, denoted by int32, float32 and string.

When used in a script file (see section 14), **string** should be single or double quoted when they include characters not allowed in identifiers (space, punctuation marks, etc.). If an ambiguous double or single quote is part of the string, it must be escaped using a '\'.

Parameters types policy is relaxed: the system makes its best to convert a parameter to the expected type, which depend on the message string. With an incorrect type and when no conversion is applied, an incorrect parameter message is issued.

1.2 Address space

The OSC address space is made of static and dynamic nodes, hierarchically organized as in figure 1.1:




Figure 1.1: The OSC address space. Nodes in italic/blue are dynamic nodes.

OSC messages are accepted at any level of the hierarchy:


- the application level responds to messages for application management (udp ports management, loading files, query messages).
 - It includes a static node named stats that collects information about incoming messages, a static log node that control an embedded log window and a static debug node that can be used to get debug information.
- the scene level contains *scores* that are associated to a window and respond to specific scene/window management messages. It includes three static nodes: a sync node for synchronization management, a signal node that is a container for *signals*, and a javascript node that makes the javascript engine available to OSC commands.
- the component level contains the scene objects and two static nodes:
 - a *signal* node that may be viewed as a folder containing signals
 - a sync node, in charge of the synchronization messages

Each component includes a static node named debug that provides debugging information.

• the signals level contains signals i.e. objects that accept data streams and that may be graphically rendered as a scene component (see Signals and Graphic signals section 12 p.42).

1.3 Aliases

An alias mechanism allows an arbitrary OSC address to be used in place of a real address. An alias message is provided to describe aliases:



- [1] sets OSCAlias as an alias of OSCAddress. The alias may be optionally followed by a message string which is then taken as an implied message i.e. the alias is translated to OSCAddress message.
- [2] removes OSCAddress aliases.

EXAMPLE

```
/ITL/scene/myobject alias '/1/fader1'
```


makes the object myobject addressable using the address /1/fader1.

NOTE Regular expressions are not supported by the alias mechanism and could lead to unpredictable results.

Common messages

Common messages are intended to control the graphic and the time space of the components of a scene. They could be sent to any address with the form /ITL/scene or /ITL/scene/identifier where identifier is the unique identifier of a scene component.

commonMsg



- show: shows or hides the destination object. The parameter is interpreted as a boolean value. Default value is 1.
- del: deletes the destination object.
- export: exports an object to an image file.
 - 1) exports to a full path name. The file extension is used to infer the export format. Supported extensions and formats are: pdf, bmp, gif, jpeg, png, pgm, ppm, tiff, xbm, xpm.
 - 2) exports to path/identifier.pdf.

When path is a relative path, exports to rootPath/path/identifier.pdf.

3) exports to rootPath/identifier.pdf.

When the destination file is not completely specified (third form or missing extension), there is an automatic numbering of output names when the destination file already exists.

• save: recursively saves objects states to a file. When a message list is present, only the specified attributes are saved. The filePath can be relative or absolute. When relative, an absolute path is build using the current rootPath (see application or scene current paths p.26 and p.31). The optional + parameter indicates an append mode for the write operation. The message must be sent to the address /ITL to save the whole application state.

Note: when a list of attributes is specified, unknown attributes are silently ignored.

Note: the file extension for INScore files is .inscore. INScore files dropped on the application or on a window are interpreted as script files (see section 14 p.55).

- 'PositionMsg' are absolute and relative position messages.
- 'ColorMsg' are absolute and relative color control messages.
- 'TimeMsg' are time management messages. They are described in section 3 p.13.
- 'WatchMsg' are described in section 13 p.48.

EXAMPLE

Export of a scene to a given file as jpeg at the current root path:

```
/ITL/scene export 'myexport.jpg'
```

Saving a scene to myScore.inscore at the current root path, the second form saves only the x, y and z attributes, the third form uses the append mode:


```
/ITL/scene save 'myScore.inscore'
/ITL/scene save x y z 'thePositions.inscore'
/ITL/scene save 'myScore.inscore' '+'
```

Hiding an object:

```
/ITL/scene/myObject show 0
```

2.1 Positioning


PositionMsg



Graphic position messages are absolute position or relative position messages. They can also control an object *origin* and transformations like rotation around an axis.

2.1.1 Absolute positioning





- x y: moves the x or y coordinate of a component. By default, components are centered on their x, y coordinates. The coordinates space range is [-1,1].
 - For a scene component, -1 is the leftmost or topmost position, 1 is the rightmost or bottommost position. [0,0] represents the center of the scene.
 - For the scene itself, it moves the window in the screen space and the coordinate space is orthonormal, based on the screen lowest dimension (*i.e.* with a 4:3 screen, y=-1 and y=1 are respectively the exact top and bottom of the screen, but neither x=-1 nor x=1 are the exact left and right of the screen). Default coordinates are [0,0].
- z: sets the z order of a component. z order is actually relative to the scene components: objects of high z order will be drawn on top of components with a lower z order. Components sharing the same z order will be drawn in an undefined order, although the order will stay the same for as long as they live.

Default z order is 0.

- angle: sets the angle value of a component, which is used to rotate it around its center. The angle is measured in clockwise degrees from the x axis.

 Default angle value is 0.
- scale: reduce/enlarge a component. Default scale is 1.


EXAMPLE

Moving and scaling an object:

```
/ITL/scene/myObject x -0.9
/ITL/scene/myObject y 0.9
/ITL/scene/myObject scale 2.0
```

2.1.2 Relative positioning

relPosMsg



- dx, dy, dz messages are similar to x, y, z but the parameters represent a displacement relative to the current target value.
- drotatex, drotatey, drotatez are relative rotation messages. dangle is equivalent to drotatez and is maintained only for compatibility reasons.
- dscale is similar to scale but the parameters represents a scale multiplying factor.

EXAMPLE

Relative displacement of an object:

/ITL/scene/myObject dx 0.1

2.1.3 Components origin

The origin of a component is the point $(x \circ, y \circ)$ such that the (x, y) coordinates and the $(x \circ, y \circ)$ point coincide graphically. For example, when the origin is the top left corner, the component top left corner is drawn at the (x, y) coordinates.

originMsg



- xorigin, yorigin are relative to the component coordinates space i.e. [-1,1], where -1 is the top or left border and 1 is the bottom or right border. The default origin is [0,0] i.e. the component is centered on its (x,y) coordinates.
- $\bullet\,$ dxorigin, dyorigin represents displacement of the current xorigin or yorigin.

EXAMPLE

Setting an object graphic origin to the top left corner.

```
/ITL/scene/myObject xorigin -1.
/ITL/scene/myObject yorigin -1.
```

2.2 Components transformations

A component tranformation specifies 2D transformations of its coordinate system. It includes shear and object rotation.

transformMsg



- rotatex rotatey rotatez: rotates the component around the corresponding axis. Parameter value expresses the rotation in degrees.
- shear transforms the component in x and y dimensions. x and y are float values expressing the transformation value in the corresponding dimension.

EXAMPLE


Rotating an object graphic on the z axis.

```
/ITL/scene/myObject rotatez 90.
```

NOTE angle and rotatez are equivalent. angle has been introduced before the transformation messages and is maintained for compatibility reasons.

2.3 Color messages


ColorMsg



Color messages are absolute or relative color control messages. Color may be expressed in RGBA or HSBA.


2.3.1 Absolute color messages

absColorMsg



red, green, blue, hue, saturation, brightness, alpha messages address a specific part of a color using the RGB or HSB scheme.

colorvalue



The value may be specified as integer or float. The data range is given in table 2.1. When the alpha component is not specified, the color is assumed to be opaque.

Component integer range		float range
red [R]	[0,255]	[-1,1]
green [G]	[0,255]	[-1,1]
blue [B]	[0,255]	[-1,1]
alpha [A]	[0,255]	[-1,1]
hue [H]	[0,360]	[-1,1] mapped to [-180,180]
saturation [S]	[0,100]	[-1,1]
brightness[B]	[0,100]	[-1,1]

Table 2.1: Color components data ranges when expressed as integer or float.

EXAMPLE

The same alpha channel specified as integer value or as floating point value:

```
/ITL/scene/myObject alpha 51
/ITL/scene/myObject alpha 0.2
```

2.3.2 The color messages


color



color sets an object color in the RGBA space. When A is not specified, the color is assumed to be opaque. Default color value is [0,0,0,255].

2.3.3 The hsb messages

hsb



hsb sets an object color in the HSBA space. When A is not specified, the color is assumed to be opaque.

2.3.4 Relative color messages

relColorMsg



- dred, dgreen, etc. messages are similar to red, green, etc. messages but the parameters values represent a displacement of the current target value.
- dcolor and dhsb are similar and each color parameter represents a displacement of the corresponding target value.

EXAMPLE

Moving a color in the RGBA space:

TL/scene/myObject dcolor 10 5 0 -10


will increase the red component by 10, the blue component by 5, and decrease the transparency by 10.

NOTE Objects that are carrying color information (images, SVG) don't respond to color change but are sensitive to transparency changes.

2.4 The 'effect' messages

The effect message sets a graphic effect on the target object.

effectMsg



- none: removes any effect set on the target object.
- blur, colorize, shadow: sets the corresponding effect. An effect always replaces any previous effect. The effect name is followed by optional specific effects parameters.

NOTE An effect affects the target object but also all the target slaves.

2.4.1 The blur effect

blurParams



Blur parameters are the blur radius and a rendering hint. The radius is an int32 value. By default, it is 5 pixels. The radius is given in device coordinates, meaning it is unaffected by scale.

blurHint



Use the performance hint to say that you want a faster blur, the quality hint to say that you prefer a higher quality blur, or the animation when you want to animate the blur radius. The default hint value is performance.

EXAMPLE

Setting a 8 pixels effect on myObject

/ITL/scene/myObject effect blur 8

2.4.2 The colorize effect

colorizeParams



Colorize parameters are a strength and a tint color. The strength is a float value. By default, it is 1.0. A strength 0.0 equals to no effect, while 1.0 means full colorization.

The color is given as a RGB triplet (see 2.3 p.8) by default, the color value is light blue (0, 0, 192).


EXAMPLE

Setting a red colorize effect on myObject with a 0.5 strength.

/ITL/scene/myObject effect colorize 0.5 200 0 0

2.4.3 The shadow effect

shadowParams



xoffset and yoffset are the shadow offset and should be given as int32 values. The default value is 8 pixels. The offset is given in device coordinates, which means it is unaffected by scale.

The color is given as a RGBA color (see 2.3 p.8) by default, the color value is a semi-transparent dark gray (63, 63, 63, 180)

The blur radius should be given as an int32 value. By default, the blur radius is 1 pixel.

EXAMPLE

Setting a shadow effect on myObject.

The shadow offset is (10,10) pixels, the color is a transparent grey (100,100,100, 50) and the blur is 8 pixels.

/ITL/scene/myObject effect shadow 10 10 100 100 100 50 8

Time management messages

Time messages control the time dimension of the score components. They could be sent to any address with the form /ITL/scene/identifier where identifier is the unique identifier string of a scene component.

timeMsg





- 1) Time is specified as a rational value d/n where 1/1 represents a whole note.
- 2) Time may be specified with a single integer, then 1 is used as implicit denominator value.
- 3) Time may be specified as a single float value that is converted using the following approximation: let f be the floating point date, the corresponding rational date is computed as f x 10000 / 10000.
- 4) Time may also be specified as a string in the form 'n/d'.
- \bullet clock: similar to MIDI clock message: advances the object date by 1/24 of quarter note.
- durClock: a clock message applied to duration: increases the object duration by 1/24 of quarter note.
- date: sets the time position of an object. Default value is 0/1.

- duration: changes the object duration. Default value is 1/1.
- ddate: relative time positioning message: adds the specified value to the object date.
- dduration: relative duration message: adds the specified value to the object duration.

EXAMPLE

Various ways to set an object date.

```
/ITL/scene/myObject date 2 1
/ITL/scene/myObject date 2 // the denominator is 1 (implied)
/ITL/scene/myObject date 0.5 // equivalent to 1/2
/ITL/scene/myObject date '1/2' // the string form
```


Similar ways to move an object date.

```
/ITL/scene/myObject clock
/ITL/scene/myObject ddate '1/96'
```

The 'set' message

The set messages can be sent to any address with the form /ITL/scene/identifier. The global form of the message is:

setMsg



It sets a scene component data.

When there is no destination for the OSC address, the component is first created before being given the message.

When the target destination type doesn't correspond to the message type, the object is replaced by an adequate object.

EXAMPLE

Setting the content of a text object.

```
/ITL/scene/myObject set txt "Hello world!"
```

Creating a rectangle with a 0.5 width and a 1.5 height.

```
/ITL/scene/myObject set rect 0.5 1.5
```

Creating a music score using a Guido Music Notation language string.

```
/ITL/scene/myObject set gmn "[ a b g ]"
```


Creating a line specified using width and angle.

```
/ITL/scene/myObject set line wa 1. 45.
```

4.1 Inline components

Format of the set message is:





- layer: a graphic layer, may be viewed as a container (see 9 p.33).
- txt: a textual component.
- html: an html component defined by an HTML string.
- gmn: a Guido score defined by a GMN string.
- gmnstream: a Guido score defined by a GMN stream (a GMN string that can be written in several times).
- svg: SVG graphics defined by a SVG string.
- graph: graphic of a signal. See section 12 p.42 for details about the graph objects data.
- fastgraph: fast rendering graphic signal. See also section 12 p.42.
- rect: a rectangle specified by a width and height. Width and height are expressed in scene coordinates space, thus a width or a height of 2 corresponds to the width or a height of the scene.
- ellipse: an ellipse specified by a width and height.


- polygon: a polygon specified by a sequence of points, each point being defined by its (x,y) coordinates. The coordinates are expressed in the scene coordinate space, but only the relative position of the points is taken into account (*i.e* a polygon $A = \{ (0,0); (1,1); (0,1) \}$ is equivalent to a polygon $B = \{ (1,1); (2,2); (1,2) \}$).
- curve: a sequence of 4-points bezier cubic curve. If the end-point of a curve doesn't match the start-point of the following one, the curves are linked by a straight line. The first curve follows the last curve. The inner space defined by the sequence of curves is filled, using the object color. The points coordinates are handled like in a polygon.
- line: a simple line specified by a point (x,y) expressed in scene coordinate space or by a width and angle. The point form is used to compute a line from (0,0) to (x,y), which is next drawn centered on the scene.
- grid: a white transparent object that provides a predefined time to graphic mapping (see section 6.5 p.24 for more details and section 10 p.34 for time to graphic relations). The parameters are int32 values representing the number of columns and rows.
- faust: a FAUST object (see section 15.1)

Note The default position of any component is [0,0]. Objects are drawn centered on their position.

Text may be specified by a single quoted string or using an arbitrary count of parameters that are converted to a single string with a space used as separator.

string int32 float32

4.2 File based components



- txtf: a textual component defined by a file.
- htmlf: an html component defined by an HTML file.

- gmnf: a Guido score defined by a GMN file.
- svgf: vectorial graphics defined by a SVG file.
- img: an image file based component. The image format is infered from the file extension.
- video: a video file based component. The video format is infered from the file extension. Note that navigation through the video is made using its date.
- file: a generic type to handle file based objects. Actually, the file type is translated into a one of the txtf, gmnf, img or video types, according to the file extension (see table 4.1).

See also: the application rootPath message (section 7 p.26) for file based objects.

EXAMPLE

Creating an image.

```
/ITL/scene/myObject set img "myImage.png"
```

Using the file type.

```
/ITL/scene/myObject set file "myImage.png"
will be translated into
/ITL/scene/myObject set img "myImage.png"
```


Table 4.1: File extensions supported by the file translation scheme.

		file extension	translated type
		.txt .text	txtf
		.htm .html	htmlf
		.gmn .xml	gmnf
		.svg	svgf
.jpg .jpeg	.png .gi	f .bmp .tiff	img
.avi	.wmv .mp	g .mpeg .mp4	video

The 'get' messages

The get messages can be sent to any valid OSC address. It is intended to query the system state. It is the counterpart of all the messages modifying this state. The result of the query is sent to the OSC output port with the exact syntax of the counterpart message. The global form of the message is:

getMsg



The get message without parameter is the counterpart of the set message. When addressed to a container (the application /ITL, a scene /ITL/scene, the signal node /ITL/scene/signal) is also distributed to all the container components.

Specific get forms may be available, depending on the component type (see sections 6.4, 7.4, 7.5.2, 11, 12.1.2, 15.1.1).

EXAMPLE

Sending the following request to an object which position is 0.3 0.5

```
/ITL/scene/myobject get x y
```

will give the following messages on outpout port:

```
/ITL/scene/myobject x 0.3
/ITL/scene/myobject y 0.5
```

Querying an object content

```
/ITL/scene/myobject get
```

will give the corresponding set message:

```
/ITL/scene/myobject set txt "Hello world!"
```

NOTE

The get width and get height messages addressed to components that have no explicit width and height (text, images, etc.) returns 0 as long as the target component has not been drew.

Type specific messages

Some of the messages are specific to the component type.

6.1 Pen control


Specific pen messages accepted by the components types $rect \mid ellipse \mid polygon \mid curve \mid line \mid graph \mid fast graph \mid grid.$

penMsg



- penColor controls the pen color. The color should be given in the RGBA space. The default value is opaque black (0 0 0 255).
- penAlpha, pendAlpha controls the pen transparency only. See section 2.3 p.8 for the expected
- penWidth controls the pen width. The default value is 0 (excepted for line objects, where 1.0 is the default value). It is expressed in arbitrary units (1 is a reasonable value).
- penStyle controls the pen style.

penstyle



The pen style default value is solid.

EXAMPLE


Setting a rectangle border width and color:

```
/ITL/scene/rect set rect 0.5 0.5
/ITL/scene/rect penWidth 2.
/ITL/scene/rect penColor 255 0 0
```

6.2 Brush control

Specific brush messages accepted by the components types rect \mid ellipse \mid polygon \mid curve \mid layer.

brushMsg



• brushStyle controls the brush style.

The brush style default value is solid. For the layer object, the brush style default value is none.

EXAMPLE


Setting a rectangle style:

```
/ITL/scene/rect set rect 0.5 0.5 /ITL/scene/rect brushStyle dense4;
```

6.3 Width and height control

Specific width and height messages accepted by the components types $\verb"rect" | ellipse" | graph | fastgraph | grid.$


widthMsg



6.4 Symbolic score management

Messages accepted by the components types gmn | gmnstream | gmnf.

scoreMsg




- page: set the score current page
- dpage: moves the score current page
- pageFormat: set the page format. The parameters are the page width and height. Note that the message has no effect when the score already includes a \pageformat tag.
- columns: for multi pages display: set the number of columns.
- rows: for multi pages display: set the number of rows.
- pageCount: a read only attribute, gives the score pages count.
- systemCount: a read only attribute, gives the number of systems on each of the score pages. The result is given as a list systems count ordered by page number (index 0 is page 1, etc.).

EXAMPLE

Displaying a multi-pages score on two pages starting at page 3:

```
/ITL/scene/myScore columns 2
/ITL/scene/myScore page 3
```

gmnstreamMsg



- write: add the stream in parameter to the global stream
- clear: reinitialize the stream

EXAMPLE


Writing a score in 3 steps:

```
/ITL/scene/myScore set gmnstream "[ c"
/ITL/scene/myScore write " d e"
/ITL/scene/myScore write " f]"
```

6.5 The 'grid' object

The grid object provides a pre-defined time to graphic mapping organized in columns and row. By default, it is not visible (white, transparent) but supports all the attributes of rectangles (color, pen, effects, etc.). Each element of a grid has a duration that is computed as the grid duration divided by the total number of elements (columns x rows) and is placed in the time space from the date 0 to the end of the grid duration.

gridMsg



- columns set the number of columns of the grid,
- rows set the number of rows of the grid,
- xborder set the horizontal spacing between the elements of the grid (default is 0.),
- yborder set the vertical spacing between the elements of the grid (default is 0.),
- order defines the time order of the elements. By default, elements are organized from left to right first and from top to bottom next (leftright). The topbottom parameter changes this order from top to bottom first and from left to right next.

EXAMPLE

Creating a 10 x 10 grid organized from top to bottom with a border:

```
/ITL/scene/grid set grid 10 10
/ITL/scene/grid xborder 3.
/ITL/scene/grid yborder 3.
/ITL/scene/grid order topbottom
```

6.6 The 'layer' object

The layer object provides a container of rectangular shape that is not drawn but creates a node to distinguish a group of objects from the rest. It can however be drawn by using the brush control (default brushStyle is 'none').

6.7 The 'debug' nodes

Each component includes a static debug nodes provided to give information about components.

debugMsg




- map is used to display the time to graphic mapping. The parameter is a boolean value. Default is 0.
- name is used to display both the object name and bounding box. The parameter is a boolean value. Default is 0.

Application messages

Application messages are accepted by the static OSC address /ITL.

7.1 Application management

ITLMsg



- quit: requests the client application to quit.
- rootPath: rootPath of an Interlude application is the default path where the application reads or writes a file when a relative path is used for this file. The default value is the user home directory. Sending the rootPath message without parameter resets the application path to its default value.
- mouse: hide or show the mouse pointer.

- default Show: changes the default show status for new objects. The default default Show value is 1.
- load: loads a file previously saved using the save message (see section 2 p.4). Note that the load operation appends the new objects to the existing scene. When necessary, it is the sender responsibility to clear the scene before loading a file.
- read: read a buffer that is expected to contain a valid inscore script.
- require: check that the current INScore version number is equal or greater to the number given as argument. The version number is given as a float value. A message is associated to the require message, which is triggered when the check fails. See section 13 p.48 for more details.
- rate: changes the time task rate. Note that null values are ignored. The default rate value is 10.
- time: sets the application current time. The time is expressed in milliseconds.
- ticks: sets the application current ticks count. The ticks count indicates the number of time tasks performed by the application.
- hello: query the host IP number. The message is intended for ITL applications discovery. Answer to the query has the following format:

IP inPort outPort errPort where IP is sent as a string and port numbers as integer values.

EXAMPLE

when sending the message:

/ITL hello


the application will answer with the following message:

/ITL 192.168.0.5 7000 7001 7003

when it runs on a host which IP number is 192.168.0.5 using the default port numbers.

7.2 Ports management

ITLPortsMsg



Changes the UDP port numbers:

- port defines the listening port number,
- outport defines the port used to send replies to queries,
- errport defines the port used to send error messages.

The int32 parameter should be a positive value in the range [1024-49150]. The default port, outport and errport values are 7000, 7001 and 7002.


NOTE

Error messages are sent as a single string.

7.3 Messages forwarding

The messages handled by the application can be forwarded to arbitrary remote hosts using the forward message. The forward message itself can't be forwarded.

ITLMsgForward



- 1) removes the set of forwarded destinations,
- 2) set a list of remote hosts for forwarding. Note that hostname can be any legal host name or IP number, optionally extended with a port number separated by a semi-colon. By default, when no port number is specified, the current application listening port number is used.

EXAMPLE

Forwarding messages to host1.adomain.org using the current application listening port number and to host2.adomain.org on port number 5100.


```
/ITL forward host1.adomain.org host2.adomain.org:5100
```

WARNING: forwarding messages to the application host results in an infinite loop with unpredictable results. Thus it is not recommended to use the local network broadcast address for forwarding unless using a different UDP port number.

7.4 Application level queries

The application supports the get messages for its parameters (see section 5 p.19). In addition, it provides the following messages to query version numbers.

ITLRequest



- version: version number request.
- quido-version: Guido engine version number request.
- musicxml-version: MusicXML and Guido converter version numbers request. Returns "not available" when the library is not found.

EXAMPLE

Querying INScore version:

/ITL version 1.00


```
/ITL get version
will give the following as output:
```

7.5 Application static nodes

The application level provides the static nodes - stats, debug and log, available at /ITL/stats /ITL/debug and /ITL/log to help debugging communication and INScore scripts design.

7.5.1 The 'stats' nodes

ITLStats



- get gives the count of handled messages at OSC and UDP levels: the UDP count indicates the count
 of messages received from the network, the OSC count includes the UDP count and the messages
 received internally.
- reset resets the counters to zero. Note that querying the stats node increments at least the OSC the counter.

EXAMPLE

Answer to a get message addressed to /ITL/stats

```
/ITL/stats osc 15 udp 10
```

7.5.2 The 'debug' nodes

The debug node is used to activate debugging information.

ITLdebug



• switch the debug mode ON or OFF. The parameter is interpreted as a boolean value. When in debug mode, INScore sends verbose messages to the OSC error port for every message that can't be correctly handled. Debugging is ON by default.

EXAMPLE


Error messages generated on error port in debug mode:

```
error: incorrect OSC address: /ITL/stat
error: incorrect parameters: /ITL/scene/foo unknown 0.1
error: incorrect parameters: /ITL/scene/foo x "incorrectType"
```

7.5.3 The 'log' nodes

The log node controls a console window that display all the messages sent to the OSC error port. Typical content is given by the example above.

ITLLog




- show show or hides the console. The parameter is a boolean value.
- clear clear the console window.
- wrap control line wrapping of the console. The parameter is a boolean value.
- write write the arg list formatted as a string to the log window.
- save save the current log content to a file. The parameter is a file name. When expressed as a relative path, the file is saved under the current application root path.

Scene messages

A scene may be viewed as a window on the score elements. Its address is /ITL/sceneIdentifier where sceneIdentifier is the scene name. It handles the following messages:

sceneMsg



- new: creates a new scene and opens it in a new window.
- del: deletes a scene and closes the corresponding window.
- reset: clears the scene (i.e. delete all components) and resets the scene to its default state (position, size and color).
- rootPath: *rootPath* of a scene is the default path where the scene reads or writes a file when a relative path is used for this file. When no value has been specified, the application *rootPath* is used.
- load: loads an INScore file to the scene. Note that the OSC addresses are translated to the scene OSC address.
- fullscreen: requests the scene to switch to full screen or normal screen. The parameter is interpreted as a boolean value. Default value is 0.

- frameless: requests the scene to switch to frameless or normal window. The parameter is interpreted as a boolean value. Default value is 0.
- absolutexy: requests the scene to absolute or relative coordinates. Absolute coordinates are in pixels relative to the top left corner of the screen. Relative coordinates are in the range [-1, 1] where [0,0] is the center of the screen. The message parameter is interpreted as a boolean value. Default value is 0.
- windowOpacity: switch the scene window to opaque or transparent mode. When in transparent mode, the scene alpha channel controls the window opacity (from completely opaque to completely transparent). In opaque mode, the scene alpha channel controls the background brush only. Default value is 0.
- commonMsg: a scene support the common graphic attributes. See section 2 p.4.

Setting a scene current path:

```
/ITL/scene rootPath "/path/to/my/folder"
```

Loading an INScore file:

```
/ITL/scene load "myscript.inscore"
```

will load /path/to/my/folder/myscript.inscore into the scene.

Setting a scene to fullscreen:

/ITL/scene fullscreen 1

Creating a new score named myScore:

/ITL/myScore new

Layers

Layers may be viewed as containers or as groups. They represent a way to structure both the address space and the graphic space.

From graphic viewpoint, a layer is a scene inside a scene. All the properties of 'rect' components are available to layers: position, scale, color, transparency, etc.). By default, a layer is not visible: it has no brush and no pen.

From time viewpoint, a layer has the common time attributes i.e. a date, a duration.

A layer may be synchronized to other objects, including other layers. It includes a sync node and supports synchronization of the enclosed objects. However, synchronization is restricted to objects from the same layer and cannot cross the border of a layer.

EXAMPLE

Creating a layer and its content:

```
/ITL/scene/layer1 set layer
/ITL/scene/layer1/score set gmnf 'myscore.gmn'
/ITL/scene/layer1/cursor set rect 0.01 0.1
```

Synchronizing 2 components of a layer:

```
!'score' and 'cursor' must be enclosed in layer1
/ITL/scene/layer1/sync cursor score;
```

Making a layer visible:

```
/ITL/scene/layer1 brushStyle solid;
/ITL/scene/layer1 color 120 120 120;
```

9.1 Layers generalization

The idea of layer is generalized to all the type of objects: any INScore object can be a container without limitation on the depth.

Mapping graphic space to time space


Time to space mapping refers to the description of relationship between an object local graphic space and its time space. A mapping consists in a set of relations between the two spaces. INScore provides specific messages to describes mappings and to synchronize arbitrary objects i.e. to display their time relationships in the graphic space.

10.1 The 'map' message

The map messages can be sent to any address with the form /ITL/scene/identifier. It is intended to describe the target object relation to time and sets a relation between an object segmentation and a time segmentation. The global form of the message is:



The relation parameter must be sent as a single string which format is described below. It consists in a list of associations between the object local space and its time space expressed as segments.



Segments are expressed as a list of intervals. For a 1 dimension resource, a segment is a made of a single interval. For a 2 dimensions resource, a segment is a made of 2 intervals: an interval on the x-axis and one

on the y-axis for graphic based resource, or an interval on columns and one on lines for text based resources. Intervals are right-opened.

The different kind of relations corresponds to:

- [1] a relation between a 2 dimensions segmentation expressed in float values and a relative time segmentation. These segmentations are used by rect, ellipse, polygon, curve, line components.
- [2] a relation between a 2 dimensions segmentation expressed in integer values and a relative time segmentation. These segmentations are used by txt, txtf, img components.
- [3] a relation between a 1 dimension segmentation expressed in integer values and a relative time segmentation. These segmentations are used by the graph component and express a relation between a signal space and time.

Table 10.1 summarizes the specific local segmentation used by each component type.

The specified map can be named with an optional mapName string; this name can be further reused, during object synchronization, to specify the mapping to use. When mapName is not specified, the mapping has a default *empty name*.


The del command deletes the mapping specified with mapName, or the 'empty name' mapping if no map name is specified.

Table 10.1: Local segmentation type for each component

	segmentation type		
	txt,	, txtf	int2DSegments
		img	int2DSegments
rect, ellipse, p	polygon,	curve	float2DSegments
		graph	int1DSegments



floatInterval



Relative time is expressed as rational values where 1 represents a whole note.

rational



EXAMPLE

Mapping an image graphic space to time:

```
/ITL/scene/myImage map
"([0, 67[ [0, 86[ ) ( [0/2, 1/2[ ) ( [67, 113[ [0, 86[ ) ( [1/2, 1/1[ ) ( [113, 153[ [0, 86[ ) ( [1/1, 3/2[ ) ( [153, 190[ [0, 86[ ) ( [3/2, 2/1[ ) ( [190, 235[ [0, 86[ ) ( [2/1, 5/2[ )"
```

the image is horizontally segmented into 5 different graphic segments that express pixel positions. The vertical dimension of the segments remains the same and corresponds to the interval [0, 86]. Each graphic segment is associated to a time interval which duration is 1/2 (a half note).

NOTE ABOUT LOCAL SPACES

- Text objects (txt txtf) local space is expressed by intervals on columns and rows.
- Html object (html, htmlf) do not support mapping because there is not correspondence between the text and the graphic space.
- Vectorial objects (rect, ellipse, polygon, curve, svg,...) express their local graphic space in internal coordinates system i.e. on the [-1.,1.] interval.
- Bitmap objects (img) express their local graphic space in pixels.

10.2 The 'map+' message

The map+ messages is similar to the map message but doesn't replace the existing mapping data: the specified relations are added to the existing one.

mapAddMsg



10.3 Mapping files

The mapf messages is similar to the map message but gives the path name of a file containing the mapping data, along with the optional map name.



10.4 Symbolic score mappings

Mapping between the graphic and time space is automatically computed for symbolic score gmn, gmnstream, gmnf. However and depending on the application, the graphic space may be segmented in different ways, for instance: different graphic segments for different staves, a single graphic segment traversing all a system, etc. Thus for a symbolic score, the map message different and is only intended to select one king mapping supported by the system.

scoreMap



- page: a page level mapping
- system: a system level mapping
- systemflat: a system level mapping without system subdivision (one graphic segment per system)
- staff n: a staff level mapping: the staff number is indicated by n, a number between 1 and the score staves count.
- voicen: a voice level mapping: the voice number is indicated by n, a number between 1 and the score voices count.

The default mapping for a symbolic score is unnamed but equivalent to staff1.

EXAMPLE

Requesting the mapping of the third staff of a score:

```
/ITL/scene/myScore map staff3
```

Requesting the system mapping:


```
/ITL/scene/myScore map system
```

Note


A voice may be distributed on several staves and thus a staff may contain several voices.

Synchronization

Synchronization between components is in charge of the static sync node, automatically embedded in each scene. Its address is /ITL/scene/sync and it supports messages to add or remove a master/slave relation between components or to query the synchronizations state.



- [1] the slave master form is followed by an optional synchronization mode (see below). It adds a slave / master relation between the first and the second component.
- [2] the slave form without master removes a slave synchronization.
- [3] the get message is intended to query the synchronization state. The optional parameter is the identifier of a component. The get message without parameter is equivalent to a get message addressed to each object declared in the sync node.



Synchronization identifiers indicates 1) the name of a scene component or 2) the name of a scene component associated to a mapping name. Using the first form (i.e. without explicit mapping name), the system uses the default unnamed mapping (see section 10.1 p.34 mappings and named mappings).

Synchronization between components has no effect if any of the required mapping is missing (see table 10.1).

NOTE

A slave object can have only one master. Synchronizing a slave object to a different object replaces the previous relation with the new one.

EXAMPLE

Synchronizing two objects:

```
/ITL/scene/sync mySlave myMaster
```

Synchronizing two objects using a specific mapping (the second object is assumed to be a symbolic score (gmn, gmnstream or gmnf) which system mapping has been previously requested:


```
/ITL/scene/sync mySlave myMaster:system
```

11.1 Synchronization modes

Synchronizing a slave component A to a master component B has the following effect:

- A position (x) is modified to match the B time position corresponding to A date.
- depending on the optional syncStretch option, A width and/or height is modified to match the corresponding B dimension (see below).
- depending on the optional syncPos option, A vertical position (y) is modified. Note that the y position remains free and could always be modified using a dy message.
- if A date has no graphic correspondence in B mapping (the date is not mapped, or out of B mapping bounds), A won't be visible.

syncmode



11.1.1 Using the master date

syncHow



The synchronization mode makes use of the master time to graphic mapping to compute the slave position. It may also use the master current date, depending on the following options:

- relative: the time position where the slave appears is relative to the mapping and to the master current date (actually, it shifts the mapping from the master current date). The relative mode is used by default.
- absolute: the time position where the slave appears corresponds to the mapping date only.

NOTE

Use of the absolute mode may take sense with nested synchronizations: let's consider an object A, slave of B, which is slave of C. In relative mode and if A and B receive the same clock messages, A will remain at a fixed position on B although it is moving in time.


EXAMPLE

Describing nested synchronizations, the first one using the absolute mode:

```
/ITL/scene/sync slave masterSlave absolute
/ITL/scene/sync masterSlave master
```

11.1.2 Synchronizing an object duration

syncStretch



The synchronization stretch mode has the following effect on the slave dimensions:

- h: the slave is horizontally stretched to align its begin and end dates to the corresponding master locations.
- v: the slave is vertically stretched to the master map vertical dimension.
- hv: combines the above parameters.

By default, no stretching is applied.


EXAMPLE

Synchronizing two objects, aligning the slave duration to the corresponding master space and stretching the slave to the master map vertical dimension:

```
/ITL/scene/sync mySlave myMaster hv
```

11.1.3 Controlling the slave y position

syncPos



The synchronization position mode has the following effects on the slave y position:

- syncOver: the center of the slave is aligned to the master center.
- syncTop: the bottom of the slave is aligned to the top of the master.
- syncBottom: the top of the slave is aligned to the bottom of the master.

The default position mode is syncover. The y attribute of the slave remains available to displacement (dy).

NOTE

The y position of a synchronized object remains a free attribute. To control this position, you should send dy messages.

Synchronizing two objects, aligning the slave duration to the corresponding master space, the slave being below the master map:

/ITL/scene/sync mySlave myMaster h syncBottom

Signals and graphic signals

The graphic representation of a signal is approached with *graphic signals*. As illustrated in figure 12.1, the graphic representation of a signal could be viewed as a stream of a limited set of parameters: the y coordinate at a time t, a thickness h and a color c. A *graphic signal* is a composite signal including a set of 3 parallel signals that control these parameters. Thus the INScore library provides messages to create signals and to combine them into *graphic signals*.




Figure 12.1: A simple graphic signal, defined at time t by a coordinate y, a thickness h and a color c

12.1 The 'signal' static node.

A scene includes a static signal node, which OSC address is /ITL/scene/signal which may be viewed as a container for signals. It is also used for *composing signals in parallel*.

The signal node supports only the get message that gives the list of the defined signals.

EXAMPLE

Querying the signal node:

```
/ITL/scene/signal get
will give the enclosed signals definitions:
/ITL/scene/signal/y size 200
/ITL/scene/signal/h size 200
```

12.1.1 Signal messages.

Signal messages can be sent to any address with the form /ITL/scene/signal/identifier, where identifier is a unique signal identifier. The set of messages supported by a signal is the following:



- [1] push an arbitrary data count into the signal buffer. The expected data range is [-1,1]. Note that the internal data buffer is a ring buffer, thus data are wrapped when the data count if greater than the buffer size.
- [2] the size message sets the signal buffer size. When not specified, the buffer size value is the size of the first data message.
- [3] the default message sets the *default signal value*. A signal *default value* is the value returned when a query asks for data past the available values.
- [4] the get message without parameter gives the signal current values. The size and default parameters are used to query the signal size and default values.
- [5] the reset message clears the signal data.
- [6] the del message deletes the signal from the signal space. Note that it is safe to delete a signal even when used by a graphic signal.

Creating a signal with a given buffer size:

```
/ITL/scene/signal/mySig size 200
```


Creating a signal with a given set of data (the buffer size will be the data size):

```
/ITL/scene/signal/mySig 0. 0.1 0.2 0.3 0.4 0.5 0.4 0.3 0.2 0.1 0. -0.1 -0.2
```


12.1.2 Composing signals in parallel.

Composing signals in parallel produces a signal which value at a time t is a vector of the composed signals values. Thus an additional read-only attribute is defined on *parallel signals*: the signal *dimension* which is size of the signals vector. Note that the dimension property holds also for simple signals.

The format of the messages for parallel signals is the following:



where



- [1] defines a new signal composed of the signals given as parameters. A signal parameter is defined as:
 - [4] an identifier i.e. a signal name referring to an existing signal in the signal node.
 - [5] or as a float value. This form is equivalent to an anonymous constant signal holding the given value.
- [2] sets the values of the signals using a projection string. See section 12.1.3 p.44.
- [3] in addition to the get format defined for signals, a parallel signal supports the get dimension message, that gives the number of simple signals in parallel. The dimension of a simple signal is 1.

EXAMPLE

Putting a signal y and constant signals 0.01 0. 1. 1. 1. in parallel:

```
/ITL/scene/signal/mySig set y 0.01 0. 1. 1. 1.
```

Querying the previously defined parallel signal:

```
/ITL/scene/signal/mySig get
will give the following output:
/ITL/scene/signal/mySig set y 0.01 0. 1. 1. 1.
```

Note


For a parallel signal:

- $\bullet\,$ the get $\,$ size message gives the maximum of the components size.
- the get default message gives the default value of the first signal.

12.1.3 Distributing data to signals in parallel

When signals are in parallel, a *projection string* may be used to distribute data over each signal. Individual components of a parallel signal may be addressed using a *projection string* that is defined as follows:

projectionString



The projection string is made of a *index value*, followed by an optional *parallel marker* (~), followed by an optional *step value*, all enclosed in brackets.

The *index value* n is the index of a target signal. When the *parallel marker* option is not present, the values are directed to the target signal. Indexes start at 0.

EXAMPLE

Sending data to the second component of a parallel signal:

```
/ITL/scene/signal/sig '[1]' 0. 0.1 0.2 0.3 0.4 0.5 0.4 0.3 0.2 0.1 0.
```

is equivalent to the following message (assuming that the second signal name is 's2'):

```
/ITL/scene/signal/s2 0. 0.1 0.2 0.3 0.4 0.5 0.4 0.3 0.2 0.1 0.
```

Note that:

- the message is ignored when n is greater than the number of signals in parallel. Default n value is 0.
- setting directly the values of a simple signal or as the projection of a parallel signal are equivalent.

The parallel marker ($\tilde{\ }$) and the step value w options affect the target signals. Let's consider s[n] as the signal at index n. The values are distributed in sequence and in loop to the signals s[n], s[n+w]...s[m] where m is the greatest value of the index n+(w.i) that is less than the signal dimension. The default step value is 1.

EXAMPLE

Sending data to the second and third components of a set of 3 parallel signals:

```
/ITL/scene/signal/sig [1~] 0.1 0.2
```

is equivalent to the following messages (assuming that the signal dimension is 3):

```
/ITL/scene/signal/sig [1] 0.1
/ITL/scene/signal/sig [2] 0.2
```

or to the following (assuming that the target signal names are 's2' and 's3'):

```
/ITL/scene/signal/s2 0.1
/ITL/scene/signal/s3 0.2
```

12.2 Graphic signals.

A graphic signal is the graphic representation of a set of parallel signals. It is created in the standard scene address space. A simple graphic signal is defined by a parallel signal controling the y deviation value, the thickness and the color at each time position. The color is encoded as HSBA colors (Hue, Saturation, Brightness, Transparency). The mapping of a signal value ([-1,1]) to the HSBA color space is given by the table 12.1.

A graphic signal responds to common component messages (section 2 p.4). Its specific messages are the following:





Figure 12.2: The HSB color space

Table 12.1: HSBA color values.

parameter	mapping	
hue	[-1,1]	corresponds to [-180, 180] angular degree where 0 is red.
saturation	[-1,1]	corresponds 0% to 100% saturation.
brigthness	[-1,1]	corresponds 0% (black) to 100% (white) brithgness.
transparency	[-1,1]	corresponds 0% to 100% tranparency.

graphicSignal



- the set message is followed by the graph type and a *signalIdentifier*, where signalIdentifier must correspond to an existing signal from the signal address space. In case signalIdentifier doesn't exist, then a new signal is created at the signalIdentifier address with default values.
- the get dimension message gives the number of graphic signals in parallel (see section 12.2.2 p.47).

EXAMPLE

Creating a signal and its graphic representation:

```
/ITL/scene/signal/y size 200
! use of constant anonymous signals for thickness and color
/ITL/scene/signal/sig set y 0.1 0. 1. 1. 1.
/ITL/scene/siggraph set graph sig
```

12.2.1 Graphic signal default values.

As mentionned above, a graphic signal expects to be connected to parallel signals having at least an y component, a graphic thickness component and HSBA components. Thus, from graphic signal viewpoint, the expected dimension of a signal should be equal or greater than 6. In case the signalIdentifier dimension is less than 6, the graphic signal will use the default values defined in table 12.2.

Table 12.2: Graphic signal default values.

parameter	default value	
У	0	the center line of the graphic
thickness	0	
hue	0	meaningless due to brigthness value
saturation	0	meaningless due to brigthness value
brigthness	-1	black
transparency	1	opaque

12.2.2 Parallel graphic signals.

When the dimension d of a signal connected to a graphic signal is greater than 6, then the input signal is interpreted like parallel graphic signals. More generally, the dimension n of a graphic signal is:

$$n \mid n \in \mathbb{N} \land 6.(n-1) < d \leq 6.n$$

where d is the dimension of the input signal.

When d is not a mutiple of 6, then the last graphic signal makes use of the default values mentionned above.

EXAMPLE

Creating parallel graphic signals:

```
/ITL/scene/signal/y1 size 200
/ITL/scene/signal/y2 size 200
! use of constant anonymous signals for thickness and color
/ITL/scene/signal/sig1 set y1 0.1 0. 1. 1. 1.
! use a different color for 'sig2'
/ITL/scene/signal/sig2 set y2 0.1 0.6 1. 1. 1.
! put 'sig1' and 'sig2' in parallel
/ITL/scene/signal/sig set sig1 sig2 ! 'sig' dimension is 12
/ITL/scene/siggraph set graph sig
```


Note

Using data projection may be convenient when the input signal represents interleaved data. For example, the projection string [n~6] distribute data over similar components of a set of graphic signals, where n represents the index of the graphic signal target component.

Events and Interaction

Interaction messages are user defined messages associated to events and triggered when these events occur. These messages accept variables as message arguments.

The general form of the message is the following:



what represents the event to watch and message is a list of associated messages, separated by a comma.

- 1 : clear all the messages for all the events.
- 2: clear the messages associated to the what event.
- 3: associate a list of messages to the what event. With watch, the messages replace previously associated messages. Using watch+, the messages are appended to the messages currently associated to the event.
- 4: associate or add a single message to the what event. This form is provided for compatibility with previous versions.

Note

The [1] and [2] form has no effect with the watch+ message.

In some environments, the comma has a special meaning, making tricky to use it as a message separator. This is why ':' is also accepted as separator in OSC messages.



The associated messages are any valid OSC message (not restricted to the INScore message set), with an extended address scheme, supporting IP addresses or host names and udp port number to be specified as OSC addresses prefix. The message parameters are any valid OSC type or variable (see section 13.2).

addressPrefix



EXAMPLE

An extended address to send messages to localhost on port 12000:


localhost:12000/your/osc/address

13.1 Events

13.1.1 UI events

User interface events are typical mouse events:

what



EXAMPLE

Triggering a message on mouse down:

/ITL/scene/myObject watch mouseDown /ITL/scene/myObject show 0

the object hides itself on mouse click.

Triggering a message on mouse down but addressed to another host on udp port 12100:

/ITL/scene/myObject watch mouseDown host.domain.org:12100/an/address start

NOTE

UI events are not supported by objects that are synchronized as slave.

Mouse events can be simulated using a event message:

uievt



where mouseEvent is one of the events described above, x and y are integer values giving the click position, expressed in pixels and relative to the target object.

EXAMPLE


Simulating a mouse down at position 10, 10:

/ITL/scene/myObject event mouseDown 10 10;

13.1.2 Time events

Events are also defined on the time domain:

what



Each event takes a time interval as parameter, defined by two time specifications (see section 3 p.13 for the time format)

- timeEnter, timeLeave are triggered when an object date is moved to or out of a watched time interval.
- durEnter, durLeave are triggered when an object duration is moved to or out of a watched time interval.


EXAMPLE

An object that moves a score to a given page number when it enters its time zone.

/ITL/scene/myObject watch timeEnter 10/1 18/1 (/ITL/scene/score page 2)

13.1.3 Miscellaneous events

what



- the export event is supported by all the components. It is triggered after an export message has been handled and could be used to simulate synchronous exports.
- the newElement event is supported at scene level only and triggered when a new element is added to the scene.
- the endPaint event is supported at scene level only and triggered after a scene has been painted.
- the del event is triggered when an object is being deleted.

Displaying a welcome message to new elements:

```
/ITL/scene watch newElement (/ITL/scene/msg set txt "Welcome")
```


13.2 Variables

Variables are values computed when an event is triggered. These values are send in place of the variable. A variable name starts with a '\$' sign.

13.2.1 Position variables

Position variables reflects the current mouse position for mouse events. They are set to 0 for the other events.

posVar



where




- \$x \$y: denotes the mouse pointer position at the time of the event. The values are in the range [0,1] where 1 is the object size in the x or y dimension. The value is computed according to the object origin: it represents the mouse pointer distance from the object x or y origin (see 2.1.3 p.7). \$x and \$y variables support an optional range in the form [low, high] that transforms the [0,1] values range into the [low, high] range.
- \$absx \$absy: denotes the mouse pointer absolute position at the time of the event. The values represent a pixel position relative to the top-left point of the target object. Note that this position is unaffected by scale. Note also that the values are not clipped to the object dimensions and could exceed its width or height or become negative in case of mouse move events.
- \$sx \$sy: denotes the mouse pointer position in the scene coordinates space.

An object that follows mouse move.

13.2.2 Time variables

Time variables reflects the date corresponding to the current mouse position for mouse events. They are set to 0 for the other events.

timeVar



- \$date: denotes the object date corresponding to the mouse pointer position at the time of the event. It is optionally followed by a colon and the name of the mapping to be used to compute the date. The \$date variable is replaced by its rational value (i.e. two integers values). The optional rational enclosed in brackets may be used to indicate a quantification: the date value is rounded to an integer count of the specified rational value. The optional %f may be used to get the date delivered as a float value.
- \$rdate: is similar to \$date but ignores the target current date: the date is relative to the object mapping only.

NOTE

A variable can be used several times in a message, but several \$date variables must always refer to the same mapping.

EXAMPLE

Sending the current date as a float value to an external application:

```
/ITL/scene/myObject watch mouseDown ( targetHost:12000/date '$date%f' )
```

13.2.3 Miscellaneous variables

variable



- \$name is replaced by the target object name.
- \$scene is replaced by the target object scene name.
- \$address is replaced by the target object OSC address.

NOTE

For the newElement event, the target object is the new element.

EXAMPLE


Using an object name:

```
/ITL/scene watch newElement (/ITL/scene/welcome set txt "Welcome" '$name')
```

13.2.4 Message based variables

A message based variable is a variable containing an OSC message which will be evaluated at the time of the event. They are supported by all kind of events. Like the variables above, a message based variable starts with a '\$' sign followed by a valid 'get' message enclosed in parenthesis:





The evaluation of a 'get' message produces a message or a list of messages. The message based variable will be replaced by the parameters of the messages resulting from the evaluation of the 'get' message. Note that all the 'get' messages attached to an event are evaluated at the same time.

EXAMPLE

An object that takes the x position of another object on mouse down:

13.2.5 OSC address variables

The OSC address of a message associated to an event supports the following variables:

- \$self: replaced by the object name.
- \$scene: replaced by the scene name.

EXAMPLE


Requesting a set of objects to send a message to themselves on a mouse event:

```
/ITL/scene/* watch mouseDown ! request all the objects of the scene (/ITL/scene/$self x '$sx') ! to send a message to themselves
```

13.3 Interaction state management

For a given object, its *interaction state* (i.e. the watched events and the associated messages) can be saved and restored.

stateMsg



Interaction states are managed using a stack where the states are pushed to or popped from.

• push: push the current interaction state on top of the stack.

• pop: replace the current interaction state with the one popped from the top of the stack.

NOTE

The effect of a pop message addressed to an object with an empty stack is to clear the object current interaction state.


13.4 File watcher

The fileWatcher is a static node of a scene that is intended to watch file modifications.

It receives messages at the address /ITL/scene/fileWatcher.

The fileWatcher support the watch and watch+ messages as described in section 13 p.48 with a file name used in place of the what parameter.

fileWatcher



EXAMPLE

Reload aa INScore script on file modification:

```
/ITL/scene/fileWatcher wach 'myScript.inscore'

( /ITL/scene load 'myScript.inscore' )
```

Scripting


INScore saves its state to files containing textual OSC messages. These files can be edited or created from scratch using any text editor. In order to provide users with a scripting language, the OSC syntax has been extended at textual level.

14.1 Statements

An INScore file is a list of textual expressions. A script expression is:

- a message: basically a textual OSC message extended to support URL like addresses and variables as parameters.
- a variable declaration.
- a foreign language script that may generate messages as output.

expression



Messages and variables declarations must be followed by a semicolon, used as statements separator.

14.2 Messages

Messages are basically OSC messages that support the address extension scheme described in section 13 p.48. Thus a script may be designed to initialize an INScore scene and external applications as well, including on remote hosts.

EXAMPLE

Initializing a score and an external application listening on port 12000 and running on a remote host named host.adomain.net.

```
/ITL/scene/score set gmnf 'myscore.gmn';
host.adomain.net:12000/run 1;
```

Messages parameters can be replaced by variables that are evaluated at parsing level. Variables are described in section 14.4.

14.3 Types

Using OSC, the message parameters are typed by the OSC protocol. With their textual version, any parameter is converted to an OSC type (i.e. int32, float or string) at parsing level. A special attention must be given to strings in order to discriminate addresses and parameters. Strings intended as parameters must:

- be quoted, using single or double quotes. Note that an ambiguous quote included in a string can be escaped using a '\'.
- or make use of the following characters set: [-a-zA-Z0-9]+ or [_a-zA-Z] [_a-zA-Z0-9]*.

EXAMPLE


Different string parameter

```
/ITL/scene/text set txt "Hello world"; ! string including a space must be quoted /ITL/scene/img set file 'anImage.png'; ! dots must be quoted too /ITL/scene/foo set txt no_quotes_needed;
```

14.4 Variables

A variable declaration associates a name with a list of parameters or a list of messages. Parameters must follow the rules given in section 14.3. They may include previously declared variables. A message list must be enclosed in parenthesis and a comma must be used as messages separator.





EXAMPLE

Variables declarations

A variable may be used in place of any message parameter. A reference to a variable must have the form \$ident where ident is a previously declared variable. A variable is evaluated at parsing level and replaced by its content.

EXAMPLE

Using a variable to share a common position:

```
x = 0.5;
/ITL/scene/a x $x;
/ITL/scene/b x $x;
```

Variables can be used in interaction messages as well, which may also use the variables available in the interaction context (see section 13.2 p.51). To differentiate between a *script* and an *interaction* variable, the latter must be quoted to be passed as strings and to prevent their evaluation by the parser.

EXAMPLE

Using variables in interaction messages: \$sx is evaluated at event occurrence and \$y is evaluated at parsing level.

```
y = 0.5;
/ITL/scene/foo watch mouseDown (/ITL/scene/foo "$sx" $y);
```

14.5 Message based parameters

Similarly to message based variables (see section 13.2.4 p.53), a message parameter may also use the result of a get message as parameters specified like a message based variable. The message must be enclosed in parameters with a leading \$ sign.





EXAMPLE

Displaying INScore version using a message parameter:

```
/ITL/scene/version set txt "INScore version is" $(/ITL get version);
```

NOTE

Message based parameters are evaluated by the parser. Thus when the system state is modified by a script before a message parameter, these modifications won't be visible at the time of the parameter evaluation because all the messages will be processed by the next time task. For example:

```
/ITL/scene/obj x 0.1
/ITL/scene/foo x $(/ITL/scene/foo get x);
```

x position of /ITL/scene/foo will be set to x position of /ITL/scene/obj at the time of the script evaluation (that may be different to 0.1).

14.6 Languages

INScore supports Javascript and Lua as scripting languages. Javascript is embedded by default (using the v8 engine¹). INScore needs to be recompiled to embed the Lua engine². A script section is indicated similarly to a Javascript section in html i.e. enclosed in an opening <? and a closing ?>.

script



The principle of using an embedded programming language in script files is the following: *javascript* or *lua* sections are given to the corresponding engine and are expected to produce INScore messages on output. These messages are then parsed as if replacing the corresponding script section.

http://code.google.com/p/v8/

²http://www.lua.org/

Note that INScore variables are exported to the current language environment.

EXAMPLE

```
<?javascript
  "/ITL/scene/version set 'txt' 'Javascript v." + version() + "';";
?>
```

A single persistent context is created at application level and for each scene. It allows scripts to reuse previously defined functions and thus to design more structured scripts.

14.6.1 The Javascript object

The Javascript engine is available at runtime at the address /ITL/scene/javascript. It has a run method that takes a javascript string as parameter.

javascript



The run method evaluates the code. Similarly to javascript sections in scripts, the output of the evaluation is expected to be a string containing valid INScore messages that are next executed. Actually, including a javascript section in a script is equivalent to send the run message with the same code as parameter to the javascript object.

The Javascript engine is based on V8 that implements ECMAScript as specified in ECMA-262, 5th edition, extended with additional functions:

- version(): gives the javascript engine version number as a string.
- print (val1 [, val2 [, ...]]) : print the arguments to the OSC standard output. The arguments list is prefixed by 'javascript:'. The function is provided for debug purpose.
- readfile (file): read a file and returns its content as a string. The file name could be specified as an absolute or relative path. When relative, the file is searched in the application current rootPath (see section 7.1 p.26).
- post (address [,...]) : build an OSC message and post it for delayed processing i.e. to be processed by the next time task. address is an OSC or an extended OSC address. Optional arguments are the message parameters.

Plugins

15.1 FAUST plugins

FAUST [Functional Audio Stream]¹ is a functional programming language specifically designed for real-time signal processing and synthesis. A FAUST/INScore architecture allows to embed FAUST processors in INScore, for the purpose of signals computation. A FAUST plugin is viewed as a parallel signal and thus it is created in the signal address space. Similarly to signals, it is associated to an OSC address in the form /ITL/scene/signal/name where name is a user defined name.

faustprocessor




A FAUST processor is created with a set message followed by the faust type, followed by the plugin path name.

15.1.1 Specific messages

A FAUST processor is characterized by the numbers of input and output channels and by a set of parameters. Each parameter carries a name defined by the FAUST processor. The set of messages supported by a FAUST processor is the set of signals messages extended with the parameters names and with specific query messages.

faustmessage



- 1 msg is any of the FAUST processor parameters, which are defined by the FAUST processor.
- 2 the get message is extended to query the FAUST processor: in and out give the number of input and output channels.

¹http://faust.grame.fr

Creating a FAUST processor and querying its input and output count:

```
/ITL/scene/signal/myFaust set faust aFaustPlugin
/ITL/scene/signal/myFaust get in out
```

gives as output:

```
/ITL/scene/signal/myFaust in 2
/ITL/scene/signal/myFaust out 4
```

Modifying the value of a FAUST processor parameter named volume:

```
/ITL/scene/signal/myFaust volume 0.8
```

NOTE


The plugins are shared libraries which extension is platform dependent. The plugin name should not include the extension. The expected extensions are the following: .dylib on MacOS and Linux, .dll on Windows.

15.1.2 Feeding and composing FAUST processors

A FAUST processor accepts float values as input, which are taken as interleaved data and distributed to the input channels.

From composition viewpoint, a FAUST processor is a parallel signal which dimension is the number of output channels. Thus, a FAUST processor can be used like any parallel signal. However, the signal identifier defined in 12.1.2 is extended to support adressing single components of parallel signal as follows:

signal



where n selects the signal #n of a parallel signal. Note that indexes start at 0.

EXAMPLE

Creating 3 parallel signals using the 3 output channels of a FAUST processor named myFaust:

```
/ITL/scene/signal/y1 set 'myFaust/0' 0.01 0. 1. 1. 1. /ITL/scene/signal/y2 set 'myFaust/1' 0.01 0.5 1. 1. 1. /ITL/scene/signal/y3 set 'myFaust/2' 0.01 -0.5 1. 1. 1.
```

15.2 Gesture Follower

INScore supports gesture following using the technology developed by the IRCAM IMTR team. These features are available as a plugin that is included in the INScore distribution (version 1.03 or greater) or available from the IRCAM.

15.2.1 Basic principle

Gesture following is provided as a mean to interact with a score. From input viewpoint, the gesture follower is similar to signals (see section 12.1.1 p.42): it accepts data stream as input both in learning and following

modes. It implements a specific set of events related to gesture following and can generate message streams parametrized with the gesture follower current state.

A gesture follower is setup to handle a given count of gestures, which are actually denoted by streams of float vectors. We'll refer to the size of the float vector as the *gesture dimension*. For example, the dimension of a gesture captured from x, y and z accelerometers is 3.

A gesture follower operates in two distinct phases: a *learning phase* where it actually stores the gestures data, and a *following phase* where it tries to match incoming data to the stored gestures data. When not learning nor following, we'll talk of an idle phase.

In the *following phase*, the system maintains a list of likelihood for the learned gestures, a list of positions in the gestures and a list of speeds representing how fast the gestures are made. Of course, the higher the likelihood, the more these data are meaningfull. It's the user responsability to decide on the meaningfull likelihood threshold value. Interaction events are triggered only in the *following phase* and for meaningfull likelihoods.

15.2.2 Messages

A gesture follower is created in a scene using the imtrgf type. It has a graphic appearance that may be used for debug purpose but it is hidden by default.

gesturefollower




The parameters are:

- gesturedimension: the size of the gestures data vector.
- bufsize: the size of the gesture data storage.
- name: a list of names to be used to refer to the learned gestures.

Note

A gesture follower is created with a fixed count of gestures that can be learned and decoded. These gestures are named gestures and can be addressed at /ITL/scene/myfollower/gesturename where the part in italic are user defined names and where myfollower is a gesture follower.

gesturefollower



- [1] input data into the gesture follower. The data are interpreted according to the current operating mode i.e. learning, following or idle.
- [2] starts to learn the gesture designated by name. Actually records the next input data to the gesture.
- [3] starts following i.e. trying to match the next input data to the recorded gestures.
- [4] stops learning or following. Actually puts the system in idle phase.
- [5] clear all the gestures data. This is equivalent to send the clear message to all the gestures.
- [6] sets the size of the window that contains the history of the likelihoods. May be viewed as how fast the likelihoods will change.
- [7] sets the follower tolerance.

Creating a gesture follower for 3 dimensional data and a typical learning sequence:


```
/ITL/scene/gf set imtrgf 3 1000 gestureA gestureB gestureC gestureD /ITL/scene/gf learn gestureA /ITL/scene/gf 0.1 0.5 -0.2 ... 0.7; ! the data size must be a multiple of 3 /ITL/scene/gf stop;
```

15.2.3 Gestures management

Messages can also be sent to gestures i.e. to addresses in the form /ITL/scene/myfollower/gesturename where myfollower is a gesture follower.

A gesture could be in two states:

- an active state: when its likelihood is greater or equal to the likelihood threshold.
- an idle state: when its likelihood is lower than the likelihood threshold.



- set: sets the gesture data. This is equivalent to learn the corresponding data. The set message could be used to restored previously saved gesture data.
- clear: clears the gesture data.
- learn: puts the gestures follower in learning mode and starts learning the corresponding gesture. This is equivalent to send OSClearn *gesturename* to the parent gesture follower.
- likelihoodThreshold: sets the gesture likelihood threshold. The parameter is a float value in the range [0,1]. Default value is 0.5.

Gestures supports also specific queries :


size

- get: without parameter, returns a set message when the gesture is not empty.
- size: gives the current size of the gesture, actually the number of recorded frames.

15.2.4 Events and interaction

Events are defined at gesture level and events management messages should be addressed to gestures.


gestureevents



- gfEnter triggered when the gesture state changes from idle to active.
- gfLeave triggered when the gesture state changes from active to idle.
- gfActive triggered in active state each time the gesture likelihood is refreshed.
- gfIdle triggered in idle state each time the gesture likelihood is refreshed.

A message associated to a gesture supports the following specific variables:

gesturevariable



These variables support the scaling feature associated to position variables and described in section 13.2.1 p.51.

- gflikelihood indicates the current likelihood
- gfpos indicates the current position in the gesture
- gfspeed indicates the current gesture execution speed

NOTE

Variables described in section 13.2 p.51 may also be used but they are meaningless and contains default values.

15.2.5 Gesture Follower Appearance

A gesture follower object has a graphic appearance and supports all the standard objects properties, including mapping and synchronization. This graphic appearance is provided mainly for debug purpose and by default, the object is hidden. Figure 15.1 shows the gesture follower appearance in its different phases:

- when idle, the upper part of the graphic indicates the buffer state of the different gestures. It also includes the gestures likelihood threshold.
- when learning, a red frame and a grey background indicates that a learning a gesture is currently in progress. The gesture buffer state is refreshed while learning.
- when following, the upper part indicates each gesture current likelihood and the lower part indicates the current estimated positions.




Figure 15.1: The gesture follower appearance in its different phases.

Appendices

16.1 Grammar definition

```
// relaxed simple INScore format specification
//___
start
       : expr
           | start expr
// expression of the script language
         : message ENDEXPR
expr
           | variabledecl ENDEXPR
           | script
// javascript and lua support
script : LUASCRIPT
           | JSCRIPT
// messages specification (extends osc spec.)
message : address
           | address params
           | address watchparams
           | address watchparams LEFTPAR messagelist RIGHTPAR
           | address watchparams script
messagelist : message
           | messagelist COMMA message
```

```
// address specification (extends osc spec.)
          : oscaddress
           | urlprefix oscaddress
oscaddress : oscpath
           | oscaddress oscpath
oscpath
           : PATHSEP identifier
           | PATHSEP WATCH
           | PATHSEP VARSTART varname
urlprefix : hostname COLON UINT
          | IPNUM COLON UINT
hostname : HOSTNAME
           | hostname POINT HOSTNAME
identifier : IDENTIFIER
           | HOSTNAME
           | REGEXP
// parameters definitions
// watchparams need a special case since messages are expected as argument
watchparams : watchmethod
          | watchmethod params
params
           : param
           | variable
           | params variable
           | params param
watchmethod : WATCH
           ;
variable : VARSTART varname
           | VARSTART LEFTPAR message RIGHTPAR
           ;
param
           : number
           | FLOAT
           | identifier
```

16.2 Lexical tokens

```
// numbers
INT a signed integer
UINT an unsigned integer FLOAT a floating point number
// hosts addresses
// allowed character set for host names (see RFC952 and RFC1123)
HOSTNAME : [-a-zA-Z0-9]+
IPNUM
             : {DIGIT}+"."{DIGIT}+"."{DIGIT}+
// OSC addresses
// allowed characters for identifiers
IDENTIFIER : [\_a-zA-Z][\_a-zA-Z0-9]*
REGEXP
              see OSC doc for regular expressions
// parameters
QUOTEDSTRING quotes could be single (') or double quotes (")
             : watch
WATCH
              | watch+
              | require
```

```
//_
// languages support
//_
JSCRIPT : <?javascript any javascript code ?>
LUASCRIPT : <?lua any lua code ?>

//_
// misc.
//
PATHSEP : '/'
POINT : '.'
VARSTART : '$'
COLON : ':'
COMMA : ','
LEFTPAR : '('
RIGHTPAR : ')'
EQUAL : '='
ENDEXPR : ';'
```

Chapter 17

Changes list

17.1 Differences to version 1.05

- save message can now take an optional list of attributes to be saved (see section 2 p.4)
- variables are now evaluated and expanded inside strings. Thus interaction variables can now be passed as argument of javascript functions.
- corrects musicxml-version output
- log window is put to front when the show menu is recalled
- object aliases are removed when the object is deleted

17.2 Differences to version 1.03

- incorrect error message for watch messages corrected
- new javascript readfile function (see section 14.6.1 p.58)
- log window is now available from the application 'Tools' menu
- new brushStyle attribute (see section 6.2 p.21)
- new layer object (see section 4.1 p.15)
- new save method specific to the log window: saves the window content to a file (see section 7.5.3 p.29)
- new event method supported at object level for UI events simulation
- new del watchable event: sent when deleting an object (see section 13.1.3 p.50)
- new gmnstream guido stream object (see section 4.1 p.15)

17.3 Differences to version 1.0

- log window utility provided as a new static node at application level (/ITL/log) (see section 7.5.3 p.29).
- new systemCount read only attribute for Guido scores (see section 6.4 p.23)
- IRCAM gesture follower support (see section 15.2 p.60)
- javascript engine is available at the static address /ITL/scene/javascript and can be activated using a 'run' method (see section 14.6.1 p.58)
- new export event (see section 13.1.3 p.50)

- new endPaint event at scene level (see section 13.1.3 p.50)
- new windowOpacity method at scene level (see section 8 p.31)
- bug correction: error messages not generated for dropped files (actually for the scene load method)
- bug correction: possible infinite loop in QStretchTilerItem::paint method
- bug correction: incorrect get alias output (all the aliases were dumped out in a single message)

17.4 Differences to version 0.98

- bug correction in streching very small objects (due to approximations)
- bug correction in \$sx and \$sy computation (xorigin and yorigin was not taken into account)
- new 'ticks' message at application level for querying or setting the current count of time tasks (see section 7.1 p.26)
- new 'time' message at application level for querying or setting the current time (see section 7.1 p.26)
- new 'forward' message at application level for messages forwarding to remote hosts (see section 7.1 p.26)
- new 'relative | absolute' synchronization mode (see section 11.1 p.39)
- 'rename' message not supported any more
- a scene accepts multiple dropped files
- significant extension and syntax changes in inscore script files (see Scripting documentation section 14 p.55)
- fileWatcher methods renamed and simplified (see section 13.4 p.54)
- 'click' and 'select' messages are not supported any more.
- new 'stats' virtual node at application level (address /ITL/stats), supports 'get' and 'reset' messages the node gives statistics about the incoming messages (see section 7.5.2 p.29)
- crash bug in signal creation corrected: a signal size created with an incorrect stream (e.g. a string value) was 0 and no buffer was allocated.
- extension of the time related events to duration: new 'durEnter' and 'durLeave' watchable events (see section 13.1.2 p.50)
- new 'absolutexy' message at scene level to switch to absolute coordinates (in pixels) (see section 8 p.31)
- new 'push' and 'pop' messages to store and restore current watched events and associated messages (see section 13.3 p.53)
- internal change: mappings are now implemented as a separable library strictly complying to the mappings formalism.
- new %f format for the date variable to request a float value (instead a rational value) (see section 13.2.2 p.52).
- dates may be specified as rational strings (see section 3 p.13).
- interaction messages are not any more generated when the date can't be resolved.
- new rate message at application level to control the time task rate (see section 7 p.26)
- new frameless message at scene level to switch to frameless or normal window (see section 8 p.31)

17.5 Differences to version 0.97

• new fastgraph object for graphic signals fast rendering (see section 4 p.15)

- \$date variable overflow catched
- files dropped on application icon correctly opened when the application is not running
- supports drag and drop of textual osc message strings
- osc error stream normalized: the message address is 'error:' or 'warning:' followed by a single message string.
- javascript and lua support: a single persistent context is created at application level and for each scene. (see section 14.6 p.57)

17.6 Differences to version 0.96

- objects position, date and watched events preserved through type change
- bug in quantified dates corrected (null denominator set to the quantified value)
- new 'alias' message providing arbitrary OSC addresses support
- bug in parser corrected: \ escape only ' and " chars, otherwise it is literal
- guido score map makes use of the new guidolib extended mapping API for staff and system
- chords map correction (corrected by guido engine)

17.7 Differences to version 0.95

- switch to v8 javascript engine
- lua not embedded by default

17.8 Differences to version 0.92

- new 'mouse' 'show/hide' message supported at application level (see section 7 p.26)
- graphic signal supports alpha messages at object level
- javascript and lua embedded and supported in inscore scripts (see section 14.6 p.57).
- bug correction in sync delete (introduced with version 0.90)

17.9 Differences to version 0.91

- bug corrected: crash with messages addressed to a signal without argument
- date and duration messages support one arg form using 1 as implicit denominator value the one arg form accepts float values (see section 3 p.13).

17.10 Differences to version 0.90

• bug in sync management corrected (introduced with the new sync parsing scheme)

17.11 Differences to version 0.82

- at application level: osc debug is now 'on' by default
- new scripting features (variables) (see section 14.4 p.56).

- ITL file format change:
 - semicolon added at the end of each message
 - '//' comment not supported any more
 - '%' comment char replaced by '!'
 - new variables scripting features
 - single quote support for strings
 - messages addressed to sync node must use the string format
- new 'grid' object for automatic segmentation and mapping

17.12 Differences to version 0.81

- new Faust plugins for signals processing
- colors management change: all the color models (RGBA and HSBA) accept now float values that are interpreted in the common [-1,1] range. For the hue value, 0 always corresponds to 'red' whatever the scale used.
- stretch adjustment for video objects (corrects gaps in sync h mode)
- support for opening inscore files on the command line
- system mapping correction
- splash screen and about menu implemented by the viewer

17.13 Differences to version 0.80

- behavior change with synchronization without stretch: now the system looks also in the slave map for a segment corresponding to the master date.
- \$date variable change: the value is now (0,0) when no date is available and \$date is time shifted according to the object date.
- date message change: the date 0 0 is ignored

17.14 Differences to version 0.79

- corrects the map not saved by the save message issue
- corrects get map output: 2D segments were not correctly converted to string

17.15 Differences to version 0.78

- crash bug corrected for the 'save' message addressed to '/ITL'
- message policy change: relaxed numeric parameters policy (float are accepted for int and int for float)
- bug in get watch for time events corrected (incorrect reply)

Known issues:

• map not saved by the save message

17.16 Differences to version 0.77

• guido system map extended: supports flat map or subdivided map (see section ?? p.??).

- new shear and rotate transformations messages (see section 2.2 p.8).
- new rename message to change an object name (and thus its OSC address) (see section 2 p.4).
- relaxed bool parameter policy: objects accept float values for bool parameters
- automatic numbering of exports when destination file is not completely specified i.e. no name, no extension. (see section 2 p.4).
- quantification introduced to \$date variable (see section 13.2 p.51).
- reset message addressed to a scene clears the scene rootPath

17.17 Differences to version 0.76

- get guido-version and musicxml-version messages supported by the application (see section 7 p.26).
- save message bug correction introduced with version 0.70: only partial state of objects was saved
- rootPath message introduced at scene level (see section 8 p.31).
- scene name translation strategy change: only the explicit 'scene' name is translated by the scene load message handler into the current scene name, other names are left unchanged.
- bitmap copy adjustment in sync stretched mode is now only made for images

17.18 Differences to version 0.75

- new require message supported by the /ITL node (see section 7 p.26).
- new event named newElement supported at scene level (see section 13.1.2 p.50).
- new name and address variables (see section 13.2 p.51).
- new system map computation making use of the new slices map provided by the guidolib version 1.42
- INScore API: the newMessage method sets now the message src IP to localhost With the previous version and the lack of src IP, replies to queries or error messages could be sent to undefined addresses (and mostly lost).
- bug corrected with ellipse and rect : integer graphic size computation changed to float (prevents objects disappearance with small width or height)
- bug in scene export: left and right borders could be cut, depending on the scene size corrected by rendering the QGraphicsView container instead the QGraphicsScene
- crash bug with \$date:name corrected: crashed when there is no mapping named name.

17.19 Differences to version 0.74

- new map+ message (see section 10.2 p.36).
- the click and select messages are deprecated (but still supported). They will be removed in a future version.

17.20 Differences to version 0.63

- new dpage message accepted by gmn objects (see section 6.4 p.23).
- x and y variables: automatic range type detection (int | float)

- set txt message: accepts polymorphic stream like parameters (see section 4 p.15).
- drag and drop files support in INScore viewer
- interaction variables extension: \$sx, \$sy variables added to support scene coordinate space (see section 13.2 p.51).
- automatic range mapping for \$x, \$y variables.
- new \$self and \$scene variables in the address field (see section 13.2.5 p.53).
- OSC identifiers characters set extended with '_' and '-' (see section 1 p.1).
- support for multiple scenes: new, del and foreground messages (see section 8 p.31).
- load message supported at scene level (see section 8 p.31).
- get watch implemented.
- watch message without argument to clear all the watched events (see section 13.2 p.51).
- order of rendering and width, height update corrected (may lead to incorrect rendering)
- bug with gmn score corrected: missing update for page, columns and rows changes.
- package delivered with the Guido Engine version 1.41 that corrects minimum staves distance and incorrect mapping when optimum page fill is off.

17.21 Differences to version 0.60

- new 'mousemove' event (see section 13.1.1 p.49).
- interaction messages accept variables (\$x, \$y, \$date...) (see section 13.2 p.51).
- SVG code and files support (see section 4.2 p.17).
- set line message change: the x y form is deprecated, it is replaced by the following forms: 'xy' x y (equivalent to the former form) and 'wa' width angle (see section 4 p.15).
- new 'effect' message (section 2.4 p.11).
- utf8 support on windows corrected
- transparency support for stretched synchronized objects corrected
- multiple application instances supported with dynamic udp port number allocation.
- command line option with –port portnumber option to set the receive udp port number at startup.

17.22 Differences to version 0.55

- new 'xorigin' and 'yorigin' messages (section 2.1.3 p.7).
- new interaction messages set (section 13 p.48).
- alpha channel handled by images and video
- bug correction in line creation corrected (false incorrect parameter returned)
- bug correction in line 'get' message handling
- memory leak correction (messages not deleted)

Known issues:

- incorrect graphic rendering when 'sync a b' is changed to 'sync b a' in the same update loop
- incorrect nested synchronization when master is horizontaly stretched,

17.23 Differences to version 0.53

- ITL parser corrected to support regexp in message string (used by messages addressed to sync node)
- format of mapping files and strings changed (section 10.1 p.34).
- format of sync messages extended to include map name (section 11 p.38).
- signal node: 'garbage' message removed
- new 'reset' message for the scene (/ITL/scene) (section 8 p.31).
- new 'version' message for the application (/ITL) (section 7 p.26).
- new 'reset' message for signals (section 12.1.1 p.42).
- bug parsing messages without params corrected
- slave segmentation used for synchronization
- new H synchronization mode (preserves slave segmentation)
- crash bug corrected for load message and missing ITL files

17.24 Differences to version 0.50

- Graphic signal thickness is now symmetrically drawn around y position.
- ITL file format supports regular expressions in OSC addresses.
- IP of a message sender is now used for the reply or for error reporting.
- new line object (section 4 p.15).
- new penStyle message for vectorial graphics (section 6 p.20).
- new color messages red, green, blue, alpha, dcolor, dred, dgreen, dblue (section 2 p.4 and 2.1.2 p.7).
- color values for objects are bounded to [0,255]
- get map message behaves according to new map message (section 5 p.19).
- get width and get height is now supported by all objects (section 5 p.19).
- bug in signal projection corrected (index 0 rejected)
- bug in signals default value delivery corrected
- new pageCount message for guido scores
- debug nodes modified state propagated to parent node (corrects the debug informations graphic update issue)
- rational values catch null denominator (to prevents divide by zero exceptions).

17.25 Differences to version 0.42

- identifier specification change (section 1 p.1).
- new application hello and default Show messages (section 7 p.26).
- new load and save messages (sections 7 p.26 and 2 p.4).
- click and select messages:
 - rightbottom and leftbottom modes renamed to bottomright and bottomleft
 - new center mode for the click message
 - query mode sent back with the reply both for click and select messages
- new file, html and htmlf types for the set message (section 4 p.15).

- get syntax change for the scene.
- \bullet fileWatcher messages completely redesigned.
- mappings can be identified by names (section 10.1 p.34).
- rect, ellipse, curve, line and polygon object support graphic to relative-time mapping
- new synchronization modes for Guido scores: voice1, voice2, ..., staff1, staff2, ..., system, page.
- Guido mapping manages repeat bars.
- Graphic signals messages design (section 12.2 p.45).

Index

ColorMsg, 8	intInterval, 35
ITLLog, 28	interactMsg, 47
ITLMsg, 25	javascript, 57
ITLMsgForward, 27	mapAddMsg, 35
ITLPortsMsg, 26	mapMsg, 33
ITLRequest, 27	mapfMsg, 35
ITLStats, 28	message, 47
ITLdebug, 28	msgVar, 52
OSCAddress, 1	msgparam, 56
OSCMessage, 1	originMsg, 7
PositionMsg, 5	parallelSignal, 42
absColorMsg, 8	penMsg, 19
absPosMsg, 6	penstyle, 19
addressPrefix, 48	posVar, 50
alias, 3	projectionString, 43
blurHint, 10	rational, 35
blurParams, 10	relColorMsg, 9
brushMsg, 20	relation, 33
color, 9	relativeTimeInterval, 34
colorizeParams, 11	relativeTimeSegment, 34
colorvalue, 8	sceneMsg, 30
commonMsg, 4	scoreMap, 36
debugMsg, 23	scoreMsg, 22
effectMsg, 10	script, 56
expression, 54	setFile, 16
faustmessage, 58	setMsg, 14
faustprocessor, 58	shadowParams, 11
fileWatcher, 53	signal, 43, 59
float2DSegment, 34	simpleSignal, 41
floatInterval, 34	stateMsg, 52
gesture, 61	sync, 37
gestureevents, 62	syncHow, 38
gesturefollower, 60	syncIdentifier, 37
gestureget, 61	syncPos, 39
gesturevariable, 62	syncStretch, 39
getMsg, 18	syncmode, 38
gmnstreamMsg, 22	time, 12
graphicSignal, 44	timeMsg, 12
gridMsg, 23	timeVar, 51
hsb, 9	transformMsg, 7
identifier, 1	txtStream, 16
int1DSegment, 34	uievt, 49
int2DSegment, 34	variable, 51

variabledecl, 55	gesture
what, 48, 49	clear, 61
widthMsg, 21	get, 62
xy, 50	size, 62
_	learn, 61
Common messages	likelihoodThreshold, 61
alias, 3	set, 61
angle, 6	gesture events
color, 8, 9	gfActive, 62
alpha, 8	gfEnter, 62
blue, 8	gfIdle, 62
brightness, 8	gfLeave, 62
green, 8	watch, 62
hue, 8	gesture follower, 60
red, 8	follow, 61
saturation, 8	learn, 61
debug	likelihoodwindow, 61
map, 24	stop, 61
name, 24	tolerance, 61
del, 4	gesture variables
dx, 6	gflikelihood, 62
dy, 6	gfpos, 62
dz, 6	gfspeed, 62
export, 4	Graphic signal
get, 18	dimension, 45
hsb, 9	set, 45
map, 33	501, 43
map+, 35	Interaction
mapf, 36	Events
save, 4	del, 50
scale, 6	doubleClick, 48
set, 15	durEnter, 49
show, 4	durLeave, 49
x, 6	endPaint, 50
у, 6	event, 49
z, 6	export, 50
	mouseDown, 48
Effect messages	mouseEnter, 48
effect	mouseLeave, 48
blur, 10	mouseLeave, 48 mouseMove, 48
colorize, 10	
none, 10	mouseUp, 48 newElement, 50
shadow, 10	· ·
	timeEnter, 49
faustprocessor	timeLeave, 49
in, 58	pop, 52
max, 58	push, 52
min, 58	variable
out, 58	absx, 50
set, 58	absy, 50
fileWatcher	address, 51
watch, 53	date, 51
watch+, 53	name, 51

rdate, 51	dred, 10
scene, 51	dsaturation, 10
sx, 50	relative
sy, 50	dangle, 6
x, 50	drotatex, 6
y, 50	drotatey, 6
y, 50 watch, 47	drotatez, 6
watch, 47 watch+, 47	dscale, 6
ITL debug	dx, 6
osc, 28	dx, 0 dxorigin, 7
ITL log	dy, 6
clear, 29	dyorigin, 7
save, 29 show, 29	dz, 6
	xorigin, 7
wrap, 29	yorigin, 7
ITL messages	Scana massagas 30
defaultShow, 25	Scene messages, 30
errport, 26	absolutexy, 30
forward, 27	del, 30
guido-version, 27	frameless, 30
hello, 25	fullscreen, 30
load, 25	load, 30
mouse, 25	new, 30
musicxml-version, 27	reset, 30
outport, 26	rootPath, 30
port, 26	Scripting
rate, 25	javascript, 56
read, 25	run, 57
require, 25	lua, 56
rootPath, 25	message based parameters, 56
ticks, 25	variable, 55
time, 25	expressions, 54
version, 27	javascript, 56
ITL stat	lua, 56
get, 28	Set type
reset, 28	curve, 15
	ellipse, 15
Position messages	fastgraph, 15
absolute	faust, 15
angle, 6	file, 16
scale, 6	gmn, 15
x, 6	gmnf, 16
y, 6	gmnstream, 15
z, 6	graph, 15
color	grid, 15
dalpha, 10	html, 15
dblue, 10	htmlf, 16
dbrightness, 10	img, 16
dcolor, 10	layer, 15
dgreen, 10	line, 15
dhsb, 10	polygon, 15
dhue, 10	rect, 15
,	, 20

15.16	
svg, 15, 16	systemCount, 22
txt, 15	write, 22
txtf, 16	width, 21
video, 16	Synchronization, 37
signal, 42	syncIdentifier, 37
parallel signal, 43	get, 37
get, 43	Guido map, 36
projection string, 44	page, 36
simple signal	staff, 36
default, 42	system, 36
del, 42	systemflat, 36
get, 42	voice, 36
reset, 42	syncHow, 38
size, 42	absolute, 38
Specific messages	relative, 38
brushColor, 21	syncmode, 38
brushStyle	syncPos, 39
bdiag, 21	syncBottom, 39
cross, 21	syncOver, 39
dense, 21	syncTop, 39
dense2, 21	syncStretch, 39
dense3, 21	h, 39
dense4, 21	hv, 39
dense5, 21	v, 39
dense6, 21	
dense7, 21	Time messages
diagCross, 21	absolute
fdiag, 21	date, 12
hor, 21	duration, 12
linearCross, 21	relative
none, 21	clock, 12
solid, 21	ddate, 12
ver, 21	dduration, 12
height, 21	durClock, 12
penAlpha, 19	Transform messages
penColor, 19	rotate, 7
pendAlpha, 19	shear, 7
penStyle, 19	
dash, 20	
dashDot, 20	
dashDot, 20	
dot, 20	
solid, 20	
penWidth, 19	
score	
clear, 22	
columns, 22	
dpage, 22	
page, 22	
pageCount, 22	
pageFormat, 22	
rows, 22	