


05 – Flow Control

CS1021 – Introduction to Computing I

Dr Jonathan Dukes | jdukes@tcd.ie School of Computer Science and Statistics Default flow of execution of a program is sequential

After executing one instruction, the next instruction in memory is executed sequentially by incrementing the program counter (PC)

To write useful programs, **sequence** needs to be combined with **selection** and **iteration**



Design and write an assembly language program to compute x^4 using repeated multiplication

```
MOV r0, #1 ; result = 1

MUL r0, r1, r0 ; result = result × value (value ^ 1)

MUL r0, r1, r0 ; result = result × value (value ^ 2)

MUL r0, r1, r0 ; result = result × value (value ^ 3)

MUL r0, r1, r0 ; result = result × value (value ^ 4)
```

Practical but inefficient and tedious for small values of y

Impractical and very inefficient and tedious for larger values

Inflexible – would like to be able to compute x^y , not just x^A

```
MOV r0, #1 ; result = 1

do y times:
    MUL r0, r1, r0 ; result = result × value
    repeat
```

For illustration purposes only! Not valid ARM Assembly Language Syntax!!

```
result = 1
while (y != 0) {
  result = result × x
  y = y - 1
}
```

Iteration

```
BEQ – Branch if EQual
```

```
; test with x = 3
       LDR r1, =3
                                ; test with y = 4
       LDR r2, =4
       MOV r0, #1
                                ; result = 1
while
       CMP r2, #0
            endwh
                                ; while (y != 0) {
       BEQ
       MUL r0, r1, r0
                                ; result = result × x
       SUB r2, r2, #1
                               ; \quad y = y - 1
           while
endwh
            stop
       В
stop
```

CMP (CoMPare) instruction performs a subtraction and updates the Condition Code Flags without storing the result of the subtraction

Subtraction allows us to determine equality (= or ≠) or inequality (< ≤ ≥ >)

Don't care about absolute value of result (i.e. don't care **by how much** x is greater than y, only whether it is or not.)

CMP always sets the Condition Code Flags – no need for **CMPS**

```
CMP r2, #0 ; subtract 0 from r2, ignoring result but
; updating the CC flags
BEQ endwh ; if the result was zero then branch to endwh
... ; otherwise (if result was not zero) then keep
; going (with sequential instruction path)
endwh
```

Pseudo-code is a useful tool for developing and documenting assembly language programs

No formally defined syntax – informally structured comments

Use any syntax that you are familiar with (and that others can read and understand!!)

Particularly helpful for developing and documenting the structure of assembly language programs

Not always a "clean" translation between pseudo-code and assembly language

Design and write an assembly language program to compute the absolute value of an integer stored in register r1. The result should also be stored in r1.

```
if (value < 0)
{
  value = 0 - value
}</pre>
```

RSB – Reverse SuBtract r = b - a instead of r = a - b

By default, the processor increments the Program Counter (PC) (by 4 bytes – 1 instruction) to "point" to the next sequential instruction in memory

causing the **sequential** path to be followed

Using a **branch** instruction, we can modify the value in the Program Counter to "point" to an instruction of our choosing

breaking the pattern of sequential execution

branch instructions can be

unconditional – always update the PC (i.e. always branch)

conditional – update the PC only if some condition is met (condition is based on Condition Code Flags, e.g. if the Zero flag is set)

```
B label ; Branch unconditionally to label

... ... ; ...
; more instructions
; ...

label some instruction ; more instructions
; ...
```

Labels ...

must be unique (within a .s file)

can contain UPPER and lower case letters, numerals and the underscore _ character

are case sensitive (mylabel is not the same label as MyLabel)

must not begin with a numeral

Unconditional branch instructions are necessary but they still result in an instruction execution path that is pre-determined when we write the program

To write useful programs, the choice of instruction execution path must be deferred until the program is running ("runtime")

i.e. the decision to take a branch or continue following the sequential path must be deferred until "runtime"

Conditional branch instructions will take a branch only if some condition is met when the branch instruction is executed

otherwise the processor continues to follow the sequential path

Design and write an assembly language program that evaluates the function max(a, b), where a and b are integers stored in r1 and r2 respectively. The result should be stored in r0.

```
if (a ≥ b) {
    max = a
} else {
    max = b
}
```

BLT – Branch if Less Than

i.e. from a preceding **CMP a,b** branch if a < b

```
LDR
             r1, =5
                                      ; test with a = 5
                                      ; test with b = 6
       LDR r2, =6
             r1, r2
                                      ; if (a \ge b)
       CMP
             elsmaxb
       BLT
             r0, r1
       MOV
                                      ; max = a
             endab
       B
elsmaxb
                                      ; else {
       MOV
             r0, r2
                                         max = b
endab
                                      ;
```

Symbol	Java	Instruction	Mnemonic							
		Equality								
=	==	BEQ	EQual							
≠	!=	BNE	Not Equal							
Inequality (unsigned values)										
<	<	BLO (or BCC)	LOwer							
<u>≤</u>	<=	BLS	Lower or Same							
<u>></u>	>=	BHS (or BCS)	Higher or Same							
>	>	BHI	HIgher							
Inequality (signed values)										
<	<	BLT	Less Than							
\leq	<=	BLE	Less than or Equal							
\geq	>=	BGE	Greater than or Equal							
>	>	BGT	Greater Than							
Flags										
		BMI	MInus							
		BPL	PLus							
		BCS (or BHS)	Carry Set							
		BCC (or BLO)	Carry Clear							
		BVS	oVerflow Set							
		BVC	oVerflow Clear							
		BEQ	EQual							
		BNE	Not Equal							
	= ≠ < < < < < < < < < < < < < < < < < <	= ==	Equality = == BEQ ≠ != BNE Inequality (unsigned values) < < BLO (or BCC) ≤ <= BLS ≥ >= BHS (or BCS) > BHI Inequality (signed values) < < BLT < = BLE ≥ >= BGE > > BGE > BMI BPL BCS (or BHS) BCC (or BLO) BVS BVC BEQ							

ARM Conditional Branch Instructions

Description	Symbol	Java	Instruction	Mnemonic
Equality				
equal	=	==	BEQ	EQ ual
not equal	≠	! =	BNE	Not Equal
Inequality (unsigned values	s)			
less than	<	<	BLO (or BCC)	LOwer
less than or equal	≤	<=	BLS	Lower or Same
greater than or equal	2	>=	BHS (or BCS)	Higher or Same
greater than	>	>	BHI	HI gher
Inequality (signed values)				
less than	<	<	BLT	Less Than
less than or equal	≤	<=	BLE	Less than or Equal
greater than or equal	≥	>=	BGE	Greater than or Equal
greater than	>	>	BGT	Greater Than
Flags				
Negative Set			BMI	MInus
Negative Clear			BPL	PL us
Carry Set			BCS (or BHS)	Carry Set
Carry Clear			BCC (or BLO)	Carry Clear
Overflow Set			BVS	oVerflow Set
Overflow Clear			BVC	oVerflow Clear
Zero Set			BEQ	EQ ual
Zero Clear			BNE	Not Equal

Equality and Inequality Mnemonics are based on a previous execution of a compare (CMP) instruction of the form CMP Rx, Ry. For example, BLE label will branch to label if Rx is less than or equal to Ry.

Pseudo Code Examples

Pseudo Code		ARM As	ARM Assembly Language		
<pre>if (x <= y) { x = x + 1; }</pre>	assume x and y are <u>signed</u> values	label	CMP BGT ADD		
<pre>if (x < y) { z = x; } else { z = y; }</pre>	assume x and y are <u>unsigned</u> values	label1 label2	CMP BHS MOV B	•	
<pre>while (x > 2) { y = x * y; x = x - 1; }</pre>	assume x and y are <u>unsigned</u> values	label1	CMP BLS MUL SUB B	<u> </u>	

ARM Flow Control "Cheat Sheet" available on Blackboard

Not available in exams, but you will have access to more formal documentation, including a description of each conditional branch instruction

Design and write an assembly language program to compute n!, where n is a non-negative integer stored in register r0

$$n! = \prod_{k=1}^{n} k \quad \forall n \in \mathbb{N}$$

```
result = 1
tmp = value

while (tmp > 1) {
    result = result * tmp
    tmp = tmp - 1
}
```

```
LDR r1, =6
                           ; test value = 6
     MOV r0, #1
                           ; result = 1
     MOVS r2, r1
                           ; tmp = value
whmul CMP r2, #1
                           ; while (tmp > 1)
     BLS endwhmul
     MUL r0, r2, r0 ; result = result \times tmp
     SUB r2, r2, \#1; tmp = tmp - 1
     B whmul
endwhmul
```

BLS – Branch if Lower or Same (unsigned ≤) – evaluates Carry and Zero flags

Use CMP to subtract 1 from r2

If r2 < 1 there will be a "borrow-in" so the Carry flag will be clear (R2 + TC(1) would clear C flag)

If r2 == 1 the Zero flag will be set

So ... branch if c clear or Z set

Template for if-then construct

Template for if-then-else construct

```
if ( <condition> )
{
      <if body>
}
else {
      <else body>
}
<rest of program>
```

```
CMP variables or constants in <condition>

Bxx elselabel on opposite <condition>
<if body>

B endiflabel unconditionally

elselabel

<else body>
endiflabel

<rest of program>
```

Template for while construct

```
<initialize>

while ( <condition> )
{
      <body>
}
<rest of program>
```

```
whilelabel

CMP variables or constants in <condition>
    Bxx endwhlabel on opposite <condition>
    <body>
    B whilelabel unconditionally
endwhlabel
    <rest of program>
```

Template for do-while construct

```
<initialize>
do {
        <body>
} while
( <condition> )

<rest of program>
```

The *n*th Fibonacci number is defined as follows:

$$F_n = F_{n-2} + F_{n-1}$$

with
$$F_0 = 0$$
 and $F_1 = 1$

Design and write an assembly language program to compute the n^{th} Fibonacci number, F_n , where n is stored in register R1.

```
fn1 = 0
fn = 1
curr = 1
while (curr < n)
       curr = curr + 1
       tmp = fn
       fn = fn + fn1
       fn1 = tmp
```

```
start
      LDR r1, =4
                             ; test with n = 4
                             ; fn1 = 0
      MOV r3, #0
      MOV r0, #1
                             ; fn = 1
      MOV r2, #1
                             ; curr = 1
                             ; while (curr < n)
      CMP r2, r1
whn
          endwhn
      BHS
      ADD r2, r2, #1
                             ; curr = curr + 1
      MOV r4, r0
                             ; tmp = fn
      ADD r0, r0, r3
                             ; fn = fn + fn1
          r3, r4
                             ; fn1 = tmp
      MOV
          whn
endwhn
```

```
if (x ≥ 40 AND x < 50)
{
    y = y + 1
}</pre>
```

Test each condition and if any one fails, branch to end of if-then construct (or if they all succeed, execute the body)

```
r1, #40
                                    ; if (x \ge 40)
       CMP
             endif
       BLO
                                    ; AND
             r1, #50
                                    ; x < 50)
       CMP
             endif
       BHS
                                    y = y + 1
       ADD r2, r2, #1
endif
        • • •
              • • •
```

```
if (x < 40 OR x ≥ 50)
{
    z = z + 1
}</pre>
```

Test each condition and if they all fail, branch to end of if-then construct (or if any test succeeds, execute the body without testing further conditions)

```
r1, #40
                                     ; if (x < 40)
        CMP
              then
        BLO
                                     ; x \ge 50)
              r1, #50
        CMP
              endif
        BLO
then
        ADD
              r2, r2, #1
                                      y = y + 1
endif
        • • •
               • • •
```

Design and write an assembly language program that will convert the ASCII character stored in r0 to UPPER CASE, if the character is a lower case letter (a-z)

Can convert lower case to UPPER CASE by subtracting 0x20 from the ASCII code

```
if (char ≥ 'a' AND char ≤ 'z')
{
    char = char - 0x20
}
```

```
LDR r0, ='d' ; test with char = 'h'

CMP r0, #'a' ; if (char ≥ 'a'

BLO notLcAlpha ; &&

CMP r0, #'z' ; char ≤ 'z')

BHI notLcAlpha ; {

SUB r0, r0, #0x20 ; char = char - 0x20

notLcAlpha ; }
```

Algorithm ignores characters not in the range ['a', 'z']

Note use of #'a', #'z' for convenience instead of #61 and #7A

Assembler converts ASCII symbol to character code