

### NAME

IO::Compress::Deflate - Write RFC 1950 files/buffers

## **SYNOPSIS**

```
use IO::Compress::Deflate qw(deflate $DeflateError) ;
my $status = deflate $input => $output [,OPTS]
    or die "deflate failed: $DeflateError\n";
my $z = new IO::Compress::Deflate $output [,OPTS]
    or die "deflate failed: $DeflateError\n";
$z->print($string);
$z->printf($format, $string);
$z->write($string);
$z->syswrite($string[, $length, $offset]);
$z->flush();
$z->tell();
$z->eof();
$z->seek($position, $whence);
$z->binmode();
$z->fileno();
$z->opened();
$z->autoflush();
$z->input_line_number();
$z->newStream( [OPTS] );
$z->deflateParams();
$z->close() ;
$DeflateError ;
# IO::File mode
print $z $string;
printf $z $format, $string;
tell $z
eof $z
seek $z, $position, $whence
binmode $z
fileno $z
close $z ;
```

# **DESCRIPTION**

This module provides a Perl interface that allows writing compressed data to files or buffer as defined in RFC 1950.

For reading RFC 1950 files/buffers, see the companion module IO::Uncompress::Inflate.



## **Functional Interface**

A top-level function, deflate, is provided to carry out "one-shot" compression between buffers and/or files. For finer control over the compression process, see the *OO Interface* section.

```
use IO::Compress::Deflate qw(deflate $DeflateError) ;
deflate $input => $output [,OPTS]
    or die "deflate failed: $DeflateError\n";
```

The functional interface needs Perl5.005 or better.

## deflate \$input => \$output [, OPTS]

deflate expects at least two parameters, \$input and \$output.

### The \$input parameter

The parameter, \$input, is used to define the source of the uncompressed data.

It can take one of the following forms:

#### A filename

If the \$input parameter is a simple scalar, it is assumed to be a filename. This file will be opened for reading and the input data will be read from it.

#### A filehandle

If the \$input parameter is a filehandle, the input data will be read from it. The string '-' can be used as an alias for standard input.

#### A scalar reference

If \$input is a scalar reference, the input data will be read from \$\$input.

#### An array reference

If \$input is an array reference, each element in the array must be a filename.

The input data will be read from each file in turn.

The complete array will be walked to ensure that it only contains valid filenames before any data is compressed.

# An Input FileGlob string

If \$input is a string that is delimited by the characters "<" and ">" deflate will assume that it is an *input fileglob string*. The input is the list of files that match the fileglob.

If the fileglob does not match any files ...

See File::GlobMapper for more details.

If the \$input parameter is any other type, undef will be returned.

## The \$output parameter

The parameter \$output is used to control the destination of the compressed data. This parameter can take one of these forms.

#### A filename

If the \$output parameter is a simple scalar, it is assumed to be a filename. This file will be opened for writing and the compressed data will be written to it.

#### A filehandle

If the \$output parameter is a filehandle, the compressed data will be written to it. The string '-' can be used as an alias for standard output.



#### A scalar reference

If \$output is a scalar reference, the compressed data will be stored in \$\$output.

#### An Array Reference

If \$output is an array reference, the compressed data will be pushed onto the array.

#### An Output FileGlob

If \$output is a string that is delimited by the characters "<" and ">" deflate will assume that it is an *output fileglob string*. The output is the list of files that match the fileglob.

When \$output is an fileglob string, \$input must also be a fileglob string. Anything else is an error.

If the \$output parameter is any other type, undef will be returned.

#### **Notes**

When \$input maps to multiple files/buffers and \$output is a single file/buffer the input files/buffers will be stored in \$output as a concatenated series of compressed data streams.

# **Optional Parameters**

Unless specified below, the optional parameters for deflate, OPTS, are the same as those used with the OO interface defined in the *Constructor Options* section below.

```
AutoClose => 0|1
```

This option applies to any input or output data streams to deflate that are filehandles.

If AutoClose is specified, and the value is true, it will result in all input and/or output filehandles being closed once deflate has completed.

This parameter defaults to 0.

```
BinModeIn => 0|1
```

When reading from a file or filehandle, set binmode before reading.

Defaults to 0.

```
Append => 0 | 1
TODO
```

## **Examples**

To read the contents of the file file1.txt and write the compressed data to the file file1.txt.1950.

```
use strict ;
use warnings ;
use IO::Compress::Deflate qw(deflate $DeflateError) ;

my $input = "file1.txt";
deflate $input => "$input.1950"
    or die "deflate failed: $DeflateError\n";
```

To read from an existing Perl filehandle, \$input, and write the compressed data to a buffer, \$buffer.

```
use strict ;
use warnings ;
use IO::Compress::Deflate qw(deflate $DeflateError) ;
use IO::File ;
```



```
my $input = new IO::File "<file1.txt"
    or die "Cannot open 'file1.txt': $!\n";
my $buffer;
deflate $input => \$buffer
    or die "deflate failed: $DeflateError\n";
```

To compress all files in the directory "/my/home" that match "\*.txt" and store the compressed data in the same directory

```
use strict ;
use warnings ;
use IO::Compress::Deflate qw(deflate $DeflateError) ;

deflate '</my/home/*.txt>' => '<*.1950>'
    or die "deflate failed: $DeflateError\n";
```

and if you want to compress each file one at a time, this will do the trick

```
use strict ;
use warnings ;
use IO::Compress::Deflate qw(deflate $DeflateError) ;

for my $input ( glob "/my/home/*.txt" )
{
    my $output = "$input.1950" ;
    deflate $input => $output
        or die "Error compressing '$input': $DeflateError\n";
}
```

# **OO** Interface

# Constructor

The format of the constructor for IO::Compress::Deflate is shown below

```
my $z = new IO::Compress::Deflate $output [,OPTS]
    or die "IO::Compress::Deflate failed: $DeflateError\n";
```

It returns an IO::Compress::Deflate object on success and undef on failure. The variable \$DeflateError will contain an error message on failure.

If you are running Perl 5.005 or better the object, \$z, returned from IO::Compress::Deflate can be used exactly like an *IO::File* filehandle. This means that all normal output file operations can be carried out with \$z. For example, to write to a compressed file/buffer you can use either of these forms

```
$z->print("hello world\n");
print $z "hello world\n";
```

The mandatory parameter \$output is used to control the destination of the compressed data. This parameter can take one of these forms.

A filename

If the \$output parameter is a simple scalar, it is assumed to be a filename. This file will be opened for writing and the compressed data will be written to it.

A filehandle



If the <code>soutput</code> parameter is a filehandle, the compressed data will be written to it. The string '-' can be used as an alias for standard output.

## A scalar reference

If \$output is a scalar reference, the compressed data will be stored in \$\$output.

If the \$output parameter is any other type, IO::Compress::Deflate::new will return undef.

## **Constructor Options**

OPTS is any combination of the following options:

This option is only valid when the <code>\$output</code> parameter is a filehandle. If specified, and the value is true, it will result in the <code>\$output</code> being closed once either the <code>close</code> method is called or the <code>IO::Compress::Deflate</code> object is destroyed.

This parameter defaults to 0.

Append  $\Rightarrow$  0 | 1

Opens \$output in append mode.

The behaviour of this option is dependent on the type of \$output.

# \* A Buffer

If \$output is a buffer and Append is enabled, all compressed data will be append to the end if \$output. Otherwise \$output will be cleared before any data is written to it.

#### \* A Filename

If \$output is a filename and Append is enabled, the file will be opened in append mode. Otherwise the contents of the file, if any, will be truncated before any compressed data is written to it.

## \* A Filehandle

If \$output is a filehandle, the file pointer will be positioned to the end of the file via a call to seek before any compressed data is written to it. Otherwise the file pointer will not be moved.

This parameter defaults to 0.

Merge 
$$\Rightarrow$$
 0|1

This option is used to compress input data and append it to an existing compressed data stream in \$output. The end result is a single compressed data stream stored in \$output.

It is a fatal error to attempt to use this option when \$output is not an RFC 1950 data stream.

There are a number of other limitations with the Merge option:

- This module needs to have been built with zlib 1.2.1 or better to work. A fatal error will be thrown if Merge is used with an older version of zlib.
- 2 If \$output is a file or a filehandle, it must be seekable.

This parameter defaults to 0.

### -Level

Defines the compression level used by zlib. The value should either be a number between 0 and 9 (0 means no compression and 9 is maximum compression), or one of the symbolic constants defined below.

Z\_NO\_COMPRESSION



```
Z_BEST_SPEED
Z_BEST_COMPRESSION
Z_DEFAULT_COMPRESSION
```

#### The default is Z\_DEFAULT\_COMPRESSION.

Note, these constants are not imported by IO::Compress::Deflate by default.

```
use IO::Compress::Deflate qw(:strategy);
use IO::Compress::Deflate qw(:constants);
use IO::Compress::Deflate qw(:all);
```

## -Strategy

Defines the strategy used to tune the compression. Use one of the symbolic constants defined below.

```
Z_FILTERED
Z_HUFFMAN_ONLY
Z_RLE
Z_FIXED
Z_DEFAULT_STRATEGY
```

#### The default is Z\_DEFAULT\_STRATEGY.

```
Strict \Rightarrow 0|1
```

This is a placeholder option.

### **Examples**

**TODO** 

## **Methods**

# print

## Usage is

```
$z->print($data)
print $z $data
```

Compresses and outputs the contents of the \$data parameter. This has the same behaviour as the print built-in.

Returns true if successful.

# printf

## Usage is

```
$z->printf($format, $data)
printf $z $format, $data
```

Compresses and outputs the contents of the \$data parameter.

Returns true if successful.

# syswrite

#### Usage is

```
$z->syswrite $data
$z->syswrite $data, $length
$z->syswrite $data, $length, $offset
```



Compresses and outputs the contents of the \$data parameter.

Returns the number of uncompressed bytes written, or undef if unsuccessful.

#### write

Usage is

```
$z->write $data
$z->write $data, $length
$z->write $data, $length, $offset
```

Compresses and outputs the contents of the \$data parameter.

Returns the number of uncompressed bytes written, or undef if unsuccessful.

#### flush

Usage is

```
$z->flush;
$z->flush($flush_type);
```

Flushes any pending compressed data to the output file/buffer.

This method takes an optional parameter, \$flush\_type, that controls how the flushing will be carried out. By default the \$flush\_type used is Z\_FINISH. Other valid values for \$flush\_type are Z\_NO\_FLUSH, Z\_SYNC\_FLUSH, Z\_FULL\_FLUSH and Z\_BLOCK. It is strongly recommended that you only set the flush\_type parameter if you fully understand the implications of what it does overuse of flush can seriously degrade the level of compression achieved. See the zlib documentation for details.

Returns true on success.

#### tell

Usage is

```
$z->tell()
tell $z
```

Returns the uncompressed file offset.

#### eof

Usage is

```
$z->eof();
eof($z);
```

Returns true if the close method has been called.

### seek

```
$z->seek($position, $whence);
seek($z, $position, $whence);
```

Provides a sub-set of the seek functionality, with the restriction that it is only legal to seek forward in the output file/buffer. It is a fatal error to attempt to seek backward.

Empty parts of the file/buffer will have NULL (0x00) bytes written to them.

The \$whence parameter takes one the usual values, namely SEEK\_SET, SEEK\_CUR or



SEEK END.Returns 1 on success, 0 on failure.

### binmode

Usage is

```
$z->binmode
binmode $z ;
```

This is a noop provided for completeness.

# opened

```
$z->opened()
```

Returns true if the object currently refers to a opened file/buffer.

#### autoflush

```
my $prev = $z->autoflush()
my $prev = $z->autoflush(EXPR)
```

If the \$z object is associated with a file or a filehandle, this method returns the current autoflush setting for the underlying filehandle. If EXPR is present, and is non-zero, it will enable flushing after every write/print operation.

If \$z is associated with a buffer, this method has no effect and always returns undef.

Note that the special variable \$ | cannot be used to set or retrieve the autoflush setting.

## input\_line\_number

```
$z->input_line_number()
$z->input_line_number(EXPR)
```

This method always returns undef when compressing.

### fileno

```
$z->fileno()
fileno($z)
```

If the \$z object is associated with a file or a filehandle, this method will return the underlying file descriptor.

If the \$z object is is associated with a buffer, this method will return undef.

## close

```
$z->close() ;
close $z ;
```

Flushes any pending compressed data and then closes the output file/buffer.

For most versions of Perl this method will be automatically invoked if the IO::Compress::Deflate object is destroyed (either explicitly or by the variable with the reference to the object going out of scope). The exceptions are Perl versions 5.005 through 5.00504 and 5.8.0. In these cases, the close method will be called automatically, but not until global destruction of all live objects when the program is terminating.

Therefore, if you want your scripts to be able to run on all versions of Perl, you should call close explicitly and not rely on automatic closing.



Returns true on success, otherwise 0.

If the AutoClose option has been enabled when the IO::Compress::Deflate object was created, and the object is associated with a file, the underlying file will also be closed.

# newStream([OPTS])

```
Usage is
```

```
$z->newStream( [OPTS] )
```

Closes the current compressed data stream and starts a new one.

OPTS consists of any of the the options that are available when creating the \$z object.

See the Constructor Options section for more details.

### deflateParams

```
Usage is
```

```
$z->deflateParams
```

#### **TODO**

# **Importing**

A number of symbolic constants are required by some methods in IO::Compress::Deflate. None are imported by default.

:all

```
Imports deflate, DeflateError and all symbolic constants that can be used by IO::Compress::Deflate. Same as doing this
```

```
use IO::Compress::Deflate qw(deflate $DeflateError :constants) ;
```

#### :constants

Import all symbolic constants. Same as doing this

```
use IO::Compress::Deflate qw(:flush :level :strategy) ;
```

:flush

These symbolic constants are used by the flush method.

```
Z_NO_FLUSH
Z_PARTIAL_FLUSH
Z_SYNC_FLUSH
Z_FULL_FLUSH
Z_FINISH
Z_BLOCK
```

:level

These symbolic constants are used by the Level option in the constructor.

```
Z_NO_COMPRESSION
Z_BEST_SPEED
Z_BEST_COMPRESSION
Z_DEFAULT_COMPRESSION
```

:strategy



These symbolic constants are used by the Strategy option in the constructor.

Z FILTERED

Z\_HUFFMAN\_ONLY

Z RLE

Z FIXED

Z\_DEFAULT\_STRATEGY

For

## **EXAMPLES**

**TODO** 

## **SEE ALSO**

Compress::Zlib, IO::Compress::Gzip, IO::Uncompress::Gunzip, IO::Uncompress::Inflate,

IO::Compress::RawDeflate, IO::Uncompress::RawInflate, IO::Compress::Bzip2,

IO::Uncompress::Bunzip2, IO::Compress::Lzop, IO::Uncompress::UnLzop, IO::Compress::Lzf,

IO::Uncompress::UnLzf, IO::Uncompress::AnyInflate, IO::Uncompress::AnyUncompress

Compress::Zlib::FAQ

File::GlobMapper, Archive::Zip, Archive::Tar, IO::Zlib

For RFC 1950, 1951 and 1952 see http://www.faqs.org/rfcs/rfc1950.html, http://www.faqs.org/rfcs/rfc1951.html and http://www.faqs.org/rfcs/rfc1952.html

The zlib compression library was written by Jean-loup Gailly gzip@prep.ai.mit.edu and Mark Adler madler@alumni.caltech.edu.

The primary site for the zlib compression library is http://www.zlib.org.

The primary site for gzip is http://www.gzip.org.

## **AUTHOR**

This module was written by Paul Marquess, pmqs@cpan.org.

### MODIFICATION HISTORY

See the Changes file.

## **COPYRIGHT AND LICENSE**

Copyright (c) 2005-2007 Paul Marquess. All rights reserved.

This program is free software; you can redistribute it and/or modify it under the same terms as Perl itself.