streamout

Generated by Doxygen 1.9.3

1	Hierarchical Index	1
	1.1 Class Hierarchy	1
2	Class Index	1
	2.1 Class List	1
2	File Index	2
•	3.1 File List	2
_		_
4	Class Documentation	4
	4.1 Buffer Class Reference	4
	4.1.1 Detailed Description	4
	4.1.2 Constructor & Destructor Documentation	4
	4.1.3 Member Function Documentation	5
	4.2 BufferLooper < SOURCE, DESTINATION > Class Template Reference	7
	4.2.1 Detailed Description	7
	4.2.2 Constructor & Destructor Documentation	7
	4.2.3 Member Function Documentation	8
	4.3 BufferLooperCounter Struct Reference	11
	4.3.1 Detailed Description	11
	4.3.2 Member Function Documentation	11
	4.3.3 Member Data Documentation	12
	4.4 DIF Class Reference	13
	4.4.1 Detailed Description	14
	4.4.2 Member Function Documentation	14
	4.5 DIFPtr Class Reference	16
	4.5.1 Detailed Description	16
	4.6 DIFSlowControl Class Reference	18
	4.6.1 Detailed Description	19
	4.6.2 Constructor & Destructor Documentation	19
	4.6.3 Member Function Documentation	19
	4.7 Event Class Reference	21
	4.7.1 Detailed Description	21
	4.7.2 Member Function Documentation	21
	4.8 Exception Class Reference	22
	4.8.1 Detailed Description	22
	4.8.2 Constructor & Destructor Documentation	22
	4.8.3 Member Function Documentation	23
	4.9 Hit Class Reference	23
	4.9.1 Detailed Description	23 24
	4.9.2 Member Function Documentation	24
	4.10 Interface Class Reference	2 4 27
	4.10.1 Detailed Description	28

	4.10.2 Constructor & Destructor Documentation	28
	4.10.3 Member Function Documentation	28
	4.11 InterfaceReader Class Reference	30
	4.11.1 Detailed Description	31
	4.11.2 Constructor & Destructor Documentation	31
	4.11.3 Member Data Documentation	31
	4.12 InterfaceWriter Class Reference	32
	4.12.1 Detailed Description	32
	4.12.2 Constructor & Destructor Documentation	32
	4.12.3 Member Function Documentation	32
	4.13 PayloadParser Class Reference	33
	4.13.1 Detailed Description	34
	4.13.2 Constructor & Destructor Documentation	34
	4.13.3 Member Function Documentation	34
	4.14 RawBufferNavigator Class Reference	39
	4.14.1 Detailed Description	39
	4.14.2 Constructor & Destructor Documentation	40
	4.14.3 Member Function Documentation	40
	4.15 RawdataReader Class Reference	41
	4.15.1 Detailed Description	42
	4.15.2 Constructor & Destructor Documentation	42
	4.15.3 Member Function Documentation	42
	4.16 ROOTWriter Class Reference	45
	4.16.1 Detailed Description	45
	4.16.2 Constructor & Destructor Documentation	45
	4.16.3 Member Function Documentation	45
	4.17 textDump Class Reference	49
	4.17.1 Detailed Description	49
	4.17.2 Constructor & Destructor Documentation	49
	4.17.3 Member Function Documentation	49
	4.18 Timer Class Reference	51
	4.18.1 Detailed Description	51
	4.18.2 Member Function Documentation	51
	4.19 Version Class Reference	52
	4.19.1 Detailed Description	52
	4.19.2 Constructor & Destructor Documentation	52
	4.19.3 Member Function Documentation	53
5.5	File Documentation	54
J	5.1 libs/core/include/Bits.h File Reference	5 4
	5.1.1 Detailed Description	54 54
	5.1.1 Detailed Description	54 54

5.1.3 Function Documentation	55
5.2 Bits.h	55
5.3 libs/core/include/Buffer.h File Reference	55
5.3.1 Detailed Description	56
5.4 Buffer.h	56
5.5 libs/core/include/BufferLooper.h File Reference	57
5.5.1 Detailed Description	57
5.6 BufferLooper.h	57
5.7 libs/core/include/BufferLooperCounter.h File Reference	30
5.7.1 Detailed Description	31
5.8 BufferLooperCounter.h	31
5.9 libs/core/include/DetectorId.h File Reference	31
5.9.1 Detailed Description	31
5.9.2 Enumeration Type Documentation	31
5.10 DetectorId.h	32
5.11 libs/core/include/DIFSlowControl.h File Reference	32
5.11.1 Detailed Description	32
5.11.2 Function Documentation	33
5.12 DIFSlowControl.h	33
5.13 libs/core/include/Exception.h File Reference	34
5.13.1 Detailed Description	34
5.14 Exception.h	34
5.15 libs/core/include/Filesystem.h File Reference	35
5.15.1 Detailed Description	35
5.15.2 Function Documentation	35
5.16 Filesystem.h	36
5.17 libs/core/include/Formatters.h File Reference	36
5.17.1 Detailed Description	36
5.17.2 Function Documentation	36
5.18 Formatters.h	70
5.19 libs/core/include/Interface.h File Reference	70
5.19.1 Detailed Description	71
5.19.2 Enumeration Type Documentation	71
5.20 Interface.h	72
5.21 libs/core/include/PayloadParser.h File Reference	73
5.21.1 Detailed Description	73
5.22 PayloadParser.h	73
5.23 libs/core/include/RawBufferNavigator.h File Reference	77
5.23.1 Detailed Description	77
5.24 RawBufferNavigator.h	77
5.25 libs/core/include/Timer.h File Reference	78
5.25.1 Detailed Description	78

5.26 Timer.h	78
5.27 libs/core/include/Utilities.h File Reference	78
5.27.1 Detailed Description	78
5.27.2 Function Documentation	79
5.28 Utilities.h	79
5.29 libs/core/include/Version.h File Reference	79
5.29.1 Detailed Description	79
5.30 Version.h	80
5.31 libs/core/include/Words.h File Reference	80
5.31.1 Detailed Description	80
5.31.2 Enumeration Type Documentation	81
5.32 Words.h	83
5.33 libs/core/src/Bits.cc File Reference	84
5.33.1 Detailed Description	84
5.33.2 Function Documentation	84
5.34 Bits.cc	84
5.35 libs/core/src/BufferLooperCounter.cc File Reference	84
5.36 BufferLooperCounter.cc	85
5.37 libs/core/src/DIFSlowControl.cc File Reference	85
5.37.1 Detailed Description	85
5.37.2 Function Documentation	85
5.38 DIFSlowControl.cc	86
5.39 libs/core/src/Filesystem.cc File Reference	89
5.39.1 Detailed Description	89
5.39.2 Function Documentation	89
5.40 Filesystem.cc	90
5.41 libs/core/src/Formatters.cc File Reference	90
5.41.1 Detailed Description	91
5.41.2 Function Documentation	91
5.42 Formatters.cc	95
5.43 libs/core/src/RawBufferNavigator.cc File Reference	96
5.43.1 Detailed Description	96
5.44 RawBufferNavigator.cc	96
5.45 libs/core/src/Version.cc File Reference	97
5.45.1 Detailed Description	97
5.46 Version.cc	97
5.47 libs/interface/Dump/include/textDump.h File Reference	98
5.47.1 Detailed Description	98
5.48 textDump.h	98
5.49 libs/interface/Dump/src/textDump.cc File Reference	99
5.49.1 Detailed Description	99
5.50 textDump.cc	99

5.51 libs/interface/LCIO/include/LCIOWriter.h File Reference	99
5.51.1 Detailed Description	99
5.52 LCIOWriter.h	100
5.53 libs/interface/LCIO/src/LCIOWriter.cc File Reference	100
5.53.1 Detailed Description	100
5.54 LCIOWriter.cc	100
5.55 libs/interface/RawDataReader/include/RawdataReader.h File Reference	100
5.55.1 Detailed Description	100
5.56 RawdataReader.h	101
5.57 libs/interface/RawDataReader/src/RawdataReader.cc File Reference	101
5.57.1 Detailed Description	101
5.58 RawdataReader.cc	102
5.59 libs/interface/ROOT/include/DIF.h File Reference	103
5.59.1 Detailed Description	103
5.59.2 Typedef Documentation	104
5.60 DIF.h	104
5.61 libs/interface/ROOT/include/DIFLinkDef.h File Reference	104
5.61.1 Detailed Description	104
5.62 DIFLinkDef.h	105
5.63 libs/interface/ROOT/include/Event.h File Reference	105
5.63.1 Detailed Description	105
5.63.2 Typedef Documentation	105
5.64 Event.h	106
5.65 libs/interface/ROOT/include/EventLinkDef.h File Reference	106
5.65.1 Detailed Description	106
5.66 EventLinkDef.h	106
5.67 libs/interface/ROOT/include/Hit.h File Reference	106
5.67.1 Detailed Description	107
5.68 Hit.h	107
5.69 libs/interface/ROOT/include/HitLinkDef.h File Reference	107
5.69.1 Detailed Description	107
5.70 HitLinkDef.h	108
5.71 libs/interface/ROOT/include/ROOTWriter.h File Reference	108
5.72 ROOTWriter.h	108
5.73 libs/interface/ROOT/src/DIF.cc File Reference	109
5.73.1 Detailed Description	109
5.74 DIF.cc	109
5.75 libs/interface/ROOT/src/Event.cc File Reference	109
5.75.1 Detailed Description	109
5.76 Event.cc	110
5.77 libs/interface/ROOT/src/Hit.cc File Reference	110
5.77.1 Detailed Description	110

1 Hierarchical Index

5.78 Hit.cc	110
5.79 libs/interface/ROOT/src/ROOTWriter.cc File Reference	111
5.79.1 Detailed Description	111
5.80 ROOTWriter.cc	111
1 Hierarchical Index	
1.1 Class Hierarchy	
This inheritance list is sorted roughly, but not completely, alphabetically:	
Buffer	4
PayloadParser	33
${\bf Buffer Looper} {<} {\bf SOURCE,DESTINATION} {>}$	7
BufferLooperCounter	11
DIFPtr	16
DIFSlowControl	18
Exception	22
Interface	27
InterfaceReader	30
RawdataReader	41
InterfaceWriter	32
ROOTWriter	45
textDump	49
RawBufferNavigator	39
Timer TObject	51
DIF	13
Event	21
Hit semver::version	23
Version	52

2 Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

	Buffer	4
	BufferLooper < SOURCE, DESTINATION >	7
	BufferLooperCounter	11
	DIF	13
	DIFPtr M3 MICROROC and HARDROC2 dataformat	16
	DIFSlowControl	18
	Event	21
	Exception	22
	Hit	23
	Interface	27
	InterfaceReader	30
	InterfaceWriter	32
	PayloadParser	33
	RawBufferNavigator Class to navigate in the raw data buffer parse the header and send the payload as Buffer	39
	RawdataReader	41
	ROOTWriter	45
	textDump	49
	Timer	51
	Version	52
3	File Index	
3.	.1 File List	
Н	ere is a list of all files with brief descriptions:	
	libs/core/include/Bits.h	54
	libs/core/include/Buffer.h	55
	libs/core/include/BufferLooper.h	57
	libs/core/include/BufferLooperCounter.h	60
	libs/core/include/DetectorId.h	61
	libs/core/include/DIFSlowControl.h	62
	libs/core/include/Exception.h	64

3.1 File List 3

libs/core/include/Filesystem.h	65
libs/core/include/Formatters.h	66
libs/core/include/Interface.h	70
libs/core/include/PayloadParser.h	73
libs/core/include/RawBufferNavigator.h	77
libs/core/include/Timer.h	78
libs/core/include/Utilities.h	78
libs/core/include/Version.h	79
libs/core/include/Words.h	80
libs/core/src/Bits.cc	84
libs/core/src/BufferLooperCounter.cc	84
libs/core/src/DIFSlowControl.cc	85
libs/core/src/Filesystem.cc	89
libs/core/src/Formatters.cc	90
libs/core/src/RawBufferNavigator.cc	96
libs/core/src/Version.cc	97
libs/interface/Dump/include/textDump.h	98
libs/interface/Dump/src/textDump.cc	99
libs/interface/LCIO/include/LCIOWriter.h	99
libs/interface/LCIO/src/LCIOWriter.cc	100
libs/interface/RawDataReader/include/RawdataReader.h	100
libs/interface/RawDataReader/src/RawdataReader.cc	101
libs/interface/ROOT/include/DIF.h	103
libs/interface/ROOT/include/DIFLinkDef.h	104
libs/interface/ROOT/include/Event.h	105
libs/interface/ROOT/include/EventLinkDef.h	106
libs/interface/ROOT/include/Hit.h	106
libs/interface/ROOT/include/HitLinkDef.h	107
libs/interface/ROOT/include/ROOTWriter.h	108
libs/interface/ROOT/src/DIF.cc	109
libs/interface/ROOT/src/Event.cc	109
libs/interface/ROOT/src/Hit.cc	110


111

4 Class Documentation

4.1 Buffer Class Reference

#include <libs/core/include/Buffer.h>

Inheritance diagram for Buffer:



Public Member Functions

- Buffer ()
- virtual ∼Buffer ()
- Buffer (const bit8_t b[], const std::size_t &i)
- Buffer (const char b[], const std::size_t &i)
- template<typename T >

Buffer (const std::vector< T > &rawdata)

- template<typename T, std::size_t N>
 Buffer (const std::array< T, N > &rawdata)
- std::size_t size () const
- std::size_t capacity () const
- bool empty ()
- void set (unsigned char *b)
- void set (const Buffer &buffer)
- bit8_t * begin () const
- $bit8_t * end () const$
- bit8_t & operator[] (const std::size_t &pos)
- bit8_t & operator[] (const std::size_t &pos) const
- void setSize (const std::size_t &size)

4.1.1 Detailed Description

Definition at line 14 of file Buffer.h.

4.1.2 Constructor & Destructor Documentation

```
4.1.2.1 Buffer() [1/5] Buffer::Buffer ( ) [inline]
Definition at line 17 of file Buffer.h.
00017 : m_Buffer(nullptr), m_Size(0), m_Capacity(0) {}
4.1.2.2 ~Buffer() virtual Buffer::~Buffer () [inline], [virtual]
Definition at line 18 of file Buffer.h.
00018 {}
4.1.2.3 Buffer() [2/5] Buffer::Buffer (
             const bit8_t b[],
             const std::size_t & i ) [inline]
Definition at line 19 of file Buffer.h.
00019 : m_Buffer(const_cast < bit8_t *> (&b[0])), m_Size(i), m_Capacity(i) {}
4.1.2.4 Buffer() [3/5] Buffer::Buffer (
             const char b[],
             const std::size_t & i ) [inline]
Definition at line 20 of file Buffer.h.
m_Capacity(i * sizeof(char)) {}
4.1.2.5 Buffer() [4/5] template<typename T >
Buffer::Buffer (
             const std::vector< T > & rawdata ) [inline]
Definition at line 21 of file Buffer.h.
4.1.2.6 Buffer() [5/5] template<typename T , std::size_t N>
Buffer::Buffer (
             const std::array< T, N > & rawdata ) [inline]
Definition at line 22 of file Buffer.h.
00022 : m_Buffer(const_cast<bit8_t \star>(reinterpret_cast<const bit8_t \star>(rawdata.data()))), m_Size(rawdata.size() \star sizeof(T)), m_Capacity(rawdata.size() \star sizeof(T)) {}
```

4.1.3 Member Function Documentation

```
4.1.3.1 begin() bit8_t * Buffer::begin ( ) const [inline]
Definition at line 35 of file Buffer.h.
00035 { return m_Buffer; }
4.1.3.2 capacity() std::size_t Buffer::capacity ( ) const [inline]
Definition at line 25 of file Buffer.h.
00025 { return m_Capacity; }
4.1.3.3 empty() bool Buffer::empty ( ) [inline]
Definition at line 27 of file Buffer.h.
00027 { return m_Size == 0; }
4.1.3.4 end() bit8_t * Buffer::end ( ) const [inline]
Definition at line 36 of file Buffer.h.
00036 { return m_Buffer + m_Size; }
4.1.3.5 operator[]() [1/2] bit8_t & Buffer::operator[] (
              const std::size_t & pos ) [inline]
Definition at line 37 of file Buffer.h.
00037 { return m_Buffer[pos]; }
4.1.3.6 operator[]() [2/2] bit8_t & Buffer::operator[] (
              const std::size_t & pos ) const [inline]
Definition at line 38 of file Buffer.h.
00038 { return m_Buffer[pos]; }
4.1.3.7 set() [1/2] void Buffer::set (
              const Buffer & buffer ) [inline]
Definition at line 29 of file Buffer.h.
00031
         m_Buffer = buffer.begin();
00032
         m_Size
                    = buffer.size();
        m_Capacity = buffer.capacity();
00033
00034
```

The documentation for this class was generated from the following file:

libs/core/include/Buffer.h

4.2 BufferLooper < SOURCE, DESTINATION > Class Template Reference

#include <libs/core/include/BufferLooper.h>

Public Member Functions

- BufferLooper (SOURCE &source, DESTINATION &dest, bool debug=false)
- void addSink (const spdlog::sink_ptr &sink, const spdlog::level::level_enum &level=spdlog::get_level())
- void loop (const std::uint32 t &m NbrEventsToProcess=0)
- void printAllCounters ()
- std::shared_ptr< spdlog::logger > log ()
- void setDetectorIDs (const std::vector< DetectorID > &detectorIDs)

4.2.1 Detailed Description

template < typename SOURCE, typename DESTINATION > class Buffer Looper < SOURCE, DESTINATION >

Definition at line 28 of file BufferLooper.h.

4.2.2 Constructor & Destructor Documentation

```
4.2.2.1 BufferLooper() template<typename SOURCE , typename DESTINATION >
BufferLooper< SOURCE, DESTINATION >::BufferLooper (
              SOURCE & source,
              DESTINATION & dest,
              bool debug = false ) [inline]
Definition at line 31 of file BufferLooper.h.
00031
                                                                         : m Source(source).
     m_Destination(dest), m_Debug(debug)
00032
00033
         m_Logger = spdlog::create<spdlog::sinks::null_sink_mt>("streamout");
00034
          if(!spdlog::get("streamout")) { spdlog::register_logger(m_Logger); }
00035
         m_Source.setLogger(m_Logger);
00036
         m_Destination.setLogger(m_Logger);
00037 }
4.2.3 Member Function Documentation
4.2.3.1 addSink() template<typename SOURCE , typename DESTINATION >
void BufferLooper< SOURCE, DESTINATION >::addSink (
              const spdlog::sink_ptr & sink,
              const spdlog::level::level_enum & level = spdlog::qet_level() ) [inline]
Definition at line 39 of file BufferLooper.h.
00040
00041
         sink->set level(level);
00042
         m_Sinks.push_back(sink);
00043
         m_Logger = std::make_shared<spdlog::logger>("streamout", begin(m_Sinks), end(m_Sinks));
00044
         m_Source.setLogger(m_Logger);
00045
         m_Destination.setLogger(m_Logger);
00046
4.2.3.2 log() template<typename SOURCE , typename DESTINATION >
std::shared_ptr< spdlog::logger > BufferLooper< SOURCE, DESTINATION >::log ( ) [inline]
Definition at line 230 of file BufferLooper.h.
00230 { return m_Logger; }
4.2.3.3 loop() template<typename SOURCE , typename DESTINATION >
void BufferLooper< SOURCE, DESTINATION >::loop (
              const std::uint32_t & m_NbrEventsToProcess = 0 ) [inline]
Definition at line 48 of file BufferLooper.h.
00050
         // clang-format off
00051
         fmt::print(fg(fmt::color::medium_orchid) | fmt::emphasis::bold,
    "\n"
00052
00053 " SSSSSSSSSSSSSS
                           tttt
     \texttt{tttt} \backslash \texttt{n"}
ttt:::t\n"
00055 "S:::::SSSSSS::::::S t::::t
t:::::t\n"
00056 "S:::::S
                  SSSSSSS t::::t
     t::::t\n"
00057 "S:::::s
                     ttttttt::::ttttttt rrrrr
                                                rrrrrrrr
                                                                eeeeeeeeee
                                                                                aaaaaaaaaaaa
     mmmmmmm
              mmmmmmm
                                                  uuuuuuttttttt::::ttttttt\n"
                            00000000000 uuuuuu
```

```
00058 "S:::::S
                           t:::::::::
                                                       r::::rrr::::::r
                                                                                  ee::::::::ee
                                                                                                         a:::::::a
        00059 " S::::SSSS
                           t::::::eeaaaaaaaa::::a
       00060 " SS:::::SSSSStttttt:::::tttttt rr::::rrrrr::::re::::e
                                                                                                e:::::e
       e::::::eeeeeeeea:::::aaaaa::::::a m::::m
       tt:::::::t\n"
ee::::::::
tt:::::::tt\n"
                                                 uu:::::::uu:::u
                  m::::m oo::::::::::
       m::::m
00068 " SSSSSSSSSSSSS
                                       tttttttttt rrrrrr
                                                                                     eeeeeeeeeee aaaaaaaaa aaaammmmmm
                                                                              ttttttttttt {}\n"
       mmmmmm
                  mmmmmm 0000000000
                                                    uuuuuuuu uuuu
00069 "\n",
00070 fmt::format(fg(fmt::color::red) | fmt::emphasis::bold, "v(}", streamout_version.to_string()));
00071
            // clang-format on
00072
             00073
             log()->info("Streamout Version : {}", streamout_version.to_string());
            log() -> info("Using InterfaceReader {} version {}", m_Source.getName(),
00074
       m_Source.getVersion().to_string());
            log() ->info("Using InterfaceWriter {} version {}", m_Destination.getName(),
00075
       m_Destination.getVersion().to_string());
00076
00077
             if(!m_Destination.checkCompatibility(m_Source.getName(), m_Source.getVersion().to_string()))
00078
               log()->critical("{} version {} is not compatible with {} version {} ! ", m_Source.getName(),
00079
       m_Source.getVersion().to_string(), m_Destination.getName(), m_Destination.getVersion().to_string());
            log()->info("Compatible Interfaces for {} are", m_Destination.getName());
00080
               for(std::map<std::string, std::string>::iterator it = m_Destination.getCompatibility().begin();
00081
        it != m_Destination.getCompatibility().end(); ++it) { log()->info("{} version {}", it->first, log()->info("{} version {}", it->first, log()->info("{} version {}", it->first, log()->info("{} version {} version {}", it->first, log()->info("{} version {}", it->first, log()->info("{} version {} ver
        it->second); }
00082
              std::exit(-1);
00083
00084
             if(!m DetectorIDs.empty())
00085
            {
               std::string ids;
00087
               for(std::vector<DetectorID>::const_iterator it = m_DetectorIDs.cbegin(); it !=
       m_DetectorIDs.cend(); ++it) ids += std::to_string(static_cast<std::uint16_t>(*it)) + ";";
00088
               log()->info("Detector ID(s) other than {} will be ignored", ids);
00089
             00090
00091
            RawBufferNavigator bufferNavigator;
00092
            Timer
00093
            timer.start();
00094
            m_Source.start();
00095
            m Destination.start();
00096
            while (m Source.nextEvent() && m NbrEventsToProcess >= m NbrEvents)
00098 /***********
00099 /*** START EVENT ***/
00100
              m_Source.startEvent();
00101
              m Destination.startEvent();
00102 /***************
00103
00104
               m Logger->warn("===*** Event {} ***===", m NbrEvents);
00105
               while (m_Source.nextDIFbuffer())
00106
             {
00107
                 const Buffer& buffer = m_Source.getBuffer();
00108
                 bufferNavigator.setBuffer(buffer);
00109
00110
                  if(std::find(m_DetectorIDs.begin(), m_DetectorIDs.end(),
      static_cast<DetectorID>(bufferNavigator.getDetectorID())) == m_DetectorIDs.end())
00111
00112
                  m_Logger->debug("Ignoring detector ID : {}", bufferNavigator.getDetectorID());
00113
                    continue;
                 }
00114
00115
00116
                 std::int32_t idstart = bufferNavigator.getStartOfPayload();
00117
                  if(m_Debug && idstart == -1) m_Logger->info(to_hex(buffer));
00118
                  c.DIFStarter[idstart]++;
                  if(!bufferNavigator.validPayload())
00119
00120
                 {
00121
                    m_Logger->error("!bufferNavigator.validBuffer()");
00122
                    continue;
00123
00124
00125 /*************
00126 /*** START DIF ***/
```

```
00127
              m_Source.startDIF();
00128
              m_Destination.startDIF();
00129 /**************
00130
              PayloadParser d;
              // This is really a big error so skip DIF entirely if exception occurs
00131
00132
00133
              {
00134
                d.setBuffer(bufferNavigator.getPayload());
00135
00136
              catch(const Exception& e)
00137
              {
               m_Logger->error("{}", e.what());
00138
00139
                continue;
00140
00141
00142
              if(buffer.end() != d.end()) m_Logger->error("DIF BUFFER END {} {}", fmt::ptr(buffer.end()),
     fmt::ptr(d.end()));
00143
             assert(buffer.end() == d.end());
00144
              c.DIFPtrValueAtReturnedPos[d.begin()[d.getEndOfDIFData() - 3]]++;
00145
00146
              assert(d.begin()[d.getEndOfDIFData() - 3] == 0xa0);
00147
00148
              c.SizeAfterDIFPtr[d.getSizeAfterDIFPtr()]++;
00149
              m_Destination.processDIF(d);
              for(std::size_t i = 0; i < d.getNumberOfFrames(); ++i)</pre>
00150
00151
              {
00152 /**************
00153 /*** START FRAME ***/
              m_Source.startFrame();
00154
00155
               m_Destination.startFrame();
00156 /***********
00157
               m_Destination.processFrame(d, i);
00158
                for(std::size_t j = 0; j < static_cast<std::size_t>(Hardware::NUMBER_PAD); ++j)
00159
00160
                  if(d.getThresholdStatus(i, j) != 0)
00161
00162
                    m Source.startPad();
00163
                    m_Destination.startPad();
00164
                    m_Destination.processPadInFrame(d, i, j);
00165
                    m_Source.endPad();
                    m_Destination.endPad();
00166
00167
00168
00169 /************/
00170 /*** END FRAME ***/
00171
               m_Source.endFrame();
00172
                m_Destination.endFrame();
00173 /*************/
            }
00174
              // If I want SlowControl I need to check for it first, If there is an error then it's not a
00175
     big deal just continue and say is bad SlowControl /*try
00176
00177 {
00178 d.setSCBuffer();
00179
00180 catch(const Exception& e)
00182 m_Logger->error("{}", e.what());
00183 }
00184
00185 bool processSC = false;
00186 if (d.hasSlowControl())
00187
00188 c.hasSlowControl++;
00189 processSC = true;
00190
00191 if (d.badSCData())
00192 {
00193 c.hasBadSlowControl++;
00194 processSC = false;
00195
00196 if(processSC) { m_Destination.processSlowControl(d.getSCBuffer()); } */
00197
              // Buffer eod = d.getEndOfAllData();
00198
00199
              // c.SizeAfterAllData[eod.size()]++;
              // bit8_t* debug_variable_3 = eod.end();
00200
00201
              // if(buffer.end() != debug_variable_3) m_Logger->info("END DATA BUFFER END {} {}",
     fmt::ptr(buffer.end()), fmt::ptr(debug_variable_3));
00202
              // assert(buffer.end() == debug_variable_3);
// if(eod.size() != 0) m_Logger->info("End of Data remaining stuff : {}", to_hex(eod));*/
00203
00204
              /*int nonzeroCount = 0;
00206 for(bit8_t* it = eod.begin(); it != eod.end(); it++)
00207 if(static_cast<int>(*it) != 0) nonzeroCount++;
00208 c.NonZeroValusAtEndOfData[nonzeroCount]++;*/
00209
00210 /************/
```

```
00211 /*** END DIF ***/
           m_Source.endDIF();
00213
             m_Destination.endDIF();
00214 /***********/
00215 \} // end of DIF while loop
           m_Logger->warn("===*** Event {} ***===", m_NbrEvents);
00216
          m_NbrEvents++;
00218 /**************/
00219 /*** END EVENT ***/
           m_Source.endEvent();
00220
00221
           m_Destination.endEvent();
00222 /**************/
00223 } // end of event while loop
00224 m_Destination.end();
        m_Source.end();
00225
       timer.stop();
00226
         fmt::print(fg(fmt::color::green) | fmt::emphasis::bold, "=== elapsed time {}ms ({}ms/event)
00227
     ===\n", timer.getElapsedTime() / 1000, timer.getElapsedTime() / (1000 * m_NbrEvents));
```

```
4.2.3.4 printAllCounters() template<typename SOURCE , typename DESTINATION > void BufferLooper< SOURCE, DESTINATION >::printAllCounters ( ) [inline]
```

Definition at line 229 of file BufferLooper.h. 00229 { c.printAllCounters(); }

```
Definition at line 232 of file BufferLooper.h.
00232 { m_DetectorIDs = detectorIDs; }
```

The documentation for this class was generated from the following file:

• libs/core/include/BufferLooper.h

4.3 BufferLooperCounter Struct Reference

#include <libs/core/include/BufferLooperCounter.h>

Public Member Functions

- void printCounter (const std::string &description, const std::map< int, int > &m, const std::ios_base::fmtflags &base=std::ios_base::dec)
- void printAllCounters ()

Public Attributes

- int hasSlowControl = 0
- int hasBadSlowControl = 0
- std::map< int, int > DIFStarter
- std::map< int, int > DIFPtrValueAtReturnedPos
- std::map< int, int > SizeAfterDIFPtr
- std::map< int, int > SizeAfterAllData
- std::map< int, int > NonZeroValusAtEndOfData

4.3.1 Detailed Description

Definition at line 12 of file BufferLooperCounter.h.

4.3.2 Member Function Documentation

4.3.2.1 printAllCounters() void BufferLooperCounter::printAllCounters ()

Definition at line 11 of file BufferLooperCounter.cc.

```
fmt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "BUFFER LOOP FINAL STATISTICS : \n");
fmt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "BUFFER LOOP FINAL STATISTICS : \n");
fnt::printCounter("Start of DIF header", DIFStarter);
fnt::printCounter("Value after DIF data are processed", DIFPtrValueAtReturnedPos, std::ios_base::hex);
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of which {} are bad\n", hasSlowControl, hasBadSlowControl);
fnt::printCounter("Size remaining after all of data have been processed", SizeAfterAllData);
frintCounter("Number on non zero values in end of data buffer", NonZeroValusAtEndOfData);
fnt::printCounter("Number on non zero values in end of data buffer", NonZeroValusAtEndOfData);
fnt::printCounter("Number on non zero values in end of data buffer", NonZeroValusAtEndOfData);
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Buffer DIFF LOOP FINAL STATISTICS : \n");
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of the printCounter("Size remaining after all of data have been processed", SizeAfterAllData);
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of the printCounter("Size remaining after all of data have been processed", SizeAfterAllData);
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of the printCounter("Size remaining after all of data have been processed", SizeAfterAllData);
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of the printCounter("Size remaining after all of data have been processed", SizeAfterAllData);
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of the printCounter("Size remaining after all of data have been processed", SizeAfterAllData);
fnt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of the printCounte
```

```
4.3.2.2 printCounter() void BufferLooperCounter::printCounter (
```

```
const std::string & description, const std::map< int, int > & m, const std::ios_base::fmtflags & base = std::ios\_base::dec )
```

Definition at line 22 of file BufferLooperCounter.cc.

```
00024
            std::string out{"statistics for " + description + " : \n"};
00025
            for(std::map<int, int>::const_iterator it = m.begin(); it != m.end(); it++)
00026
00027
               if(it != m.begin()) out += ",";
              out += " [";
00028
00029
               switch(base)
00030
                 case std::ios_base::dec:    out += to_dec(static_cast<std::uint32_t>(it->first)); break;
case std::ios_base::hex:    out += to_hex(static_cast<std::uint32_t>(it->first)); break;
case std::ios_base::oct:    out += to_oct(static_cast<std::uint32_t>(it->first)); break;
default:    out += to_dec(static_cast<std::uint32_t>(it->first)); break;
00031
00032
00033
00034
00035
00036
              out += "]=" + std::to_string(it->second);
00037
00038
            Out += "\n":
            fmt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, out);
00039
00040 }
```

4.3.3 Member Data Documentation

4.3.3.1 DIFPtrValueAtReturnedPos std::map<int, int> BufferLooperCounter::DIFPtrValueAt↔ ReturnedPos

Definition at line 18 of file BufferLooperCounter.h.

4.4 DIF Class Reference 13

4.3.3.2 DIFStarter std::map<int, int> BufferLooperCounter::DIFStarter

Definition at line 17 of file BufferLooperCounter.h.

4.3.3.3 hasBadSlowControl int BufferLooperCounter::hasBadSlowControl = 0

Definition at line 16 of file BufferLooperCounter.h.

4.3.3.4 hasSlowControl int BufferLooperCounter::hasSlowControl = 0

Definition at line 15 of file BufferLooperCounter.h.

4.3.3.5 NonZeroValusAtEndOfData std::map<int, int> BufferLooperCounter::NonZeroValusAtEnd↔ OfData

Definition at line 21 of file BufferLooperCounter.h.

4.3.3.6 SizeAfterAllData std::map<int, int> BufferLooperCounter::SizeAfterAllData

Definition at line 20 of file BufferLooperCounter.h.

4.3.3.7 SizeAfterDIFPtr std::map<int, int> BufferLooperCounter::SizeAfterDIFPtr

Definition at line 19 of file BufferLooperCounter.h.

The documentation for this struct was generated from the following files:

- libs/core/include/BufferLooperCounter.h
- libs/core/src/BufferLooperCounter.cc

4.4 DIF Class Reference

#include <libs/interface/ROOT/include/DIF.h>

Inheritance diagram for DIF:



Public Member Functions

```
• void clear ()
```

- void addHit (const Hit &)
- void setID (const std::uint8 t &)
- std::uint8_t getID () const
- void setDTC (const std::uint32_t &)
- std::uint32_t getDTC () const
- void setGTC (const std::uint32_t &)
- std::uint32_t getGTC () const
- void setDIFBCID (const std::uint32_t &)
- std::uint32_t getDIFBCID () const
- void setAbsoluteBCID (const std::uint64_t &)
- std::uint64_t getAbsoluteBCID () const
- std::vector< Hit >::const_iterator cbegin () const
- std::vector< Hit >::const_iterator cend () const

4.4.1 Detailed Description

Definition at line 16 of file DIF.h.

4.4.2 Member Function Documentation

```
\textbf{4.4.2.2 cbegin()} \quad \texttt{std::vector} < \\ \texttt{Hit} > :: \texttt{const\_iterator} \\ \\ \texttt{DIF::cbegin ( )} \\ \\ \texttt{const} \\ \\ \texttt{A.4.2.2} \\ \\ \texttt{Const\_iterator} \\ \texttt{DIF::cbegin ( )} \\ \\ \texttt{const\_iterator} \\ \texttt{DIF::cbegin ( )} \\ \\ \texttt{const\_iterator} \\ \texttt{DIF::cbegin ( )} \\ \texttt{const\_iterator} \\ \texttt{const\_
```

```
Definition at line 32 of file DIF.cc.
00032 { return m_Hits.cbegin(); }
```

```
\textbf{4.4.2.3} \quad \textbf{cend()} \quad \texttt{std::vector} < \\ \texttt{Hit} > :: \texttt{const\_iterator} \\ \\ \texttt{DIF::cend} \\ \text{( ) } \\ \texttt{const} \\ \\ \text{} \\ \text{( ) } \\ \text{
```

```
Definition at line 34 of file DIF.cc. 00034 { return m_Hits.cend(); }
```

4.4 DIF Class Reference 15

```
4.4.2.4 clear() void DIF::clear ()
Definition at line 36 of file DIF.cc.
00036 { m_Hits.clear(); }
4.4.2.5 getAbsoluteBCID() std::uint64_t DIF::getAbsoluteBCID ( ) const
Definition at line 30 of file DIF.cc.
00030 { return m_AbsoluteBCID; }
4.4.2.6 getDIFBCID() std::uint32_t DIF::getDIFBCID ( ) const
Definition at line 26 of file DIF.cc.
00026 { return m_DIFBCID; }
4.4.2.7 getDTC() std::uint32_t DIF::getDTC ( ) const
Definition at line 18 of file DIF.cc.
00018 { return m_DTC; }
4.4.2.8 getGTC() std::uint32_t DIF::getGTC ( ) const
Definition at line 22 of file DIF.cc.
00022 { return m_GTC; }
4.4.2.9 getID() std::uint8_t DIF::getID ( ) const
Definition at line 14 of file DIF.cc.
00014 { return m_ID; }
4.4.2.10 setAbsoluteBCID() void DIF::setAbsoluteBCID (
              const std::uint64_t & absolutebcid )
Definition at line 28 of file DIF.cc.
00028 { m_AbsoluteBCID = absolutebcid; }
```

```
4.4.2.11 setDIFBCID() void DIF::setDIFBCID (
              const std::uint32_t & difbcid )
Definition at line 24 of file DIF.cc.
00024 { m_DIFBCID = difbcid; }
4.4.2.12 setDTC() void DIF::setDTC (
              const std::uint32_t & dtc )
Definition at line 16 of file DIF.cc.
00016 { m_DTC = dtc; }
4.4.2.13 setGTC() void DIF::setGTC (
              const std::uint32_t & gtc )
Definition at line 20 of file DIF.cc.
00020 { m_GTC = gtc; }
4.4.2.14 setID() void DIF::setID (
              const std::uint8_t & id )
Definition at line 12 of file DIF.cc.
00012 { m_ID = id; }
```

The documentation for this class was generated from the following files:

- libs/interface/ROOT/include/DIF.h
- libs/interface/ROOT/src/DIF.cc

4.5 DIFPtr Class Reference

M3 MICROROC and HARDROC2 dataformat.

#include <libs/core/include/PayloadParser.h>

4.5.1 Detailed Description

M3 MICROROC and HARDROC2 dataformat.

Data from the DAQ (once at the beginning of the file):

```
(1 fois par fichier) [Données venant de la DAQ]
data format version (8 bits)
daq software version (16 bits)
SDCC firmware version (16 bits)
DIF firmware version (16 bits)
timestamp (32bits) (secondes depuis le 01/01/1970) (a)
timestamp (32bits) (milliseconde)
```

Explication:

- data format version = la version du format de données utilisée, c'est la version 13
- daq software version = la version du soft d'acquisition labview ou Xdaq
- SDCC firmware version = la version du code VHDL de la carte SDCC
- DIF firmware version = la version du code VHDL de la carte DIF
- timestamp = secondes et milliseconde depuis le 01/01/1970

Figure 1 Data from the DAQ (once at the beginning of the file)

Data from the DIF analog or/and digital (loop):




Figure 2 Data from the DIF analog or/and digital

Data from the DAQ (slowcontrol) :

```
(1 fois par slow control, c'est à dire 1 fois par fichier par DIF) [Données venant de la DAQ]

SC Header (0xB1)

DIF ID (8 bits)

ASIC Header (8 bits)

Size SC ASIC [74 ou 109 selon le chip]

SC ASIC (n x 8bits)

DIF ID (8 bits)

ASIC Header (8 bits)

Size SC ASIC [74 ou 109 selon le chip]

SC ASIC (n x 8bits)

Size SC ASIC [74 ou 109 selon le chip]

SC ASIC (n x 8bits)

In= 74 ou 109 selon le chip]

...

SC Trailer (0xA1)
```

Explication:

- SC Header (0xB1) / SC Trailer (0xA1) = balise pour repérer les infos sur le Slow Control
- DIF ID = identité de la DIF qui envoient les data
- Size SC ASIC = taille de la trame SC d'un CHIP (MR=74 byte, HR = 109 byte)
- ASIC header (8 bits): header dans le SC
- SC ASIC (n x 8bits) : de 1 a 48 par DIF moins ceux qui sont bypassés

Figure 3 Data from the DAQ (slowcontrol)

The documentation for this class was generated from the following file:

libs/core/include/PayloadParser.h

4.6 DIFSlowControl Class Reference

```
#include <libs/core/include/DIFSlowControl.h>
```

Public Member Functions

- DIFSlowControl (const std::uint8_t &version, const std::uint8_t &DIFid, unsigned char *buf)
 Constructor.
- std::uint8_t getDIFId ()

get DIF id

std::map< int, std::map< std::string, int > > getChipsMap ()

Get chips map.

• std::map< std::string, int > getChipSlowControl (const int &asicid)

Get one chip map.

• int getChipSlowControl (const std::int8_t &asicid, const std::string ¶m)

Get one Chip value.

- $std::map < int, std::map < std::string, int > >::const_iterator cbegin () const$
- std::map< int, std::map< std::string, int > >::const_iterator cend () const

4.6.1 Detailed Description

Definition at line 13 of file DIFSlowControl.h.

4.6.2 Constructor & Destructor Documentation

Constructor.

Parameters

version	Data format version
DIFid	DIF id
buf	Pointer to the Raw data buffer

Definition at line 7 of file DIFSlowControl.cc.

```
m_Version(version), m_DIFId(DIfId), m_AsicType(2)
80000
00009
        if(cbuf[0] != 0xb1) return;
00010
        int header_shift{6};
        if (m_Version < 8) m_NbrAsic = cbuf[5];</pre>
00011
00012
        else
00013
         m_DIFId
00014
                        = cbuf[1];
00015
          m_NbrAsic
                        = cbuf[2];
          header_shift = 3;
00016
00017
        int size_hardroc1 = m_NbrAsic * 72 + header_shift + 1;
if(cbuf[size_hardroc1 - 1] != 0xa1) size_hardroc1 = 0;
00018
00019
00020
00021
        int size_hardroc2 = m_NbrAsic * 109 + header_shift + 1;
        if(cbuf[size_hardroc2 - 1] != 0xa1) size_hardroc2 = 0;
00022
        if(size_hardroc1 != 0)
00023
00024
00025
          FillHR1(header_shift, cbuf);
00026
          m_AsicType = 1;
00027
00028
        else if(size_hardroc2 != 0)
00029
          FillHR2(header_shift, cbuf);
00030
        else
00031
          return;
00032 }
```

4.6.3 Member Function Documentation

```
4.6.3.1 cbegin() std::map< int, std::map< std::string, int > > :: const_iterator DIFSlow \leftarrow Control::cbegin () const [inline]
```

Definition at line 47 of file DIFSlowControl.h.

```
00047 { return m_MapSC.cbegin(); }
```

```
4.6.3.2 cend() std::map< int, std::map< std::string, int > >::const_iterator DIFSlowControl ← ::cend () const [inline]
```

Definition at line 49 of file DIFSlowControl.h.

```
00049 { return m_MapSC.cend(); }
```

Get one chip map.

Parameters

```
asicid ASIC ID
```

Returns

a map of <string (parameter name),int (parameter value) >

Definition at line 38 of file DIFSlowControl.cc.

```
00038 { return m_MapSC[asicid]; }
```

```
4.6.3.4 getChipSlowControl() [2/2] int DIFSlowControl::getChipSlowControl ( const std::int8_t & asicid, const std::string & param ) [inline]
```

Get one Chip value.

Parameters

asicid	ASic ID
param	Parameter name

Definition at line 40 of file DIFSlowControl.cc.

```
00040 { return getChipSlowControl(asicid)[param]; }
```

```
4.6.3.5 getChipsMap() std::map< int, std::map< std::string, int >> DIFSlowControl::get\leftarrow ChipsMap ( ) [inline]
```

Get chips map.

Returns

a map of < Asic Id, map of < string (parameter name),int (parameter value) >

Definition at line 36 of file DIFSlowControl.cc.

```
00036 { return m_MapSC; }
```

```
4.6.3.6 getDIFId() std::uint8_t DIFSlowControl::getDIFId ( ) [inline]
```

get DIF id

Definition at line 34 of file DIFSlowControl.cc. 00034 { return m_DIFId; }

The documentation for this class was generated from the following files:

- libs/core/include/DIFSlowControl.h
- libs/core/src/DIFSlowControl.cc

4.7 Event Class Reference

#include <libs/interface/ROOT/include/Event.h>

Inheritance diagram for Event:



Public Member Functions

- void clear ()
- void addDIF (const DIF &dif)
- std::map< std::uint8_t, DIF >::const_iterator cbegin () const
- std::map< std::uint8_t, DIF >::const_iterator cend () const

4.7.1 Detailed Description

Definition at line 15 of file Event.h.

4.7.2 Member Function Documentation

```
4.7.2.1 addDIF() void Event::addDIF ( const DIF & dif )
```

Definition at line 10 of file Event.cc. 00010 { DIFs[dif.getID()] = dif; }

```
4.7.2.2 cbegin() std::map< std::uint8_t, DIF >::const_iterator Event::cbegin ( ) const

Definition at line 12 of file Event.cc.
00012 { return DIFs.cbegin(); }

4.7.2.3 cend() std::map< std::uint8_t, DIF >::const_iterator Event::cend ( ) const

Definition at line 14 of file Event.cc.
00014 { return DIFs.cend(); }

4.7.2.4 clear() void Event::clear ( )

Definition at line 8 of file Event.cc.
00008 { DIFs.clear(); }
```

The documentation for this class was generated from the following files:

- libs/interface/ROOT/include/Event.h
- libs/interface/ROOT/src/Event.cc

4.8 Exception Class Reference

#include <libs/core/include/Exception.h>

Public Member Functions

- virtual const char * what () const noexcept
- Exception (const std::string &message)
- Exception (const std::int32_t &error, const std::string &message)
- std::int32_t error ()
- std::string message ()

4.8.1 Detailed Description

Definition at line 11 of file Exception.h.

4.8.2 Constructor & Destructor Documentation

4.8.3.1 error() std::int32_t Exception::error () [inline]

4.8.3 Member Function Documentation

```
Definition at line 17 of file Exception.h.
00017 { return m_Error; }

4.8.3.2 message() std::string Exception::message ( ) [inline]

Definition at line 18 of file Exception.h.
00018 { return m_Message; }
```

4.8.3.3 what() virtual const char * Exception::what () const [inline], [virtual], [noexcept]

Definition at line 14 of file Exception.h.
00014 { return m_What.c_str(); }

The documentation for this class was generated from the following file:

• libs/core/include/Exception.h

4.9 Hit Class Reference

#include <libs/interface/ROOT/include/Hit.h>

Inheritance diagram for Hit:



4.9 Hit Class Reference 25

Public Member Functions

- void clear ()
- void setDIF (const std::uint8_t &)
- void setASIC (const std::uint8_t &)
- void setChannel (const std::uint8_t &)
- void setThreshold (const std::uint8_t &)
- void setDTC (const std::uint32_t &)
- void setGTC (const std::uint32_t &)
- void setDIFBCID (const std::uint32 t &)
- void setFrameBCID (const std::uint32 t &)
- void setTimestamp (const std::uint32 t &)
- void setAbsoluteBCID (const std::uint64_t &)
- std::uint8_t getDIFid () const
- std::uint8_t getASICid () const
- std::uint8_t getChannel () const
- std::uint8 t getThreshold () const
- std::uint32_t getDTC () const
- std::uint32 t getGTC () const
- std::uint32_t getDIFBCID () const
- std::uint32_t getFrameBCID () const
- std::uint32_t getTimestamp () const
- std::uint64_t getAbsoluteBCID () const

4.9.1 Detailed Description

Definition at line 10 of file Hit.h.

4.9.2 Member Function Documentation

4.9.2.1 clear() void Hit::clear ()

Definition at line 7 of file Hit.cc.

```
00008 {
00009
        m_DIF
00010
        m_ASIC
00011
        m_Channel
00012
       m\_Threshold
                       = 0;
00013
       m_DTC
                       = 0;
       m_GTC
00014
                       = 0;
                       = 0;
00015
       m_DIFBCID
00016
       m_FrameBCID
                       = 0;
00017
        m\_Timestamp
00018
       m_AbsoluteBCID = 0;
00019 }
```

4.9.2.2 getAbsoluteBCID() std::uint64_t Hit::getAbsoluteBCID () const

```
Definition at line 59 of file Hit.cc. 00059 { return m_AbsoluteBCID; }
```

```
4.9.2.3 getASICid() std::uint8_t Hit::getASICid ( ) const
Definition at line 43 of file Hit.cc.
00043 { return m_ASIC; }
\textbf{4.9.2.4} \quad \textbf{getChannel()} \quad \texttt{std::uint8\_t Hit::getChannel ( ) const}
Definition at line 45 of file Hit.cc.
00045 { return m_Channel; }
4.9.2.5 getDIFBCID() std::uint32_t Hit::getDIFBCID ( ) const
Definition at line 53 of file Hit.cc.
00053 { return m_DIFBCID; }
4.9.2.6 getDIFid() std::uint8_t Hit::getDIFid ( ) const
Definition at line 41 of file Hit.cc.
00041 { return m_DIF; }
4.9.2.7 getDTC() std::uint32_t Hit::getDTC ( ) const
Definition at line 49 of file Hit.cc.
00049 { return m_DTC; }
4.9.2.8 getFrameBCID() std::uint32_t Hit::getFrameBCID ( ) const
Definition at line 55 of file Hit.cc.
00055 { return m_FrameBCID; }
4.9.2.9 getGTC() std::uint32_t Hit::getGTC ( ) const
Definition at line 51 of file Hit.cc.
00051 { return m_GTC; }
```

4.9 Hit Class Reference 27

```
4.9.2.10 getThreshold() std::uint8_t Hit::getThreshold ( ) const
Definition at line 47 of file Hit.cc.
00047 { return m_Threshold; }
4.9.2.11 getTimestamp() std::uint32_t Hit::getTimestamp ( ) const
Definition at line 57 of file Hit.cc.
00057 { return m_Timestamp; }
4.9.2.12 setAbsoluteBCID() void Hit::setAbsoluteBCID (
               const std::uint64_t & absolutebcid )
Definition at line 39 of file Hit.cc.
00039 { m_AbsoluteBCID = absolutebcid; }
4.9.2.13 setASIC() void Hit::setASIC (
               const std::uint8_t & asic )
Definition at line 23 of file Hit.cc.
00023 { m_ASIC = asic; }
4.9.2.14 setChannel() void Hit::setChannel (
               const std::uint8_t & channel )
Definition at line 25 of file Hit.cc.
00025 { m\_Channel = channel; }
4.9.2.15 setDIF() void Hit::setDIF (
               const std::uint8_t & dif )
Definition at line 21 of file Hit.cc.
00021 { m_DIF = dif; }
\textbf{4.9.2.16} \quad \textbf{setDIFBCID()} \quad \texttt{void Hit::setDIFBCID} \ \ \textbf{(}
               const std::uint32_t & difbcid )
Definition at line 33 of file Hit.cc.
00033 { m_DIFBCID = difbcid; }
```

```
4.9.2.17 setDTC() void Hit::setDTC (
              const std::uint32_t & dtc )
Definition at line 29 of file Hit.cc.
00029 { m_DTC = dtc; }
4.9.2.18 setFrameBCID() void Hit::setFrameBCID (
              const std::uint32_t & framebcid )
Definition at line 35 of file Hit.cc.
00035 { m_FrameBCID = framebcid; }
4.9.2.19 setGTC() void Hit::setGTC (
              const std::uint32_t & gtc )
Definition at line 31 of file Hit.cc.
00031 { m_GTC = gtc; }
4.9.2.20 setThreshold() void Hit::setThreshold (
              const std::uint8_t & threshold )
Definition at line 27 of file Hit.cc.
00027 { m_Threshold = threshold; }
4.9.2.21 setTimestamp() void Hit::setTimestamp (
              const std::uint32_t & timestamp )
Definition at line 37 of file Hit.cc.
00037 { m_Timestamp = timestamp; }
```


The documentation for this class was generated from the following files:

- libs/interface/ROOT/include/Hit.h
- libs/interface/ROOT/src/Hit.cc

4.10 Interface Class Reference

#include <libs/core/include/Interface.h>

Inheritance diagram for Interface:



Public Member Functions

- Interface (const std::string &name, const std::string &version, const InterfaceType &type)
- virtual ∼Interface ()=default
- virtual void startEvent ()
- virtual void endEvent ()
- virtual void startDIF ()
- virtual void endDIF ()
- virtual void startFrame ()
- virtual void endFrame ()
- virtual void startPad ()
- virtual void endPad ()
- std::shared_ptr< spdlog::logger > & log ()
- void setLogger (const std::shared_ptr< spdlog::logger > &logger)
- std::string getName ()
- Version getVersion ()

4.10.1 Detailed Description

Definition at line 38 of file Interface.h.

4.10.2 Constructor & Destructor Documentation

Definition at line 41 of file Interface.h.

```
00041 : m_Name(name), m_Version(version) {}
```

```
4.10.2.2 ~Interface() virtual Interface::~Interface ( ) [virtual], [default]
```

4.10.3 Member Function Documentation

```
4.10.3.1 endDIF() virtual void Interface::endDIF ( ) [inline], [virtual]
```

Reimplemented in ROOTWriter.

```
Definition at line 46 of file Interface.h. 00046 {}
```

```
4.10.3.2 endEvent() virtual void Interface::endEvent ( ) [inline], [virtual]
Reimplemented in ROOTWriter.
Definition at line 44 of file Interface.h.
00044 {}
4.10.3.3 endFrame() virtual void Interface::endFrame ( ) [inline], [virtual]
Reimplemented in ROOTWriter.
Definition at line 48 of file Interface.h.
00048 {}
4.10.3.4 endPad() virtual void Interface::endPad ( ) [inline], [virtual]
Reimplemented in ROOTWriter.
Definition at line 50 of file Interface.h.
00050 {}
4.10.3.5 getName() std::string Interface::getName ( ) [inline]
Definition at line 53 of file Interface.h.
00053 { return m_Name; }
4.10.3.6 getVersion() Version Interface::getVersion() [inline]
Definition at line 54 of file Interface.h.
00054 { return m_Version; }
\textbf{4.10.3.7} \quad \textbf{log()} \quad \texttt{std::shared\_ptr} < \text{spdlog::logger} > \& \text{Interface::log ()} \quad \texttt{[inline]}
Definition at line 51 of file Interface.h.
00051 { return m_Logger; }
4.10.3.8 setLogger() void Interface::setLogger (
               const std::shared_ptr< spdlog::logger > & logger ) [inline]
Definition at line 52 of file Interface.h.
00052 { m_Logger = logger; }
```

```
4.10.3.9 startDIF() virtual void Interface::startDIF ( ) [inline], [virtual]

Reimplemented in ROOTWriter.

Definition at line 45 of file Interface.h.

00045 {}

4.10.3.10 startEvent() virtual void Interface::startEvent ( ) [inline], [virtual]

Reimplemented in ROOTWriter.

Definition at line 43 of file Interface.h.

00043 {}

4.10.3.11 startFrame() virtual void Interface::startFrame ( ) [inline], [virtual]

Reimplemented in ROOTWriter.

Definition at line 47 of file Interface.h.

00047 {}
```

4.10.3.12 startPad() virtual void Interface::startPad () [inline], [virtual]

Reimplemented in ROOTWriter.

Definition at line 49 of file Interface.h. 00049 {}


The documentation for this class was generated from the following file:

• libs/core/include/Interface.h

4.11 InterfaceReader Class Reference

#include <libs/core/include/Interface.h>

Inheritance diagram for InterfaceReader:



Public Member Functions

- InterfaceReader (const std::string &name, const std::string &version)
- virtual ∼InterfaceReader ()=default

Protected Attributes

• Buffer m_Buffer

4.11.1 Detailed Description

Definition at line 63 of file Interface.h.

4.11.2 Constructor & Destructor Documentation

```
4.11.2.1 InterfaceReader() InterfaceReader::InterfaceReader ( const std::string & name, const std::string & version ) [inline]
```

Definition at line 66 of file Interface.h.

```
00066 : Interface(name, version, InterfaceType::Reader) {}
```

```
\textbf{4.11.2.2} \quad \sim \textbf{InterfaceReader()} \quad \text{virtual InterfaceReader::} \sim \textbf{InterfaceReader ()} \quad \textbf{[virtual], [default]}
```

4.11.3 Member Data Documentation

```
4.11.3.1 m_Buffer Buffer InterfaceReader::m_Buffer [protected]
```

Definition at line 70 of file Interface.h.


The documentation for this class was generated from the following file:

• libs/core/include/Interface.h

4.12 InterfaceWriter Class Reference

#include <libs/core/include/Interface.h>

Inheritance diagram for InterfaceWriter:



Public Member Functions

- InterfaceWriter (const std::string &name, const std::string &version)
- void addCompatibility (const std::string &name, const std::string &version)
- std::map< std::string, std::string > getCompatibility ()
- bool checkCompatibility (const std::string &name, const std::string &version)
- virtual ∼InterfaceWriter ()=default

4.12.1 Detailed Description

Definition at line 73 of file Interface.h.

4.12.2 Constructor & Destructor Documentation

```
4.12.2.1 InterfaceWriter() InterfaceWriter::InterfaceWriter ( const std::string & name, const std::string & version ) [inline]
```

Definition at line 76 of file Interface.h.

```
00076 : Interface(name, version, InterfaceType::Writer) {}
```

 $\textbf{4.12.2.2} \quad \sim \textbf{InterfaceWriter()} \quad \text{virtual InterfaceWriter::} \sim \textbf{InterfaceWriter ()} \quad \text{[virtual], [default]}$

4.12.3 Member Function Documentation

```
4.12.3.2 checkCompatibility() bool InterfaceWriter::checkCompatibility ( const std::string & name, const std::string & version ) [inline]
```

Definition at line 82 of file Interface.h.

```
00083
00084
       if(m_Compatible.find(name) != m_Compatible.end())
00085
        00086
00087
00088
         if(ran.satisfies(ver, false)) return true;
00089
          return false;
00090
00091
00092
      else
00093
        return false;
00094 }
```

```
4.12.3.3 getCompatibility() std::map< std::string > InterfaceWriter::getCompatibility () [inline]
```

```
Definition at line 80 of file Interface.h. 00080 { return m_Compatible; }
```


The documentation for this class was generated from the following file:

• libs/core/include/Interface.h

4.13 PayloadParser Class Reference

#include <libs/core/include/PayloadParser.h>

Inheritance diagram for PayloadParser:



Public Member Functions

- PayloadParser ()=default
- void setBuffer (const Buffer &buffer)
- bool hasTemperature () const
- bool hasAnalogReadout () const
- · bool hasSlowControl () const
- float getTemperatureDIF () const
- float getTemperatureASU1 () const
- float getTemperatureASU2 () const
- Buffer getSlowControl () const
- std::vector< bit8_t * > getFramesVector () const
- std::vector< bit8_t * > getLinesVector () const
- std::uint32_t getSizeAfterDIFPtr () const
- std::uint32_t getEndOfDIFData () const
- std::uint32 t getDTC () const
- std::uint32_t getGTC () const
- std::uint64_t getAbsoluteBCID () const
- std::uint32_t getBCID () const
- bool hasLine (const std::uint32 t &) const
- std::uint32_t getNumberOfFrames () const
- bit8_t * getFramePtr (const std::uint32_t &) const
- std::uint32 t getFrameBCID (const std::uint32 t &) const
- std::uint32_t getFrameTimeToTrigger (const std::uint32_t &) const
- bool getFrameLevel (const std::uint32_t &, const std::uint32_t &, const std::uint32_t &) const
- std::uint32 t getDIFid () const
- std::uint32_t getASICid (const std::uint32_t &) const
- std::uint32_t getThresholdStatus (const std::uint32_t &, const std::uint32_t &) const
- std::uint32_t getDIF_CRC () const

4.13.1 Detailed Description

Definition at line 36 of file PayloadParser.h.

4.13.2 Constructor & Destructor Documentation

4.13.2.1 PayloadParser() PayloadParser::PayloadParser () [default]

4.13.3 Member Function Documentation

```
4.13.3.1 getAbsoluteBCID() std::uint64_t PayloadParser::getAbsoluteBCID ( ) const [inline]
Definition at line 233 of file PayloadParser.h.
00235
        std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
     Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER};
     std::uint64_t LBC = ((begin()[shift] « 16) | (begin()[shift + 1] « 8) | (begin()[shift + 2])) *
16777216ULL /* to shift the value from the 24 first bits*/
+ ((begin()[shift + 3] « 16) | (begin()[shift + 4] « 8) | (begin()[shift + 5]));
00236
00238
       return LBC;
00239 }
4.13.3.2 getASICid() std::uint32_t PayloadParser::getASICid (
               const std::uint32_t & i ) const [inline]
Definition at line 277 of file PayloadParser.h.
00277 { return m_Frames[i][0] & 0xFF; }
4.13.3.3 getBCID() std::uint32_t PayloadParser::getBCID ( ) const [inline]
Definition at line 241 of file PayloadParser.h.
00242 {
        std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
     Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID};
00244
       return (begin()[shift] « 16) + (begin()[shift + 1] « 8) + begin()[shift + 2];
00245 }
4.13.3.4 getDIF CRC() std::uint32_t PayloadParser::getDIF_CRC ( ) const [inline]
Definition at line 281 of file PayloadParser.h.
00282 {
       std::uint32_t shift{getEndOfDIFData() - (Size::CRC_MSB + Size::CRC_LSB)};
00284
        return (begin()[shift] « 8) + begin()[shift + 1];
00285 }
4.13.3.5 getDIFid() std::uint32_t PayloadParser::getDIFid ( ) const [inline]
Definition at line 271 of file PayloadParser.h.
00272 {
00273
       std::uint32_t shift{+Size::GLOBAL_HEADER};
       return begin()[shift] & 0xFF;
00275 }
4.13.3.6 getDTC() std::uint32_t PayloadParser::getDTC ( ) const [inline]
Definition at line 221 of file PayloadParser.h.
00222 {
00223
        std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF};
00224
        return (begin()[shift] < 24) + (begin()[shift + 1] < 16) + (begin()[shift + 2] < 8) + begin()[shift
      + 3];
00225 }
```

```
4.13.3.7 getEndOfDIFData() std::uint32_t PayloadParser::getEndOfDIFData ( ) const [inline]
Definition at line 289 of file PayloadParser.h.
00289 { return theGetFramePtrReturn_; }
4.13.3.8 getFrameBCID() std::uint32_t PayloadParser::getFrameBCID (
              const std::uint32_t & i ) const [inline]
Definition at line 257 of file PayloadParser.h.
00258 {
       std::uint32_t shift{+Size::MICROROC_HEADER};
00259
       return GrayToBin((m_Frames[i][shift] « 16) + (m_Frames[i][shift + 1] « 8) + m_Frames[i][shift + 2]);
00260
00261 }
4.13.3.9 getFrameLevel() bool PayloadParser::getFrameLevel (
              const std::uint32_t & i,
              const std::uint32_t & ipad,
              const std::uint32_t & ilevel ) const [inline]
Definition at line 265 of file PayloadParser.h.
00266 {
00267
        std::uint32_t shift{Size::MICROROC_HEADER + Size::BCID};
        return ((m_Frames[i][shift + ((3 - ipad / 16) * 4 + (ipad % 16) / 4)] » (7 - (((ipad % 16) % 4) * 2
00268
     + ilevel))) & 0x1);
00269 }
4.13.3.10 getFramePtr() bit8_t * PayloadParser::getFramePtr (
              const std::uint32_t & i ) const [inline]
Definition at line 255 of file PayloadParser.h.
00255 { return m_Frames[i]; }
4.13.3.11 getFramesVector() std::vector< bit8_t * > PayloadParser::getFramesVector ( ) const
[inline]
Definition at line 217 of file PayloadParser.h.
00217 { return m_Frames; }
4.13.3.12 getFrameTimeToTrigger() std::uint32_t PayloadParser::getFrameTimeToTrigger (
              const std::uint32_t & i ) const [inline]
Definition at line 263 of file PayloadParser.h.
00263 { return getBCID() - getFrameBCID(i); }
```

```
4.13.3.13 getGTC() std::uint32_t PayloadParser::getGTC ( ) const [inline]
Definition at line 227 of file PayloadParser.h.
00229
       std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
     Size::INFORMATION_COUNTER};
      return (begin()[shift] « 24) + (begin()[shift + 1] « 16) + (begin()[shift + 2] « 8) + begin()[shift
00230
00231 }
4.13.3.14 getLinesVector() std::vector< bit8_t * > PayloadParser::getLinesVector ( ) const
[inline]
Definition at line 219 of file PayloadParser.h.
00219 { return m_Lines; }
4.13.3.15 getNumberOfFrames() std::uint32_t PayloadParser::getNumberOfFrames () const [inline]
Definition at line 253 of file PayloadParser.h.
00253 { return m_Frames.size(); }
4.13.3.16 getSizeAfterDIFPtr() std::uint32_t PayloadParser::getSizeAfterDIFPtr ( ) const [inline]
Definition at line 287 of file PayloadParser.h.
00287 { return size() - theGetFramePtrReturn_; }
4.13.3.17 getSlowControl() Buffer PayloadParser::getSlowControl ( ) const [inline]
Definition at line 210 of file PayloadParser.h.
00211 {
00212
       if(hasSlowControl()) return Buffer(&begin()[getEndOfDIFData()], size() - getEndOfDIFData());
       else
00214
         return Buffer();
00215 }
4.13.3.18 getTemperatureASU1() float PayloadParser::getTemperatureASU1 ( ) const [inline]
Definition at line 198 of file PayloadParser.h.
00199 {
00200
        if(!hasTemperature()) throw Exception("Don't have TemperatureASUl information");
00201
       return (getTASU1() » 3) * 0.0625;
00202 }
```

```
4.13.3.19 getTemperatureASU2() float PayloadParser::getTemperatureASU2 ( ) const [inline]
Definition at line 204 of file PayloadParser.h.
00205 {
        if(!hasTemperature()) throw Exception("Don't have TemperatureASU2 information");
00206
       return (getTASU2() » 3) * 0.0625;
00207
00208 }
4.13.3.20 getTemperatureDIF() float PayloadParser::getTemperatureDIF ( ) const [inline]
Definition at line 192 of file PayloadParser.h.
00194
        if(!hasTemperature()) throw Exception("Don't have TemperatureDIF information");
00195
       return 0.508 * getTDIF() - 9.659;
00196 }
4.13.3.21 getThresholdStatus() std::uint32_t PayloadParser::getThresholdStatus (
              const std::uint32_t & i,
              const std::uint32_t & ipad ) const [inline]
Definition at line 279 of file PayloadParser.h.
00279 { return (((std::uint32_t)getFrameLevel(i, ipad, 1)) « 1) | ((std::uint32_t)getFrameLevel(i, ipad,
     0)); }
4.13.3.22 hasAnalogReadout() bool PayloadParser::hasAnalogReadout ( ) const [inline]
Definition at line 144 of file PayloadParser.h.
00144 { return getNumberLines() != 0; }
4.13.3.23 hasLine() bool PayloadParser::hasLine (
              const std::uint32_t & line ) const [inline]
Definition at line 247 of file PayloadParser.h.
00248 {
       std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
00249
     Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID + Size::BCID_DIF};
00250
       return ((begin()[shift] » line) & 0x1);
00251 }
4.13.3.24 hasSlowControl() bool PayloadParser::hasSlowControl ( ) const [inline]
Definition at line 172 of file PayloadParser.h.
00172 { return theGetFramePtrReturn_ != size(); }
```

4.13.3.25 hasTemperature() bool PayloadParser::hasTemperature () const [inline]


```
4.13.3.26 setBuffer() void PayloadParser::setBuffer ( const Buffer & buffer ) [inline]
```

Definition at line 92 of file PayloadParser.h.

The documentation for this class was generated from the following file:

• libs/core/include/PayloadParser.h

4.14 RawBufferNavigator Class Reference

class to navigate in the raw data buffer parse the header and send the payload as Buffer

```
#include <libs/core/include/RawBufferNavigator.h>
```

Public Member Functions

- RawBufferNavigator ()
- ∼RawBufferNavigator ()=default
- void setBuffer (const Buffer &)
- std::uint8_t getDetectorID ()
- bool findStartOfPayload ()
- std::int32_t getStartOfPayload ()
- bool validPayload ()
- Buffer getPayload ()

Static Public Member Functions

· static void StartAt (const int &start)

4.14.1 Detailed Description

class to navigate in the raw data buffer parse the header and send the payload as Buffer

Definition at line 13 of file RawBufferNavigator.h.

4.14.2 Constructor & Destructor Documentation

```
4.14.2.1 RawBufferNavigator() RawBufferNavigator::RawBufferNavigator ()
```

Definition at line 16 of file RawBufferNavigator.cc. $\tt 00016 \ \{\}$

4.14.2.2 ~RawBufferNavigator() RawBufferNavigator::~RawBufferNavigator () [default]

4.14.3 Member Function Documentation

4.14.3.1 findStartOfPayload() bool RawBufferNavigator::findStartOfPayload ()

Definition at line 27 of file RawBufferNavigator.cc.

```
00028 {
00029
        if (m_StartPayloadDone == true)
00030
00031
          if (m_StartPayload == -1) return false;
00032
          else
00033
            return true;
00034
        else
00035
00036
00037
          m_StartPayloadDone = true;
00038
          for(std::size_t i = m_Start; i < m_Buffer.size(); i++)</pre>
00039
00040
            if(static_cast<std::uint8_t>(m_Buffer[i]) == static_cast<std::uint8_t>(Value::GLOBAL_HEADER) ||
     static_cast<std::uint8_t>(m_Buffer[i]) == static_cast<std::uint8_t>(Value::GLOBAL_HEADER_TEMP))
00041
00042
              m_StartPayload = i;
00043
              return true;
           }
00044
00045
00046
         m_StartPayload = -1;
00047
          return false;
00048
       }
00049 }
```

$\textbf{4.14.3.2} \quad \textbf{getDetectorID()} \quad \texttt{std::uint8_t} \quad \texttt{RawBufferNavigator::getDetectorID} \quad \textbf{()}$

Definition at line 25 of file RawBufferNavigator.cc. 00025 { return m_Buffer[0]; }

```
4.14.3.3 getPayload() Buffer RawBufferNavigator::getPayload ( )
```

```
Definition at line 59 of file RawBufferNavigator.cc.
00059 { return Buffer(&(m_Buffer.begin()[m_StartPayload]), m_Buffer.size() - m_StartPayload); }
```

```
4.14.3.4 getStartOfPayload() std::int32_t RawBufferNavigator::getStartOfPayload ( )
```

Definition at line 51 of file RawBufferNavigator.cc.

```
00052 {
00053    findStartOfPayload();
00054    return m_StartPayload;
00055 }
```

```
4.14.3.5 setBuffer() void RawBufferNavigator::setBuffer ( const Buffer & b )
```

Definition at line 18 of file RawBufferNavigator.cc.

```
4.14.3.6 StartAt() void RawBufferNavigator::StartAt ( const int & start ) [static]
```

Definition at line 11 of file RawBufferNavigator.cc.

```
00012 {
00013    if(start >= 0) m_Start = start;
00014 }
```

4.14.3.7 validPayload() bool RawBufferNavigator::validPayload ()

```
Definition at line 57 of file RawBufferNavigator.cc. 00057 { return m_StartPayload != -1; }
```


The documentation for this class was generated from the following files:

- libs/core/include/RawBufferNavigator.h
- libs/core/src/RawBufferNavigator.cc

4.15 RawdataReader Class Reference

#include <libs/interface/RawDataReader/include/RawdataReader.h>

Inheritance diagram for RawdataReader:



Public Member Functions

- RawdataReader (const char *fileName)
- void start ()
- void end ()
- float getFileSize ()
- void openFile (const std::string &fileName)
- void closeFile ()
- bool nextEvent ()
- bool nextDIFbuffer ()
- const Buffer & getBuffer ()
- virtual ∼RawdataReader ()

Static Public Member Functions

• static void setDefaultBufferSize (const std::size_t &size)

Additional Inherited Members

4.15.1 Detailed Description

Definition at line 17 of file RawdataReader.h.

4.15.2 Constructor & Destructor Documentation

4.15.2.2 ~RawdataReader() virtual RawdataReader::~RawdataReader () [inline], [virtual]

```
Definition at line 29 of file RawdataReader.h. 00029 { closeFile(); }
```

4.15.3 Member Function Documentation

```
4.15.3.1 closeFile() void RawdataReader::closeFile ( )
```

```
Definition at line 47 of file RawdataReader.cc.
```

4.15.3.2 end() void RawdataReader::end ()

Definition at line 26 of file RawdataReader.cc.

00026 { closeFile(); }

4.15.3.3 getBuffer() const Buffer & RawdataReader::getBuffer ()

Definition at line 122 of file RawdataReader.cc.

```
00123 {
00124 uncompress();
00125 return m_Buffer;
00126 }
```

4.15.3.4 getFileSize() float RawdataReader::getFileSize ()

Definition at line 130 of file RawdataReader.cc.

00130 { return m_FileSize; }

4.15.3.5 nextDIFbuffer() bool RawdataReader::nextDIFbuffer ()

Definition at line 95 of file RawdataReader.cc. 00096 $\{$

```
00097
00098
        {
00099
         static int DIF_processed{0};
00100
          if(DIF_processed >= m_NumberOfDIF)
00101
           DIF_processed = 0;
00102
00103
           return false;
00104
00105
          else
00106
           DIF_processed++;
00107
00108
           std::uint32_t bsize{0};
           m_FileStream.read(reinterpret_cast<char*>(&bsize), sizeof(std::uint32_t));
00109
00110
           m_FileStream.read(reinterpret_cast<char*>(&m_buf[0]), bsize);
00111
            m_Buffer = Buffer(m_buf);
00112
         }
00113
00114
        catch(const std::ios_base::failure& e)
00115
00116
         log()->error("Caught an ios_base::failure in openFile : {}", e.what());
00117
         return false;
00118
00119
       return true;
00120 }
```

4.15.3.6 nextEvent() bool RawdataReader::nextEvent ()

Definition at line 81 of file RawdataReader.cc.

```
00082 {
00083
00084
00085
         m_FileStream.read(reinterpret_cast<char*>(&m_EventNumber), sizeof(std::uint32_t));
         m_FileStream.read(reinterpret_cast<char*>(&m_NumberOfDIF), sizeof(std::uint32_t));
00087
88000
       catch(const std::ios_base::failure& e)
00089
00090
         return false;
00091
00092
       return true;
00093 }
```

```
4.15.3.7 openFile() void RawdataReader::openFile ( const std::string & fileName )
```

Definition at line 60 of file RawdataReader.cc.

```
00062
00063
00064
           m_FileStream.rdbuf()->pubsetbuf(0, 0);
           m_FileStream.exceptions(std::ifstream::failbit | std::ifstream::badbit);
00065
      m_FileStream.open(fileName.c_str(), std::ios::in | std::ios::binary | std::ios::ate); // Start at the end to directly calculate the size of the file then come back to beginning
00066
00067
           m_FileStream.rdbuf()->pubsetbuf(0, 0);
00068
           if(m_FileStream.is_open())
00069
00070
             setFileSize(m_FileStream.tellq());
00071
             m FileStream.seekg(0, std::ios::beg);
00072
           }
00073
00074
        catch(const std::ios_base::failure& e)
00075
00076
           log()->error("Caught an ios_base::failure in openFile : {}", e.what());
00077
           throw;
00078
00079 }
```

```
4.15.3.8 setDefaultBufferSize() void RawdataReader::setDefaultBufferSize ( const std::size_t & size ) [static]
```

Definition at line 16 of file RawdataReader.cc.

```
00016 { m_BufferSize = size; }
```

```
4.15.3.9 start() void RawdataReader::start ( )
```

Definition at line 24 of file RawdataReader.cc.
00024 { openFile(m_Filename); }


The documentation for this class was generated from the following files:

- libs/interface/RawDataReader/include/RawdataReader.h
- libs/interface/RawDataReader/src/RawdataReader.cc

4.16 ROOTWriter Class Reference

#include <libs/interface/ROOT/include/ROOTWriter.h>

Inheritance diagram for ROOTWriter:



Public Member Functions

- ROOTWriter ()
- void setFilename (const std::string &)
- void start ()
- void processDIF (const PayloadParser &)
- void processFrame (const PayloadParser &, const std::uint32_t &frameIndex)
- void processPadInFrame (const PayloadParser &, const std::uint32_t &frameIndex, const std::uint32_←
 t &channeIIndex)
- void processSlowControl (const Buffer &)
- void end ()
- virtual void startEvent ()
- virtual void endEvent ()
- virtual void startDIF ()
- virtual void endDIF ()
- virtual void startFrame ()
- virtual void endFrame ()
- virtual void startPad ()
- virtual void endPad ()

4.16.1 Detailed Description

Definition at line 18 of file ROOTWriter.h.

4.16.2 Constructor & Destructor Documentation

```
4.16.2.1 ROOTWriter() ROOTWriter::ROOTWriter ( )

Definition at line 10 of file ROOTWriter.cc.
00010 : InterfaceWriter("ROOTWriter", "1.0.0") { addCompatibility("RawdataReader", ">=1.0.0"); }
```

4.16.3 Member Function Documentation

4.16.3.1 end() void ROOTWriter::end ()

Definition at line 19 of file ROOTWriter.cc.

4.16.3.2 endDIF() void ROOTWriter::endDIF () [virtual]

Reimplemented from Interface.

Definition at line 75 of file ROOTWriter.cc.

4.16.3.3 endEvent() void ROOTWriter::endEvent () [virtual]

Reimplemented from Interface.

Definition at line 63 of file ROOTWriter.cc.

4.16.3.4 endFrame() void ROOTWriter::endFrame () [virtual]

Reimplemented from Interface.

Definition at line 87 of file ROOTWriter.cc.

4.16.3.5 endPad() void ROOTWriter::endPad () [virtual]

Reimplemented from Interface.

```
Definition at line 95 of file ROOTWriter.cc. 00095 \{\}
```

```
4.16.3.6 processDIF() void ROOTWriter::processDIF (
               const PayloadParser & d )
Definition at line 30 of file ROOTWriter.cc.
00032
        m_DIF->setID(d.getDIFid());
00033
        m_DIF->setDTC(d.getDTC());
       m_DIF->setGTC(d.getGTC());
m_DIF->setDIFBCID(d.getBCID());
00034
00035
00036
       m_DIF->setAbsoluteBCID(d.getAbsoluteBCID());
00037 }
4.16.3.7 processFrame() void ROOTWriter::processFrame (
               const PayloadParser & d,
               const std::uint32_t & frameIndex )
Definition at line 39 of file ROOTWriter.cc.
00040 {
        m_Hit->setDIF(d.getDIFid());
00042
        m_Hit->setASIC(d.getASICid(frameIndex));
00043
        m_Hit->setDTC(d.getDTC());
00044
        m_Hit->setGTC(d.getGTC());
00045
        m_Hit->setDIFBCID(d.getBCID());
00046
        m_Hit->setAbsoluteBCID(d.getAbsoluteBCID());
       m_Hit->setFrameBCID(d.getFrameBCID(frameIndex));
m_Hit->setTimestamp(d.getFrameTimeToTrigger(frameIndex));
00047
00049 }
4.16.3.8 processPadInFrame() void ROOTWriter::processPadInFrame (
               const PayloadParser & d,
               const std::uint32_t & frameIndex,
               const std::uint32_t & channelIndex )
Definition at line 51 of file ROOTWriter.cc.
00052 {
00053
        m_Hit->setChannel(channelIndex);
00054
       m_Hit->setThreshold(static_cast<std::uint8_t>(d.getThresholdStatus(frameIndex, channelIndex)));
00055 }
4.16.3.9 processSlowControl() void ROOTWriter::processSlowControl (
               const Buffer & ) [inline]
Definition at line 29 of file ROOTWriter.h.
00029 { ; }
4.16.3.10 setFilename() void ROOTWriter::setFilename (
               const std::string & filename )
Definition at line 8 of file ROOTWriter.cc.
00008 { m_Filename = filename; }
```

4.16.3.11 start() void ROOTWriter::start ()

Definition at line 12 of file ROOTWriter.cc.

4.16.3.12 startDIF() void ROOTWriter::startDIF () [virtual]

Reimplemented from Interface.

Definition at line 69 of file ROOTWriter.cc.

```
00070 {
00071    m_DIF = new DIF();
00072    // m_DIF->clear();
00073 }
```

4.16.3.13 startEvent() void ROOTWriter::startEvent () [virtual]

Reimplemented from Interface.

Definition at line 57 of file ROOTWriter.cc.

```
00058 {
00059    m_Event = new Event();
00060    // m_Event->clear();
00061 }
```

4.16.3.14 startFrame() void ROOTWriter::startFrame () [virtual]

Reimplemented from Interface.

Definition at line 81 of file ROOTWriter.cc.

4.16.3.15 startPad() void ROOTWriter::startPad () [virtual]

Reimplemented from Interface.

```
Definition at line 93 of file ROOTWriter.cc.
```


The documentation for this class was generated from the following files:

- libs/interface/ROOT/include/ROOTWriter.h
- libs/interface/ROOT/src/ROOTWriter.cc

4.17 textDump Class Reference

#include <libs/interface/Dump/include/textDump.h>

Inheritance diagram for textDump:



Public Member Functions

- textDump ()
- · void start ()
- void processDIF (const PayloadParser &)
- void processFrame (const PayloadParser &, uint32 t frameIndex)
- void processPadInFrame (const PayloadParser &, uint32_t frameIndex, uint32_t channelIndex)
- void processSlowControl (Buffer)
- void end ()
- std::shared_ptr< spdlog::logger > & print ()
- void setLevel (const spdlog::level::level_enum &level)

4.17.1 Detailed Description

Definition at line 14 of file textDump.h.

4.17.2 Constructor & Destructor Documentation

```
4.17.2.1 textDump() textDump::textDump()
```

```
Definition at line 9 of file textDump.cc.
```

4.17.3 Member Function Documentation

```
4.17.3.1 end() void textDump::end ()
Definition at line 33 of file textDump.cc.
00033 { print()->info("textDump end of report"); }
4.17.3.2 print() std::shared_ptr < spdlog::logger > & textDump::print ( ) [inline]
Definition at line 24 of file textDump.h.
00024 { return m_InternalLogger; }
4.17.3.3 processDIF() void textDump::processDIF (
                                   const PayloadParser & d )
Definition at line 19 of file textDump.cc.
00019 { print()->info("DIF_ID : {}, DTC : {}, GTC : {}, DIF BCID {}, Absolute BCID : {}, Nbr frames {}", d.getDIFid(), d.getDTC(), d.getGTC(), d.getBCID(), d.getAbsoluteBCID(), d.getNumberOfFrames()); }
4.17.3.4 processFrame() void textDump::processFrame (
                                   const PayloadParser & d,
                                   uint32_t frameIndex )
Definition at line 21 of file textDump.cc.
00022 {
00023
                   print() - sinfo("\tDisplaying frame number {} : ASIC ID {}, Frame BCID {}, Frame Time To Trigger frame SCID {}, Frame Time To Trigger frame SCID {}, Frame Time To Trigger frame SCID {}, Frame SCID {
              (a.k.a timestamp) is {}", frameIndex, d.getASICid(frameIndex), d.getFrameBCID(frameIndex),
d.getFrameTimeToTrigger(frameIndex));
00024 }
4.17.3.5 processPadInFrame() void textDump::processPadInFrame (
                                   const PayloadParser & d,
                                   uint32_t frameIndex,
                                   uint32_t channelIndex )
Definition at line 26 of file textDump.cc.
                   00028
               {}", channelIndex, d.getThresholdStatus(frameIndex, channelIndex)); }
00029 }
4.17.3.6 processSlowControl() void textDump::processSlowControl (
                                   Buffer )
Definition at line 31 of file textDump.cc.
00031 { print()->error("textDump::processSlowControl not implemented yet."); }
```

The documentation for this class was generated from the following files:

- libs/interface/Dump/include/textDump.h
- libs/interface/Dump/src/textDump.cc

4.18 Timer Class Reference

```
#include <libs/core/include/Timer.h>
```

Public Member Functions

- void start ()
- void stop ()
- float getElapsedTime ()

4.18.1 Detailed Description

Definition at line 9 of file Timer.h.

4.18.2 Member Function Documentation

```
4.18.2.1 getElapsedTime() float Timer::getElapsedTime ( ) [inline]

Definition at line 14 of file Timer.h.
00014 { return std::chrono::duration_cast<std::chrono::microseconds>(m_StopTime - m_StartTime).count(); }

4.18.2.2 start() void Timer::start ( ) [inline]

Definition at line 12 of file Timer.h.
00012 { m_StartTime = std::chrono::high_resolution_clock::now(); }
```

```
4.18.2.3 stop() void Timer::stop ( ) [inline]

Definition at line 13 of file Timer.h.
00013 { m_StopTime = std::chrono::high_resolution_clock::now(); }
```


The documentation for this class was generated from the following file:

• libs/core/include/Timer.h

4.19 Version Class Reference

```
#include <libs/core/include/Version.h>
```

Inheritance diagram for Version:



Public Member Functions

- Version (const std::uint8_t &mj, const std::uint8_t &mn, const std::uint8_t &pt, const semver::prerelease &prt=semver::prerelease::none, const std::uint8_t &prn=0) noexcept
- Version (const std::string_view &str)
- · Version ()=default
- std::uint8 t getMajor ()
- std::uint8_t getMinor ()
- std::uint8_t getPatch ()
- std::string getPreRelease ()
- std::uint8 t getPreReleaseNumber ()

4.19.1 Detailed Description

Definition at line 11 of file Version.h.

4.19.2 Constructor & Destructor Documentation

```
4.19.2.2 Version() [2/3] Version::Version (
               const std::string_view & str ) [inline], [explicit]
Definition at line 15 of file Version.h.
00015 : semver::version(str) {}
4.19.2.3 Version() [3/3] Version::Version ( ) [default]
4.19.3 Member Function Documentation
4.19.3.1 getMajor() std::uint8_t Version::getMajor ( )
Definition at line 9 of file Version.cc.
00009 { return major; }
4.19.3.2 getMinor() std::uint8\_t Version::getMinor ( )
Definition at line 11 of file Version.cc.
00011 { return minor; }
4.19.3.3 getPatch() std::uint8_t Version::getPatch ( )
Definition at line 13 of file Version.cc.
00013 { return patch; }
4.19.3.4 getPreRelease() std::string Version::getPreRelease ( )
Definition at line 15 of file Version.cc.
00016 {
00017
        switch (prerelease_type)
00018
          case semver::prerelease::alpha: return "alpha";
case semver::prerelease::beta: return "beta";
case semver::prerelease::rc: return "rc";
00019
00020
00021
00022
          case semver::prerelease::none: return "";
00023
          default: return "";
00024
00025 }
```

5 File Documentation 55

```
4.19.3.5 getPreReleaseNumber() std::uint8_t Version::getPreReleaseNumber ( )

Definition at line 27 of file Version.cc.

00027 { return prerelease_number; }
```

The documentation for this class was generated from the following files:

- libs/core/include/Version.h
- libs/core/src/Version.cc

5 File Documentation

5.1 libs/core/include/Bits.h File Reference

```
#include <cstdint>
#include <iosfwd>
```

Typedefs

```
using bit8_t = std::uint8_t
using bit16_t = std::uint16_t
using bit32_t = std::uint32_t
using bit64_t = std::uint64_t
```

Functions

std::ostream & operator << (std::ostream &os, const bit8_t &c)
 Stream operator to print bit8_t aka std::uint8_t and not char or unsigned char.

5.1.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Bits.h.

5.1.2 Typedef Documentation

```
5.1.2.1 bit16_t using bit16_t = std::uint16_t
```

Definition at line 11 of file Bits.h.

```
5.1.2.2 bit32_t using bit32_t = std::uint32_t
```

Definition at line 12 of file Bits.h.

```
5.1.2.3 bit64_t using bit64_t = std::uint64_t
```

Definition at line 13 of file Bits.h.

```
5.1.2.4 bit8_t using bit8_t = std::uint8_t
```

Definition at line 10 of file Bits.h.

5.1.3 Function Documentation

Stream operator to print bit8_t aka std::uint8_t and not char or unsigned char.

```
Definition at line 8 of file Bits.cc. 00008 { return os « c + 0; }
```

5.2 Bits.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include <cstdint>
00008 #include <iosfwd>
00009
00010 using bit8_t = std::uint8_t; /*<! type to represent 8bits words (1 byte) */
00011 using bit16_t = std::uint16_t; /*<! type to represent 16bits words (2 bytes) */
00012 using bit32_t = std::uint32_t; /*<! type to represent 32bits words (4 bytes) */
00013 using bit64_t = std::uint64_t; /*<! type to represent 64bits words (8 bytes) */
00014
00016 std::ostream& operator (std::ostream& os, const bit8_t& c);</pre>
```

5.3 libs/core/include/Buffer.h File Reference

```
#include "Bits.h"
#include <array>
#include <string>
#include <vector>
```

5.4 Buffer.h 57

Classes

class Buffer

5.3.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde A.Pingault L.Mirabito

See also

```
https://github.com/apingault/Trivent4HEP
```

Definition in file Buffer.h.

5.4 Buffer.h

Go to the documentation of this file.

```
00001
00006 #pragma once
00007
00008 #include "Bits.h"
00010 #include <array>
00011 #include <string>
00012 #include <vector>
00013
00014 class Buffer
00015 {
00016 public:
00017
       Buffer() : m_Buffer(nullptr), m_Size(0), m_Capacity(0) {}
        virtual ~Buffer() {}
00018
00019
        Buffer(const bit8_t b[], const std::size_t& i) : m_Buffer(const_cast<bit8_t*>(&b[0])), m_Size(i),
      m_Capacity(i) {}
       bit8_t*>(&b[0]))), m_Size(i * sizeof(char)), m_Capacity(i * sizeof(char)) {}
       template<typename T> Buffer(const std::vector<T>& rawdata) :
       \texttt{m\_Buffer(const\_cast<bit8\_t*>(reinterpret\_cast<const\_bit8\_t*>(rawdata.data()))), } \texttt{m\_Size(rawdata.size())} 
* sizeof(T)), m_Capacity(rawdata.capacity() * sizeof(T)) {}
00022  template<typename T, std::size_t N> Buffer(const std::array<T, N>& rawdata) :
    m_Buffer(const_cast<bit8_t*>(reinterpret_cast<const bit8_t*>(rawdata.data()))), m_Size(rawdata.size())
      * sizeof(T)), m_Capacity(rawdata.size() * sizeof(T)) {}
00023
00024
        std::size_t size()const { return m_Size; }
00025
        std::size_t capacity()const { return m_Capacity; }
00026
        bool empty() { return m_Size == 0; }
00027
00028
        void set(unsigned char* b) { m_Buffer = b; }
00029
        void set (const Buffer& buffer)
00030
00031
         m_Buffer = buffer.begin();
                     = buffer.size();
00032
          m Size
00033
         m_Capacity = buffer.capacity();
00034
00035
        bit8_t* begin()const { return m_Buffer; }
00036
        bit8_t* end()const { return m_Buffer + m_Size; }
00037
        bit8_t& operator[](const std::size_t& pos) { return m_Buffer[pos]; }
00038
        bit8_t& operator[](const std::size_t& pos)const { return m_Buffer[pos]; }
00039
00040
        void setSize(const std::size_t& size) { m_Size = size; }
00041
00042 private:
      bit8_t*
00043
                   m_Buffer{nullptr};
00044
        std::size_t m_Size{0};
       std::size_t m_Capacity{0};
00045
00046 };
```

5.5 libs/core/include/BufferLooper.h File Reference

```
#include "AppVersion.h"
#include "Buffer.h"
#include "BufferLooperCounter.h"
#include "DetectorId.h"
#include "Formatters.h"
#include "PayloadParser.h"
#include "RawBufferNavigator.h"
#include "Timer.h"
#include "Words.h"
#include <algorithm>
#include <cassert>
#include <fmt/color.h>
#include <map>
#include <memory>
#include <spdlog/sinks/null_sink.h>
#include <spdlog/spdlog.h>
#include <string>
#include <vector>
```

Classes

class BufferLooper< SOURCE, DESTINATION >

5.5.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file BufferLooper.h.

5.6 BufferLooper.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include "AppVersion.h"
00008 #include "Buffer.h"
00009 #include "BufferLooperCounter.h"
00010 #include "DetectorId.h"
00011 #include "Formatters.h"
00012 #include "PayloadParser.h"
00012 #include Tayloadrarser.n
00013 #include "RawBufferNavigator.h"
00014 #include "Timer.h"
00015 #include "Words.h"
00016
00017 #include <algorithm>
00018 #include <cassert>
00019 #include <fmt/color.h>
00020 #include <map>
00021 #include <memory>
00022 #include <spdlog/sinks/null_sink.h>
00023 #include <spdlog/spdlog.h>
00024 #include <string>
00025 #include <vector>
00026 // function to loop on buffers
```

5.6 BufferLooper.h 59

```
00028 template<typename SOURCE, typename DESTINATION> class BufferLooper
00029 {
00030 public:
00031
      BufferLooper(SOURCE& source, DESTINATION& dest, bool debug = false) : m_Source(source),
    m\_Destination(dest), m\_Debug(debug)
00032
00033
        m_Logger = spdlog::create<spdlog::sinks::null_sink_mt>("streamout");
        if(!spdlog::get("streamout")) { spdlog::register_logger(m_Logger); }
00034
00035
        m_Source.setLogger(m_Logger);
00036
        m_Destination.setLogger(m_Logger);
00037
00038
00039
      void addSink(const spdlog::sink ptr& sink, const spdlog::level::level enum& level =
    spdlog::get_level())
00040
00041
        sink->set_level(level);
00042
        m_Sinks.push_back(sink);
00043
        m_Logger = std::make_shared<spdlog::logger>("streamout", begin(m_Sinks), end(m_Sinks));
00044
        m_Source.setLogger(m_Logger);
00045
        m_Destination.setLogger(m_Logger);
00046
00047
00048
      void loop(const std::uint32_t& m_NbrEventsToProcess = 0)
00049
00050
        // clang-format off
       fmt::print(fg(fmt::color::medium_orchid) | fmt::emphasis::bold,
00052
00053 " SSSSSSSSSSSSSS
    tttt\n"
\texttt{ttt} :: : \texttt{t} \backslash \texttt{n"}
00055 "S:::::SSSSSS::::::S t::::t
     t::::t\n"
00056 "S:::::S
               SSSSSSS t::::t
     t:::::t \backslash n "
00057 "S:::::S
             aaaaaaaaaaaa
mmmmmm mmmmmmm
00058 "S:::::S +...
                                                                     a::::::::a
    u::::ut:::::::::t\n"
00059 " S::::SSSS t::::::::t r:::::::r e:::::eeeee::::eeaaaaaaaaa::::a
a::::a
r::::re:::::eeeee:::::e aaaaaaa:::::a
    " SSS::::::SS t::::t r::::r m::::mmm:::::mm:::::mo::::o o::::ou::::u
                                             u::::u
                                                        t:::::t\n"
          SSSSSS::::S t::::t
00062 "
                                    r::::r
                                               rrrrrre:::::: a m::::m
m::::m m::::mo::::o o::::ou::::u u::::u t:::::t\n"
                       S:::::S t:::::t
                                                    e:::::eeeeeeeeee a::::aaaa::::::a m::::m
    m::::m m::::mo::::o
00064 "
              S:::::S t:::::t ttttttr::::r
                                                   e:::::e
                                                                    a::::a
                                                                           a:::::a m:::::m
    m::::m m::::mo::::o
                                                          tttttt\n"
00065 "SSSSSSS S::::S t:::::tttt:::::r
                                                     e::::::e
                                                                    a::::a a:::::a m::::m
                                                 t:::::t\n"
    00066 "S:::::SSSSSS:::::S tt::::::::tr::::r
                                                     e::::::eeeeeeeea:::::aaaa::::::a m::::m
    tt:::::::t\n"
tt::::::tt\n"
           m::::m
00068 " SSSSSSSSSSSSS
                         tttttttttt rrrrrr
                                                        eeeeeeeeee aaaaaaaaa aaammmmmm
mmmmmm mmmmmm 0000000000 00069 "\n",
                                 uuuuuuuu uuuu
                                                   ttttttttttt {}\n"
00070 fmt::format(fg(fmt::color::red) | fmt::emphasis::bold, "v{}", streamout_version.to_string()));
00071
        // clang-format on
00072
        log()->info("Streamout Version : {}", streamout_version.to_string());
00073
        log()->info("Using InterfaceReader {} version {}", m_Source.getName(),
00074
    m_Source.getVersion().to_string());
00075
        log()->info("Using InterfaceWriter {} version {}", m_Destination.getName(),
    m_Destination.getVersion().to_string());
00077
        if(!m_Destination.checkCompatibility(m_Source.getName(), m_Source.getVersion().to_string()))
00078
         \log() ->critical("{} version {} is not compatible with {} version {} ! ", m_Source.getName(),
00079
    m_Source.getVersion().to_string(), m_Destination.getName(), m_Destination.getVersion().to_string());
    log()->info("Compatible Interfaces for {} are", m_Destination.getName());
    for(std::map<std::string, std::string>::iterator it = m_Destination.getCompatibility().begin();
00080
00081
     it != m_Destination.getCompatibility().end(); ++it) { log()->info("{} version {}", it->first,
     it->second); }
00082
         std::exit(-1);
00083
00084
        if(!m DetectorIDs.emptv())
00085
00086
          std::string ids;
          for(std::vector<DetectorID>::const_iterator it = m_DetectorIDs.cbegin(); it !=
    m_DetectorIDs.cend(); ++it) ids += std::to_string(static_cast<std::uint16_t>(*it)) + ";";
00088
         log()->info("Detector ID(s) other than {} will be ignored", ids);
00089
00090
```

```
RawBufferNavigator bufferNavigator;
00092
                             timer;
00093
         timer.start();
00094
          m_Source.start();
00095
          m Destination.start();
00096
          while (m_Source.nextEvent() && m_NbrEventsToProcess >= m_NbrEvents)
00098 /***********
00099 /*** START EVENT ***/
00100
           m Source.startEvent();
00101
           m_Destination.startEvent();
00102 /*************/
00103
00104
            m_Logger->warn("===*** Event {} ***===", m_NbrEvents);
00105
            while (m_Source.nextDIFbuffer())
00106
00107
              const Buffer& buffer = m Source.getBuffer();
00108
00109
              bufferNavigator.setBuffer(buffer);
00110
              if(std::find(m_DetectorIDs.begin(), m_DetectorIDs.end(),
     static_cast<DetectorID>(bufferNavigator.getDetectorID())) == m_DetectorIDs.end())
00111
             {
00112
               m_Logger->debug("Ignoring detector ID : {}", bufferNavigator.getDetectorID());
00113
               continue;
             }
00114
00115
00116
              std::int32_t idstart = bufferNavigator.getStartOfPayload();
00117
              if(m_Debug && idstart == -1) m_Logger->info(to_hex(buffer));
00118
              c.DIFStarter[idstart]++;
              if(!bufferNavigator.validPayload())
00119
00120
             {
00121
               m_Logger->error("!bufferNavigator.validBuffer()");
00122
               continue;
00123
00124
00125 /*************
00126 /*** START DIF ***/
             m_Source.startDIF();
00128
              m_Destination.startDIF();
00129 /**************
00130
             PayloadParser d;
              // This is really a big error so skip DIF entirely if exception occurs
00131
00132
00133
             {
00134
               d.setBuffer(bufferNavigator.getPayload());
00135
00136
              catch(const Exception& e)
00137
              {
               m_Logger->error("{}", e.what());
00138
00139
               continue:
00140
00141
fmt::ptr(d.end()));
00143
00142
              if(buffer.end() != d.end()) m_Logger->error("DIF BUFFER END {} {}", fmt::ptr(buffer.end()),
             assert(buffer.end() == d.end());
00144
00145
              c.DIFPtrValueAtReturnedPos[d.begin()[d.getEndOfDIFData() - 3]]++;
00146
              assert(d.begin()[d.getEndOfDIFData() - 3] == 0xa0);
00147
00148
              c.SizeAfterDIFPtr[d.getSizeAfterDIFPtr()]++;
00149
             {\tt m\_Destination.processDIF(d);}
              for(std::size_t i = 0; i < d.getNumberOfFrames(); ++i)</pre>
00150
00151
00152 /***********
00153 /*** START FRAME ***/
00154
               m_Source.startFrame();
00155
               m_Destination.startFrame();
00156 /***********
00157
              m_Destination.processFrame(d, i);
00158
                for(std::size_t j = 0; j < static_cast<std::size_t>(Hardware::NUMBER_PAD); ++j)
00159
00160
                  if(d.getThresholdStatus(i, j) != 0)
00161
00162
                   m Source.startPad();
00163
                   m Destination.startPad();
                    m_Destination.processPadInFrame(d, i, j);
00164
00165
                    m_Source.endPad();
00166
                    m_Destination.endPad();
00167
               }
00168
00169 /*************
00170 /*** END FRAME ***/
00171
               m_Source.endFrame();
00172
                m_Destination.endFrame();
00173 /*************/
00174
00175
              // If I want SlowControl I need to check for it first, If there is an error then it's not a
```

```
big deal just continue and say is bad SlowControl
00176
                        /*try
00177 {
00178 d.setSCBuffer();
00179 }
00180 catch(const Exception& e)
00181 {
00182 m_Logger->error("{}", e.what());
00183 }
00184
00185 bool processSC = false;
00186 if (d.hasSlowControl())
00187
00188 c.hasSlowControl++;
00189 processSC = true;
00190
00191 if (d.badSCData())
00192 {
00193 c.hasBadSlowControl++;
00194 processSC = false;
00195
00196 if (processSC) { m_Destination.processSlowControl(d.getSCBuffer()); } */
00197
                          // Buffer eod = d.getEndOfAllData();
00198
00199
                          // c.SizeAfterAllData[eod.size()]++;
                         // bit8_t* debug_variable_3 = eod.end();
                          // if(buffer.end() != debug_variable_3) m_Logger->info("END DATA BUFFER END {} {}",
00201
         fmt::ptr(buffer.end()), fmt::ptr(debug_variable_3));
00202  // assert(buffer.end() == debug_variable_3);
00203  // if(eod.size() != 0) m_Logger->info("End of Data remaining stuff : {}", to_hex(eod));*/
00204
00205
                          /*int nonzeroCount = 0;
00206 for(bit8_t* it = eod.begin(); it != eod.end(); it++)
00207 if(static_cast<int>(*it) != 0) nonzeroCount++;
00208 c.NonZeroValusAtEndOfData[nonzeroCount]++; */
00209
00210 /***********
00211 /*** END DIF ***/
00212
                     m_Source.endDIF();
00213
                         m_Destination.endDIF();
00214 /************/
                ^{\cdot} // end of DIF while loop
00215
                     m_Logger->warn("===*** Event {} ***===", m_NbrEvents);
00216
                     m_NbrEvents++;
00219 /*** END EVENT ***/
00220 m_Source.endEvent();
00221
                     m_Destination.endEvent();
00222 /*************
00223 } // end of event while loop
00224
                m_Destination.end();
               m_Source.end();
timer.stop();
00225
00226
                  \label{fmt::print} fmt::print(fg(fmt::color::green) \ | \ fmt::emphasis::bold, \ "=== \ elapsed \ time \ \{\} ms \ (\{\} ms/event) \} = (ff(fmt)) + (ff(f
00227
          ===\n", timer.getElapsedTime() / 1000, timer.getElapsedTime() / (1000 * m_NbrEvents));
00228 }
00229
                                                                           printAllCounters() { c.printAllCounters(); }
00230
              std::shared_ptr<spdlog::logger> log() { return m_Logger; }
00231
00232
              void setDetectorIDs(const std::vector<DetectorID>& detectorIDs) { m_DetectorIDs = detectorIDs; }
00233
00234 private:
00235
              std::vector<DetectorID>
                                                                          m_DetectorIDs;
00236
              std::shared_ptr<spdlog::logger> m_Logger{nullptr};
00237
               std::vector<spdlog::sink_ptr> m_Sinks;
00238
              BufferLooperCounter
                                                                          c;
                                                                          m_Source{nullptr};
00239
              SOURCE&
              DESTINATION&
00240
                                                                          m Destination { nullptr } ;
00241
             bool
                                                                          m Debug{false};
              std::uint32_t
                                                                          m_NbrEvents{1};
00243 };
```

5.7 libs/core/include/BufferLooperCounter.h File Reference

```
#include <ios>
#include <map>
#include <memory>
#include <string>
```

Classes

· struct BufferLooperCounter

5.7.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file BufferLooperCounter.h.

5.8 BufferLooperCounter.h

Go to the documentation of this file.

```
00005 #pragma once
00006
00007 #include <ios>
00008 #include <map>
00009 #include <memory>
00010 #include <string>
00011
00012 struct BufferLooperCounter
00013 {
00014 public:
00015 int
00016 int
                                 hasSlowControl
                                 hasBadSlowControl = 0;
00017
         std::map<int, int> DIFStarter;
         std::map<int, int> DIFPtrValueAtReturnedPos;
std::map<int, int> SizeAfterDIFPtr;
00018
00019
00020 std::map<int, int> SizeAfterAllData;
00021 std::map<int, int> NonZeroValusAtEndOfData;
00022
         void printCounter(const std::string& description, const std::map<int, int>& m, const
std::ios_base::fmtflags& base = std::ios_base::dec);
00024     void printAllCounters();
00025 };
```

5.9 libs/core/include/DetectorId.h File Reference

#include <cstdint>

Enumerations

• enum class DetectorID : std::uint16_t { HARDROC = 100 , HARDROC_NEW = 150 , RUNHEADER = 255 }

5.9.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file DetectorId.h.

5.9.2 Enumeration Type Documentation

5.9.2.1 DetectorID enum class DetectorID : std::uint16_t [strong]

5.10 DetectorId.h 63

Enumerator

HARDROC	
HARDROC_NEW	
RUNHEADER	

Definition at line 9 of file DetectorId.h.

5.10 DetectorId.h

Go to the documentation of this file.

```
00001

00005 #pragma once

00006

00007 #include <cstdint>

00008

00009 enum class DetectorID : std::uint16_t

00010 {

00011 HARDROC = 100,

00012 HARDROC_NEW = 150,

00013 RUNHEADER = 255

00014 };
```

5.11 libs/core/include/DIFSlowControl.h File Reference

```
#include <bitset>
#include <cstdint>
#include <iosfwd>
#include <map>
#include <string>
```

Classes

class DIFSlowControl

Functions

std::string to_string (const DIFSlowControl &c)

5.11.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file DIFSlowControl.h.

5.11.2 Function Documentation

```
5.11.2.1 to string() std::string to_string (
                 const DIFSlowControl & c )
Definition at line 256 of file DIFSlowControl.cc.
00258
         std::string ret;
00259
         for(std::map<int, std::map<std::string, int>::const_iterator it = c.cbegin(); it != c.cend(); it++)
00260
           ret += "ASIC " + std::to_string(it->first) + " :\n";
00261
      for (std::map<std::string, int>::const_iterator jt = (it->second).begin(); jt != (it->second).end(); jt++) ret += jt->first + " : " + std::to_string(jt->second) +
00262
                                                                    + std::to_string(jt->second) + "\n";
00263
00264
         return ret;
00265 }
```

5.12 DIFSlowControl.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include <bitset>
00008 #include <cstdint>
00009 #include <iosfwd>
00010 #include <map>
00011 #include <string>
00012
00013 class DIFSlowControl
00014 {
00015 public:
00017
00022
       DIFSlowControl(const std::uint8_t& version, const std::uint8_t& DIFid, unsigned char* buf);
00023
00025
       std::uint8_t getDIFId();
00026
00028
00031
       std::map<int, std::map<std::string, int> getChipsMap();
00032
00034
00038
       std::map<std::string, int> getChipSlowControl(const int& asicid);
00039
00041
00045
        int getChipSlowControl(const std::int8_t& asicid, const std::string& param);
00046
00047
        std::map<int, std::map<std::string, int»::const_iterator cbegin()const { return m_MapSC.cbegin(); }</pre>
00048
00049
        std::map<int, std::map<std::string, int»::const_iterator cend()const { return m_MapSC.cend(); }
00050
00051 private:
00053
       DIFSlowControl() = delete;
00055
        void FillHR1(const int& header shift, unsigned char* cbuf);
        void FillHR2(const int& header_shift, unsigned char* cbuf);
00057
        void FillAsicHR1(const std::bitset<72 * 8>& bs);
00061
       void FillAsicHR2(const std::bitset<109 * 8>& bs);
00062
00063
       unsigned int
                                                   m DIFId(0);
00064
                                                  m_Version{0};
       unsigned int
00065
                                                   m_AsicType{0}; // asicType_
        unsigned int
00066
                                                  m_NbrAsic{0};
       unsigned int
00067
        std::map<int, std::map<std::string, int> m_MapSC;
00068 };
00069
00070 std::string to_string(const DIFSlowControl& c);
00071 /* void setSCBuffer()
00073 if(!hasSlowControl()) return;
00074 if(m_SCbuffer.size() != 0) return; // deja fait
00075 if (m_BadSlowControl) return;
00076 m_SCbuffer.set(&(begin()[getEndOfDIFData()]));
00077 // compute Slow Control size
00078 std::size_t maxsize{size() - getEndOfDIFData() + 1}; // should I +1 here ?
00079 uint32_t
                 k{1};
                                                             // SC Header
```

```
00080 uint32_t
                   dif_ID{m_SCbuffer[1]};
                   chipSize{m_SCbuffer[3]};
00081 uint32_t
00082 while((dif_ID != 0xal && m_SCbuffer[k] != 0xal && k < maxsize) || (dif_ID == 0xal && m_SCbuffer[k + 2]
      == chipSize && k < maxsize))
00084 k += 2; // DIF ID + ASIC Header
00085 uint32_t scsize = m_SCbuffer[k];
00086 if(scsize != 74 && scsize != 109)
00087 {
00088 k
00089 m_BadSlowControl = true;
00090 throw Exception(fmt::format("PROBLEM WITH SC SIZE {}", scsize));
00091 }
00092 k++;  // skip size bit
00093 k += scsize;  // skip the data
00094
00095 if(m_SCbuffer[k] == 0xa1 \&\& !m_BadSlowControl) m_SCbuffer.setSize(k + 1); // add the trailer
00096 else
00098 m_BadSlowControl = true;
00099 throw Exception(fmt::format("PROBLEM SC TRAILER NOT FOUND "));
00100 }
00101 }*/
```

5.13 libs/core/include/Exception.h File Reference

```
#include <cstdint>
#include <exception>
#include <string>
```

Classes

· class Exception

5.13.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Exception.h.

5.14 Exception.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include <cstdint>
00008 #include <exception>
00009 #include <string>
00010
00011 class Exception
00013 public:
00014
       virtual const char* what() const noexcept { return m_What.c_str(); }
00015
       explicit Exception(const std::string& message) : m_Message(message) { constructWhat(); }
        Exception(const std::int32_t& error, const std::string& message) : m_Error(error),
00016
     m_Message(message) { constructWhat(); }
00017 std::int32_t error() { return m_Error; }
00018 std::string message() { return m_Message
       std::string message() { return m_Message; }
00019
00020 private:
00021
        void constructWhat()
00022
        {
00023
          if(m_Error == 0) m_What = m_Message;
00024
00025
            m_What = std::string("Error ") + std::to_string(m_Error) + std::string(" : ") + m_Message;
00026
00027
        std::string m_What;
00028
       std::string m_Message;
std::int32_t m_Error{0};
00029
00030 };
```

5.15 libs/core/include/Filesystem.h File Reference

```
#include <string>
```

Functions

- std::string path (const std::string &)
- std::string extension (const std::string &)
- std::string filename (const std::string &)

5.15.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Filesystem.h.

5.15.2 Function Documentation

```
5.15.2.1 extension() std::string extension (
              const std::string & file )
Definition at line 13 of file Filesystem.cc.
      std::size_t position = file.find_last_of(".");
return (std::string::npos == position || position == 0) ? "" : file.substr(position + 1);
00015
00016
00017 }
5.15.2.2 filename() std::string filename (
              const std::string & file )
Definition at line 19 of file Filesystem.cc.
00020 {
- 1);
00024 }
5.15.2.3 path() std::string path (
              const std::string & file )
Definition at line 7 of file Filesystem.cc.
00008 {
       std::size_t pos = file.find_last_of("\\/");
return (std::string::npos == pos) ? "" : file.substr(0, pos);
00009
00010
00011 }
```

5.16 Filesystem.h 67

5.16 Filesystem.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include <string>
00008
00009 std::string path(const std::string&);
00010 std::string extension(const std::string&);
00011 std::string filename(const std::string&);
```

5.17 libs/core/include/Formatters.h File Reference

```
#include "Bits.h"
#include <iosfwd>
#include <string>
```

Functions

```
    std::string to dec (const Buffer &b, const std::size t &begin=0, const std::size t &end=-1)

std::string to_dec (const bit8_t &)

    std::string to_dec (const bit16_t &)

    std::string to_dec (const bit32_t &)

    std::string to dec (const bit64 t &)

    std::string to_hex (const Buffer &b, const std::size_t &begin=0, const std::size_t &end=-1)

std::string to_hex (const bit8_t &)

    std::string to_hex (const bit16_t &)

std::string to_hex (const bit32_t &)

    std::string to_hex (const bit64_t &)

• std::string to_bin (const Buffer &b, const std::size_t &begin=0, const std::size_t &end=-1)
std::string to_bin (const bit8_t &)

    std::string to_bin (const bit16_t &)

    std::string to_bin (const bit32_t &)

std::string to_bin (const bit64_t &)

    std::string to_oct (const Buffer &b, const std::size_t &begin=0, const std::size_t &end=-1)

    std::string to_oct (const bit8_t &)

    std::string to_oct (const bit16_t &)

    std::string to_oct (const bit32_t &)

    std::string to_oct (const bit64_t &)
```

5.17.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Formatters.h.

5.17.2 Function Documentation

```
5.17.2.1 to_bin() [1/5] std::string to_bin (
               const bit16_t & b )
Definition at line 71 of file Formatters.cc.
00071 { return fmt::format("{:#016b}", b); }
5.17.2.2 to_bin() [2/5] std::string to_bin (
               const bit32_t & b )
Definition at line 73 of file Formatters.cc.
00073 { return fmt::format("{:#032b}", b); }
5.17.2.3 to_bin() [3/5] std::string to_bin (
               const bit64_t & b )
Definition at line 75 of file Formatters.cc.
00075 { return fmt::format("{:#064b}", b); }
5.17.2.4 to_bin() [4/5] std::string to_bin (
               const bit8_t & b )
Definition at line 69 of file Formatters.cc.
00069 { return fmt::format("{:#08b}", b); }
5.17.2.5 to_bin() [5/5] std::string to_bin (
               const Buffer & b,
               const std::size_t & begin = 0,
               const std::size_t & end = -1)
Definition at line 56 of file Formatters.cc.
00057 {
       std::size_t iend = end;
00059
        <u>if(iend == -1) iend = b.size();</u>
00060
        std::string ret;
00061
        for(std::size_t k = begin; k < iend; k++)</pre>
       ret += to_bin(b[k]);
ret += " - ";
}
00062
00063
00064
00065
00066
       return ret;
00067 }
5.17.2.6 to_dec() [1/5] std::string to_dec (
               const bit16_t & b )
Definition at line 29 of file Formatters.cc.
00029 { return fmt::format("{:#d}", b); }
```

```
5.17.2.7 to_dec() [2/5] std::string to_dec (
               const bit32_t & b )
Definition at line 31 of file Formatters.cc.
00031 { return fmt::format("{:#d}", b); }
5.17.2.8 to dec() [3/5] std::string to_dec (
               const bit64_t & b )
Definition at line 33 of file Formatters.cc.
00033 { return fmt::format("{:#d}", b); }
5.17.2.9 to_dec() [4/5] std::string to_dec (
               const bit8_t & b )
Definition at line 27 of file Formatters.cc.
00027 { return fmt::format("{:#d}", b); }
5.17.2.10 to_dec() [5/5] std::string to_dec (
               const Buffer & b,
               const std::size_t & begin = 0,
               const std::size_t & end = -1)
Definition at line 14 of file Formatters.cc.
00015 {
        std::size_t iend = end;
00017
        if(iend == -1) iend = b.size();
       std::string ret;
for(std::size_t k = begin; k < iend; k++)</pre>
00018
00019
00020
       ret += to_dec(b[k]);
ret += " - ";
00021
00022
00023
00024
       return ret;
00025 }
5.17.2.11 to_hex() [1/5] std::string to_hex (
               const bit16_t & b )
Definition at line 50 of file Formatters.cc.
00050 { return fmt::format("{:#04x}", b); }
5.17.2.12 to_hex() [2/5] std::string to_hex (
               const bit32_t & b )
Definition at line 52 of file Formatters.cc.
```

00052 { return fmt::format("{:#08x}", b); }

```
5.17.2.13 to_hex() [3/5] std::string to_hex (
              const bit64_t & b )
Definition at line 54 of file Formatters.cc.
00054 { return fmt::format("{:#016x}", b); }
5.17.2.14 to_hex() [4/5] std::string to_hex (
               const bit8_t & b )
Definition at line 48 of file Formatters.cc.
00048 { return fmt::format("{:#02x}", b); }
5.17.2.15 to_hex() [5/5] std::string to_hex (
               const Buffer & b,
               const std::size_t & begin = 0,
               const std::size_t & end = -1)
Definition at line 35 of file Formatters.cc.
00036 {
       std::size_t iend = end;
if(iend == -1) iend = b.size();
std::string ret;
00037
00038
00039
       for(std::size_t k = begin; k < iend; k++)</pre>
00040
00045 return ret;
5.17.2.16 to_oct() [1/5] std::string to_oct (
              const bit16_t & b )
Definition at line 92 of file Formatters.cc.
00092 { return fmt::format("{:#080}", b); }
5.17.2.17 to_oct() [2/5] std::string to_oct (
               const bit32_t & b )
Definition at line 94 of file Formatters.cc.
00094 { return fmt::format("{:#0160}", b); }
5.17.2.18 to_oct() [3/5] std::string to_oct (
               const bit64_t & b )
Definition at line 96 of file Formatters.cc.
00096 { return fmt::format("{:#0320}", b); }
```

5.18 Formatters.h 71

```
5.17.2.19 to_oct() [4/5] std::string to_oct (
              const bit8_t & b )
Definition at line 90 of file Formatters.cc.
00090 { return fmt::format("{:#040}", b); }
5.17.2.20 to_oct() [5/5] std::string to_oct (
              const Buffer & b,
              const std::size_t & begin = 0,
              const std::size_t & end = -1)
Definition at line 77 of file Formatters.cc.
        std::size_t iend = end;
08000
        if(iend == -1) iend = b.size();
00081
        std::string ret;
       for(std::size_t k = begin; k < iend; k++)</pre>
00082
00083
00084
         ret += to_oct(b[k]);
        ret += " - ";
00086
00087
       return ret;
00088 }
```

5.18 Formatters.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include "Bits.h"
80000
00009 #include <iosfwd>
00010 #include <string>
00011
00012 class Buffer;
00014 std::string to_dec(const Buffer& b, const std::size_t& begin = 0, const std::size_t& end = -1);
00015 std::string to_dec(const bit8_t&);
00016 std::string to_dec(const bit16_t&);
00017 std::string to_dec(const bit32_t&);
00018 std::string to_dec(const bit64_t&);
00020 std::string to_hex(const Buffer& b, const std::size_t& begin = 0, const std::size_t& end = -1);
00021 std::string to_hex(const bit8_t&);
00022 std::string to_hex(const bit16_t&);
00023 std::string to_hex(const bit32_t&);
00024 std::string to_hex(const bit64_t&);
00025
00026 std::string to_bin(const Buffer& b, const std::size_t& begin = 0, const std::size_t& end = -1);
00027 std::string to_bin(const bit8_t&);
00028 std::string to_bin(const bit16_t&);
00029 std::string to_bin(const bit32_t&);
00030 std::string to_bin(const bit64_t&);
00031
00032 std::string to_oct(const Buffer& b, const std::size_t& begin = 0, const std::size_t& end = -1);
00033 std::string to_oct(const bit8_t&);
00034 std::string to_oct(const bit16_t&);
00035 std::string to_oct(const bit32_t&);
00036 std::string to_oct(const bit64_t&);
```

5.19 libs/core/include/Interface.h File Reference

```
#include "AppVersion.h"
#include "Buffer.h"
#include "Version.h"
```

```
#include <map>
#include <memory>
#include <semver.hpp>
#include <spdlog/logger.h>
#include <string>
```

Classes

- · class Interface
- · class InterfaceReader
- · class InterfaceWriter

Enumerations

enum class InterfaceType { Unknown = 0 , Reader = 1 , Writer = 2 }
 template class should implement void SOURCE::start(); bool SOURCE::next(); void SOURCE::end(); const Buffer&
 SOURCE::getBuffer();

5.19.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Interface.h.

5.19.2 Enumeration Type Documentation

5.19.2.1 InterfaceType enum class InterfaceType [strong]

template class should implement void SOURCE::start(); bool SOURCE::next(); void SOURCE::end(); const Buffer& SOURCE::getBuffer();

void DESTINATION::begin(); void DESTINATION::processDIF(const DIFPtr&); void DESTINATION::process Frame(const DIFPtr&,const std::uint32_t& frameIndex); void DESTINATION::processPadInFrame(const DIFPtr&,const std::uint32_t& frameIndex,const std::uint32_t& channelIndex); void DESTINATION::processSlowControl(const Buffer&); void DESTINATION::end();

Enumerator

Unknown	
Reader	
Writer	

Definition at line 31 of file Interface.h.

5.20 Interface.h 73

5.20 Interface.h

```
00001
00004 #pragma once
00005
00006 #include "AppVersion.h"
00007 #include "Buffer.h'
00008 #include "Version.h"
00009
00010 #include <map>
00011 #include <memory>
00012 #include <semver.hpp>
00013 #include <spdlog/logger.h>
00014 #include <string>
00015
00031 enum class InterfaceType
00032 {
00033
       Unknown = 0,
      Reader = 1,
Writer = 2
00034
00035
00036 };
00037
00038 class Interface
00039 {
00040 public:
        Interface(const std::string& name, const std::string& version, const InterfaceType& type) :
     m_Name(name), m_Version(version) {}
00042
       virtual ~Interface() = default;
00043
       virtual void
                                          startEvent() {}
00044
       virtual void
                                          endEvent() {}
00045
       virtual void
                                          startDIF() {}
00046
       virtual void
                                          endDIF() {}
00047
       virtual void
                                          startFrame() {}
00048
       virtual void
                                          endFrame() {}
00049
       virtual void
                                          startPad() {}
00050
       virtual void
                                          endPad() {}
00051
       std::shared_ptr<spdlog::logger>& log() { return m_Logger; }
00052
                                         setLogger(const std::shared_ptr<spdlog::logger>& logger) { m_Logger
= logger; }
00053 std::string
                                          getName() { return m_Name; }
00054
       Version
                                         getVersion() { return m_Version; }
00055
00056 private:
      std::shared_ptr<spdlog::logger> m_Logger{nullptr};
00058
        std::string
                                        m_Name;
00059
       Version
                                        m_Version;
00060
       InterfaceType
                                        m_Type{InterfaceType::Unknown};
00061 };
00062
00063 class InterfaceReader : public Interface
00064 {
00065 public:
00066
       InterfaceReader(const std::string& name, const std::string& version) : Interface(name, version,
     InterfaceType::Reader) {}
00067
       virtual ~InterfaceReader() = default;
00068
00069 protected:
00070
      Buffer m_Buffer;
00071 };
00072
00073 class InterfaceWriter: public Interface
00074 {
00075 public:
        InterfaceWriter(const std::string& name, const std::string& version) : Interface(name, version,
     InterfaceType::Writer) {}
00077
00078
       void addCompatibility(const std::string& name, const std::string& version) { m_Compatible[name] =
00079
08000
        std::map<std::string, std::string> getCompatibility() { return m_Compatible; }
00081
00082
        bool checkCompatibility(const std::string& name, const std::string& version)
00083
00084
          if (m_Compatible.find(name) != m_Compatible.end())
```

```
ran = semver::range::detail::range(m_Compatible[name]);
00087
           semver::version ver = semver::version(version);
00088
           if(ran.satisfies(ver, false)) return true;
00089
00090
             return false;
00091
        else
00093
           return false;
00094
00095
       virtual ~InterfaceWriter() = default;
00096
00097
00098 private:
00099
      std::map<std::string, std::string> m_Compatible;
00100 };
```

5.21 libs/core/include/PayloadParser.h File Reference

```
#include "Bits.h"
#include "Buffer.h"
#include "Exception.h"
#include "Formatters.h"
#include "Utilities.h"
#include "Words.h"

#include <cstdint>
#include <spdlog/spdlog.h>
#include <string>
#include <vector>
```

Classes

• class PayloadParser

5.21.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file PayloadParser.h.

5.22 PayloadParser.h

```
00001
00005 #pragma once
00006
00007 #include "Bits.h"
00008 #include "Buffer.h"
00009 #include "Exception.h"
00010 #include "Formatters.h"
00011 #include "Utilities.h"
00012 #include "Words.h"
00013
00014 #include <cstdint>
00015 #include <spdlog/spdlog.h>
00016 #include <string>
00017 #include <vector>
00018
00036 class PayloadParser : public Buffer
```

```
00038 public:
       PayloadParser() = default;
00040
00041
       void setBuffer(const Buffer& buffer);
00042
00043
       bool hasTemperature() const;
00044
00045
       bool hasAnalogReadout() const;
00046
00047
       bool hasSlowControl() const;
00048
00049
       float getTemperatureDIF() const;
00050
00051
       float getTemperatureASU1() const;
00052
00053
       float getTemperatureASU2() const;
00054
00055
       Buffer getSlowControl() const;
00056
00057
       std::vector<bit8_t*> getFramesVector() const;
00058
00059
       std::vector<bit8_t*> getLinesVector() const;
00060
       std::uint32_t getSizeAfterDIFPtr() const;
00061
00062
       std::uint32_t getEndOfDIFData() const;
       std::uint32_t getDTC() const;
00063
00064
        std::uint32_t getGTC() const;
00065
       std::uint64_t getAbsoluteBCID() const;
00066
        std::uint32_t getBCID() const;
                     hasLine(const std::uint32_t&) const;
00067
       bool
       std::uint32_t getNumberOfFrames() const;
00068
00069
                     getFramePtr(const std::uint32_t&) const;
       bit8 t*
00070
       std::uint32_t getFrameBCID(const std::uint32_t&) const;
00071
        std::uint32_t getFrameTimeToTrigger(const std::uint32_t&) const;
00072
       bool
                     getFrameLevel(const std::uint32_t&, const std::uint32_t&, const std::uint32_t&)
        std::uint32_t getDIFid() const;
00073
00074
       std::uint32_t getASICid(const std::uint32_t&) const;
       std::uint32_t getThresholdStatus(const std::uint32_t&, const std::uint32_t&) const;
00076
       std::uint32_t getDIF_CRC() const;
00077
00078 private:
00079
       std::uint16_t m_Version{13};
       std::uint32_t parsePayload();
08000
00081
       std::uint32_t getNumberLines() const;
00082
       std::uint32_t parseAnalogLine(const std::uint32_t& idx);
00083
       std::uint32_t getTASU1() const;
00084
       std::uint32_t getTASU2() const;
00085
       std::uint32_t getTDIF() const;
00086
00087
       std::vector<bit8 t*> m Lines;
00088
       std::vector<bit8_t*> m_Frames;
00089
       std::uint32_t
                            theGetFramePtrReturn_{0};
00090 };
00091
00092 inline void PayloadParser::setBuffer(const Buffer& buffer)
00093 {
00094
       set (buffer) :
00095
       m Frames.clear();
00096
       m_Lines.clear();
00097
       theGetFramePtrReturn_ = parsePayload();
00098 }
00099
00100 inline std::uint32_t PayloadParser::parsePayload()
00101 {
00102
        std::uint32_t fshift{static_cast<std::uint32_t>(Size::GLOBAL_HEADER)}; // Pass Global Header
00103
        if(m_Version >= 13)
00104
        {
         // Pass DIF_ID, DIF Trigger counter, Information counter, Global Trigger counter, Absolute BCID,
00105
     BCID DIF, NB line
00106
         fshift += Size::DIF_IF + Size::DIF_TRIGGER_COUNTER + Size::INFORMATION_COUNTER
     Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID + Size::BCID_DIF + Size::NUMBER_LINE;
00107
          // If has temperature infos then pass Temp ASU 1, Temp ASU 2, Temp DIF \,
00108
          if(hasTemperature()) fshift += Size::TEMP_ASU1 + Size::TEMP_DIF;
00109
          // If has AnalogReadout pass them
          if(hasAnalogReadout()) fshift = parseAnalogLine(fshift); // to be implemented
00110
00111
00112
00113
         throw Exception(fmt::format("Version {} is not implemented", m_Version));
00114
00115
       while (static cast<std::uint8 t>(begin()[fshift]) !=
     static cast<std::uint8 t>(Value::GLOBAL TRAILER))
00116
00117
          // If I found a FRAME_HEADER there is 2 cases :
          // 1) Nothing inside so FRAME_TRAILER comes just after
00118
          // 2) Come MICROROC Header, BCID, DATA max 128 times
00119
00120
          if(static_cast<std::uint8_t>(begin()[fshift]) == static_cast<std::uint8_t>(Value::FRAME_HEADER))
00121
```

```
00122
            fshift += +Size::FRAME HEADER;
            if(static_cast<std::uint8_t>(begin()[fshift]) == static_cast<std::uint8_t>(Value::FRAME_TRAILER)
      || static_cast<std::uint8_t>(begin()[fshift]) =
      static_cast<std::uint8_t>(Value::FRAME_TRAILER_ERROR)) { fshift += +Size::FRAME_TRAILER; }
00124
            else
00125
00126
              while(static_cast<std::uint8_t>(begin()[fshift]) !=
      static_cast<std::uint8_t>(Value::FRAME_TRAILER) && static_cast<std::uint8_t>(begin()[fshift]) !=
      static_cast<std::uint8_t>(Value::FRAME_TRAILER_ERROR))
00127
00128
                m_Frames.push_back(&begin()[fshift]);
                fshift += Size::MICROROC_HEADER + Size::BCID + Size::DATA;
00129
00130
00131
              fshift += +Size::FRAME_TRAILER;
00132
00133
         }
00134
        // Pass Global trailer
00135
00136
       fshift += +Size::GLOBAL_TRAILER;
00137
        // Pass CRC MSB, CRC LSB
        fshift += Size::CRC_MSB + Size::CRC_LSB;
00138
00139
        return fshift;
00140 }
00141
00142 inline bool PayloadParser::hasTemperature()const { return (static_cast<std::uint8_t>(begin()[0]) ==
     static_cast<std::uint8_t>(Value::GLOBAL_HEADER_TEMP)); }
00143
00144 inline bool PayloadParser::hasAnalogReadout()const { return getNumberLines() != 0; }
00145
00146 inline std::uint32 t PavloadParser::getNumberLines()const
00147 {
00148
        std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
     Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID + Size::BCID_DIF};
00149
       return ((begin()[shift] » 4) & 0x5);
00150 }
00151
00152 inline std::uint32 t PayloadParser::parseAnalogLine(const std::uint32 t& idx)
00153 {
00154
        std::uint32 t fshift{idx};
00155
        // Pass Header line
00156
        if(static_cast<std::uint8_t>(begin()[fshift]) != static_cast<std::uint8_t>(Value::HEADER_LINE))
     return fshift;
00157
       else
00158
         fshift += +Size::HEADER_LINE;
00159
        while (static_cast<std::uint8_t>(begin()[fshift]) != static_cast<std::uint8_t>(Value::TRAILER_LINE))
00160
00161
          m_Lines.push_back(&begin()[fshift]);
00162
          // Get Number of CHIPS
          std::uint32 t nchip{begin()[fshift]};
00163
          // Pass Number of CHIPS, NB Asicline *64 *16bits
00164
00165
         fshift += +Size::NUMBER_CHIPS + static_cast<std::uint32_t>(Size::LINE_SIZE) * nchip;
00166
00167
        // Pass Trailer line
00168
       fshift += +Size::TRAILER_LINE;
        return fshift:
00169
00170 }
00172 inline bool PayloadParser::hasSlowControl()const { return theGetFramePtrReturn_ != size(); }
00173
00174 inline std::uint32_t PayloadParser::getTASU1()const
00175 {
       std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
00176
      Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID + Size::BCID_DIF +
      Size::NUMBER_LINE );
00177
        return (begin()[shift] « 24) + (begin()[shift + 1] « 16) + (begin()[shift + 2] « 8) + begin()[shift
      + 3];
00178 }
00179
00180 inline std::uint32_t PayloadParser::getTASU2()const
00181 {
        std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
00182
      Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID + Size::BCID_DIF +
      Size::NUMBER_LINE + Size::TEMP_ASU1};
        return (begin()[shift] « 24) + (begin()[shift + 1] « 16) + (begin()[shift + 2] « 8) + begin()[shift
00183
      + 3];
00184 }
00185
00186 inline std::uint32_t PayloadParser::getTDIF()const
00187 {
       std::uint32 t shift{Size::GLOBAL HEADER + Size::DIF IF + Size::DIF TRIGGER COUNTER +
00188
     Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID + Size::BCID_DIF + Size::NUMBER_LINE + Size::TEMP_ASU1 + Size::TEMP_ASU2};
00189
       return begin()[shift];
00190 }
00191
00192 inline float PayloadParser::getTemperatureDIF()const
00193 {
```

```
if(!hasTemperature()) throw Exception("Don't have TemperatureDIF information");
00195
        return 0.508 * getTDIF() - 9.659;
00196 }
00197
00198 inline float PayloadParser::getTemperatureASU1()const
00199 {
        if(!hasTemperature()) throw Exception("Don't have TemperatureASU1 information");
        return (getTASU1() » 3) * 0.0625;
00201
00202 }
00203
00204 inline float PayloadParser::getTemperatureASU2()const
00205 {
00206
        if(!hasTemperature()) throw Exception("Don't have TemperatureASU2 information");
00207
        return (getTASU2() » 3) * 0.0625;
00208 }
00209
00210 inline Buffer PayloadParser::getSlowControl()const
00211 {
00212
        if(hasSlowControl()) return Buffer(&begin()[getEndOfDIFData()], size() - getEndOfDIFData());
00213
       else
00214
00215 }
00216
00217 inline std::vector<br/>bit8 t*> PayloadParser::getFramesVector()const { return m Frames; }
00218
00219 inline std::vector<bit8_t*> PayloadParser::getLinesVector()const { return m_Lines; }
00220
00221 inline std::uint32_t PayloadParser::getDTC()const
00222 {
00223
        std::uint32 t shift{Size::GLOBAL HEADER + Size::DIF IF};
       return (begin()[shift] « 24) + (begin()[shift + 1] « 16) + (begin()[shift + 2] « 8) + begin()[shift
00224
      + 3];
00225 }
00226
00227 inline std::uint32_t PayloadParser::getGTC()const
00228 {
        std::uint32 t shift{Size::GLOBAL HEADER + Size::DIF IF + Size::DIF TRIGGER COUNTER +
00229
      Size::INFORMATION_COUNTER;
00230
        return (begin()[shift] « 24) + (begin()[shift + 1] « 16) + (begin()[shift + 2] « 8) + begin()[shift
00231 }
00232
00233 inline std::uint64 t PayloadParser::getAbsoluteBCID()const
00234 {
00235
        std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
      Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER};
00236
       std::uint64_t LBC = ((begin()[shift] « 16) | (begin()[shift + 1] « 8) | (begin()[shift + 2])) *
     16777216ULL /* to shift the value from the 24 first bits*/
00237
                          + ((begin()[shift + 3] « 16) | (begin()[shift + 4] « 8) | (begin()[shift + 5]));
00238
        return LBC:
00239 }
00240
00241 inline std::uint32_t PayloadParser::getBCID()const
00242 {
        std::uint32 t shift{Size::GLOBAL HEADER + Size::DIF IF + Size::DIF TRIGGER COUNTER +
00243
     Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID};
00244
       return (begin()[shift] « 16) + (begin()[shift + 1] « 8) + begin()[shift + 2];
00245 }
00246
00247 inline bool PayloadParser::hasLine(const std::uint32_t& line)const
00248 {
        std::uint32_t shift{Size::GLOBAL_HEADER + Size::DIF_IF + Size::DIF_TRIGGER_COUNTER +
00249
     Size::INFORMATION_COUNTER + Size::GLOBAL_TRIGGER_COUNTER + Size::ABSOLUTE_BCID + Size::BCID_DIF};
00250
        return ((begin()[shift] » line) & 0x1);
00251 }
00252
00253 inline std::uint32_t PayloadParser::getNumberOfFrames()const { return m_Frames.size(); }
00254
00255 inline bit8 t* PayloadParser::getFramePtr(const std::uint32_t& i)const { return m_Frames[i]; }
00256
00257 inline std::uint32_t PayloadParser::getFrameBCID(const std::uint32_t& i)const
00258 {
00259
        std::uint32_t shift{+Size::MICROROC_HEADER};
        return GrayToBin((m_Frames[i][shift] « 16) + (m_Frames[i][shift + 1] « 8) + m_Frames[i][shift + 2]);
00260
00261 }
00263 inline std::uint32_t PayloadParser::getFrameTimeToTrigger(const std::uint32_t& i)const { return
      getBCID() - getFrameBCID(i); }
00264
00265 inline bool PayloadParser::getFrameLevel(const std::uint32 t& i, const std::uint32 t& ipad, const
      std::uint32 t& ilevel)const
00266 {
        std::uint32_t shift{Size::MICROROC_HEADER + Size::BCID};
return ((m_Frames[i][shift + ((3 - ipad / 16) * 4 + (ipad % 16) / 4)] » (7 - (((ipad % 16) % 4) * 2
00267
00268
      + ilevel))) & 0x1);
00269 }
00270
```

```
00271 inline std::uint32_t PayloadParser::getDIFid()const
00272 {
00273
        std::uint32_t shift{+Size::GLOBAL_HEADER};
00274
       return begin()[shift] & 0xFF;
00275 }
00276
00277 inline std::uint32_t PayloadParser::getASICid(const std::uint32_t& i)const { return m_Frames[i][0] &
00278
00279 inline std::uint32_t PayloadParser::getThresholdStatus(const std::uint32_t& i, const std::uint32_t&
      ipad)const { return (((std::uint32_t)getFrameLevel(i, ipad, 1)) « 1) |
      ((std::uint32_t)getFrameLevel(i, ipad, 0)); }
00280
00281 inline std::uint32_t PayloadParser::getDIF_CRC()const
00282 {
00283
        std::uint32_t shift{getEndOfDIFData() - (Size::CRC_MSB + Size::CRC_LSB)};
00284
        return (begin()[shift] « 8) + begin()[shift + 1];
00285 }
00286
00287 inline std::uint32_t PayloadParser::getSizeAfterDIFPtr()const { return size() - theGetFramePtrReturn_;
00288
00289 inline std::uint32_t PayloadParser::getEndOfDIFData()const { return theGetFramePtrReturn_; }
```

5.23 libs/core/include/RawBufferNavigator.h File Reference

```
#include "Buffer.h"
```

Classes

· class RawBufferNavigator

class to navigate in the raw data buffer parse the header and send the payload as Buffer

5.23.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file RawBufferNavigator.h.

5.24 RawBufferNavigator.h

```
00001
00005 #pragma once
00006
00007 #include "Buffer.h"
80000
00013 class RawBufferNavigator
00014 {
00015 public:
00016
       static void StartAt (const int& start);
00017
       RawBufferNavigator();
       ~RawBufferNavigator() = default;
00018
00019
                    setBuffer(const Buffer&);
00020
       std::uint8_t getDetectorID();
00021
       bool
                     findStartOfPayload();
       std::int32_t getStartOfPayload();
00022
00023
                    validPayload();
       bool
00024
       Buffer
                    getPayload();
00025
00026 private:
00027 static int
                    m_Start;
00028
       Buffer
                    m_Buffer;
00029
                    m_StartPayloadDone{false};
       bool
00030 std::int32_t m_StartPayload{-1}; // -1 Means not found !
00031 };
```

5.25 libs/core/include/Timer.h File Reference

```
#include <chrono>
```

Classes

class Timer

5.25.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Timer.h.

5.26 Timer.h

Go to the documentation of this file.

5.27 libs/core/include/Utilities.h File Reference

```
#include <cstdint>
```

Functions

std::uint64_t GrayToBin (const std::uint64_t &n)

5.27.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Utilities.h.

5.27.2 Function Documentation

```
5.27.2.1 GrayToBin() std::uint64_t GrayToBin (
                const std::uint64_t & n ) [inline]
Definition at line 9 of file Utilities.h.
00010 {
        std::uint64_t ish{1};
00011
00012
        std::uint64_t anss{n};
std::uint64_t idiv{0};
00013
        std::uint64_t ishmax{sizeof(std::uint64_t) * 8};
00014
00015
        while (true)
00016
00017
          idiv = anss » ish;
        anss ^= idiv;

if(idiv <= 1 || ish == ishmax) return anss;
00018
00019
         ish «= 1;
00021 }
```

5.28 Utilities.h

00022 }

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include <cstdint>
80000
00009 inline std::uint64_t GrayToBin(const std::uint64_t& n)
00010 {
00011 std::uint64_t ish{1};
00012 std::uint64_t anss{n};
00013
        std::uint64_t idiv{0};
00014
       std::uint64_t ishmax{sizeof(std::uint64_t) * 8};
00015
        while(true)
00016
00017
          idiv = anss » ish;
00018
         anss ^= idiv;
          if(idiv <= 1 || ish == ishmax) return anss;</pre>
00019
00020
          ish «= 1;
00021 }
00022 }
```

5.29 libs/core/include/Version.h File Reference

```
#include <cstdint>
#include <semver.hpp>
#include <string>
```

Classes

class Version

5.29.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Version.h.

5.30 Version.h 81

5.30 Version.h

```
Go to the documentation of this file.
```

```
00005 #pragma once
00006
00007 #include <cstdint>
00008 #include <semver.hpp>
00009 #include <string>
00010
00011 class Version : public semver::version
00012 {
00013 public:
       Version(const std::uint8_t& mj, const std::uint8_t& mn, const std::uint8_t& pt, const semver::prerelease& prt = semver::prerelease::none, const std::uint8_t& prn = 0) noexcept :
00014
semver::version(mj, mn, pt, prt, prn) {}
00015 explicit Version(const std::string_view& str) : semver::version(str) {}
          Version() = default;
00016
00017
         std::uint8_t getMajor();
00018
         std::uint8_t getMinor();
00019
         std::uint8_t getPatch();
00020 std::string getPreRelease();
00021 std::uint8_t getPreReleaseNumber();
00022 };
```

5.31 libs/core/include/Words.h File Reference

```
#include <cstdint>
```

Enumerations

```
enum class Hardware : std::uint8_t { NUMBER_PAD = 64 }
enum class Size : std::uint8_t {
 DATA_FORMAT_VERSION = 1 , DAQ_SOFTWARE_VERSION = 2 , SDCC_FIRMWARE_VERSION = 2 ,
 DIF_FIRMWARE_VERSION = 2,
 TIMESTAMP_SECONDES = 4, TIMESTAMP_MILLISECONDS = 4, GLOBAL_HEADER = 1, DIF_IF = 1,
 DIF TRIGGER COUNTER = 4, INFORMATION COUNTER = 4, GLOBAL TRIGGER COUNTER = 4,
 ABSOLUTE_BCID = 6,
 BCID_DIF = 3, NUMBER_LINE = 1, TEMP_ASU1 = 4, TEMP_ASU2 = 4,
 TEMP_DIF = 1, HEADER_LINE = 1, NUMBER_CHIPS = 1, LINE_SIZE = 64 * 2,
 TRAILER LINE = 1, FRAME HEADER = 1, MICROROC HEADER = 1, BCID = 3,
 DATA = 16, FRAME TRAILER = 1, GLOBAL TRAILER = 1, CRC MSB = 1,
 CRC_LSB = 1, SC_HEADER = 1, DIF_ID = 1, ASIC_HEADER = 1,
 SC_ASIC_SIZE = 1, SC_TRAILER = 1 }
enum class Value : std::uint8_t {
 GLOBAL_HEADER = 0xb0 , GLOBAL_HEADER_TEMP = 0xbb , HEADER_LINE = 0xc4 , TRAILER_LINE =
 FRAME HEADER = 0xb4 , FRAME TRAILER = 0xa3 , FRAME TRAILER ERROR = 0xc3 ,
 GLOBAL_TRAILER = 0xa0,
 SC_HEADER = 0xb1 , SC_TRAILER = 0xa1 }
```

5.31.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Words.h.

5.31.2 Enumeration Type Documentation

5.31.2.1 Hardware enum class Hardware : std::uint8_t [strong]

Enumerator

NUMBER_PAD

Definition at line 9 of file Words.h.

5.31.2.2 Size enum class Size : std::uint8_t [strong]

Enumerator

DATA_FORMAT_VERSION	
DAQ_SOFTWARE_VERSION	
SDCC_FIRMWARE_VERSION	
DIF_FIRMWARE_VERSION	
TIMESTAMP_SECONDES	
TIMESTAMP_MILLISECONDS	
GLOBAL_HEADER	
DIF_IF	
DIF_TRIGGER_COUNTER	
INFORMATION_COUNTER	
GLOBAL_TRIGGER_COUNTER	
ABSOLUTE_BCID	
BCID_DIF	
NUMBER_LINE	
TEMP_ASU1	
TEMP_ASU2	
TEMP_DIF	
HEADER_LINE	
NUMBER_CHIPS	
LINE_SIZE	
TRAILER_LINE	
FRAME_HEADER	
MICROROC_HEADER	
BCID	
DATA	
FRAME_TRAILER	
GLOBAL_TRAILER	
CRC_MSB	
CRC_LSB	
SC_HEADER	

Enumerator

DIF_ID	
ASIC_HEADER	
SC_ASIC_SIZE	
SC_TRAILER	

Definition at line 14 of file Words.h.

```
00015 {
00016
          // Header
          DATA_FORMAT_VERSION
00017
         DATA_FORMAT_VERSION = 1,
DAQ_SOFTWARE_VERSION = 2,
SDCC_FIRMWARE_VERSION = 2,
DIF_FIRMWARE_VERSION = 2,
TIMESTAMP_SECONDES = 4,
TIMESTAMP_MILLISECONDS = 4,
00018
00019
00020
00021
00022
00023
          // Payload
00024
          GLOBAL_HEADER
         DIF_IRIGGER_COUNTER = 4,
INFORMATION_COUNTER = 4,
GLOBAL_TRIGGER_COUNTER = 4,
00025
00026
00027
00028
00029
          ABSOLUTE_BCID
00030
          BCID_DIF
00031
          NUMBER_LINE
00032
          TEMP_ASU1
                                        = 4,
00033
00034
          TEMP_ASU2
                                        = 1,
          TEMP_DIF
          HEADER_LINE
                                        = 1,
00035
          HEADER_LINE
NUMBER_CHIPS
LINE_SIZE
TRAILER_LINE
00036
00037
00038
                                        = 1,
          MICROROC_HEADER
BCID
                                        = 1,
00039
                                        = 1,
00040
00041
00042
          DATA
                                        = 1,
00043
          FRAME_TRAILER
00044
          GLOBAL_TRAILER
         CRC_MSB
CRC_LSB
// Slowcontrol
                                        = 1,
00045
                                        = 1,
00046
00047
          SC_HEADER
00048
                                        = 1,
00049
         DIF_ID
                                        = 1,
00050
          ASIC_HEADER
                                        = 1,
                                        = 1,
= 1
00051 SC_ASIC_SIZE
00052
         SC_TRAILER
00053 };
```

5.31.2.3 Value enum class Value : std::uint8_t [strong]

Enumerator

GLOBAL_HEADER	
GLOBAL_HEADER_TEMP	
HEADER_LINE	
TRAILER_LINE	
FRAME_HEADER	
FRAME_TRAILER	
FRAME_TRAILER_ERROR	
GLOBAL_TRAILER	
SC_HEADER	
SC_TRAILER	

Definition at line 59 of file Words.h.

```
00060 {
00061
         GLOBAL_HEADER
                                = 0xb0,
         GLOBAL_HEADER_TEMP = 0xbb,
00062
         HEADER\_LINE = 0xc4,
00063
                                = 0xd4.
00064
         TRATLER LINE
        FRAME_HEADER = 0xb4,
FRAME_TRAILER = 0xa3,
00065
00066
00067
         FRAME_TRAILER_ERROR = 0xc3,
         GLOBAL_TRAILER = 0xa0,
SC_HEADER = 0xb1,
SC_TRAILER = 0xa1
00068
        SC_HEADER
SC_TRAILER
00069
00070
00071 };
```

5.32 Words.h

```
00001
00005 #pragma once
00007 #include <cstdint>
80000
00009 enum class Hardware : std::uint8_t
00010 {
       NUMBER PAD = 64,
00011
00012 };
00013
00014 enum class Size : std::uint8_t
00015 {
00016 // Header
00017 DATA_FORMAT_VERSION
        DAQ_SOFTWARE_VERSION = 2,
SDCC_FIRMWARE_VERSION = 2,
00018
       DIF_FIRMWARE_VERSION = 2,
TIMESTAMP_SECONDES = 4,
00020
00021
        TIMESTAMP_SECONDES
        TIMESTAMP_MILLISECONDS = 4,
00022
       // Payload
GLOBAL_HEADER
00023
00024
00025
        DIF_IF
00026
        DIF_TRIGGER_COUNTER = 4,
00027
        INFORMATION_COUNTER
        GLOBAL_TRIGGER_COUNTER = 4,
00028
00029
        ABSOLUTE_BCID
00030
        BCID_DIF
00031
        NUMBER_LINE
00032
        TEMP_ASU1
00033
        TEMP_ASU2
00034
        TEMP_DIF
                                = 1,
       HEADER_LINE
NUMBER_CHIPS
00035
                                = 1,
00036
00037
        LINE_SIZE
                                = 64 * 2,
                                = 1,
00038
        TRAILER_LINE
00039
        FRAME_HEADER
                                = 1,
00040
        MICROROC_HEADER
                                = 1,
                                = 3.
00041
        BCTD
00042
        DATA
                                = 16,
00043
        FRAME_TRAILER
                                = 1,
00044
        GLOBAL_TRAILER
00045
        CRC_MSB
00046
        CRC_LSB
                                = 1,
       // Slowcontrol
SC_HEADER
00047
00048
                                = 1.
        DIF_ID
ASIC_HEADER
00049
                                = 1,
                                = 1,
00051
        SC_ASIC_SIZE
00052
       SC_TRAILER
00053 };
00054
00055 static inline std::uint32_t operator+(const Size& a, const Size& b) { return
     static_cast<std::uint32_t>(a) + static_cast<std::uint32_t>(b); }
00056 static inline std::uint32_t operator+(const std::uint32_t& a, const Size& b) { return a +
      static_cast<std::uint32_t>(b); }
00057 static inline std::uint32_t operator+(const Size& a) { return static_cast<std::uint32_t>(a); }
00058
00059 enum class Value : std::uint8_t
00060 {
00061
        GLOBAL_HEADER
00062
        GLOBAL_HEADER_TEMP = 0xbb,
                      = 0xc4,
00063
        HEADER_LINE
        TRATLER LINE
00064
                            = 0xb4
00065
        FRAME_HEADER
                             = 0xa3,
00066
        FRAME_TRAILER
        FRAME_TRAILER_ERROR = 0xc3,
```

```
00068 GLOBAL_TRAILER = 0xa0,
00069 SC_HEADER = 0xb1,
00070 SC_TRAILER = 0xa1
00071 };
```

5.33 libs/core/src/Bits.cc File Reference

```
#include "Bits.h"
```

Functions

std::ostream & operator << (std::ostream &os, const bit8_t &c)
 Stream operator to print bit8_t aka std::uint8_t and not char or unsigned char.

5.33.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Bits.cc.

5.33.2 Function Documentation

```
5.33.2.1 operator << () std::ostream & operator << ( std::ostream & os, const bit8_t & c )
```

Stream operator to print bit8_t aka std::uint8_t and not char or unsigned char.

```
Definition at line 8 of file Bits.cc. 00008 { return os « c + 0; }
```

5.34 Bits.cc

Go to the documentation of this file.

```
00001

00006 #include "Bits.h"

00007

00008 std::ostream& operator«(std::ostream& os, const bit8_t& c) { return os « c + 0; }
```

5.35 libs/core/src/BufferLooperCounter.cc File Reference

```
#include "BufferLooperCounter.h"
#include "Formatters.h"
#include <fmt/color.h>
```

5.36 BufferLooperCounter.cc

```
Go to the documentation of this file.
```

```
00005 #include "BufferLooperCounter.h"
00006
00007 #include "Formatters.h"
80000
00009 #include <fmt/color.h>
00010
00011 void BufferLooperCounter::printAllCounters()
00012 {
00013
         \texttt{fmt::print} (\texttt{fg}(\texttt{fmt::color::crimson}) \; | \; \texttt{fmt::emphasis::bold}, \; \texttt{"BUFFER} \; \texttt{LOOP} \; \texttt{FINAL} \; \texttt{STATISTICS} \; : \; \\ \setminus \texttt{n"});
        printCounter("Start of DIF header", DIFStarter);
printCounter("Value after DIF data are processed", DIFPtrValueAtReturnedPos, std::ios_base::hex);
00014
00015
         printCounter("Size remaining in buffer after end of DIF data", SizeAfterDIFPtr);
00016
         fmt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, "Number of Slow Control found {} out of
      which {} are bad\n", hasSlowControl, hasBadSlowControl);
00018 printCounter("Size remaining after all of data have been processed", SizeAfterAllData);
00019
         printCounter("Number on non zero values in end of data buffer", NonZeroValusAtEndOfData);
00020 }
00021
00022 void BufferLooperCounter::printCounter(const std::string& description, const std::map<int, int>& m,
      const std::ios_base::fmtflags& base)
00023 {
00024
         std::string out{"statistics for " + description + " : n};
         for(std::map<int, int>::const_iterator it = m.begin(); it != m.end(); it++)
00025
00026
           if(it != m.begin()) out += ",";
out += " [";
00027
00028
00029
           switch (base)
00030
00031
             case std::ios_base::dec: out += to_dec(static_cast<std::uint32_t>(it->first)); break;
             case std::ios_base::hex:    out += to_hex(static_cast<std::uint32_t>(it->first));    break;
case std::ios_base::oct:    out += to_oct(static_cast<std::uint32_t>(it->first));    break;
00032
00033
             default: out += to_dec(static_cast<std::uint32_t>(it->first)); break;
00035
00036
           out += "]=" + std::to_string(it->second);
00037
         out += "\n":
00038
         fmt::print(fg(fmt::color::crimson) | fmt::emphasis::bold, out);
00039
00040 }
```

5.37 libs/core/src/DIFSlowControl.cc File Reference

#include "DIFSlowControl.h"

Functions

• std::string to_string (const DIFSlowControl &c)

5.37.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file DIFSlowControl.cc.

5.37.2 Function Documentation

5.38 DIFSlowControl.cc 87

Definition at line 256 of file DIFSlowControl.cc.

```
00257 {
00258     std::string ret;
00259     for(std::map<int, std::map<std::string, int»::const_iterator it = c.cbegin(); it != c.cend(); it++)
00260     {
00261          ret += "ASIC " + std::to_string(it->first) + " :\n";
00262          for(std::map<std::string, int>::const_iterator jt = (it->second).begin(); jt !=
                (it->second).end(); jt++) ret += jt->first + " : " + std::to_string(jt->second) + "\n";
00263     }
00264     return ret;
00265 }
```

5.38 DIFSlowControl.cc

```
00005 #include "DIFSlowControl.h"
00006
00007 DIFSlowControl::DIFSlowControl(const std::uint8_t& version, const std::uint8_t& DIfId, unsigned char*
      cbuf) : m_Version(version), m_DIFId(DIfId), m_AsicType(2)
00008 {
00009
        if(cbuf[0] != 0xb1) return;
00010
        int header_shift{6};
00011
        if (m_Version < 8) m_NbrAsic = cbuf[5];</pre>
00012
        else
00013
                      = cbuf[1];
= cbuf[2];
00014
         m DIFId
00015
          m_NbrAsic
00016
          header_shift = 3;
00017
        int size_hardroc1 = m_NbrAsic * 72 + header_shift + 1;
if(cbuf[size_hardroc1 - 1] != 0xal) size_hardroc1 = 0;
00018
00019
00020
        int size_hardroc2 = m_NbrAsic * 109 + header_shift + 1;
00021
00022
        if(cbuf[size_hardroc2 - 1] != 0xa1) size_hardroc2 = 0;
00023
        if(size_hardroc1 != 0)
00024
00025
         FillHR1(header shift, cbuf);
00026
          m_AsicType = 1;
00027
        else if(size_hardroc2 != 0)
00028
00029
         FillHR2(header_shift, cbuf);
00030
        else
00031
          return:
00032 }
00033
00034 inline std::uint8_t DIFSlowControl::getDIFId() { return m_DIFId; }
00035
00036 inline std::map<int, std::map<std::string, int» DIFSlowControl::getChipsMap() { return m_MapSC; }
00037
00038 inline std::map<std::string, int> DIFSlowControl::getChipSlowControl(const int& asicid) { return
      m_MapSC[asicid]; }
00039
00040 inline int DIFSlowControl::getChipSlowControl(const std::int8_t& asicid, const std::string& param) {
      return getChipSlowControl(asicid)[param]; }
00041
00042 void DIFSlowControl::FillHR1(const int& header shift, unsigned char* cbuf)
00043 {
00044
        int nasic{cbuf[header_shift - 1]};
00045
        int idx{header_shift};
00046
        for (int k = 0; k < nasic; k++)
00047
00048
          std::bitset<72 * 8> bs:
          // printf("%x %x \n",cbuf[idx+k*72+69],cbuf[idx+k*72+70]);
00049
          for (int 1 = 71; 1 >= 0; 1--)
00050
00051
          {
00052
            // printf("%d %x : %d -->",1,cbuf[idx+k*72+1],(71-1)*8);
00053
            for (int m = 0; m < 8; m++)
00054
00055
              \frac{1}{1} f(((1 « m) & cbuf[idx + k * 72 + 1]) != 0) bs.set((71 - 1) * 8 + m, 1);
00056
              else
00057
                bs.set((71 - 1) * 8 + m, 0);
00058
              // printf("%d",(int) bs[(71-1)*8+m]);
00059
            // printf("\n");
00060
00061
00062
          FillAsicHR1(bs);
00063
```

```
00064 }
00065
00066 void DIFSlowControl::FillHR2(const int& header_shift, unsigned char* cbuf)
00067 {
00068
         // int scsize1=cbuf[header shift-1]*109+(header shift-1)+2;
00069
         int nasic{cbuf[header_shift - 1]};
         int idx{header_shift};
00071
          // std::cout«" DIFSlowControl::FillHR nasic "«nasic«std::endl;
00072
         for(int k = 0; k < nasic; k++)
00073
00074
           std::bitset<109 * 8> bs;
            // printf("%x %x \n",cbuf[idx+k*109+69],cbuf[idx+k*109+70]);
for(int 1 = 108; 1 >= 0; 1--)
00075
00076
00077
00078
                   printf("%d %x : %d -->",1,cbuf[idx+k*109+1],(71-1)*8);
00079
              for (int m = 0; m < 8; m++)
08000
00081
                 if(((1 \le m) \le cbuf[idx + k \le 109 + 1]) != 0) bs.set((108 - 1) \le 8 + m, 1);
00082
                   bs.set((108 - 1) * 8 + m, 0);
00083
00084
                 // printf("%d",(int) bs[(71-1)*8+m]);
00085
00086
              // printf("\n");
00087
00088
           FillAsicHR2(bs);
00089
         }
00090 }
00091
00092 void DIFSlowControl::FillAsicHR1(const std::bitset<72 * 8>& bs)
00093 {
00094
         // Asic Id
00095
         int asicid{0};
         for (int j = 0; j < 8; j++)
if (bs[j + 9] != 0) asicid += (1 « (7 - j));
00096
00097
00098
         std::map<std::string, int> mAsic;
00099
         // Slow Control
         mAsic["SSCO"]
00100
                                     = static cast<int>(bs[575]);
         mAsic["SSC1"]
                                     = static_cast<int>(bs[574]);
00102
         mAsic["SSC2"]
                                     = static_cast<int>(bs[573]);
00103
         mAsic["Choix_caisson"] = static_cast<int>(bs[572]);
                               = static_cast<int>(bs[571]);
00104
         mAsic["SW 50k"]
         mAsic["SW_100k"]
                                     = static_cast<int>(bs[570]);
00105
         mAsic["SW 100f"]
                                     = static_cast<int>(bs[569]);
00106
00107
         mAsic["SW_50f"]
                                     = static_cast<int>(bs[568]);
00108
00109
         mAsic["Valid_DC"] = static_cast<int>(bs[567]);
         mAsic["ON_Discri"] = static_cast<int>(bs[566]);
mAsic["ON_Fsb"] = static_cast<int>(bs[565]);
00110
         mAsic["ON_Fsb"] = static_cast<int>(bs[565]);
mAsic["ON_Otaq"] = static_cast<int>(bs[564]);
00111
00112
         mAsic["ON_W"]
00113
                                = static_cast<int>(bs[563]);
         mAsic["ON_Ss"]
00114
                               = static_cast<int>(bs[562]);
                               = static_cast<int>(bs[561]);
= static_cast<int>(bs[560]);
00115
         mAsic["ON_Buf"]
00116
         mAsic["ON_Paf"]
00117
         // Gain
         for (int i = 0; i < 64; i++)
00118
00119
00120
           int gain{0};
           int gain(v);
for(int j = 0; j < 6; j++)
   if(bs(176 + i * 6 + j] != 0) gain += (1 « j);
mAsic["Channel_" + std::to_string(i) + "_" + "Gain"]
mAsic["Channel_" + std::to_string(i) + "_" + "CTest"]</pre>
00121
00122
00123
                                                                                   = gain;
                                                                                   = bs[112 + i1:
00124
           mAsic["Channel_" + std::to_string(i) + "_" + "Valid_trig"] = static_cast<int>(bs[25 + i]);
00125
00126
00127
         mAsic["ON_Otabg"] = static_cast<int>(bs[111]);
mAsic["ON_Dac"] = static_cast<int>(bs[110]);
mAsic["ON_Otadac"] = static_cast<int>(bs[109]);
00128
00129
00130
00131
         // DAC
00132
         int dac1{0};
         for(int j = 0; j < 10; j++)
if(bs[j + 99] != 0) dac1 += (1 « j);
00133
00134
         mAsic["DAC1"] = dac1;
00135
00136
         int dac0{0};
         for (int j = 0; j < 10; j++)
  if (bs[j + 89] != 0) dac0 += (1 « j);</pre>
00137
00138
         mAsic["DACO"]
00139
                                     = dac0;
00140
         mAsic["EN_Raz_Ext"]
                                        = static_cast<int>(bs[23]);
         mAsic["EN_Raz_Int"] = static_cast<int>(bs[22]);
mAsic["EN_Out_Raz_Int"] = static_cast<int>(bs[21]);
00141
00142
         mAsic["EN_Trig_Ext"]
                                       = static_cast<int>(bs[20]);
00143
         mAsic["EN_Trig_Int"]
                                       = static_cast<int>(bs[19]);
00144
         mAsic["EN_out_Trig_Int"] = static_cast<int>(bs[18]);
mAsic["Bypass_Chip"] = static_cast<int>(bs[17]);
00145
00146
00147
         mAsic["HardrocHeader"]
                                       = static_cast<int>(asicid);
         mAsic["EN_Out_Discri"]
00148
                                       = static_cast<int>(bs[8]);
         masic["EN_Transmit_On"] = static_cast<int>(bs[7]);
00149
00150
        mAsic["EN_Dout"]
                                       = static cast<int>(bs[6]);
```

```
mAsic["EN_RamFull"]
                                     = static_cast<int>(bs[5]);
        m_MapSC[asicid]
00152
00153 }
00154
00155 void DIFSlowControl::FillAsicHR2(const std::bitset<109 * 8>& bs)
00156 {
00157
         int asicid{0};
        for(int j = 0; j < 8; j++)
  if(bs[j + (108 - 7) * 8 + 2] != 0) asicid += (1 « (7 - j));</pre>
00158
00159
         std::map<std::string, int> mAsic;
00160
00161
        for (int i = 0; i < 64; i++)
00162
        {
00163
           int gain{0};
00164
           int mask{0};
           mAsic["Channel_" + std::to_string(i) + "_" + "cTest"] = bs[i];
00165
           for(int j = 0; j < 8; j++)
  if(bs[64 + i * 8 + j] != 0) gain += (1 « j);
mAsic["Channel_" + std::to_string(i) + "_" + "Gain"] = gain;
for(int j = 0; j < 3; j++)
  if(bs[8 * 77 + 2 + i * 3 + j] != 0) mask += (1 « j);</pre>
00166
00167
00168
00169
00170
           mAsic["Channel_" + std::to_string(i) + "_" + "Mask"] = mask;
00171
00172
00173
        mAsic["PwrOnPA"] = static_cast<int>(bs[8 * 72]);
        mAsic["Cmdb3SS"] = static_cast<int>(bs[8 * 72 + 1]);
00174
00175
        mAsic["Cmdb2SS"] = static_cast<int>(bs[8 * 72 + 2]);
        mAsic["Cmdb1SS"] = static_cast<int>(bs[8 * 72 + 3]);
00176
        mAsic["CmdbOSS"] = static\_cast < int > (bs[8 * 72 + 4]);
00177
        mAsic["SwSsc0"] = static_cast<int>(bs[8 * 72 + 5]);
mAsic["SwSsc1"] = static_cast<int>(bs[8 * 72 + 6]);
00178
00179
        mAsic["SwSsc2"] = static_cast<int>(bs[8 * 72 + 7]);
00180
00181
00182
        mAsic["PwrOnBuff"] = static_cast<int>(bs[8 * 73]);
        mAsic["PwrOnSS"] = static_cast<int>(bs[8 * 73 + 1]);
00183
00184
        mAsic["PwrOnW"]
                              = static_cast<int>(bs[8 * 73 + 2]);
        mAsic["Cmdb3Fsb2"] = static_cast<int>(bs[8 * 73 + 3]);
mAsic["Cmdb2Fsb2"] = static_cast<int>(bs[8 * 73 + 4]);
00185
00186
        mAsic["Cmdb1Fsb2"] = static_cast<int>(bs[8 * 73 + 5]);
00187
        mAsic["Cmdb0Fsb2"] = static_cast<int>(bs[8 * 73 + 6]);
00188
00189
        mAsic["Sw50k2"]
                              = static cast<int>(bs[8 * 73 + 71);
00190
        mAsic["Sw100k2"] = static_cast<int>(bs[8 * 74]);
mAsic["Sw100f2"] = static_cast<int>(bs[8 * 74 + 1]);
masic["Sw100f2"] = static_cast<int>(bs[8 * 74 + 1]);
00191
00192
        mAsic["Sw50f2"]
                              = static_cast<int>(bs[8 * 74 + 2]);
00193
        mAsic["Cmdb3Fsb1"] = static_cast<int>(bs[8 * 74 + 3]);
00194
        mAsic["Cmdb2Fsb1"] = static_cast<int>(bs[8 * 74 + 4]);
00195
00196
        mAsic["Cmdb1Fsb1"] = static_cast < int > (bs[8 * 74 + 5]);
00197
        mAsic["Cmdb0Fsb1"] = static_cast<int>(bs[8 * 74 + 6]);
00198
        mAsic["Sw50k1"]
                              = static cast<int>(bs[8 * 74 + 7]);
00199
        mAsic["Sw100k1"]
00200
                            = static cast<int>(bs[8 * 75]);
        mAsic["Sw100f1"] = static_cast<int>(bs[8 * 75 + 1]);
mAsic["Sw50f1"] = static_cast<int>(bs[8 * 75 + 2]).
00201
        mAsic["Sw50f1"]
                              = static_cast<int>(bs[8 * 75 + 2]);
00202
00203
        mAsic["Sel0"]
                              = static_cast<int>(bs[8 * 75 + 3]);
        mAsic["Sel11"]
00204
                              = static_cast<int>(bs[8 * 75 + 4]);
        mAsic["PwrOnFsb"] = static_cast<int>(bs[8 * 75 + 5]);
00205
        mAsic["PwrOnFsb1"] = static_cast<int>(bs[8 * 75 + 6]);
00206
        mAsic["PwrOnFsb2"] = static_cast<int>(bs[8 * 75 + 7]);
00208
        mAsic["Sw50k0"]
mAsic["Sw100k0"]
00209
                                 = static_cast<int>(bs[8 * 76]);
00210
                                = static_cast < int > (bs[8 * 76 + 1]);
        mAsic["Sw100f0"]
                                = static_cast<int>(bs[8 * 76 + 2]);
00211
        mAsic["Sw50f0"]
                                 = static_cast<int>(bs[8 * 76 + 3]);
00212
00213
        mAsic["EnOtaQ"]
                                = static_cast<int>(bs[8 * 76 + 4]);
        mAsic["OtaQ_PwrADC"] = static_cast<int>(bs[8 * 76 + 5]);
00214
00215
        mAsic["Discri_PwrA"] = static_cast<int>(bs[8 * 76 + 6]);
00216
        mAsic["Discri2"]
                                = static_cast<int>(bs[8 * 76 + 7]);
00217
                                 = static_cast<int>(bs[8 * 77]);
00218
        mAsic["Discri1"]
        mAsic["RS_or_Discri"] = static_cast<int>(bs[8 * 77 + 1]);
00219
00221
        mAsic["Header"] = asicid;
00222
         for (int i = 0; i < 3; i++)
00223
00224
          int B = 0;
           for(int j = 0; j < 10; j++)
  if(bs[8 * 102 + 2 + i * 10 + j] != 0) B += (1 « j);</pre>
00225
00226
           mAsic["B" + std::to_string(i)] = B;
00227
00228
00229
        mAsic["Smalldac"] = static_cast<int>(bs[8 * 106]);
00230
        mAsic["DacSw"]
                              = static_cast<int>(bs[8 * 106 + 1]);
00231
        mAsic["OtagBgSw"] = static_cast<int>(bs[8 * 106 + 2]);
00232
        mAsic["Trig2b"]
                              = static_cast<int>(bs[8 * 106 + 3]);
00233
        mAsic["Trig1b"]
00234
                              = static_cast<int>(bs[8 * 106 + 4]);
        mAsic["Trig0b"]
00235
                              = static_cast<int>(bs[8 * 106 + 5]);
        mAsic["EnTrigOut"] = static_cast<int>(bs[8 * 106 + 6]);
00236
00237
        mAsic["DiscrOrOr"] = static_cast<int>(bs[8 * 106 + 7]);
```

```
00238
         mAsic["TrigExtVal"] = static_cast<int>(bs[8 * 107]);
mAsic["RazChnIntVal"] = static_cast<int>(bs[8 * 107 + 1]);
mAsic["RazChnExtVal"] = static_cast<int>(bs[8 * 107 + 2]);
mAsic["ScOn"] = static_cast<int>(bs[8 * 107 + 3]);
mAsic["CLKMux"] = static_cast<int>(bs[8 * 107 + 4]);
00239
00240
00241
00242
00243
00245
          // EnOCDout1b EnOCDout2b EnOCTransmitOn1b
                                                                                                 EnOCChipsatb SelStartReadout
       SelEndReadout
00246 mAsic["SelEndReadout"]
                                           = static_cast<int>(bs[8 * 108 + 1]);
         mAsic["SelStartReadout"] = static_cast<int>(bs[8 * 108 + 2]);
00247
         mAsic["EnOCChipsatb"]
                                           = static_cast<int>(bs[8 * 108 + 3]);
00248
         mAsic["EnOCTransmitOn2b"] = static_cast<int>(bs[8 * 108 + 4]);
00249
00250
         mAsic["EnOCTransmitOn1b"] = static_cast<int>(bs[8 * 108 + 5]);
         mAsic["EnOCDout2b"] = static_cast<int>(bs[8 * 108 + 6]);
mAsic["EnOCDout1b"] = static_cast<int>(bs[8 * 108 + 7]);
00251
         mAsic["EnOCDout1b"]
00252
00253
         m_MapSC[asicid]
                                           = mAsic:
00254 }
00255
00256 std::string to_string(const DIFSlowControl& c)
00257 {
00258
         std::string ret;
00259
         for(std::map<int, std::map<std::string, int»::const_iterator it = c.cbegin(); it != c.cend(); it++)</pre>
00260
          ret += "ASIC " + std::to_string(it->first) + " :\n";
00261
       for (std::map<std::string, int>::const_iterator jt = (it->second).begin(); jt != (it->second).end(); jt++) ret += jt->first + " : " + std::to_string(jt->second) + "\n";
00263 }
00264
          return ret;
00265 }
```

5.39 libs/core/src/Filesystem.cc File Reference

```
#include "Filesystem.h"
```

Functions

- std::string path (const std::string &file)
- std::string extension (const std::string &file)
- std::string filename (const std::string &file)

5.39.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Filesystem.cc.

5.39.2 Function Documentation

5.40 Filesystem.cc 91

```
5.39.2.2 filename() std::string filename ( const std::string & file )
```

Definition at line 19 of file Filesystem.cc.

```
std::size_t position = file.find_last_of(".");
00022    std::size_t pos = file.find_last_of("\\/");
00023    return (std::string::npos == pos) ? file.substr(0, position) : file.substr(pos + 1, position - pos - 1);
00024 }
```

Definition at line 7 of file Filesystem.cc.

5.40 Filesystem.cc

Go to the documentation of this file.

```
00001
00005 #include "Filesystem.h"
00006
00007 std::string path(const std::string& file)
00008 {
00009    std::size_t pos = file.find_last_of("\\");
00010    return (std::string::npos == pos) ? "" : file.substr(0, pos);
00011 }
00012
00013 std::string extension(const std::string& file)
00014 {
00015    std::size_t position = file.find_last_of(".");
00016    return (std::string::npos == position || position == 0) ? "" : file.substr(position + 1);
00017 }
00018
00019 std::string filename(const std::string& file)
00020 {
00021    std::size_t position = file.find_last_of(".");
00022    std::size_t position = file.find_last_of("\\");
00023    return (std::string::npos == pos) ? file.substr(0, position) : file.substr(pos + 1, position - pos - 1);
00024 }
```

5.41 libs/core/src/Formatters.cc File Reference

```
#include "Formatters.h"
#include "Bits.h"
#include "Buffer.h"
#include "Words.h"
#include <fmt/format.h>
```

Functions

```
• std::string to_dec (const Buffer &b, const std::size_t &begin, const std::size_t &end)
• std::string to_dec (const bit8_t &b)
• std::string to dec (const bit16 t &b)
• std::string to_dec (const bit32_t &b)

    std::string to_dec (const bit64_t &b)

    std::string to_hex (const Buffer &b, const std::size_t &begin, const std::size_t &end)

• std::string to_hex (const bit8_t &b)
• std::string to hex (const bit16 t &b)
• std::string to_hex (const bit32_t &b)
• std::string to hex (const bit64 t &b)

    std::string to_bin (const Buffer &b, const std::size_t &begin, const std::size_t &end)

• std::string to_bin (const bit8_t &b)

    std::string to_bin (const bit16_t &b)

• std::string to_bin (const bit32_t &b)

    std::string to_bin (const bit64_t &b)

• std::string to_oct (const Buffer &b, const std::size_t &begin, const std::size_t &end)
std::string to_oct (const bit8_t &b)
• std::string to_oct (const bit16_t &b)
• std::string to_oct (const bit32_t &b)

    std::string to_oct (const bit64_t &b)
```

5.41.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Formatters.cc.

5.41.2 Function Documentation

```
5.41.2.3 to_bin() [3/5] std::string to_bin (
                                           const bit64_t & b )
 Definition at line 75 of file Formatters.cc.
 00075 { return fmt::format("{:#064b}", b); }
5.41.2.4 to bin() [4/5] std::string to_bin (
                                           const bit8_t & b )
 Definition at line 69 of file Formatters.cc.
 00069 { return fmt::format("{:#08b}", b); }
5.41.2.5 to_bin() [5/5] std::string to_bin (
                                           const Buffer & b,
                                           const std::size_t & begin,
                                           const std::size_t & end )
Definition at line 56 of file Formatters.cc.
                      std::size_t iend = end;
if(iend == -1) iend = b.size();
std::string ret;
 00058
 00059
 00060
clipmed | c
                      for(std::size_t k = begin; k < iend; k++)</pre>
00066 return ret;
00067 }
5.41.2.6 to_dec() [1/5] std::string to_dec (
                                           const bit16_t & b )
 Definition at line 29 of file Formatters.cc.
 00029 { return fmt::format("{:#d}", b); }
5.41.2.7 to_dec() [2/5] std::string to_dec (
                                           const bit32_t & b )
Definition at line 31 of file Formatters.cc.
 00031 { return fmt::format("{:#d}", b); }
5.41.2.8 to_dec() [3/5] std::string to_dec (
                                           const bit64_t & b )
Definition at line 33 of file Formatters.cc.
 00033 { return fmt::format("{:#d}", b); }
```

```
5.41.2.9 to_dec() [4/5] std::string to_dec (
                const bit8_t & b )
Definition at line 27 of file Formatters.cc.
00027 { return fmt::format("{:#d}", b); }
5.41.2.10 to dec() [5/5] std::string to_dec (
                const Buffer & b,
                const std::size_t & begin,
                const std::size_t & end )
Definition at line 14 of file Formatters.cc.
        std::size_t iend = end;
if(iend == -1) iend = b.size();
std::string ret;
for(std::size_t k = begin; k < iend; k++)</pre>
00016
00017
00018
00019
        ret += to_dec(b[k]);
ret += " - ";
00021
ret += "
00023 }
00024 return ret;
00025 }
5.41.2.11 to_hex() [1/5] std::string to_hex (
                const bit16_t & b )
Definition at line 50 of file Formatters.cc.
00050 { return fmt::format("{:#04x}", b); }
5.41.2.12 to_hex() [2/5] std::string to_hex (
                const bit32_t & b )
Definition at line 52 of file Formatters.cc.
00052 { return fmt::format("{:#08x}", b); }
5.41.2.13 to_hex() [3/5] std::string to_hex (
                const bit64_t & b )
Definition at line 54 of file Formatters.cc.
00054 { return fmt::format("{:#016x}", b); }
5.41.2.14 to_hex() [4/5] std::string to_hex (
                const bit8_t & b )
Definition at line 48 of file Formatters.cc.
00048 { return fmt::format("{:#02x}", b); }
```

```
5.41.2.15 to_hex() [5/5] std::string to_hex (
                const Buffer & b,
                const std::size_t & begin,
                const std::size_t & end )
Definition at line 35 of file Formatters.cc.
 00036 {
         std::size_t iend = end;
if(iend == -1) iend = b.size();
 00037
 00038
         std::string ret;
00042 ret += to_hex(b[k]);

00043 ret += " - ";

00044 }

00045 return ret;
 00040
         for(std::size_t k = begin; k < iend; k++)</pre>
5.41.2.16 to_oct() [1/5] std::string to_oct (
                const bit16_t & b )
Definition at line 92 of file Formatters.cc.
 00092 { return fmt::format("{:#080}", b); }
5.41.2.17 to_oct() [2/5] std::string to_oct (
                const bit32_t & b )
Definition at line 94 of file Formatters.cc.
00094 { return fmt::format("{:#0160}", b); }
5.41.2.18 to_oct() [3/5] std::string to_oct (
                const bit64_t & b )
Definition at line 96 of file Formatters.cc.
00096 { return fmt::format("{:#0320}", b); }
5.41.2.19 to_oct() [4/5] std::string to_oct (
                const bit8_t & b )
Definition at line 90 of file Formatters.cc.
```

00090 { return fmt::format("{:#040}", b); }

```
5.41.2.20 to_oct() [5/5] std::string to_oct (
               const Buffer & b,
              const std::size_t & begin,
               const std::size_t & end )
Definition at line 77 of file Formatters.cc.
00078 {
        std::size_t iend = end;
08000
        if (iend == -1) iend = b.size();
00081
        std::string ret;
00082
        for(std::size_t k = begin; k < iend; k++)</pre>
00083
00084
         ret += to_oct(b[k]);
00085
         ret += " - ";
00086
00087
        return ret;
00088 }
```

5.42 Formatters.cc

```
00001
00006 #include "Formatters.h"
00007
00008 #include "Bits.h"
00000 #include "Buffer.h"
00010 #include "Words.h"
00011
00012 #include <fmt/format.h>
00013
00014 std::string to_dec(const Buffer& b, const std::size_t& begin, const std::size_t& end)
00015 {
00016
        std::size_t iend = end;
        if(iend == -1) iend = b.size();
00017
00018
        std::string ret;
00019
        for(std::size_t k = begin; k < iend; k++)</pre>
       ret += to_dec(b[k]);
ret += " - ";
}
00020
00021
00022
00023
00024
        return ret:
00025 }
00026
00027 std::string to_dec(const bit8_t& b) { return fmt::format("{:#d}", b); }
00028
00029 std::string to_dec(const bit16_t& b) { return fmt::format("{:#d}", b); }
00030
00031 std::string to_dec(const bit32_t& b) { return fmt::format("{:#d}", b); }
00032
00033 std::string to_dec(const bit64_t& b) { return fmt::format("{:#d}", b); }
00034
00035 std::string to_hex(const Buffer& b, const std::size_t& begin, const std::size_t& end)
00036 {
00037
        std::size_t iend = end;
00038
        <u>if</u>(iend == -1) iend = b.size();
        std::string ret;
00039
00040
        for(std::size_t k = begin; k < iend; k++)</pre>
00041
00042
          ret += to hex(b[k]);
        ret += " - ";
00043
00044
00045
        return ret;
00046 }
00047
00048 std::string to_hex(const bit8_t& b) { return fmt::format("{:#02x}", b); }
00049
00050 std::string to_hex(const bit16_t& b) { return fmt::format("{:#04x}", b); }
00051
00052 std::string to_hex(const bit32_t& b) { return fmt::format("{:#08x}", b); }
00053
00054 std::string to_hex(const bit64_t& b) { return fmt::format("{:#016x}", b); }
00055
00056 std::string to_bin(const Buffer& b, const std::size_t& begin, const std::size_t& end)
00057 {
        std::size_t iend = end;
00058
00059
        if(iend == -1) iend = b.size();
        std::string ret;
for(std::size_t k = begin; k < iend; k++)</pre>
00060
00061
00062
       {
00063
          ret += to_bin(b[k]);
```

```
00064
         ret += " - ";
00065
00066
00067 }
00068
00069 std::string to_bin(const bit8_t& b) { return fmt::format("{:#08b}", b); }
00070
00071 std::string to_bin(const bit16_t& b) { return fmt::format("{:#016b}", b); }
00072
00073 std::string to_bin(const bit32_t& b) { return fmt::format("{:#032b}", b); }
00074
00075 std::string to_bin(const bit64_t& b) { return fmt::format("{:#064b}", b); }
00076
00077 std::string to_oct(const Buffer& b, const std::size_t& begin, const std::size_t& end)
00078 {
00079
       std::size_t iend = end;
08000
        if(iend == -1) iend = b.size();
00081
       std::string ret;
00082
       for(std::size_t k = begin; k < iend; k++)</pre>
00083
        ret += to_oct(b[k]);
ret += " - ";
00084
00085
00086
00087
       return ret;
00088 }
00089
00090 std::string to_oct(const bit8_t& b) { return fmt::format("{:#040}", b); }
00091
00092 std::string to_oct(const bit16_t& b) { return fmt::format("{:#080}", b); }
00093
00094 std::string to_oct(const bit32_t& b) { return fmt::format("{:#0160}", b); }
00095
00096 std::string to_oct(const bit64_t& b) { return fmt::format("{:#0320}", b); }
```

5.43 libs/core/src/RawBufferNavigator.cc File Reference

```
#include "RawBufferNavigator.h"
#include "Words.h"
```

5.43.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file RawBufferNavigator.cc.

5.44 RawBufferNavigator.cc

```
00001
00005 #include "RawBufferNavigator.h"
00006
00007 #include "Words.h"
00009 int RawBufferNavigator::m_Start = 92;
00010
00011 void RawBufferNavigator::StartAt(const int& start)
00012 {
00013
       if(start >= 0) m_Start = start;
00014 }
00015
00016 RawBufferNavigator::RawBufferNavigator() {}
00017
00018 void RawBufferNavigator::setBuffer(const Buffer& b)
00019 {
00020 m_Buffer
                          = b;
00021 m_StartPayload
                          = -1;
```

```
00022
       m_StartPayloadDone = false;
00023 }
00024
00025 std::uint8_t RawBufferNavigator::getDetectorID() { return m_Buffer[0]; }
00026
00027 bool RawBufferNavigator::findStartOfPayload()
00028 {
00029
        if (m_StartPayloadDone == true)
00030
00031
          if (m_StartPayload == -1) return false;
00032
         else
00033
           return true:
00034
00035
        else
00036
         m_StartPayloadDone = true;
for(std::size_t i = m_Start; i < m_Buffer.size(); i++)</pre>
00037
00038
00039
         {
00040
            if(static_cast<std::uint8_t>(m_Buffer[i]) == static_cast<std::uint8_t>(Value::GLOBAL_HEADER) ||
     static_cast<std::uint8_t>(m_Buffer[i]) == static_cast<std::uint8_t>(Value::GLOBAL_HEADER_TEMP))
00041
00042
              m_StartPayload = i;
00043
              return true;
00044
           }
00045
00046
          m_StartPayload = -1;
00047
          return false;
00048
00049 }
00050
00051 std::int32_t RawBufferNavigator::getStartOfPayload()
00052 {
00053
        findStartOfPayload();
00054
        return m_StartPayload;
00055 }
00056
00057 bool RawBufferNavigator::validPayload() { return m_StartPayload != -1; }
00059 Buffer RawBufferNavigator::getPayload() { return Buffer(&(m_Buffer.begin()[m_StartPayload]),
      m_Buffer.size() - m_StartPayload); }
```

5.45 libs/core/src/Version.cc File Reference

#include "Version.h"

5.45.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Version.cc.

5.46 Version.cc

```
00001
00005 #include "Version.h"
00006
00007 const static Version streamout_version;
00008
00009 std::uint8_t Version::getMajor() { return major; }
00010
00011 std::uint8_t Version::getMinor() { return minor; }
00012
00013 std::uint8_t Version::getPatch() { return patch; }
00014
00015 std::string Version::getPreRelease()
00016 {
```

5.47 libs/interface/Dump/include/textDump.h File Reference

```
#include "Interface.h"
#include "PayloadParser.h"
#include "spdlog/sinks/stdout_color_sinks.h"
#include <memory>
#include <spdlog/logger.h>
```

Classes

class textDump

5.47.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file textDump.h.

5.48 textDump.h

```
00001
00005 #pragma once
00006
00007 #include "Interface.h"
00008 #include "PayloadParser.h"
00009 #include "spdlog/sinks/stdout_color_sinks.h"
00010
00011 #include <memory>
00012 #include <spdlog/logger.h>
00013
00014 class textDump : public InterfaceWriter
00015 {
00016 public:
00017
       textDump();
00018
       void
00019
                                         processDIF(const PayloadParser&);
       void
00020
                                         processFrame(const PayloadParser&, uint32_t frameIndex);
       void
00021
                                         processPadInFrame(const PayloadParser&, uint32_t frameIndex,
     uint32_t channelIndex);
00022 void
                                         processSlowControl(Buffer);
00023
       void
                                         end();
       std::shared_ptr<spdlog::logger>& print() { return m_InternalLogger; }
00024
00025
                                         setLevel(const spdlog::level::level_enum& level) {
     m_InternalLogger->set_level(level); }
00026
00027 private:
00028
       // This class is a dumb class to print on terminal so we need the logger + the standard one given by
     the interface.
       std::shared_ptr<spdlog::logger> m_InternalLogger{nullptr};
00030 };
```

5.49 libs/interface/Dump/src/textDump.cc File Reference

```
#include "textDump.h"
#include "PayloadParser.h"
```

5.49.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file textDump.cc.

5.50 textDump.cc

Go to the documentation of this file.

```
00001
00005 #include "textDump.h"
00006
00007 #include "PayloadParser.h"
80000
00009 textDump::textDump() : InterfaceWriter("textDump", "1.0.0")
00010 {
        m_InternalLogger = std::make_shared<spdlog::logger>("textDump",
      std::make_shared<spdlog::sinks::stdout_color_sink_mt>());
00012 m_InternalLogger->set_level(spdlog::level::trace);
00013 addCompatibility("RawdataReader", ">=1.0.0");
00014 addCompatibility("DIFdataExample", ">=1.0.0");
00016
00017 void textDump::start() { print()->info("Will dump bunch of DIF data"); }
00018
00019 void textDump::processDIF(const PayloadParser& d) { print()->info("DIF_ID : {}, DTC : {}, GTC : {},
      DIF BCID {}, Absolute BCID : {}, Nbr frames {}", d.getDIFid(), d.getDTC(), d.getGTC(), d.getBCID(),
      d.getAbsoluteBCID(), d.getNumberOfFrames()); }
00020
00021 void textDump::processFrame(const PayloadParser& d, uint32_t frameIndex)
00022 {
      print()->info("\tDisplaying frame number {}: ASIC ID {}, Frame BCID {}, Frame Time To Trigger
(a.k.a timestamp) is {}", frameIndex, d.getASICid(frameIndex), d.getFrameBCID(frameIndex),
00023
      d.getFrameTimeToTrigger(frameIndex));
00024 }
00025
00026 void textDump::processPadInFrame(const PayloadParser& d, uint32_t frameIndex, uint32_t channelIndex)
00027 {
00028
         if(d.getThresholdStatus(frameIndex, channelIndex) > 0) { print()->info("\t\tChannel {}, Threshold
      {}", channelIndex, d.getThresholdStatus(frameIndex, channelIndex)); }
00029 }
00030
00031 void textDump::processSlowControl(Buffer) { print()->error("textDump::processSlowControl not
      implemented yet."); }
00033 void textDump::end() { print()->info("textDump end of report"); }
```

5.51 libs/interface/LCIO/include/LCIOWriter.h File Reference

5.51.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file LCIOWriter.h.

5.52 LCIOWriter.h

5.52 LCIOWriter.h

Go to the documentation of this file.

```
00001
00005 #pragma once
```

5.53 libs/interface/LCIO/src/LCIOWriter.cc File Reference

5.53.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file LCIOWriter.cc.

5.54 LCIOWriter.cc

Go to the documentation of this file.

5.55 libs/interface/RawDataReader/include/RawdataReader.h File Reference

```
#include "Interface.h"
#include <array>
#include <cstdint>
#include <fstream>
#include <string>
#include <vector>
```

Classes

· class RawdataReader

5.55.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file RawdataReader.h.

00031

00035

00037

00038

00039

00040 00041

00042 };

00032 private: 00033 void 00034 std::

void

std::ifstream

std::size_t

std::string

std::uint32_t

std::uint32_t

static std::size_t m_BufferSize;

std::vector<bit8_t> m_buf;

5.56 RawdataReader.h

Go to the documentation of this file.

```
00005 #pragma once
00006
00007 #include "Interface.h"
80000
00009 #include <arrav>
00010 #include <cstdint>
00011 #include <fstream>
00012 #include <string>
00013 #include <vector>
00014
00015 class Buffer;
00016
00017 class RawdataReader : public InterfaceReader
00018 {
00019 public:
00020
         explicit RawdataReader(const char* fileName);
00021
         void start();
00022
        void end();
float getFileSize();
void openFile(const std::string& fileName);
void closeFile();
bool nextEvent();
bool nextDIFbuffer();
const Buffer& getPuffer();
         void
                          end();
00023
00024
00025
00026
00027
        const Buffer& getBuffer();
virtual ~RawdataReader() { closeFile(); }
00028
00029
00030
        static void setDefaultBufferSize(const std::size_t& size);
```

uncompress(); uncompress(); m_FileStream;

m_NumberOfDIF{0};

m_EventNumber{0};

.._SurrerSize;
m_FileSize{0};
t m_NumberOfDIP'

m_Filename;

libs/interface/RawDataReader/src/RawdataReader.cc File Reference

setFileSize(const std::size t& size);

```
#include "RawdataReader.h"
#include "Exception.h"
#include <cstdint>
#include <cstring>
#include <stdexcept>
#include <zlib.h>
```

5.57.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file RawdataReader.cc.

5.58 RawdataReader.cc 103

5.58 RawdataReader.cc

```
00004 #include "RawdataReader.h"
00005
00006 #include "Exception.h"
00007
00008 #include <cstdint>
00009 #include <cstring>
00010 #include <stdexcept>
00011 #include <zlib.h>
00012
00014 std::size_t RawdataReader::m_BufferSize = 0x100000;
00015
00016 void RawdataReader::setDefaultBufferSize(const std::size t& size) { m BufferSize = size; }
00017
00018 RawdataReader::RawdataReader(const char* fileName) : InterfaceReader("RawdataReader", "1.0.0")
00019 {
00020
        m_buf.reserve(m_BufferSize);
        m_Filename = fileName;
00021
00022 }
00024 void RawdataReader::start() { openFile(m_Filename); }
00025
00026 void RawdataReader::end() { closeFile(); }
00027
00028 void RawdataReader::uncompress()
00029 {
00030
        static const std::size_t size_buffer{0x20000};
00031
                                  shift{3 * sizeof(std::uint32_t) + sizeof(std::uint64_t)};
        std::size_t
00032
        static bit8_t
                                  obuf[size_buffer];
                                  size_buffer_end{0x20000}; // NOLINT(runtime/int)
       unsigned long
00033
                                 rc = ::uncompress(obuf, &size_buffer_end, &m_Buffer[shift], m_Buffer.size()
00034 std::int8 t
      - shift);
00035
        switch(rc)
00036
00037
          case Z_OK: break;
          case Z_MEM_ERROR: throw Exception(Z_MEM_ERROR, "Not enough memory"); break;
case Z_BUF_ERROR: throw Exception(Z_BUF_ERROR, "Not enough room in the output buffer"); break;
00038
00039
          case Z_DATA_ERROR: throw Exception(Z_DATA_ERROR, "The input data was corrupted or incomplete");
00040
00041
                    throw Exception("The input data was corrupted or incomplete"); break;
00042
00043
        memcpy(&m_Buffer[shift], obuf, size_buffer_end);
00044
        m Buffer.setSize(size_buffer_end + shift);
00045 }
00046
00047 void RawdataReader::closeFile()
00048 {
00049
00050
00051
          if(m FileStream.is open()) m FileStream.close();
00052
00053
        catch(const std::ios_base::failure& e)
00054
00055
          log()->error("Caught an ios_base::failure in closeFile : {} ", e.what(), e.code().value());
00056
         throw;
00057
00058 }
00059
00060 void RawdataReader::openFile(const std::string& fileName)
00061 {
00062
00063
00064
          m_FileStream.rdbuf()->pubsetbuf(0, 0);
00065
          m_FileStream.exceptions(std::ifstream::failbit | std::ifstream::badbit);
          m_FileStream.open(fileName.c_str(), std::ios::in | std::ios::binary | std::ios::ate); // Start at
00066
      the end to directly calculate the size of the file then come back to beginning
00067
          m_FileStream.rdbuf()->pubsetbuf(0, 0);
00068
          if (m_FileStream.is_open())
00069
          {
00070
            setFileSize(m_FileStream.tellg());
00071
            m_FileStream.seekg(0, std::ios::beg);
00072
00073
00074
        catch(const std::ios_base::failure& e)
00075
00076
          log()->error("Caught an ios_base::failure in openFile : {}", e.what());
00077
         throw;
00078
00079 }
08000
00081 bool RawdataReader::nextEvent()
00082 {
00083
```

```
00084
00085
         m_FileStream.read(reinterpret_cast<char*>(&m_EventNumber), sizeof(std::uint32_t));
00086
         m_FileStream.read(reinterpret_cast<char*>(&m_NumberOfDIF), sizeof(std::uint32_t));
00087
00088
       catch(const std::ios_base::failure& e)
00089
         return false;
00091
00092
       return true;
00093 }
00094
00095 bool RawdataReader::nextDIFbuffer()
00096 {
00097
00098
00099
         static int DIF_processed{0};
         if(DIF_processed >= m_NumberOfDIF)
00100
00101
          DIF_processed = 0;
00102
00103
           return false;
00104
00105
         else
00106
           DIF_processed++;
00107
00108
           std::uint32_t bsize{0};
00109
           m_FileStream.read(reinterpret_cast<char*>(&bsize), sizeof(std::uint32_t));
00110
           m_FileStream.read(reinterpret_cast<char*>(&m_buf[0]), bsize);
00111
           m_Buffer = Buffer(m_buf);
00112
00113
00114
       catch (const std::ios base::failure& e)
00115
00116
         log()->error("Caught an ios_base::failure in openFile : {}", e.what());
00117
         return false;
00118
00119
       return true;
00120 }
00122 const Buffer& RawdataReader::getBuffer()
00123 {
00124
       uncompress();
00125
       return m_Buffer;
00126 }
00127
00128 void RawdataReader::setFileSize(const std::size_t& size) { m_FileSize = size; }
00129
00130 float RawdataReader::getFileSize() { return m_FileSize; }
```

5.59 libs/interface/ROOT/include/DIF.h File Reference

```
#include "Hit.h"
#include <TObject.h>
#include <cstdint>
#include <map>
#include <vector>
```

Classes

· class DIF

Typedefs

using Hits_const_iterator = std::vector< Hit >::const_iterator

5.59.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file DIF.h.

5.60 DIF.h 105

5.59.2 Typedef Documentation

```
5.59.2.1 Hits_const_iterator using Hits_const_iterator = std::vector<Hit>::const_iterator
```

Definition at line 14 of file DIF.h.

5.60 DIF.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include "Hit.h"
80000
00009 #include <TObject.h>
00010 #include <cstdint>
00011 #include <map>
00012 #include <vector>
00014 using Hits_const_iterator = std::vector<Hit>::const_iterator;
00015
00016 class DIF : public TObject
00017
00018 public:
00019
       void
                                          clear();
00020
                                          addHit(const Hit&);
        void
00021
        void
                                          setID(const std::uint8_t&);
00022
       std::uint8_t
                                          getID() const;
                                          setDTC(const std::uint32_t&);
getDTC() const;
00023
        void
00024
       std::uint32 t
00025
                                          setGTC(const std::uint32_t&);
        void
00026
        std::uint32_t
                                          getGTC() const;
00027
        void
                                          setDIFBCID(const std::uint32_t&);
                                          getDIFBCID() const;
setAbsoluteBCID(const std::uint64_t&);
00028
        std::uint32_t
00029
        void
00030
                                          getAbsoluteBCID() const;
       std::uint64 t
00031
       std::vector<Hit>::const_iterator cbegin() const;
00032
       std::vector<Hit>::const_iterator cend() const;
00033
00034 private:
       std::uint8_t
00035
                         m_ID{0};
       std::uint32_t
00036
                         m_DTC{0};
00037
       std::uint32_t
                         m_GTC{0};
00038
       std::uint32_t
                         m_DIFBCID{0};
00039
       std::uint64_t
                         m_AbsoluteBCID{0};
00040
       std::vector<Hit> m_Hits;
00041
       ClassDef(DIF, 1);
00042 };
```

5.61 libs/interface/ROOT/include/DIFLinkDef.h File Reference

#include <vector>

5.61.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file DIFLinkDef.h.

5.62 DIFLinkDef.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006 #include <vector>
00007
00008 #ifdef __CLING__
00009 #pragma link C++ class DIF;
00010 #pragma link C++ class Hit;
00011 #pragma link C++ class std::vector < Hit>;
00012 #endif
```

5.63 libs/interface/ROOT/include/Event.h File Reference

```
#include "DIF.h"
#include <TObject.h>
#include <cstdint>
#include <map>
```

Classes

class Event

Typedefs

• using DIFs_const_iterator = std::map< std::uint8_t, DIF >::const_iterator

5.63.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Event.h.

5.63.2 Typedef Documentation

```
5.63.2.1 DIFs_const_iterator using DIFs_const_iterator = std::map<std::uint8_t, DIF>::const_\leftarrow iterator
```

Definition at line 13 of file Event.h.

5.64 Event.h 107

5.64 Event.h

Go to the documentation of this file.

```
00005 #pragma once
00006
00007 #include "DIF.h"
80000
00009 #include <TObject.h>
00010 #include <cstdint>
00011 #include <map>
00012
00013 using DIFs_const_iterator = std::map<std::uint8_t, DIF>::const_iterator;
00014
00015 class Event : public TObject
00016 {
00017 public:
00018 void
                                                              clear();
00019
         void
                                                              addDIF(const DIF& dif);
00020 std::map<std::uint8_t, DIF>::const_iterator cbegin() const;
00021 std::map<std::uint8_t, DIF>::const_iterator cend() const;
00022
00023 private:
00024 std::map<std::uint8_t, DIF> DIFs;
00025 ClassDef(Event, 1);
00026 };
```

5.65 libs/interface/ROOT/include/EventLinkDef.h File Reference

```
#include <cstdint>
#include <map>
#include <vector>
```

5.65.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file EventLinkDef.h.

5.66 EventLinkDef.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006 #include <cstdint>
00007 #include <map>
00008 #include <vector>
00009 #ifdef __CLING__
00010 #pragma link C++ class DIF;
00011 #pragma link C++ class std::vector < DIF>;
00012 #pragma link C++ class Hit;
00013 #pragma link C++ class std::vector < Hit>;
00014 #pragma link C++ class std::vector < Hit>;
00015 #pragma link C++ class std::vector < Event>;
00016 #pragma link C++ class std::vector < Event>;
00016 #pragma link C++ class std::wector < Std::wettor < DIF>;
0017 #endif
```

5.67 libs/interface/ROOT/include/Hit.h File Reference

```
#include <TObject.h>
#include <cstdint>
```

Classes

· class Hit

5.67.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Hit.h.

5.68 Hit.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006
00007 #include <TObject.h>
00008 #include <cstdint>
00009
00010 class Hit : public TObject
00011 {
00012 public:
          void clear();
void setDIF(const std::uint8_t&);
void setASIC(const std::uint8_t&);
void setChannel(const std::uint8_t&);
void setThreshold(const std::uint8_t&);
void setDTC(const std::uint32_t&);
void setGTC(const std::uint32_t&);
void setDIFBCID(const std::uint32_t&);
void setFrameBCID(const std::uint32_t&);
void setTimestamp(const std::uint32_t&);
void setAbsoluteBCID(const std::uint32_t&);
00013
00014
00015
00016
00017
00018
00019
00020
00021
00022
00023
          void
                              setAbsoluteBCID(const std::uint64_t&);
          00024
00025
00027
00028
          std::uint32_t getDTC() const;
00029
          std::uint32_t getGTC() const;
          std::uint32_t getDIFBCID() const;
std::uint32_t getFrameBCID() const;
00030
00031
00032
         std::uint32_t getTimestamp() const;
00033
          std::uint64_t getAbsoluteBCID() const;
00034
00035 private:
00036 std::uint8_t m_DIF{0};
00037 std::uint8_t m_ASIC{0}
          std::uint8_t m_ASIC{0};
std::uint8_t m_Channel{0};
00038
00039
          std::uint8_t m_Threshold{0};
00040
          std::uint32_t m_DTC{0};
00041
          std::uint32_t m_GTC{0};
00042
          std::uint32_t m_DIFBCID{0};
          std::uint32_t m_FrameBCID{0};
00043
00044
          std::uint32_t m_Timestamp{0};
00045
           std::uint64_t m_AbsoluteBCID{0};
00046
         ClassDef(Hit, 1);
00047 };
```

5.69 libs/interface/ROOT/include/HitLinkDef.h File Reference

5.69.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file HitLinkDef.h.

5.70 HitLinkDef.h 109

5.70 HitLinkDef.h

Go to the documentation of this file.

```
00001
00005 #pragma once
00006 #ifdef __CLING__
00007 #pragma link C++ class Hit;
00008 #endif
```

5.71 libs/interface/ROOT/include/ROOTWriter.h File Reference

```
#include "Buffer.h"
#include "Event.h"
#include "Interface.h"
#include "PayloadParser.h"
#include <TFile.h>
#include <TTree.h>
#include <string>
#include <vector>
```

Classes

• class ROOTWriter

5.72 ROOTWriter.h

```
00006 #pragma once
00007
00008 #include "Buffer.h"
00000 #include "Event.h"
00010 #include "Interface.h"
00011 #include "PayloadParser.h"
00012
00013 #include <TFile.h>
00014 #include <TTree.h>
00015 #include <string>
00016 #include <vector>
00017
00018 class ROOTWriter : public InterfaceWriter
00019 {
00020 public:
00021 ROOTWriter();
00022
00023
        void setFilename(const std::string&);
00024
00025
00026 void processDIF(const PayloadParser&);
00027 void processFrame(const PayloadParser&, const std::uint32_t& frameIndex);
00028 void processPadInFrame(const PayloadParser&, const std::uint32_t& frameIndex, const std::uint32_t&
      channelIndex);
00029     void processSlowControl(const Buffer&) { ; }
00030     void end();
00031
00032
        virtual void startEvent();
00033
        virtual void endEvent();
00034
        virtual void startDIF();
00035
        virtual void endDIF();
00036
        virtual void startFrame();
00037
        virtual void endFrame();
00038
        virtual void startPad();
00039
        virtual void endPad();
00040
00041 private:
00042 TFile*
                    m_File{nullptr};
00043
        TTree*
                     m_Tree{nullptr};
00044
        Event*
                      m_Event{nullptr};
00045
        DTF*
                      m_DIF{nullptr};
00046
        Hit*
                      m Hit{nullptr};
00047
      std::string m_Filename;
00048 };
```

5.73 libs/interface/ROOT/src/DIF.cc File Reference

```
#include "DIF.h"
#include <cstdint>
```

5.73.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file DIF.cc.

5.74 DIF.cc

Go to the documentation of this file.

```
00006 #include "DIF.h"
00007
00008 #include <cstdint>
00009
00010 void DIF::addHit(const Hit& hit) { m_Hits.push_back(hit); }
00011
00012 void DIF::setID(const std::uint8_t& id) { m_ID = id; }
00013
00014 std::uint8_t DIF::getID()const { return m_ID; }
00015
00016 void DIF::setDTC(const std::uint32_t& dtc) { m_DTC = dtc; }
00017
00018 std::uint32_t DIF::getDTC()const { return m_DTC; }
00019
00020 void DIF::setGTC(const std::uint32_t& gtc) { m_GTC = gtc; }
00021
00022 std::uint32_t DIF::getGTC()const { return m_GTC; }
00023
00024 void DIF::setDIFBCID(const std::uint32_t& difbcid) { m_DIFBCID = difbcid; }
00025
00026 std::uint32_t DIF::getDIFBCID()const { return m_DIFBCID; }
00027
00028 void DIF::setAbsoluteBCID(const std::uint64_t& absolutebcid) { m_AbsoluteBCID = absolutebcid; }
00029
00030 std::uint64_t DIF::getAbsoluteBCID()const { return m_AbsoluteBCID; }
00031
00032 std::vector<Hit>::const_iterator DIF::cbegin()const { return m_Hits.cbegin(); }
00033
00034 std::vector<Hit>::const_iterator DIF::cend()const { return m_Hits.cend(); }
00036 void DIF::clear() { m_Hits.clear(); }
```

5.75 libs/interface/ROOT/src/Event.cc File Reference

```
#include "Event.h"
```

5.75.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Event.cc.

5.76 Event.cc 111

5.76 Event.cc

Go to the documentation of this file.

```
00001
00006 #include "Event.h"
00007
00008 void Event::clear() { DIFs.clear(); }
00009
00010 void Event::addDIF(const DIF& dif) { DIFs[dif.getID()] = dif; }
00011
00012 std::map<std::uint8_t, DIF>::const_iterator Event::cbegin()const { return DIFs.cbegin(); }
00013
00014 std::map<std::uint8_t, DIF>::const_iterator Event::cend()const { return DIFs.cend(); }
```

5.77 libs/interface/ROOT/src/Hit.cc File Reference

```
#include "Hit.h"
```

5.77.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file Hit.cc.

5.78 Hit.cc

```
00001
00006 #include "Hit.h"
00007 void Hit::clear()
00008 {
00009
       m DIF
                       = 0;
                       = 0;
00010
       m_ASIC
00011
       m_Channel
00012
        {\tt m\_Threshold}
                       = 0;
00013
       m_DTC
                       = 0:
00014
       m_GTC
                       = 0;
00015
       m DIFBCID
                       = 0;
00016
       m_FrameBCID
                      = 0;
00017
        m_Timestamp
00018
       m_AbsoluteBCID = 0;
00019 }
00020
00021 void Hit::setDIF(const std::uint8 t& dif) { m DIF = dif; }
00022
00023 void Hit::setASIC(const std::uint8_t& asic) { m_ASIC = asic; }
00024
00025 void Hit::setChannel(const std::uint8_t& channel) { m_Channel = channel; }
00026
00027 void Hit::setThreshold(const std::uint8_t& threshold) { m_Threshold = threshold; }
00028
00029 void Hit::setDTC(const std::uint32_t& dtc) { m_DTC = dtc; }
00030
00031 void Hit::setGTC(const std::uint32_t& gtc) { m_GTC = gtc; }
00032
00033 void Hit::setDIFBCID(const std::uint32_t& difbcid) { m_DIFBCID = difbcid; }
00034
00035 void Hit::setFrameBCID(const std::uint32_t& framebcid) { m_FrameBCID = framebcid; }
00036
00037 void Hit::setTimestamp(const std::uint32_t& timestamp) { m_Timestamp = timestamp; }
00038
00039 void Hit::setAbsoluteBCID(const std::uint64_t& absolutebcid) { m_AbsoluteBCID = absolutebcid; }
00040
00041 std::uint8_t Hit::getDIFid()const { return m_DIF; }
00042
```

```
00043 std::uint8_t Hit::getASICid()const { return m_ASIC; }
00044
00045 std::uint8_t Hit::getChannel()const { return m_Channel; }
00046
00047 std::uint8_t Hit::getThreshold()const { return m_Threshold; }
00048
00049 std::uint32_t Hit::getDTC()const { return m_DTC; }
00050
00051 std::uint32_t Hit::getGTC()const { return m_GTC; }
00052
00053 std::uint32_t Hit::getDIFBCID()const { return m_DIFBCID; }
00054
00055 std::uint32_t Hit::getFrameBCID()const { return m_FrameBCID; }
00056
00057 std::uint32_t Hit::getTimestamp()const { return m_Timestamp; }
00058
00059 std::uint64_t Hit::getAbsoluteBCID()const { return m_AbsoluteBCID; }
```

5.79 libs/interface/ROOT/src/ROOTWriter.cc File Reference

```
#include "ROOTWriter.h"
```

5.79.1 Detailed Description

Copyright

2022 G.Grenier F.Lagarde

Definition in file ROOTWriter.cc.

5.80 ROOTWriter.cc

```
00001
00006 #include "ROOTWriter.h"
00007
00008 void ROOTWriter::setFilename(const std::string& filename) { m_Filename = filename; }
00009
00010 ROOTWriter::ROOTWriter() : InterfaceWriter("ROOTWriter", "1.0.0") { addCompatibility("RawdataReader",
      ">=1.0.0"); }
00011
00012 void ROOTWriter::start()
00013 {
       m_File = TFile::Open(m_Filename.c_str(), "RECREATE", m_Filename.c_str(),
     ROOT::CompressionSettings(ROOT::kZLIB, 5));
00015 m_Tree = new TTree("RawData", "Raw SDHCAL data tree");
00016
       m_Tree->Branch("Events", &m_Event, 512000, 99);
00017 }
00018
00019 void ROOTWriter::end()
00020 {
00021
        if (m_Tree) m_Tree->Write();
00022
        if (m_File)
00023
00024
         m_File->Write();
00025
         m_File->Close();
00026
00027
       if (m_File) delete m_File;
00028 }
00029
00030 void ROOTWriter::processDIF(const PayloadParser& d)
00031 {
00032
       m_DIF->setID(d.getDIFid());
00033
        m_DIF->setDTC(d.getDTC());
00034
        m_DIF->setGTC(d.getGTC());
        m_DIF->setDIFBCID(d.getBCID());
00035
00036
       m_DIF->setAbsoluteBCID(d.getAbsoluteBCID());
00037 }
00038
```

5.80 ROOTWriter.cc 113

```
00039 void ROOTWriter::processFrame(const PayloadParser& d, const std::uint32_t& frameIndex)
00040 {
00041
        m_Hit->setDIF(d.getDIFid());
00042
        m_Hit->setASIC(d.getASICid(frameIndex));
        m_Hit->setDTC(d.getDTC());
00043
        m_Hit->setGTC(d.getGTC());
00044
        m_Hit->setDIFBCID(d.getBCID());
00046
        m_Hit->setAbsoluteBCID(d.getAbsoluteBCID());
00047
        m_Hit->setFrameBCID(d.getFrameBCID(frameIndex));
00048
        m_Hit->setTimestamp(d.getFrameTimeToTrigger(frameIndex));
00049 }
00050
00051 void ROOTWriter::processPadInFrame(const PayloadParser& d, const std::uint32_t& frameIndex, const
      std::uint32_t& channelIndex)
00052 {
00053
        m_Hit->setChannel(channelIndex);
       m_Hit->setThreshold(static_cast<std::uint8_t>(d.getThresholdStatus(frameIndex, channelIndex)));
00054
00055 }
00056
00057 void ROOTWriter::startEvent()
00058 {
00059
       m_Event = new Event();
00060 // m_Event->clear();
00061 }
00062
00063 void ROOTWriter::endEvent()
00064 {
00065 m_Tree->Fill();
00066
       if (m_Event) delete m_Event;
00067 }
00068
00069 void ROOTWriter::startDIF()
00070 {
00071
       m_DIF = new DIF();
00072
       // m_DIF->clear();
00073 }
00074
00075 void ROOTWriter::endDIF()
00076 {
00077 m_Event->addDIF(*m_DIF);
00078 delete m_DIF;
00079 }
08000
00081 void ROOTWriter::startFrame()
00082 {
00083
       m_Hit = new Hit();
00084 // m_Hit->clear();
00085 }
00086
00087 void ROOTWriter::endFrame()
00088 {
00089 m_DIF->addHit(*m_Hit);
00090
       delete m_Hit;
00091 }
00092
00093 void ROOTWriter::startPad() {}
00094
00095 void ROOTWriter::endPad() {}
```