

Provision an SVM by using a preconfigured ONTAP template

ONTAP 9

aherbin April 27, 2021

Table of Contents

Provision an SVM b	v using a preconfigured	ONTAP template	
I TOTICION AND OTHER	, asing a proceningarea	Oltifu template	

Provision an SVM by using a preconfigured ONTAP template

Starting with ONTAP 9.3, you can create and provision an SVM by using a preconfigured template. You must provide values for the parameters that are defined in the template. **QUESTION: WHY would a user need to do this?**

All of the required feature licenses must be installed on the cluster.

The VserverEnvironmentSetup template is the preconfigured template that you can use for configuring SVMs. The VserverEnvironmentSetup template enables you to set up the following configurations:

- Security style, language setting, and IPspace of the SVM
- Protocols
- Data LIFs
- · Network routes
- DNS configuration
- · Active Directory configuration
- NIS configuration
- LDAP client and server configuration
- · CIFS server

The VserverEnvironmentSetup template is a read-only template. You cannot modify the default parameter values of this template. If you want to modify the default values of any of the parameters in the template, you must copy the template, and then modify the default values of the parameters.

1. View and note down the values for the parameters that are defined in the template for creating and configuring the SVM: template parameter show

Template: Vserver: Permission: readonl		etup		
Parameter		Default Value		
				1
vserver	string	-	no	Vserver Name
security_style	string	unix	no	Vserver Security
Style				
language	string	C.UTF-8	no	Vserver Language
ipspace	string	Default	no	Vserver IPSpace
protocols	enum	-	no	Protocols to
configure				
Allowed Values:	nfs, cifs, i	scsi, fcp		
data_lif	array of li	fInfoStruct		
		-	yes	Data LIF Info Struct
data_lif[#].ipaddr	IPAddress	-	no	IP Addr
data_lif[#].netmask	IPAddress	-	no	NetMask
data_lif[#].protoco	1			
	string	-	no	LIF Protocol
data_lif[#].homenod	е			
	string	-	no	Node Name
data_lif[#].homepor	t			
	string	-	no	Port
gateway	array of IPAddress			
		-	yes	Gateway
gateway[#]	IPAddress		no	Gateway
search_domain	string	-	no	Search Domain
dns_server	string	_	no	DNS IP Addresses Lis
ad_admin_name	string	_	no	AD Admin Name
ad_admin_passwd	string	* * *	no	AD Admin Passwd
ad_domain	string	-	no	AD Domain
ad_ou	string	CN=Computers	no	Organizational Name
wg_name	string	-	no	WG Name
nis_domain	string	_	no	NIS Domains
nis_ipaddr	string	_	no	NIS IP Address
ldap_server	string	_	no	LDAP Server IP
ldap_base_dn	string	-	no	LDAP Base DN
client_config	_	-	no	LDAP Client Config
cifs server	string		no	CIFS Server Name

2. If you want to modify the default value of any parameter in the template, customize the existing template:

a. Copy the template: template copy -name template_name -destination_name
 new template name

```
cluster1::> template copy -name VserverEnvironmentSetup -destination
-name template1
```

The new template is a read/write template.

b. Modify the default value of the parameter that you want to change: template parameter modify -template template_name -name parameter_name -default-value new default value

```
cluster1::> template parameter modify -template template1 -name
security_style -default-value ntfs
```

3. Provision the SVM by specifying values for the parameters in the template: template provision -name template name

```
cluster-1::> template provision -name template1
       Press Ctrl+C to abort.
       ******
       * Setup of vserver *
       *****
      Vserver Name: vs0
      Vserver Language [C.UTF-8]:
      Vserver Security Style [ntfs]:
      Vserver IPSpace [Default]:
       *****
       * Setup of network.interface *
       ******
       Enter number of instances for object network.interface: 2
       (1/2) LIF Protocol: nfs
       (1/2) IP Addr: 1.1.1.1
       (1/2) NetMask: 255.255.255.0
       (1/2) Node Name: node1-vsim1
       (1/2) Port: e0c
       (2/2) LIF Protocol: nfs
       (2/2) IP Addr: 1.1.1.1
       (2/2) NetMask: 255.255.255.0
       (2/2) Node Name: node1-vsim1
       (2/2) Port: e0c
       *****
       * Setup of network.routes *
```

```
******
Enter number of instances for object network.routes: 1
(1/1) Gateway: 1.1.1.1
****
* Setup of access.dns *
*****
Search Domain: netapp.com
DNS IP Addresses List: 1.1.1.1
*****
* Setup of security.nis *
*****
NIS Domains: netapp.com
NIS IP Address: 1.1.1.1
******
* Setup of security *
*****
LDAP Client Config: ldapconfig
LDAP Server IP: 1.1.1.1
LDAP Base DN: dc=examplebasedn
*****
* Setup of protocols *
*****
Protocols to configure: nfs
[Job 15] Configuring vserver for vs0 (100%)
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.