STANDFIRE

Release

Contents

I		NDFIRE User Guide	3
		Overview of STANDFIRE	
	1.2	Installation	3
	1.3	Basic Usage	3
	1.4	Advance Topics	3
	1.5	Tutorials	3
2	2.1	MDFIRE API Reference fuels module	
3	Indic	ees and tables	15
Ру	thon N	Module Index	17
In	dex		19

Contents:

Contents 1

2 Contents

STANDFIRE User Guide

Contents:

Overview of STANDFIRE

Installation

Basic Usage

Advance Topics

Tutorials

Contents:

Interfacing with FVS

Use Suppose to generate a keyword file. Or use the following example .key

NOSCREEN							
RANNSEED	0						
!STATS							
STDIDENT							
STANDFIRE_e	xample						
DESIGN	-10	500	5	9			
STDINFO	103	140	60.0	0.0	0.0	36.0	
INVYEAR	2010						
NUMCYCLE	10						
TREEDATA							
FMIN							
END							
STATS							
SVS	0		0	0	15		
FMIn							
Potfire							
FuelOut							

```
BurnRept
MortRept
FuelRept
SnagSum
End
PROCESS
STOP
```

If don't have a FVS tree list file, then copy and paste the following text and save it to the same directory where the keyword file lives, give it the same prefix as the .key but with a .tre extension.

1	95	9PP 105	35		0 0
1	96	OPP 43	17	1	0 0
1	97	OPP 148	43	2	0 0
1	98	OPP 49	30	1	0 0
1	99	9PP 54	30		0 0
1	100	OPP 100	40	3	0 0
1	101	OPP 42	30	2	0 0
1	102	OPP 53	34	1	0 0
1	103	OPP 97	42	3	0 0
1	104	OPP 61	35	1	0 0
1	105	OPP 81	40	1	0 0
1	106	9PP 80	33		0 0
1	107	OPP 41	32	2	0 0
1	108	9PP 71	40		0 0
1	109	9PP 73	41		0 0
1	110	9PP 94	35		0 0
1	111	9PP 103	32		0 0

Once you have a keyword file and a tree list file in the same directory we can start to build a script to do some work.

First we import the Fvsfuels class from the fuels module.

```
>>> from standfire.fuels import Fvsfuels
```

Next create an instance of the class passes the desired variant as an argument and register the keyword file.

```
>>> stand_1 = Fvsfuel("iec")
>>> stand_1.set_keyword("/Users/standfire/fvs_exp/example.key")
TIMEINT not found in keyword file, default is 10 years
```

We get a message telling us that the TIMEINT keyword was not found in the keyword file. No problem, STANDFIRE automatically sets this value to 10 years.

```
>>> stand_1.keywords
{'TIMEINT': 10, 'NUMCYCLE': 10, 'INVYEAR': 2010, 'SVS': 15, 'FUELOUT': 1}
```

Notice the keys in the keywords dictionary. TIMEINT is the time interval of the FVS simulation in year, NUMCYCLE is the number of cycles, INVYEAR is the year of the inventory, and SVS and FUELOUT are there to check if these keywords are in the keyword file. If the SVS and FUELOUT keywords are not defined the keyword file then FVS will not calculate tree positions or fuel attributes. So be sure you add these to your keyword file before registering the .key with FVS. You can use *post processors** in Suppose to do so. TIMEINT, NUMCYCLE, and INVYEAR can be manually changed by calling setters for each. For instance, if you only want to calculate fuel attributes for trees during the year of the inventory then simply change the NUMCYCLE value in the keyword dictionary.

```
>>> stand_1.set_num_cycle(0)
>>> stand_1.keywords
{'TIMEINT': 10, 'NUMCYCLE': 0, 'INVYEAR': 2010, 'SVS': 15, 'FUELOUT': 1}
```

Now that we have our simulation parameters established, we startup FVS.

>>> stand_1.run_fvs()

1.5. Tutorials 5

STANDFIRE API Reference

Contents:

fuels module

Contents:

Fysfuels

```
class fuels .Fvsfuels (variant)
     Bases: object
```

A Fvsfuels object is used to calculate component fuels at the individual tree level using the Forest Vegetation Simulator. To create an instance of this class you need two items: a keyword file (.key) and tree list file (.tre) with the same prefix as the keyword file. If you don't already have a tree list file then you can use 'fuels.Inventory' class to generate one.

Parameters variant (string) - FVS variant to be imported

Example:

A basic example to extract live canopy biomass for individual trees during year of inventory

```
>>> from standfire.fuels import Fvsfuels
>>> stand001 = Fvsfuels("iec")
>>> stand001.set_keyword("/Users/standfire/test/example.key")
TIMEINT not found in keyword file, default is 10 years
>>> stand001.keywords
{'TIMEINT': 10, 'NUMCYCLE': 10, 'INVYEAR': 2010, 'SVS': 15, 'FUELOUT': 1}
```

The keyword file is setup to simulate 100 years at a time interval of 10 years. Lets change this to only simulate the inventory year.

```
>>> stand001.set_num_cycles(0)
>>> stand001.keywords
{'TIMEINT': 10, 'NUMCYCLE': 0, 'INVYEAR': 2010, 'SVS': 15, 'FUELOUT': 1}
>>> stand001.run_fvs()
```

Now we can write the trees data frame to disk

```
>>> stand001.save_trees_by_year(2010)
```

Note: The argument must match one of the available variant in the PyFVS module. Search through stand-fire/pyfvs/ to see all variants

get_simulation_years()

Returns a list of the simulated years

Returns simulated year

Return type list of integers

get_snags (year)

Returns pandas data fram of the snags by indexed year

Parameters year(int) – simulation year of the data frame to return

Returns data frame of snags at indexed year

Return type pandas dataframe

Note: If a data frame for the specified year does not exist then a message will be printed to the console.

get_standid()

Returns stand ID as defined in the keyword file of the class instance

Returns stand ID value

Return type string

get_trees (year)

Returns pandas data fram of the trees by indexed year

Parameters year (int) – simulation year of the data frame to return

Returns data frame of trees at indexed year

Return type pandas dataframe

Note: If a data frame for the specified year does not exist then a message will be printed to the console.

run_fvs()

Runs the FVS simulation

This method run a FVS simulation using the previously specified keyword file. The simulation will be paused at each time interval and the trees and snag data collected and appended to the fuels attribute of the Fvsfuels object.

Example:

```
>>> from standfire.fuels import Fvsfuels
>>> stand010 = Fvsfuels("iec")
>>> stand010.set_keyword("/Users/standfire/example/test.key")
>>> stand010.run_fvs()
>>> stand010.fuels["trees"][2010]
xloc yloc species dbh ht
                                crd cratio crownwt0 crownwt1 ...
33.49 108.58 PIPO 19.43 68.31 8.77 25 33.46
                                                       4.3
24.3 90.4 PIPO
                   11.46 56.6 5.63
                                        15
                                              6.55
                                                       2.33
88.84 162.98 PIPO
                   18.63 67.76 9.48
                                              75.88
```

```
save all()
```

Writes all data frame in the fuels attribute of the class to the specified working directory. Output file are .csv.

```
save_snags_by_year (year)
```

Writes snag data frame at indexed year to .csv in working directory

```
save_trees_by_year (year)
```

Writes tree data frame at indexed year to .csv in working directory

```
set dir(wdir)
```

Sets the working directory of a Fysfuels object

This method is called by Fvsfuels.set_keyword(). Thus, the default working directory is the folder containing the specified keyword file. If you wish to store simulation outputs in a different directory then use this methods to do so.

Parameters wdir (string) – path/to/desired_directory

Example

```
>>> from standfire.fuel import Fvsfuels
>>> test = Fvsfuels("emc")
>>> test.set_keyword("/Users/standfire/test/example.key")
```

Whoops, I would like to store simulation outputs elsewhere...

```
>>> test.set_dir("/Users/standfire/outputs/")
```

```
set_inv_year (inv_year)
```

Sets inventory year for FVS simulation

Parameters inv_year (int) – year of the inventory

```
set_keyword(keyfile)
```

Sets the keyword file to be used in the FVS simulation

Date 2015-8-12

Authors Lucas Wells

This method will initalize a FVS simulation by registering the specified keyword file (.key) with FVS. The working directory of a Fvsfuels object will be set to the folder containing the keyword file. You can manually change the working directory with Fvsfuels.set_dir(). This function will also call private methods in this class to extract information from the keyword file and set class fields accordingly for use in other methods.

Parameters keyfile (string) – path/to/keyword_file. This must have a .key extension

Example:

```
>>> from standfire.fuels import Fvsfuels
>>> test = Fvsfuels("iec")
>>> test.set_keyword("/Users/standfire/test/example.key")
```

set_num_cycles (num_cyc)

Sets number of cycles for FVS simulation

Parameters num_cyc (int) – number of simulation cycles

set_time_int(time_int)

Sets time interval for FVS simulation

Parameters time_int (int) - length of simulation time step

2.1. fuels module 9

Inventory

class fuels. Inventory

Bases: object

This class contains methods for converting inventory data to FVS .tre format

This class currently does not read inventory data from an FVS access database. The FVS_TreeInit database first needs to be exported as comma delimited values. Multiple stands can be exported in the same file, the formatFvsTreeFile() function will format a .tre string for each stand. All column headings must be default headings and unaltered during export. You can view the default format by importing this class and typing FMT. See the FVS guide ¹ for more information regarding the format of .tre files.

Example:

```
>>> from standfire import fuels
>>> toDotTree = fuels.Inventory()
>>> toDotTree.read_inventory("path/to/FVS_TreeInit.csv")
>>> toDotTree.format_fvs_tree_file()
>>> toDotTree.save()
```

References

convert_sp_codes (method='2to4')

Converts species codes from 4 letter codes to 2 letter codes or vise versa

Parameters method (string) – must be either "2to4" or "4to2"

```
crwratio_percent_to_code()
```

Converts crown ratio from percent to ICR code

ICR code is described in the Essential FVS Guide on pages 58 and 59. This method should only be used if crown ratios values are percentages in the FVS_TreeInit.csv. If you use this method before calling formatFvsTreeFile() then you must set the optional argument cratioToCode to False.

```
filter_by_stand(stand_list)
```

Filters data by a list of stand IDs

Parameters stand_list (python list) - List of stand ID to retain in the data. All other stands will be removed

```
format_fvs_tree_file (cratio_to_code=True)
```

Converts data in FVS_TreeInit.csv to FVS .tre format

This methods reads entries in the pandas data frame (self.data) and writes them to a formated text string following FVS .tre data formating standards shown in FMT. If multiple stands exist in self.data then each stand will written as a (key,value) pair in self.fvsTreeFile where the key is the stand ID and the value is the formated text string.

```
Parameters cratio_to_code (boolean) - default = True
```

Note: If the <code>crwratio_percent_to_code()</code> methods has been called prior to call this methods, then the <code>cratio_to_code</code> optional argument must be set to <code>False</code> to prevent errors in crown ratio values.

Example:

¹ Gary E. Dixon, Essential FVS: A User's Guide to the Forest Vegetation Simulator Tech. Rep., U.S. Department of Agriculture, Forest Service, Forest Management Service Center, Fort Collins, Colo, USA, 2003.

```
>>> toDotTree.format_fvs_tree_file()
>>> toDotTree.fvsTreeFile['Stand_ID_1']
   1 5
            OPP 189
                      65
                                 3
                                                   0 0
   2 15
5
            OPP 110
                       52
                                 2
                                                   0 0
5
   3
      5
            OPP 180
                       64
                                 5
                                                   0 0
5
   4
      14
            OPP 112
                       56
                                 3
                                                   0 0
5
   5
            OPP 167
      6
                       60
                                 4
                                                   0 0
5
   6
      5
            OPP 190
                       60
                                 5
                                                   0 0
5
   7
      7
            OPP 161
                       62
                                 3
                                                   0 0
5
  8 86
                       37
                                                   0 0
            OPP 46
                                 1
5
  9 10
                       50
                                 2
            OPP 130
                                                   0 0
5
  10 5
            OPP 182
                       60
                                 3
                                                   0 0
5
  11 8
            9PP 144
                       50
                                                   0 0
6
  1 16
            OPP 107
                       42
                                 4
                                                   0 0
6
   2 109
            OPP 41
                       27
                                 2
                                                   0 0
```

get_fvs_cols()

Get list of FVS standard columns

Returns FVS standard columns

Return type list of strings

get_stands()

Returns unique stand IDs

Returns stand IDs

Return type list of strings

Example:

```
>>> toDotTree.get_stands()
['BR', 'TM', 'SW', HB']
```

print_format_standards()

Print FVS formating standards

The FVS formating standard for .tre files as described in the Essenital FVS Guide is stored in FMT as a class attribute. This method is for viewing this format. The keys of the dictionary are the column headings and values are as follows: 0 = variable name, 1 = variable type, 2 = column location, 3 = units, and 4 = implied decimal place.

Example:

```
>>> toDotTree.print_format_standards()
{'Plot_ID'
              : ['ITRE',
                                'integer', [0,3],
                                                      None,
                                                                 None],
 'Tree_ID'
                : ['IDTREE2',
                                 'integer', [4,6],
                                                      None,
                                                                 None],
                                            [7,12], None,
                                 'integer',
 'Tree_Count'
                : ['PROB',
                                                                 None],
                                 'integer', [13,13], 'trees',
 'History'
                : ['ITH',
                                                                 0 1,
                                                                 None],
 'Species'
                : ['ISP',
                                 'alphanum', [14,16], None,
 'DBH'
                                 'real', [17,20], 'inches',
                                                                1 ],
                : ['DBH',
 'DG'
                                 'real',
                                            [21,23], 'inches', 1
                : ['DG',
                                                                   ],
 'Ht'
                : ['HT',
                                'real',
                                            [24,26], 'feet',
                                                                 0
                                                                   ],
 'HtTopK'
                : ['THT',
                                'real',
                                            [27,29], 'feet',
                                                                 0
                                                                   ],
                                            [30,33], 'feet',
 'HTG'
                 : ['HTG',
                                 'real',
                                                                 1 ],
                                            [34,34], None,
 'CrRatio'
                 : ['ICR',
                                 'integer',
                                                                 Nonel,
 'Damage1'
                 : ['IDCD(1)',
                                 'integer',
                                            [35,36], None,
                                                                 None],
                                 'integer',
 'Severity1'
                 : ['IDCD(2)',
                                             [37,38], None,
                                                                 Nonel,
                                 'integer',
 'Damage2'
                 : ['IDCD(3)',
                                             [39,40], None,
                                                                 None],
```

2.1. fuels module

```
'Severity2' : ['IDCD(4)', 'integer', [41,42], None, None],
'Damage3' : ['IDCD(5)', 'integer', [43,44], None, None],
'Severity3' : ['IDCD(6)', 'integer', [45,46], None, None],
'TreeValue' : ['IMC', 'integer', [47,47], None, None],
'Prescription' : ['IPRSC', 'integer', [48,48], None, None],
'Slope' : ['IPVARS(1)', 'integer', [49,50], 'percent', None],
'Aspect' : ['IPVARS(2)', 'integer', [51,53], 'code', None],
'PV_Code' : ['IPVARS(3)', 'integer', [54,56], 'code', None],
'TopoCode' : ['IPVARS(4)', 'integer', [57,59], 'code', None],
'SitePrep' : ['IPVARS(5)', 'integer', [58,58], 'code', None],
'Age' : ['ABIRTH', 'real', [59,61], 'years', 0 ]}
```

See page 61 and 62 in the Essential FVS Guide.

read_inventory(fname)

Reads a .csv file containing tree records.

The csv must be in the correct format as described in FMT. This method check the format of the file by calling a private method _is_correct_format() that raises a value error.

Parameters fname (string) – path to and file name of the Fvs_TreeInit.csv file

Example:

```
>>> from standfire import fuels
>>> toDotTree = fuels.Inventory()
>>> toDotTree.readInventory("path/to/FVS_TreeInit.csv")
>>> np.mean(toDotTree.data['DBH'])
9.0028318584070828
```

The read_inventory() method stores the data in a pandas data frame. There are countless operations that can be performed on these objects. For example, we can explore the relationship between diameter and height by fitting a linear model

```
>>> import statsmodels.formula.api as sm
>>> fit = sm.ols(formula="HT ~ DBH", data=test.data).fit()
>>> print fit.params
Intercept 19.688167
DBH
         2.161420
dtype: float64
>>> print fit.summary()
OLS Regression Results
______
                         Ht R-squared:
Dep. Variable:
                                                      0.738
                                                     0.736
              OLS Adj. R-squared:
Least Squares F-statistic:
Model:
Method:
                                                      351.8
              Tue, 07 Jul 2015 Prob (F-statistic):
Date:
                                                   3.77e-38
                    08:32:02 Log-Likelihood:
                                                     -407.10
No. Observations:
                         127
                             AIC:
                                                       818.2
                         125
                             BIC:
                                                       823.9
Df Residuals:
Df Model:
                          1
                nonrobust
Covariance Type:
______
coef std err t P>|t| [95.0% Conf. Int.]
______

      19.6882
      1.205
      16.338
      0.000
      17.303
      22.073

      2.1614
      0.115
      18.757
      0.000
      1.933
      2.389

______
                       2.658 Durbin-Watson:
                                                       0.995
                    0.265 Jarque-Bera (JB):
Prob(Omnibus):
```

Skew:	-0.251	Prob(JB):	0.347
Kurtosis:	3.385	Cond. No.	23.8
=======================================			

Read more about pandas at http://pandas.pydata.org/

save (outputPath)

Writes formated fvs tree files to specified location

If multiple stands exist in the FVS_TreeInit then the same number of files will be created in the specified directory. The file names will be the same as the Stand_ID with a .tre extension.

Parameters outputPath (string) – directory to store output .tre files

Note: This method will throw an error if it is called prior to the format_fvs_tree_file() method.

```
set_FVS_variant(var)
```

Sets FVS variant. This is need if converting from USDA plant symbols (PSME) to alpha codes (DF). If so, then all stand you wish to process must be of the same FVS variant

Parameters var (string) – FVS variant ('iec', 'emc' ...)

intervene module

The intervene module is a collection of treatment algorithms

Contents:

SpaceCrowns

```
class intervene.SpaceCrowns (trees)
    Bases: intervene.BaseSilv
```

Variables crown_space – instance variable for crown spacing; initial value = 0

```
add_to_treatment_collection (treatment, ID)
```

Adds treatment to static class attribute in intervene.BaseSilv()

```
clear_treatment_collection()
```

Deletes all treatment currently in the treatment collection class attribute

```
get distance(tree a, tree b)
```

Calculate the distance between two trees

Uses Pythagoras' theorem to calculate distance between two tree crowns in units of input data frame

Parameters

- **tree_a** (*int*) indexed row of tree a in Pandas data frame
- **tree_b** (*int*) indexed row of tree b in Pandas data frame

Returns distance between two crowns in units of input data frame

Return type float

```
get_extent()
```

Returns bounding box of tree coordinates

Returns [min_x, min_y, max_x, max_y]

2.2. intervene module 13

Return type list of floats

Examples

```
>>> from standfire.intervene import SpaceCrowns
>>> space = SpaceCrowns("/Users/standfire/test_trees.csv")
>>> bbox = space.get_extent()
>>> bbox
[1.3, 3.5, 63.1, 61.4]
```

get_treatment_options()

Returns dictionary of treatment options

Returns treatment option codes and description

Return type dictionary

get_trees()

Returns the trees data frame of the object

Returns trees data frame

Return type Pandas.DataFrame

```
set_crown_space (crown_space)
```

Sets spacing between crowns for the treatment

Parameters crown_space (float) - crown spacing in units of input data frame

```
set_extent (min_x, min_y, max_x, max_y)
```

Sets extent instance variable

Parameters

- min_x (float) minimum x coordinate
- min_y (float) minimum y coordinate
- max_x (float) maximum x coordinate
- max_y (float) maximum y coordinate

Note: set_extent is automatically called by BaseSilv() constructor

treat()

Treatment algorithm for removing trees based on input crown spacing

Todo

Optimize algorithm by incorporating search_rad.

Todo

split this function into 3

treatment_collection = {}

CHAPTER 3

Indices and tables

- genindex
- modindex
- search

Python Module Index

```
f
fuels,7
i
intervene,13
```

18 Python Module Index

A	S			
add_to_treatment_collection() (intervene.SpaceCrowns method), 13	save() (fuels.Inventory method), 13 save_all() (fuels.Fvsfuels method), 8			
C	save_snags_by_year() (fuels.Fvsfuels method), 9 save_trees_by_year() (fuels.Fvsfuels method), 9			
clear_treatment_collection() (intervene.SpaceCrowns method), 13 convert_sp_codes() (fuels.Inventory method), 10 crwratio_percent_to_code() (fuels.Inventory method), 10	set_crown_space() (intervene.SpaceCrowns method), 14 set_dir() (fuels.Fvsfuels method), 9 set_extent() (intervene.SpaceCrowns method), 14 set_FVS_variant() (fuels.Inventory method), 13			
F	set_inv_year() (fuels.Fvsfuels method), 9 set_keyword() (fuels.Fvsfuels method), 9			
filter_by_stand() (fuels.Inventory method), 10 format_fvs_tree_file() (fuels.Inventory method), 10 fuels (module), 7	set_num_cycles() (fuels.Fvsfuels method), 9 set_time_int() (fuels.Fvsfuels method), 9 SpaceCrowns (class in intervene), 13			
Fysfuels (class in fuels), 7	Т			
get_distance() (intervene.SpaceCrowns method), 13 get_extent() (intervene.SpaceCrowns method), 13 get_fvs_cols() (fuels.Inventory method), 11 get_simulation_years() (fuels.Fvsfuels method), 8 get_snags() (fuels.Fvsfuels method), 8 get_standid() (fuels.Fvsfuels method), 8 get_stands() (fuels.Inventory method), 11 get_treatment_options() (intervene.SpaceCrowns method), 14 get_trees() (fuels.Fvsfuels method), 8 get_trees() (intervene.SpaceCrowns method), 14	treat() (intervene.SpaceCrowns method), 14 treatment_collection (intervene.SpaceCrowns attribute), 14			
intervene (module), 13				
Inventory (class in fuels), 10				
P				
print_format_standards() (fuels.Inventory method), 11				
R				
read_inventory() (fuels.Inventory method), 12 run_fvs() (fuels.Fysfuels method), 8				