Contents

Basic Information

Contents	1
Recent Updates:	
)verview:	4
Installation:	6
IEPMC3:	8
Input:	9
PPMJET:	17
Output	19
Class Diagram	21
File Descriptions	22

Recent Updates:

Vxxx (Oct. 24, 2025) The Phi and K*0 are added in starlight+dpmjet output and their decay daughter are removed (dpmjet/dpmjetint.f). Proper switch (on/off) are added in slight.in.dpmjet to implement this. A proper boost is also applied to Phi and K*0 inside src/starlightdpmjet.cpp from particle CMS frame to DPMJET lab frame(in default case, inside dpmjet boost is only giving to stable particle).

vxxx (Nov. 13, 2024) Removed warning that ω -> $\pi^+\pi^-\pi^0$ is unstable, since it seems OK.

vxxx (Nov. 10, 2023) Added Option for photoproduction of phi + direct KK, just like rho + direct pipi. This is particle type 933. The phi:direct KK ratio default is the same as for the rho + direct pipi

v328 - Implemented the HEPMC3 standard for two-photon interactions and coherent photonuclear interactions with INTERFERENCE turned off and 0n0n breakup modes. Made changes to the parameterization of the normalization constant for the default nuclear density distribution (2-parameter Fermi Model) in STARlight.

v327 - Updated CMAkeLists.tx and cmake_modules/FindDMJet.cmake with versions from Luan Arbeletche that accommodate the new version of DPMJET. Updated documentation to point to that version. n. b. There may still be a problem with running DPMJet, but this is much closer

v326 - Updated the Documentations to reflect recent changes.

v325 - Moved the repository from HEPForge to GIT. Hosted remotely on GitHub. Created a README.md and an AGPL LICENSE file for the repository.

GIT

v320 - Added channel: $\phi \rightarrow e^+e^-$. with code (333011) - Nov 9 2022

v319 - updated the nuclear model for oxygen to the three parameter Fermi Model. Updated the code for Eta cut application to work correctly in assymetric collisions. Added PT_CUT and Eta_Cut functionalities for the FOURPRONG, ZOVERZ03, F2, F2Prime,and AXION Channels. Fixed the errors and bugs in the output of ω -> $\pi^+\pi^-\pi^0$ Channel - Eta cuts are now applied only to the charged pions and not on the uncharged pion. Fixed the bug causing incomplete output EVENTS

- in the FOURPRONG and Omega3pion channel. Fixed other bugs and potential bugs. Created copy constructors to fix warnings on new gcc compilers.
- v317 remove register keyword from randomgenerator.cpp for compatibility with C++17
- ${\rm v316}$ -added destructors for randomnumbergenerator and paramterbase, for LHCb
- v315: added documentation for PRINTVM=2 command and a note about the last line of slight.in not working.
- v313: Found a bug in channel: ω -> $\pi^+\pi^-\pi^0$. Reconstructed ω mass is about 0.4% too high. While debugging, resolved an unrelated error. Marked ω -> $\pi^+\pi^-\pi^0$ as UNSTABLE in this document.
- v311: (UNSTABLE) Added channel: ω -> $\pi^+\pi^-\pi^0$ with code (223211111).
- v309: Added channels: ρ^0 -> e^+e^- and ρ^0 -> $\mu^+\mu^-$ with codes(113011) and (113013) respectively.
- v308: Added an option to display a header in the output file. This header will show input parameters in a similar format to eSTARlight. Option is controlled by input parameter "OUTPUT HEADER", see below.
- v307: Fixed 4-prong mass spectrum, properly converting dsigma/ds to dsigma/dW. The net effect is to scale the mass spectrum by $1/M \{4\pi\}$, reducing the number of high-mass states.
- v306: Updated gammavm.cpp, to properly output 4 pions with net charge 0. Also changed default Wmax for 4-prong final state to be the larger of the kinematic limit or 10 GeV; previously, it was unduly large for the LHC.
- v305: Changed coefficient in calculation of pt2 in gammavm.cpp from 8 to 32. This changes the maximum p_T for vector mesons for calculations without interference from about 250 MeV/c to about 1 Gev/c. In the long run, we could rename INT_PT_MAX and make it required parameter with or without interference. This could make the running a bit more efficient.
- v304: Fixed a bug in gammaaluminosity.cpp lines 404, where photonDensity was called with its arguments reversed. This bug affected the p T spectrum when interference is turned on.
- v299: Added hard-coded Woods-Saxon radii, thickness and density for 96 Ru and 96 Zr, for the RHIC isobar run. Data is from arXiv:1607.04697
- v297: Changed normalized for Woods-Saxon density for non-predefined (i. e. not gold, lead, xenon or copper or nuclei with Z<7) so that the density is properly normalized $\inf d^3r \ rho(r) = A$. The normalization was previously done for a hard-sphere nucleus, so this over-estimated the cross-sections by 5-10%.

v295: Added hard-coded values for xenon-129 to match the recent LHC run. Radius= $5.36~\mathrm{fm}$, density=0.18406

v293: Introduced shared random number generator which can be externally passed by the user. All particle constants (masses, widths, branching ratios, and spins) can now also be set by the user, but should be changed from the default values with care.

v290: Added an new BREAKUP_MODE option to generate two-photon events in peripheral collisions. BREAKUP_MODE=8 sets a fixed impact parameter range, regardless of the presence of nuclear breakup; it is intended to study two-photon production in peripheral collisions. It requires two additional otherwise optional input lines, BMIN and BMAX, to set the impact parameter range. It does not (yet?) work for photonuclear interactions.

278: Added two new optional parameters:

IMPULSE_VM Normally 0, but can be set to 1 to perform an impulse
approximation calculation (i.e. ignoring nuclear effects)

QUANTUM_GLAUBER. When set to 1, performs a quantum Glauber calculation, rather than a classical one. This leads to greatly increased rho and omega cross-sections for heavy nuclei, little effect for heavier mesons.

Also added a final state, 4432212, for J/psi -> pbar p

v276: Added two new optional parameters (BSLOPE DEFINITION and BSLOPE_VALUE) for the p_{T} spectrum ('bslope') for proton targets or incoherent production on nuclei

v275: Added $\gamma\gamma$ to axion channel as two-photon channel 88, per S. Knapen et al., arXiv:1607.07083 v273: "Baseline" version, described in arXiv:1607.03838)

Overview:

The STARlight Monte Carlo models 2-photon and photon-Pomeron interactions in ultra-peripheral heavy ion collisions. The physics approach for the photon-Pomeron interactions is described in Klein and Nystrand, Phys. Rev. C60, 014903 (1999), with the p_t spectrum (including vector meson interference) discussed in Phys. Rev. Lett. 84, 2330 (2000). The 2-photon interactions are described in Baltz, Gorbunov, Klein, Nystrand, Phys.Rev. C80 044902 (2009).

STARlight has several input files, all of which are expected to be in the same directory as the starlight code. User-specified input

parameters are read from a file named "slight.in"; these parameters are described below in $\underline{\text{Input}}$. Note that STARlight ignores the last line of slight.in, so it should be something irrelevant.

The simulated events are written to an ASCII file named "slight.out", which is described below in Output.

Installation:

GitHub Based Installation:

As of present, STARlight has been moved from HEPforge to GitHub. The detailed installation instructions for the latest version on GitHub can be found in the READMe.md file via this link https://github.com/STARlightsim/STARlight/blob/main/README.md. Please note that instructions on enabling either PYTHIA or DPMJET is still the same for both HEPforge and GitHub, so consult this material for those portions of the installation instructions.

Hepforge Based Installation:

The portion below may not be relevant anymore. This is because STARlight has been moved from HEPforge to GitHub with all its history. So you can easily find any previous version you might be interested in, in the GitHub repository. The HEPforge version is no longer maintained nor updated, and though the HEPforge repository has not yet been closed, this installation process cannot be guaranteed to work properly any longer.

To install & run STARlight in a *nix based environment, follow these steps(README):

Download the starlight package from 'Downloads' on the left sidebar of the homepage. The version in the example might be outdated.

-wget 'https://starlight.hepforge.org/downloads?f=starlight r300.tar'

-mv 'downloads?f=starlight_r300.tar' starlight_r300.tar

-tar xvf starlight r300.tar

Alternatively, one may obtain the latest version via svn. HEPforge uses phabricator and no longer allows for anonymous checkouts of the repository. (Please read https://www.hepforge.org/guide.pdf .)

To obtain an account, register here: https://www.hepforge.org/register

Once you are registered, login: https://phab.hepforge.org/auth/start/?next=%2F

Set up a version control settings (VCS) password under your account's Settings->AUTHENTICATION->VCS password . The VCS password is needed to checkout the code.

(For remote users) To identify yourself, upload a SSH public key under account's Settings->AUTHENTICATION->SSH Public Keys with the button SSH Key Actions->Upload Public Key. This key will provide your identity when checking out the code as VCS. If you do not have a public ssh key to

upload, you may generate a pair on the same SSH Public Keys page with the button SSH Key Actions-> Generate Keypair.

With the private ssh key loaded on your machine (and public on their machine), use svn to checkout the trunk/:
-svn co svn+ssh://vcs@phab.hepforge.org/source/starlightsvn/trunk

Change to the installation directory of your choice
-mkdir /home/my/installation/dir
-cd /home/my/installation/dir
Setup the compilation with cmake
-cmake /path/to/trunk
Compile with (g)make
-gmake
Setup the input file, slight.in, for your simluation needs
-cp /path/to/trunk/config/slight.in .
-vim slight.in

-vim slight.in
Run
-./starlight >& output.txt&

For more information and special scenarios, such as running with PYTHIA

If you would like to browse the code, please visit: https://phab.hepforge.org/source/starlightsvn/

or DPMJET, consult the README files located in trunk/

----Before HEPForge updated their repository management system---To obtain the latest version:
-svn co http://starlight.hepforge.org/svn/trunk

Alternatively:

- -Visit https://starlight.hepforge.org/trac/browser
- -Download the trunk [click on the download symbol in the Size column]
- -Unpackage the zip file. The trunk/ represents <PathToSource>

To build Starlight:

- First create your build directory <BUILDDIR> (e.g. mkdir bin)
- \$ cd <BUILDDIR>
- \$ cmake <PathToSource>
- \$ make

This creates an executable file, starlight, in the build directory.

To clean the build:

- \$ make clean

To run starlight, a configuration file, slight.in, is needed. Examples of slight.in may be found in the config/ directory.

To run:

\$./starlight

Enabling Pythia:

To simulate the η , η' , and η_c channels, you need Pythia v8.2 or higher to handle their decays. To enable Pythia support you need to run cmake with the option -DENABLE_PYTHIA=ON and have \$PYTHIADIR pointing to the top directory of Pythia8. [Note: when building Pythia, be sure to enable shared libraries(.so). ./configure --enable-shared before compiling Pythia.]

- \$ setenv PYTHIADIR /my/local/pythia8
- \$ cmake <PathToSource> -DENABLE PYTHIA=ON

Note: v8.2+ is necessary since the Pythia directory structure changed[trunk/cmake_modules/FindPythia8.cmake depends on the structure layout], libhapdfdummy was removed, and Standalone:allowResDec was removed.

To enable DPMJET, please see the passage on DPMJET

HEPMC3:

The HEPMC3 standard is the latest standard for writing event records or output files in high energy physics event generators. STARlight has implemented this new standard by interfacing with the CERN HEPMC3 module. But it is important to note the following as there are situations where STARlight reverts to the old output standard.

The HEPMC3 standard is implemented for both two-photon and photonuclear interactions. But in photonuclear interactions, it is not implemented for incoherent interaction, neither is it implemented for coherent interactions when INTERFERENCE is turned on. So in these cases, STARlight reverts to the old output standard.

The HEPMC3 standard has only been implemented for the breakup-mode where there is no coulomb or hadronic breakup. This is BREAKUP_MODE = 4, 0n0n. In all other breakup modes, STARlight reverts to the old standard.

How to turn-on the HEPMC3 feature.

When the HEPMC3 feature is turned off (the default situation), STARlight's output follows the old standard and is written out to the slight.out file. To turn on the HEPMC3 feature, the CERN HEPMC3 module needs to be installed and linked to STARlight, when

STARlight's code is being compiled. With this successfully done, STARlight provides two outputs, the slight.hepmc file (in hepmc3 format) and the slight.out file (in the old STARlight format).

An extended version of the old STARlight output that contains the momenta and energy of the outgoing beams, as an addition to those of the outgoing final state particles, can also be accessed (with/without installing the CERN HEPMC3 module) in the slight.out file, by setting the HEPMC3_EXTENDED_OUTPUT parameter to 1 in the input slight.in file.

The instructions on how to install the CERN HEPMC3 module, link to STARlight and compile STARlight with the HEPMC3 option enabled is well described in HEPMC3 Output section of the Github README.md file at https://github.com/STARlightsim/STARlight/blob/main/README.md.

Input:

The input parameters are listed below with typical values for LHC Pb-Pb running given in parentheses. Optional parameters are denoted with \star

baseFileName	# The name of the output files. STARlight will copy the input slight.in to baseFileName.in, and produce output files baseFileName.txt and baseFileName.out. (slight)
BEAM_1_Z = 82 BEAM_1_A = 208 BEAM_2_Z = 82 BEAM_2_A = 208 BEAM_1_GAMMA = 1470	# Charge of beam one projectile. (82) # Atomic number of beam one projectile. (208) # Charge of beam two projectile. (82) # Atomic number of beam two projectile. (208)
BEAM_2_GAMMA = 1470.0	,
W_MAX = 12.0	# Maximum value for the gamma-gamma center of mass energy, W = $4E_1E_2$, in GeV. Setting W_MAX = -1 tells STARlight to use the default value specified in inputParameters.cpp (recommended for single meson production). For single mesons, the default W_MAX is the particle mass plus five times the width. For lepton pairs, the default W_MAX is given by $2\hbar c \sqrt{\frac{\gamma_1 \gamma_2}{R_1 R_2}}$. These are defined in
W_MIN = -1	src/inputParameters.cpp (-1) #Min value of w. Minimum value for the gamma-gamma center of mass energy, $W = 4E_1E_2$, in GeV. Setting $W_MIN = -1$ tells STARlight to use the default

W N BINS = 40

 $RAP_MAX = 8.$ RAP N BINS = 80

CUT PT* = 0

 $PT_MIN* = 1.0$

PT MAX* = 3.0

 $CUT_ETA* = 0$

ETA MIN* = -10

ETA MAX* = 10

PROD MODE = 2

value specified in inputParameters.cpp (recommended for single meson production). The default W_MIN is the larger of the kinematic limit ($e.g.~2m_\pi$ for ρ decays) or the particle mass minus five times the width. (-1)

#Bins w maximum and minimum values for w (the gamma-gamma center of mass energy, w = $4E_1E_2$), and the number of w bins in the lookup tables (40)

Maximum rapidity of produced particle. (8)

Number of rapidity bins used in the cross section calculation (80)

Specifies whether the user chooses to place restrictions on the transverse momentum of the decay products. 0= no, 1= yes. (0)

If a transverse momentum cut is applied, this specifies the minimum value produced, in GeV/c. (1.0)

If a transverse momentum cut is applied, this specifies the maximum value produced, in GeV/c. (3.0)

Specifies whether the user chooses to place restrictions on the pseudorapidity of the decay products. 0= no, 1 = yes. (0). PLEASE NOTE that in the ω -> $\pi^+\pi^-\pi^0$ channel Eta cuts are not applied to the uncharged pion. It is only applied to the 2 charged pions.

If a pseudorapidity cut is applied, this
specifies the minimum value produced. (-10)
If a pseudorapidity cut is applied, this
specifies the maximum value produced. (10)

#PROD_MODE=1: Two-photon interaction.

PROD_MODE=2: Coherent photonuclear vector meson production assuming narrow resonances. This option should also be used for exclusive vector meson production in pp collision. In pA or pp collisions, this option means that the proton emits the photon and that the gamma-A interaction is coherent.

PROD_MODE=3: Coherent photonuclear vector meson
production assuming wide resonances. This option
should in be used for exclusive \$\rho^0\$
production.

PROD_MODE=4: Incoherent photonuclear vector meson production. In pA collisions, this option means that the nucleus emits the photon. Do not use for pp.

PROD_MODE=5: Photonuclear one photon exchange
uses DPMJET single.

PROD_MODE=6: Photonuclear two photon exchange
(both nuclei excited) uses DPMJET double.

PROD_MODE=7: Photonuclearsinglepa uses DPMJET
Single, proton mode.

PROD_MODE=8: [not supported/verified] Photonuclear
singlepapy uses Pythia 6

#Number of events produced (1000) N EVENTS = 10# For PROD\ MODE 1 through 4, this selects the PROD PID = 443013channel to be produced, in PDG notation. Currently supported options are list below. (443013) RND SEED = 34533# Seed for random number generator. (34533) BREAKUP MODE = 5 # Specifies the way nuclear break-up is handled. This option only works for lead or gold. It has no meaning in proton-proton or proton-nucleus collisions 1 = hard sphere nuclei (no hadronic break-up if impact parameter is greater than the sum of nuclear radii, no restriction on Coulomb breakup). 2 = requires Coulomb break-up of both nuclei, with no restriction on the number of neutrons emitted by either nucleus (XnXn). 3 = requires Coulomb break-up of both nuclei, but requires that a single neutron is emitted from each nucleus (1n1n). 4 = requires Coulomb break-up of neither nucleus. (0n0n) 5 = requires that there be no hadronic break up, no restriction on Coulomb break-up (This is similar to option 1, but with the actual hadronic interaction probability). 6 = requires Coulomb break up of one or both nuclei, with no restriction on the number of neutrons emitted (XnXn + 0nXn + Xn0n). 7 = requires Coulomb break up of only one nucleus, with no restriction on the number of neutrons emitted (0nXn+ Xn0n). 8 = selectable input parameter range (i.e. for peripheral collisions, not UPCs) regardless of nuclear breakup. Fixed input range between BMAX and BMIN (set by two otherwise optional cards, below) INTERFERENCE = 0# Specifies whether interference based on the ambiguity of which nucleus emits the photon is included. The effect of this interference is only visible at very small transverse momentum. 0 = interference off, 1 = interference on. (0) IF STRENGTH = 1. # If interference is turned on, specifies the percentage of interference. The range is -1.0 -1.0.; 1 is the standard value for ion-ion collisions, while -1.0 is expected for protonantiproton collisions. (1) INT PT MAX = 0.24# Used only when the interference option above is turned on. This specifies the maximum transverse momentum considered, in GeV/c. (0.24) # Used only when the interference option above is INT PT N BINS = 120turned on. This specifies the number of bins in

transverse momentum to use. (120)

INT_PT_WIDTH = 0	#Used only when the interference option above is turned on. This specifies the width of bins in			
XSEC_METHOD* = 0	transverse momentum to use. (0) #Determines which method is used to calculate the cross-section for γ cross-sections. XSEC_METHOD=0 is faster, but works only for symmetric collisions (i.e. with identical nuclei). XSEC_METHOD=1			
BSLOPE_DEFINITION*=0	always works, but is slower. (0) Used for proton and nucleon (i. e. incoherent nuclear) collisions to set the t-spectrum, dN/dt=exp(-bt). When BSLOPE_DEFINITION=1, then the slope is determined by BSLOPE_VALUE (below). When BSLOPE_DEFINITION=2, the slope is calculated as a function of γp center of mass energy per the H1 analysis, Eur. Phys. J. C46, 585 (2006): b=4.63/GeV ² + $4\alpha ln (W_{\gamma p}/90 \text{ GeV})$ The default value, BSLOPE_DEFINITION=0 has no effect. Note that this affects the t-slope only; it does			
BSLOPE VALUE*	not affect the total cross-section WHEN BSLOPE DEFINITION=1, this determines the			
-	exponential slope for dN/dt=exp(-BSLOPE_VALUE*t)			
SELECT_IMPULSE_VM	When set =1, performs an impulse approximation calculation (this ignores most nuclear physics, including shadowing). Default=0; no change			
QUANTUM_GLAUBER	When set =1, perform a quantum Glauber calculation, rather than classical, which is the default (or when set =0)			
BMIN	Needed for Breakup_mode=8. Sets the minimum impact			
BMAX	parameter Needed for Breakup mode=8. Sets sthe maximum			
OUTPUT_HEADER	impact parameter. Adds a header to the output file. This header will contain various input parameters. (1 for header, 0			
for no header, default is no header) KEEP_PHI= 0				
stable particles and removed from output,	<pre>1 = K*0 is store in output along with other its decay daughters are 0 = K*0 is not store in cay daughter which are</pre>			

The physics constants used by STARlight can be set with the following parameters:

stable kept in output (default case of dpmjet).

Used in starlight + dpmjet production

```
deuteron slope parameter (effective temperature)
deuteronSlopePar
                          [(GeV/c)^-2]
                        mass of the proton [GeV/c^2]
protonMass
                       mass of the pi^+/- [GeV/c^2]
pionChargedMass
pionNeutralMass
                        mass of the pi^0 [GeV/c^2]
kaonChargedMass
                       mass of the K^+/- [GeV/c^2]
                        mass of the e^+/- [GeV/c^2]
mel
                     mass of the mu^+/- [GeV/c^2] mass of the tau^+/- [GeV/c^2] mass of the f_0(980) [GeV/c^2] width of the f_0(980) [GeV/c^2] branching ratio f_0(980) -> pi^+ pi^- and pi^0
muonMass
tauMass
f0Mass
f0Width
f0BrPiPi
pi^0
                      mass of the eta [GeV/c^2] width of the eta [GeV/c^2]
etaMass
etaWidth
                        mass of the eta' [GeV/c^2]
etaPrimeMass
                     width of the eta' [GeV/c^2]
etaPrimeWidth
etaCMass
                         mass of the eta c [GeV/c^2]
etaCWidth
                        width of the eta c [GeV/c^2]
f2Mass
                        mass of the f 2(1270) [GeV/c<sup>2</sup>]
                      width of the f_2(1270) [GeV/c^2] [GeV/c] f_2(1270) -> pi^+ pi^- mass of the a_2(1320) [GeV/c^2]
f2Width
f2BrPiPi
a2Mass
a2Width
                       width of the a_2(1320) [GeV/c<sup>2</sup>]
                       mass of the f' 2(1525) [GeV/c^2]
f2PrimeMass
                         width of the f' 2(1525) [GeV/c<sup>2</sup>]
f2PrimeWidth
                         branching ratio f' 2(1525) \rightarrow K^+ K^- and K^0
f2PrimeBrKK
zoverz03Mass
                          mass of four-quark resonance (rho^0 pair
                          production) [GeV/c^2]
f0PartialggWidth
                         partial width f 0(980) \rightarrow g g [GeV/c^2]
etaPartialqqWidth partial width eta -> g g [GeV/c^2]
etaPrimePartialggWidth partial width eta' -> g g [GeV/c^2]
etaCPartialggWidth partial width eta c -> g g [GeV/c^2]
                        partial width f 2(1270) \rightarrow g g [GeV/c^2]
f2PartialggWidth
                        partial width a_2(1320) \rightarrow g g [GeV/c^2]
a2PartialggWidth
f2PrimePartialggWidth partial width f' 2(1525) -> g g [GeV/c^2]
zoverz03PartialggWidth partial width four-quark resonance -> g g (rho^0
                         pair production) [GeV/c^2]
f0Spin
                         spin of the f 0(980)
                         spin of the eta
etaSpin
etaPrimeSpin
                        spin of the eta'
                         spin of the eta c
etaCSpin
                        spin of the f 2(1270)
f2Spin
                      spin of the a_2(1320)
spin of the f'_2(1525)
spin of the four-quark resonance -> g g (rho^0
a2Spin
f2PrimeSpin
zoverz03Spin
                        pair production)
axionSpin
                        spin of the axion
                       mass of the rho^0 [GeV/c^2]
rho0Mass
                       width of the rho^0 [GeV/c^2]
branching ratio rho^0 -> pi^+ pi^-
rho0Width
rhoOBrPiPi
                       mass of the rho'^0 (4 pi^+/^- final state)
rho0PrimeMass
                          [GeV/c^2]
```

mass of the omega $[GeV/c^2]$ OmegaMass OmegaWidth width of the omega $[GeV/c^2]$ OmegaBrPiPi branching ratio omega -> pi^+ pi^mass of the phi [GeV/c^2] PhiMass PhiWidth width of the phi $[GeV/c^2]$ branching ratio phi -> K^+ K^-PhiBrKK mass of the J/psi [GeV/c^2] JpsiMass JpsiWidth width of the J/psi [GeV/c^2] JpsiBree branching ratio J/psi -> e^+ e^-JpsiBrmumu branching ratio J/psi -> mu^+ mu^branching ratio J/psi -> p pbar
mass of the psi(2S) [GeV/c^2] JpsiBrppbar Psi2SMass Psi2SWidth width of the psi(2S) $[GeV/c^2]$ branching ratio psi(2S) -> e^+ e^-Psi2SBree branching ratio psi(2S) -> e^+ e^branching ratio psi(2S) -> mu^+ mu^mass of the Upsilon(1S) [GeV/c^2]
width of the Upsilon(1S) [GeV/c^2]
branching ratio Upsilon(1S) -> e^+ e^branching ratio Upsilon(1S) -> mu^+ mu^mass of the Upsilon(2S) [GeV/c^2] Psi2SBrmumu Upsilon1SMass Upsilon1SWidth Upsilon1SBree Upsilon1SBrmumu Upsilon2SMass width of the Upsilon(2S) [GeV/c^2] Upsilon2SWidth branching ratio Upsilon(2S) -> e^+ e^-Upsilon2SBree branching ratio Upsilon(2S) -> mu^+ mu^-Upsilon2SBrmumu mass of the Upsilon(3S) $[GeV/c^2]$ Upsilon3SMass Upsilon3SWidth width of the Upsilon(3S) [GeV/c^2] Upsilon3SBree branching ratio Upsilon(3S) -> e^+ e^-Upsilon3SBrmumu branching ratio Upsilon(3S) -> mu^+ mu^-The following parameters are used only when interfacing with the PYTHIA and/or DPMJET interfaces: #Allows the user to set the minimum photon energy MIN GAMMA ENERGY = 6(in GeV) in the rest frame of the target nucleus. The default is 6.0 GeV and it should never be set below this value since DPMJET was not designed to handle low energy interactions. MAX GAMMA ENERGY = 600000 #Allows the user to set the maximum photon energy (in GeV) in the rest frame of the target nucleus. The default is 60000.0 GeV. PYTHIA PARAMS = "" **#Used** to supply input parameters to the PYTHIA interface. This takes a string to pass on semicolon separated parameters to PYTHIA 6. eg: "mstj(1)=0; paru(13)=0.1" (the default is a blank string " ") PYTHIA FULL EVENT RECORD = 1 #Determines whether the full event record from PYTHIA is written to slight.out. true = yes,

width of the rho'^0 (4 pi^+/- final state)

branching ratio rho'^0 -> pi^+ pi^-

[GeV/c^2]

rho0PrimeWidth

rho0PrimeBrPiPi

false = no (false). The additional information
added is as follows: daughter production vertex (x
[mm], y [mm], z [mm], t [mm/c]), mother1, mother2,

daughter1, daughter2, PYTHIA particle status code. PYTHA 8 Particle Properties page describes in more detail the properties of mother, daughter, and status code designations.

PRINT VM=2

This command will make STARlight print out a table of y and W_{gamma-p}, kdN_gamma/dk and sigma(gamma-A) for the two possible photon directions. PRINT_VM=0, the assumed default, will not produce this ouptput.

Channels of Interest:

2-Photon Channels

Currently supported 2-photon (prod. mode = 1) channel options:

jetset 1a	particle	
 221	eta	
331	eta-prime	
441	eta-c	
9010221	f0(975)	
225	f2(1270)	
115	a2(1320)	
335	f2(1525)	
33	rho0 pair	
11	e+/e- pair	
13	mu+/mu- pair	
15	tau+/tau- pair	
88	axion-like particle	(ALP)

Process 88 refers to the single production of a hypothetical axion-like particle (ALP), which decays to a pair of photons. The ALP mass has to be specified by the user through the parameter AXION_MASS. The narrow width approximation is assumed here, with a fixed axion decay constant of \Lambda=1 TeV. (See equation (1) of arXiv:1607.06083 for the appropriate conventions.) The cross section can be then rescaled to arbitrary \Lambda, as long as the narrow width approximation remains valid.

Pomeron-Photon Channels

jetset id

Currently supported vector meson (prod. mode = 2/3/4) options:

 113	rho0
113011	rho0> e+e-
113013	rho0> mu+mu-
223	omega
223211111	omega> pi+pi-pi0
333	phi
933	phi direct KK
333011	phi> e+e-
443011	J/psi> e+e-
443013	J/Psi> mu+mu-
4432212	J/psi> proton antiproton
444011	Psi(2S)> e+e-

particle

```
444013
            Psi(2S) --> mu+mu-
            Upsilon(1S) --> e+e-
553011
553013
            Upsilon(1S) --> mu+mu-
554011
            Upsilon(2S) --> e+e-
554013
            Upsilon(2S) --> mu+mu-
            Upsilon(3S) --> e+e-
555011
            Upsilon(3S) --> mu+mu-
555013
            {\tt rho0} + {\tt direct} {\tt pi+pi-} (with interference). The {\tt direct}
913
            pi+pi- fraction is from the ZEUS results, EPJ C2 p247
            (1998)
999
            four-prong final states (rho'-like to pi+pi-pi+pi-)
```

DPMJET:

Simulation of photonuclear interactions with STARlight is possible through an interface with DPMJet. These interfaces can be enabled through options passed to cmake during the configuration process. [Depreciated: Using Pythia 6 as a substitute for DPMJet]

The gfortran compiler is required to use the photonuclear interfaces.

The DPMJet package can be obtained by contacting the authors as explained here: http://sroesler.web.cern.ch/sroesler/dpmjet3.html

Once you have the code proceed with these steps:

Change the line containing the OPT variable in the DPMJet Makefile:

OPT = -c -C -std=legacy -O -O3 -g -fexpensive-optimizations -funroll-loops -fno-automatic -fbounds-check -v -fPIC

```
----- 64-bit -----
```

Make sure that all -m32 options are removed from the Makefile.

Unfortunately, the DPMJet package depends on a floating point exception trap implementation, and only a 32-bit version of that is included in the package, which needs to be replaced. An example implementation can be found here:

http://www.arsc.edu/arsc/support/news/hpcnews/hpcnews376/

Under "Fortran Floating Point Traps for Linux" there is a code example. A file based on this, fpe.c, can be found in the external/ directory in STARlight. Move that to your DPMJet directory to replace the original file and run:

```
$ gcc -o fpe.o fpe.c
```

Note: if the above command returns the following error: /usr/lib/../lib64/crt1.o: In function `_start': (.text+0x20): undefined reference to `main' /tmp/ccs2CQsd.o: In function `enable_exceptions_': fpe.c:(.text+0xe): undefined reference to `feenableexcept'

```
collect2: error: ld returned 1 exit status
     Try: gcc fpe.c -Wall -g -c
           feenableexcept is a gcc extension and gcc may need all of the
     headers present.
                 ----- End 64-bit -----
     Then in the DPMJet directory run:
           $ make
     Note: When compiling at RCAS(BNL), needed to change q77 \rightarrow
gfortran, needed to install fluka and setenv FLUPRO /path/to/fluka, and
modify phojet before compiling. The changes for phojet is at line 29875,
from:
         PRINT LO, 'PHO DIFSLP: ERROR: this option is not installed !'
     to:
        WRITE(LO, '(/1X, A, I2)')
       & 'PHO DIFSLP: ERROR: this option is not installed
       & !', ISWMDL(13)
----- 1.2. Compiling Starlight with DPMJet interface ------
           To enable the compilation of the DPMJet interface please
     follow these steps:
            CMake uses an environment variable $DPMJETDIR to locate the
            DPMJet object files, so define it.
           $ export DPMJETDIR=<path to dpmjet>
           Then create a build directory for STARlight
           $ mkdir <build-dir>
           and change into it
           $ cd <build-dir>
           Run CMake with the option to enable DPMJet
           $ cmake <path-to-starlight-source> -DENABLE_DPMJET=ON
           Then build it
```

Note: When compiling at RCAS(BNL), needed to add the gfortran library to the CMakeLists.txt and left it there.

\$ make

----- 1.3. Running Starlight with DPMJet interface -----

To run Starlight with the DPMJet interface a couple of files are needed in the directory where you want to run Starlight.

The files needed are:

slight.in (Starlight config file. An example suitable for DPMJet can be found in config/slight.in.dpmjet)

my.input (DPMJet config file. An example can be found in config/my.input)

dpmjet.dat (Can be found in the DPMJet source directory)

In the slight.in file the relevant production modes (PROD_MODE) for DPMJET is:

5: A+A single excitation

6: A+A double excitation

7: p+A single excitation

In addition the minimum and maximum gamma energies must be set. These must be within the interval set in the my.input file.

To run:

\$./starlight < my.input</pre>

[DPMJET reads from direct input/interactive]

Output

STARlight outputs an ASCII file named slight.out.

If OUTPUT_HEADER = 1 (set in input file), then there will be a header at the beginning of the output file followed by a list of events. If OUTPUT_HEADER = 0, or if OUTPUT_HEADER is not set, then there will be no header in the output file and the file will start with the list of events.

If there is a header, it will be three lines, with the following format:

CONFIG_OPT: prod_mod particle_id nevents q_glauber impulse seed

where prod_mod indicates if a wide or narrow resonance has been used, particle_id specifies the vector meson species (and decay channel) being produced, nevents indicates the total number of events in the simulation, q_glauber indicates if a quantum (=1) or classical (=0) Glauber has been selected, impulse indicates if the nuclear effects are being modelled (=0) or a simple impulse approx. is employed, and

finally seed records the random number seed used when initializing the Monte Carlo. The config opt line is followed by two lines with brief descriptions of beams in the collision, with the format:

BEAM 1(2): beam1(2) Z beam1(2) A beam1(2) LorentzGamma

where beam1(2)Z is the is the charge of the particles in beam 1(2), beam1(2)A indicates the atomic number of beam 1(2) and beam1(2)LorentzGamma is the Lorentz gamma factor associated to beam 1(2)

For each event, a summary line is printed, with the format

EVENT: n ntracks nvertices,

where n is the event number (starting with 1), ntracks is the number of tracks in the event, and nvertices is the number of vertices in the event (STARlight does not currently produce events with more than one vertex).

EVENT line is followed by a description of the vertex, with the format

VERTEX: x y z t nv nproc nparent ndaughters,

where x, y, z and t are the 4-vector components of the vertex location, nv is the vertex number, nproc is a number intended to represent physical process (always set to 0), nparent is the track number of parent track (0 for primary vertex) and ndaughters is the number of daughter tracks from this vertex.

This is followed by a series of lines describing each of the daughter tracks emanating from this vertex. Each track line has the format

TRACK: GPID px py nev ntr stopv PDGPID,

where GPID is the Geant particle id code, px, py and pz are the three vector components of the track's momentum, nev is the event number, ntr is the number of this track within the vertex (starting with 0), stopy is the vertex number where track ends (0 if track does not terminate within the event), and PDGPID is the Monte Carlo particle ID code endorsed by the Particle Data Group.

Class Diagram inputParameters inputParser inputrarser + inputrarser() + ~ inputrarser() + parseFile() + parseString() + addIntParameter() + addVintParameter() + addSouParameter() + addBoolParameter() + addSoolParameter() + inputParameters() + ~ inputParameters() + init() + configureFromFile() + baseFileName() pythiaDecayer + beam1Z() + beam1A() + beam2Z() twoPhotonLuminosity photonNucleusLuminosity starlightLimits + twoPhotonLuminosity() + photonNucleusLuminosity() + pythiaDecayer() + nucleus() + nucleus() photonNucleusLuminosity() pythiaDecaver(+ ~ nucleus() + init() + Z() + A() + init() + beam2A() twoPhotonDifferentialLuminosity() photonNucleusDifferentialLuminosity() addParticle() + beamLorentzGamma() - addStringParameter() D2LDMDY() vmsigmapt() bessel + execute() - pythiaDecayer() - operator ==() + beam1LorentzGamma() + beam2LorentzGamma() + printParameterInfo() + validateParameters() D2LDMDY() nofe() D2LDMDY Threaded() + maxW() + addParameter() + addParameter() nuclearRadius() integral() starlightParticleCodes + nuclearRadius() + formFactor() + dipoleFormFactor() + thickness() + minW() + minW() + maxRapidity() + maxRapidity() + ptCuttnabled() + ptCuttMin() + ptCuttMin() + etaCuttMin() + etaCuttMin() + etaCuttMin() + etaCuttMin() + productionMode() + mmbEvents() + productionMode() + randomSeed() + randomSeed() + beamBreakupMode() + interferenceStrepth() + minW() pythiaStarlight + jetsetToGeant() - pythiaStarlight() - init() starlightConstants getPythia() starlightStandalone + starlightStandalone() starlightStandalone() photonNucleusCrossSection incoherentPhotonNucleusLuminosity + init() + run() + baseFileName() + configFileName() + eventDataFileName() + setBaseFileName() 5' setConfigFileName() + setEventDataFileName(+ boostEvent() photonNucleusCrossSection() + incoherentPhotonNucleusLuminosity() beamBeamSystem beamBeamSystem() + beamBeamSystem() + beamBeamSystem() + beam() + beam() + beam() + beam() + broab() + broab() + cmsBoost() + init() - generateBreakupProbabilities() - probabilityOfHadronBreakup() - probabilityOfHadronBreakup() ~ photonNucleusCrossSection(+ ~ incoherentPhotonNucleusLuminosity() - incoherentPhotonNucleusDifferentialLuminosity() slopeParameter() + beam() + ~ beam() + photonFlux() + rapidity() getChannelMass() getBNORM() luminosity() wideResonanceCrossSection getbbs() + wideResonanceCrossSection() + ~ wideResonanceCrossSection() + crossSectionCalculation() + interferenceStrength() vmPhotonCoupling() + bbs setBeamLorentzGamma() + maxPtInterference() getDefaultC() + nmbPtBinsInterference() + ptBinWidthInterference() + coherentProduct maxPhotonEnergy() crossSectionCalculation() + crossSectionC + getcsgA() + photonFlux() + sigmagp() + sigma_A() + sigma_N() + breitWigner() + nepoint() incoherentVMCrossSection + incoherentFactor() + incoherentVMCrossSection() + minGammaEnergy() - maxGammaEnergy() ~ incoherentVMCrossSection() + pythiaParams() + bbs + crossSectionCalculation() + pythiaFullEventRecord() + xsecCalcMethod() + starlight + pythia-full-Ventikecord() + xsecCalc-Method() + prodParticleType() + prodParticleDecayType() + interactionType() + protonEnergy() + setBaseFileName() + setBeam1Z() + setBeam1Z() + setBeam2Z() + setBeam2A() + setBeam2A() + setBeam2A() + setBeam1LorentzGamma() + setBeam1LorentzGamma() + setBeam2LorentzGamma() + setMaxW() + setMinW() + setMinW() + setMaxRapidity() + setMaxRapidity() + setMaxRapidity() + setMaxRapidity() starlight narrowResonanceCrossSection + starlight() + narrowResonanceCrossSection() + starlight() + ~ starlight() + rotal () + produceEvent() + baseFileName() + nmbAtempts() + nmbAccepted() + setInputParameters() - luminosityTableIsValid() - createEventChannel() + ~ narrowResonanceCrossSection() + crossSectionCalculation() starlightPythia randomGenerator + starlightPythia() + starlightPythia() + ~ starlightPythia() + init() + produceEvent() + produceEvent() + produceEvent() + setSingleMode() + setDoubleMode() + setMinGammaEngray() fileWriter eventFileWriter + fileWriter() +_randy + eventFileWriter() + eventFileWriter() + writeEvent() + writeFullPythiaInfo() ~ fileWriter() eventChannel + eventChannel() readLuminosity eventChannel(nmbAttempts() + readLuminosity() + ~ readLuminosity() setMinGammaEnergy() nmbAccepted() setMaxGammaEnergy() + setNmbRapidityBins() + setPtCutEnabled() 0..1 + setFullEventRecord() + read() +_inputParameter starlightPythia() + setPtCutMin() starlightPythia() spectrumProtonNucleus + setPtCutMax() + setEtaCutEnabled() + spectrumProtonNucleus() operator ==() + setEtaCutMin() getNucleonNucleonSigma() setEtaCutMax() starlightDpmJet generateBreakupProbabilities() setProductionMode() # getSigma() + setNmbEvents() + starlightDpmJet() setProdParticleId() + init() + Gammagammasingle() + Cammagammasingle() + Cammagammasingle() + singleCrossSection() + produceEvent() - prickw() - pickw() - parentMomentum() - pp1() produceEvent() + setRandomSeed() + setBamBreakupMode() + setInterferenceEnabled() + setInterferenceEnrapt() + setMaxPitnterference() + setMaxPitnterference() + setPtBinWidthInterference() + setCoherentProduction() + setMaxGammaEnergy() + setMaxGammaEnergy() + setPythiaParams() + setPythiaParams() + setPythiaPullEventRecord() + setXsecCall Method() produceSingleEvent() produceDoubleEvent() produceEvent() setSingleMode() setDoubleMode() starlightParticle lorentzVector + starlightParticle() + lorentzVector() setMinGammaEnergy() + pTgamma() setMaxGammaEnergy() + ~ lorentzVector() + lorentzVector() vmpt() · vmpt() · twoBodyDecay() · fourBodyDecay() + setProtonMode() - starlightDpmJet() ~ starlightParticle() pp1() picky() + setPdgCode() + getPdgCode() + SetXYZT() pp2() + SetPxPyPzE() twoBodyDecay() pp_1() getMass() + GetPx() + GetPy() setCharge() getMass() pp_2() getWidth() getCharge() setFirstParent() twoBodyDecay() getWidth() + getTheta() + GetPz() getSpin() thetalep() + getSpin() setLastParent() + GetE() + setProdParticleType() tauDecay() + getDaughterMass() getFirstParent() operator +=() + setProdParticleDecayType() + setInteractionType() + setProtonEnergy() + setParameter() getMass() + pseudoRapidity() getLastParent() setFirstDaughter() getFirstDaughter() setLastDaughter() + operator -=() + M2() getWidth() + M2() + M() + BoostVector() + Boost() + operator <<() + setLastDaughter() + getLastDaughter() + setStatus() + getStatus() + setVertex() + getVertex() + print() + write() validate : bool + parameterValueKey() parameter nBodyPhaseSpaceGen + parameter() vector3 + vector3() + vector3() + vector3() + vector3() + cetVector() + SetVector() + SetVector() + operator =() + operator :=() operator =() parameterbase upcEvent value() + upcEvent() validationkey() toString() + upcEvent() + operator <<() ~ upcEvent() addParticle() Gammaaincoherentym Gammaar Gammaawidevm addVertex() + setRequired() + validationkey() addGamma() + Gammaaincoherentym() + Gammaanarrowym() + Gammaawidevm() + addGamma() + getParticles() + getVertices() + getGammaEne + operator =() + operator +() + boost() parameterlist + operator <<(- parameter() Gammaaincoherentvm() + operator +=(+ operator -=() + X() + Y() + Z() + Mag2() + Mag() + parameterlist() + add() + validationKey() + operator <<()

File Descriptions

Readme.pdf

[This file.] provides information on the installation, operation, and construction of STARlight.

CMakeLists.txt

controls STARlight compilation. For details, please see above in Installation. This is the default/supported compilation method.

Makefile

A sample Makefile for compilation on *nix systems. This file is not actively supported. Please use CMake.

starlightconfig.h.in

passes on some compiler settings; such as enabling the Pythia/DPMJet sections within the source code.

starlightDoxyfile.conf

Doxygen configuration file.

CMake Modules:

FindPythia8.cmake

used by CMake to find the Pythia 8 files needed to compile STARlight with Pythia 8 dependent options enabled. It searches for: Pythia.h, Index.xml, libpythia8

FindPythia6.cmake

used by CMake to find the Pythia 6 files needed to compile STARlight with Pythia 6 dependent options enabled. It searches for: libPythia6. Pythia 6 functionality has been deprecated.

FindDPMJet.cmake

used by CMake to find the DPMJET files needed to compile STARlight with DPMJET dependent options enabled. It searches for: dpmjet3.0-5.0, pythia6115dpm3v1.0, and phojet1.12-35c4.0

FindROOT.cmake

used by CMake to find the ROOT files needed to compile STARlight with ROOT dependent options enabled. It searches for: root-config. root-config is then used to set the rest of the paths/options needed to enable ROOT within STARlight.

CommonMacros.cmake

A collection of useful cmake macos.

FindLHAPDF.cmake

used by CMake to find the LHAPDF dependent options enabled. This was necessary for older versions of Pythia8, but this is no longer the case. However, this file is being kept in the

distribution for users that would like to re-enable it. It searches for: Pythia.h and libhhapdfdummy

Config files:

my.input

A sample DPMJET configuration file.

slight.in

A sample STARlight input file, to select the desired final state and associated options. The section <u>Input</u> has more information.

slight.in.dpmjet

A sample slight.in file to use the DPMJET options (eg: PROD_MODE = 5, 6, 7, and MIN_GAMMA_ENERGY, and MAX_GAMMA_ENERGY. and KEEP PHI = 0,1 and KEEP KSTAR = 0,1).

slight.in.ee rhic

A sample slight.in file for e+e- production by Au-Au at top RHIC energies

slight.in.jpsi_lhc

A sample slight.in file for \mbox{J}/ψ production by Pb-Pb at the LHC.

slight.in.pPb_lhc

A sample slight.in file for \mbox{J}/ψ production by p-Pb at the LHC.

slight.in.rho rhic

A sample slight.in file for ρ production by Au-Au at top RHIC energies.

dpmjet:

dpmjetint.f

This is a DPMJET library, used in the CMakeLists.txt file to link when enabling DPMJET.

external:

fpe.c

corrects for the floating point trap differences between 32 and 64-bit. The $\underline{\text{DPMJET section}}$ has more information.

pythia6:

pythiainterface.h

interfaces Pythia6 with STARlight. Pythia 6 functionality has been deprecated.

utils:

Ana.C

This macro runs Analyze.cxx, which takes as input an ASCII STARlight output file, slight.out, and creates a standard set of histograms, which are stored in histograms.root

Analyze.cxx

This macro reads in a starlight output file and creates histograms of the p_T and rapidity of the daughters, as well as the p_T, rapidity and mass of the parent. It assumes there are only 2 daughter tracks that are electrons, muons, or pions. The histograms for the daughter particles are called fPt2, fPt2, fRap1, and fRap2. Parent histograms are created for each possible daughter species (e.g., parent p_T histograms are created with the names fPtE1, fPtMu, and fPtPi), but only the ones corresponding to the actual daughter particle are filled. The histograms are saved in a file called histograms.root.

To use this Analyze.cxx, modify the file Ana.C to call your input file (as downloaded, it calls slight.out) and the number of events you wish to process (as downloaded, it processes 20 events). Then open root and type ".x Ana.C".

Analyze.h

The header file for Analyze.cxx and Ana.C.

AnalyzeTree.cxx

This macro reads the starlight.root file produced by ConvertStarlightAsciiToTree.C, which contains TLorentzVectors for the parents and a TClonesArray of TLorentzVectors for the daughters. It creates histograms of the p_T and rapidity of the daughters, as well as the p_T, rapidity and mass of the parent. While the parents may have been created as the vector sum of any number of daughter particles, this macro currently produces histograms for only the first two daughter particles. The daughter histograms are called D1Pt, D2Pt, D1Rapidity, and D1Rapidity. Parent histograms are named ParentPt, ParentRapidity, and ParentMass. The histograms are stored in starlight histos.root.

To use Analyzetree.cxx, first run
ConvertStarlightAsciiToTree.C to produce the starlight.root
file. If needed, modify the file AnalyzeTree.h to call your
input file (as downloaded, it calls starlight.root). Then
open root and type .x AnaTree.C.

AnalyzeTree.h

The header file for AnalyzeTree.cxx.

AnaTree.C

compiles and runs AnalyzeTree.cxx, which takes as input the starlight.root file produced by ConvertStarlightAsciiToTree.cxx output histograms are stored in starlight histos.root

ConvertStarlightAsciiToTree.C

reads a starlight output file (default name slight.out) and creates a root file with TLorentzVectors for the parent and a TClonesArray of TLorentzVectors for the daughter particles. The output is stored in a root file (default name starlight.root) with one branch labeled "parent" and the other labeled "daughters". Any number of daughter tracks can be accommodated. Daughter species currently accommodated are: electrons, muons, charged or neutral pions, charged or neutral kaons, and protons.

To use AnaTree.C, open root and then type .x ConvertStarlightAsciiToTree.C("inputfilename", "outputfilename") The root file produced can be examined in a root TBrowser.

A macro to read this root file and make some standard plots is also provided. This macro is called AnalyzeTree.cxx; it can be compiled and run with the AnaTree.C macro by opening root and typing .x AnaTree.C()

Source Files:

beam.cpp

generates the beam class, which inherits from the nucleus class (cf. nucleus.cpp). The object represents an accelerated nucleus, or a beam.

Functions:

beam::beam
beam::~beam

beambeamsystem.cpp

represents the colliding system of interest.

Functions:

beamBeamSystem::beamBeamSystem
beamBeamSystem::rbeamBeamSystem
beamBeamSystem::probabilityOfBreakup

beamBeamSystem::generateBreakupProbabilities
beamBeamSystem::probabilityOfHadronBreakup
beamBeamSystem::probabilityOfPhotonBreakup

bessel.cpp

calculate modified Bessel functions of the first and second ${\tt kind.}$

Functions:

bessel::besI0
bessel::dbesk0
bessel::dbesk1
bessel::besI1

eventchannel.cpp

inherits from readLuminosity. It is a base for class for functions to produce events that is overloaded by other classes (Gammagammaleptonpair, Gammagammasingle, Gammaavectormeson, starlightDpmJet, and starlightPythia).

Functions:

eventfilewriter.cpp

writes event information in the output file.

Functions:

eventFileWriter::eventFileWriter
eventFileWriter::~eventFileWriter
eventFileWriter::writeEvent

filewriter.cpp

The base class for eventFileWriter, which is writes event information in the output file.

Functions:

fileWriter::fileWriter()
fileWriter::~fileWriter()
fileWriter::open
fileWriter::open(filename)
fileWriter::close

gammaaluminosity.cpp

contains the photonNucleusLuminosity class, which inherits from photonNucleusCrossSection. It calculates the differential cross-section for gamma-A interactions.

Functions:

photonNucleusLuminosity::photonNucleusLuminosity
photonNucleusLuminosity::~photonNucleusLuminosity
photonNucleusLuminosity::photonNucleusDifferentialLuminosi
ty //Calculates and outputs the differential luminosity
photonNucleusLuminosity::pttablegen // Calculates the pt
spectra for VM production with interference per S. Klein
and J. Nystrand, Phys. Rev Lett. 84, 2330 (2000).
photonNucleusLuminosity::vmsigmapt //calculates the effect
of the nuclear form factor on the pt spectrum, for use in
interference calculations. It calculates the cross section
suppression SIGMAPT(PT) as a function of pt. The input pt
values come from pttable.inc
photonNucleusLuminosity::nofe //calculates the 'photon
density'd^2N gamma/db^2

gammaavm.cpp

is responsible for classes Gammaavectormeson, Gammaanarrowvm, and Gammaawidevm. Both Gammaanarrowvm and Gammaawidevm inherit from Gammaavectormeson, which inherits from eventChannel. The classes are responsible for generating and

decaying the vector mesons produced by photon-nucleus interactions.

Functions:

```
Gammaavectormeson::Gammaavectormeson
Gammaavectormeson::~Gammaavectormeson
Gammaavectormeson::pickwy //responsible for selecting the
events center of mass energy and rapidity
Gammaavectormeson::twoBodyDecay // This routine decays a
particle into two particles of mass mdec, taking spin into
account
Gammaavectormeson::fourBodyDecay // decays a particle into
four particles with isotropic angular distribution
Gammaavectormeson::getDaughterMass //returns the daughter
particles mass, & the final particles id...
Gammaavectormeson::getTheta //This depends on the decay
angular distribution
Gammaavectormeson::getWidth
Gammaavectormeson::getMass
Gammaavectormeson::getSpin //it's a VM, returns 1
Gammaavectormeson::momenta // calculates momentum and
energy of vector meson given W and Y, without
interference.
Gammaavectormeson::pTgamma //finds the photon pT
Gammaavectormeson::vmpt // calculates momentum and energy
of a vector meson given W and Y, including interference.
It gets the pt distribution from a lookup table.
produceEvent
pseudorapidity
Gammaanarrowvm::Gammaanarrowvm
Gammaanarrowvm::~Gammaanarrowvm
Gammaanarrowvm::gammaaincoherentvm
Gammaawidevm::Gammaawidevm
Gammaawidevm::~Gammaawidevm
```

gammagammaleptonpair.cpp

inherits from eventChannel. It calculates the lepton pair's cross-section and generates and decayes the lepton pairs.

Functions:

```
Gammagammaleptonpair::Gammagammaleptonpair
Gammagammaleptonpair::~Gammagammaleptonpair
Gammagammaleptonpair::twoLeptonCrossSection // calculates
section for 2-particle decay, per, see STAR Note 243, Eq.
9. It calculates the 2-lepton differential cross section
Gammagammaleptonpair::twoMuonCrossSection // gives the
two muon cross section as a function of Y&W, per G.Soff
et. al Nuclear Equation of State, part B, 579
Gammagammaleptonpair::pickw // Picks a w for the 2- photon
calculation.
Gammagammaleptonpair::picky // Picks a y given a W
Gammagammaleptonpair::pairMomentum // calculates
px,py,pz,and E given w and y
Gammagammaleptonpair::pp 1
                             // For beam 1, returns a
random momentum drawn from pp_1(E) distribution
Gammagammaleptonpair::pp 2 // For beam 2, returns a
random momentum drawn from from pp 2(E) distribution
```

```
Gammagammaleptonpair::twoBodyDecay //decays a particle
into two particles of mass mdec, taking spin into account
Gammagammaleptonpair::thetalep // calculates the cross-
section as a function of angle for a given W and Y, for
the production of two muons or taus, per Brodsky et al.
PRD 1971, 1532 equation 5.7
Gammagammaleptonpair::produceEvent //returns the vector
with the decay particles inside
Gammagammaleptonpair::calculateTable //calculates the
tables that are used elsewhere in the Monte Carlo the tau
decay follows V-A theory, 1 - 1/3 cos(theta) the energy of
each of the two leptons in tau decay is calculated using
formula 10.35 in "Introduction to elementary particles by
D. Griffiths," which assumes that the mass of the electron
is 0. The maximum electron energy in in such a system is
0.5 * mass of the tau
Gammagammaleptonpair::tauDecay
                                // assumes that the
tauons decay to electrons and calculates the directons of
the decays
Gammagammaleptonpair::getMass
Gammagammaleptonpair::getWidth
Gammagammaleptonpair::getSpin
```

gammagammasingle.cpp

inherits from eventChannel. It calculates the cross-section for single mesons and generates and decays the single mesons from gamma-gamma interactions. It also generates single mesons which are then decayed by Pythia 8.

Functions:

```
Gammagammasingle::Gammagammasingle
Gammagammasingle::~Gammagammasingle
Gammagammasingle::singleCrossSection // calculates the
cross-section in the narrow-width approximation, per STAR
Note 243, Eq. 8
Gammagammasingle::pickw // picks a w for the 2-photon
calculation.
Gammagammasingle::picky
Gammagammasingle::parentMomentum // calculates
px,py,pz,and E given w and y
Gammagammasingle::pp 1
                       // For beam 1, returns a random
momentum drawn from from pp(E) distribution
Gammagammasingle::pp 2
                       // For beam 2, returns a random
momentum drawn from from pp(E) distribution
Gammagammasingle::twoBodyDecay //decays a particle into
two particles of mass mdec, taking spin into account
Gammagammasingle::produceEvent
Gammagammasingle::getMass
Gammagammasingle::getSpin
```

incoherentPhotonNucleusLuminosity.cpp

is responsible for the incoherentPhotonNucleusLuminosity class and inherits from photonNucleusCrossSection. It houses the differential luminosity calculation for incoherent gamma-A interactions.

Functions:

```
incoherentPhotonNucleusLuminosity::incoherentPhotonNucleus
Luminosity
```

incoherentPhotonNucleusLuminosity::~incoherentPhotonNucleu
sLuminosity

incoherentPhotonNucleusLuminosity::incoherentPhotonNucleus
DifferentialLuminosity

incoherentPhotonNucleusLuminosity::nofe //Function for the
calculation of the "photon density".

incoherentVMCrossSection.cpp

inherits from photonNucleusCrossSection. It calculates the cross-section for incoherent photon-nucleus interactions.

Functions:

incoherentVMCrossSection::incoherentVMCrossSection incoherentVMCrossSection::~incoherentVMCrossSection incoherentVMCrossSection::crossSectionCalculation // calculates the vector meson cross section assuming a narrow resonance. For reference, see STAR Note 386.

inputParameters.cpp

sets and stores STARlight's input parameters.

Functions:

inputParameters::inputParameters
inputParameters::~inputParameters

inputParameters::init

inputParameters::configureFromFile

inputParameters::print
inputParameters::write

inputParameters::parameterValueKey

inputParser.cpp

parses the input files and stores the information in the inputParameters.

Functions:

inputParser::inputParser()
inputParser::~inputParser()
inputParser::parseFile
inputParser::parseString
inputParser::addIntParameter
inputParser::addVintParameter
inputParser::addFloatParameter
inputParser::addDoubleParameter
inputParser::addBoolParameter
inputParser::addStringParameter
inputParser::printParameterInfo
inputParser::validateParameters

lorentzvector.cpp

holds Lorentz 4-vectors.

Functions:

lorentzVector::lorentzVector
lorentzVector::~lorentzVector
SetXYZT

main.cpp

the "main" file/function-where the program starts.

narrowResonanceCrossSection.cpp

inherits from photonNucleusCrossSection. It calculates the cross-section for narrow resonance vector mesons.

Functions:

narrowResonanceCrossSection::narrowResonanceCrossSection narrowResonanceCrossSection::~narrowResonanceCrossSection narrowResonanceCrossSection::crossSectionCalculation // calculates the vector meson cross section assuming a narrow resonance, per STAR Note 386.

nBodyPhaseSpaceGen.cpp

is responsible for the kinematics used in the four-prong decays.

Functions:

nBodyPhaseSpaceGen::nBodyPhaseSpaceGen nBodyPhaseSpaceGen::~nBodyPhaseSpaceGen nBodyPhaseSpaceGen::setDecay // sets decay constants and prepares internal variables nBodyPhaseSpaceGen::generateDecay// generates event with certain n-body mass and momentum and returns event weight general purpose function nBodyPhaseSpaceGen::generateDecayAccepted// generates full event with certain n-body mass and momentum only, when event is accepted (return value = true) this function is more efficient, if only weighted evens are needed nBodyPhaseSpaceGen::pickMasses// randomly choses the (n -2) effective masses of the respective (i + 1)-body systems nBodyPhaseSpaceGen::calcWeight// computes event weight (= integrand value) and breakup momenta uses vector of intermediate two-body masses prepared by pickMasses() nBodyPhaseSpaceGen::calcEventKinematics// calculates complete event from the effective masses of the (i + 1)body systems, the Lorentz vector of the decaying system, and the decay angles uses the break-up momenta calculated by calcWeight() nBodyPhaseSpaceGen::estimateMaxWeight// calculates maximum weight for given n-body mass nBodyPhaseSpaceGen::print

nucleus.cpp

defines the basis properties of a nucleus such as radius, form factor, and thickness.

Functions:

nucleus::nucleus
nucleus::~nucleus
nucleus::init
nucleus::nuclearRadius

nucleus::formFactor

nucleus::dipoleFormFactor

nucleus::thickness// calculates the nuclear thickness function per Eq. 4 in Klein and Nystrand, PRC 60

photonNucleusCrossSection.cpp

calculates the cross-section for coherent photon-Nucleus interactions.

Functions:

photonNucleusCrossSection::photonNucleusCrossSection photonNucleusCrossSection::~photonNucleusCrossSection photonNucleusCrossSection::getcsgA // returns the crosssection for photon-nucleus interaction producing vector photonNucleusCrossSection::photonFlux // gives the photon flux as a function of energy Egamma for arbitrary nuclei and gamma. The first time it is called, it calculates a lookup table which is used on subsequent calls. It returns dN gamma/dE (dimensions 1/E), not dI/dE energies are in GeV, in the lab frame photonNucleusCrossSection::nepoint// gives the spectrum of virtual photons, dn/dEgamma, for a point charge q=Ze sweeping past the origin with velocity gamma, integrated over impact parameter from bmin to infinity, per Eq. 15.54 of Jacksons Classical Electrodynamics photonNucleusCrossSection::sigmagp// gives the gammaproton --> VectorMeson cross section. Wgp is the gammaproton CM energy. Unit for cross section: fm**2 photonNucleusCrossSection::sigma A// Nuclear Cross Section sig N, sigma A in (fm**2) photonNucleusCrossSection::sigma N// Nucleon Cross Section in (fm**2)photonNucleusCrossSection::breitWigner// uses simple fixed-width s-wave Breit-Wigner without coherent backgorund for rho' (PDG '08 eq. 38.56)

pythiadecayer.cpp

links Pythia 8 and STARlight, and initalizes Pythia 8.

pythiaDecayer::pythiaDecayer pythiaDecayer::~pythiaDecayer

pythiaDecaver::init

pythiaDecayer::addParticle pythiaDecayer::execute

randomgenerator.cpp

STARlight's random number generator, using the same algorithm as ROOTs TRANDOM3 class. It is based on M. Matsumoto and T. Nishimura, Mersenne Twistor: A 623-dimensionally equidistributed uniform pseudorandom number generator. For more information see

http://www.math.keio.ac.jp/~matumoto/emt.html

randomGenerator::SetSeed randomGenerator::Rndom

readinluminosity.cpp

reads in the luminosity tables from slight.txt, which is generated in the early stages of the program.

Functions:

readLuminosity::readLuminosity readLuminosity::~readLuminosity

readLuminosity::read

spectrum.cpp

sets up functions needed to make cross-section calculations for general photonuclear interactions modeled with DPMJET.

Functions:

spectrum::spectrum

spectrum::generateKsingle
spectrum::generateKdouble
spectrum::drawKsingle
spectrum::drawKdouble

spectrum::generateBreakupProbabilities

spectrum::getFnSingle
spectrum::getFnDouble

spectrum::getTransformedNofe

sprectrumprotonnucleus.cpp

sets up functions needed to make cross-section calculations for general photonuclear interactions modeled with DPMJET.

Functions:

spectrumProtonNucleus::spectrumProtonNucleus
spectrumProtonNucleus::generateBreakupProbabilities
spectrumProtonNucleus::getSigma

starlight.cpp

initializes and then produces and decays events.

Functions:

starlight::starlight
starlight::~starlight

starlight::init

starlight::produceEvent

starlight::luminosityTableIsValid
starlight::createEventChannel

starlightdpmjet.cpp

hosts the class starlightDpmJet which inherits from the eventChannel class. It includes methods to generate diffractive events with DPMJET.

Functions:

starlightDpmJet::starlightDpmJet

starlightDpmJet::init

starlightDpmJet::produceEvent

starlightDpmJet::produceSingleEvent
starlightDpmJet::produceDoubleEvent

starlightparticle.cpp

is a container to store particle information.

Functions:

starlightParticle::starlightParticle
starlightParticle::~starlightParticle

starlightparticlecodes.cpp

 ${f c}$ onverts jetset particle numbers to the corresponding GEANT code.

Functions:

starlightParticleCodes::jetsetToGeant

starlightpythia.cpp

inherits from the eventChannel class. It includes methods to calculate diffractive events with Pythia6. Pythia 6 functionality has been deprecated.

Functions:

starlightPythia::starlightPythia
starlightPythia::~starlightPythia

starlightPythia::init

starlightPythia::produceEvent

starlightStandalone.cpp

is used by Main.cpp and in turn calls methods from the starlight class.

Functions:

starlightStandalone::starlightStandalone
starlightStandalone::~starlightStandalone
starlightStandalone::init
starlightStandalone::run
starlightStandalone::boostEvent

twophotonluminosity.cpp

inherits from beamBeamSystem, and is responsible for calculating the two photon luminosity table based on W and Y.

Functions:

twoPhotonLuminosity::twoPhotonLuminosity
twoPhotonLuminosity::~twoPhotonLuminosity
twoPhotonDifferentialLuminosity
twoPhotonLuminosity::D2LDMDY
twoPhotonLuminosity::D2LDMDY_Threaded
twoPhotonLuminosity::integral
twoPhotonLuminosity::radmul
twoPhotonLuminosity::integrand
twoPhotonLuminosity::Nphoton

upcevent.cpp

stores the final event information.

Functions:

upcEvent::upcEvent
upcEvent::operator=
upcEvent::operator+
upcEvent::boost

vector3.cpp

is a container for 3D-vectors.

Functions:

vector3::vector3
vector3::~vector3
vector3::SetVector

wideResonanceCrossSection.cpp

inherits from photnNucleusCrossSection. It is responsible for calculating the cross-section of vector mesons with a wide resonance (eg. Rho).

Functions:

wideResonanceCrossSection::wideResonanceCrossSection

```
wideResonanceCrossSection::~wideResonanceCrossSection
wideResonanceCrossSection::crossSectionCalculation //
calculates the cross-section assuming a wide (Breit-Wigner)
resonance.
```

Include Files:

```
beam.h //This class includes a single beam of nucleons
            Included in files
                  beambeamsystem.h
                  twophotonluminosity.h
                  beam.cpp
                  gammaaluminosity.cpp
                  incoherentPhotonNucleusLuminosity.cpp
                  spectrumprotonnucleus.cpp
                  twophotonluminosity.cpp
            Functions
                  beam
                  ~beam
                  rapidity
                  photonFlux
                  setBeamLorentzGamma
      beambeamsystem.h //This class covers a coliding beam system
            Included in files
                  eventchannel.h
                  gammaaluminosity.h
                  gammaavm.h
                  gammagammasingle.h
                  incoherentPhotonNucleusLuminosity.h
                  photonNucleusCrossSection.h
                  starlightpythia.h
                  twophotonluminosity.h
                  beambeamsystem.cpp
                  gammaaluminosity.cpp
                  incoherentPhotonNucleusLuminosity.cpp
                  spectrum.cpp
                  spectrumprotonnucleus.cpp
                  twophotonluminosity.cpp
            Functions
                  beamBeamSystem
                  ~beamBeamSystem
                  cmsBoost
                  beamLorentzGamma
                  beam1
                  beam2
                  probabilityOfBreakup
                  init
                  generateBreakupProbabilities
                  probabilityOfHadronBreakup
                  probabilityOfPhotonBreakup
```

bessel.h

Included in files

beam.cpp

```
beambeamsystem.cpp
            bessel.cpp
            gammaaluminosity.cpp
            incoherentPhotonNucleusLuminosity.cpp
            photonNucleusCrossSection.cpp
            twophotonluminosity.cpp
      Functions
            hes TO
            dbesk0
            dbesk1
            besI1
eventchannel.h
      Included in files
            gammaavm.h
            gammagammaleptonpair.h
            gammagammasingle.h
            starlight.h
            starlightdpmjet.h
            starlightpythia.h
            eventchannel.cpp
            starlight.cpp
      Functions
            eventChannel
            ~eventChannel
            nmbAttempts ///< returns number of attempted events
            nmbAccepted ///< returns number of accepted events</pre>
            produceEvent
            transform ///< Lorentz-transforms given 4-vector</pre>
            pseudoRapidity ///< calculates pseudorapidity for
            given 3-momentum
eventfilewriter.h
      Included in files
            eventfilewriter.cpp
            main.cpp
            starlight.cpp
            starlightStandalone.cpp
      Functions
            eventFileWriter
            writeEvent /** Write an UPC event to file */
            writeFullPythiaInfo /** Set if we want to write full
            pythia information */
filewriter.h
      Included in files
            eventfilewriter.h
            eventfilewriter.cpp
            filewriter.cpp
            main.cpp
            starlight.cpp
            starlightStandalone.cpp
      Functions
            fileWriter
            ~fileWriter
            open //opens the file
```

gammaaluminosity.h

Included in files

gammaaluminosity.cpp
starlight.cpp

Functions

gammaavm.h

Included in files

gammaavm.cpp
starlight.cpp

Functions

Gammaavectormeson \sim Gammaavectormeson produceEvent pickwy momenta pTgamma vmpt twoBodyDecay fourBodyDecay getMass getWidth getTheta getSpin getDaughterMass pseudoRapidity Gammaanarrowvm ~Gammaanarrowvm Gammaawidevm ~Gammaawidevm Gammaaincoherentvm ~Gammaaincoherentvm

gammagammaleptonpair.h

Included in files

gammagammaleptonpair.cpp
starlight.cpp

Functions

Gammagammaleptonpair ~Gammagammaleptonpair twoLeptonCrossSection calculateTable produceEvent twoMuonCrossSection pickw picky pairMomentum pp_1

pp 2 twoBodyDecay thetalep tauDecay getMass getWidth getSpin gammagammasingle.h Included in files gammagammasingle.cpp starlight.cpp Functions Gammagammasingle ~Gammagammasingle singleCrossSection produceEvent pickw picky parentMomentum twoBodyDecay thephi getMass getWidth getSpin incoherentPhotonNucleusLuminosity.h Included in files incoherentPhotonNucleusLuminosity.cpp starlight.cpp **Functions** incoherentPhotonNucleusLuminosity ~incoherentPhotonNucleusLuminosity incoherentPhotonNucleusDifferentialLuminosity nofe Included in files gammaavm.cpp incoherentVMCrossSection.cpp **Functions** incoherentVMCrossSection ~incoherentVMCrossSection

incoherentVMCrossSection.h

crossSectionCalculation

inputParameters.h

Included in files

beam.h gammaaluminosity.h incoherentPhotonNucleusLuminosity.h readinluminosity.h starlightpythia.h beam.cpp beambeamsystem.cpp gammaaluminosity.cpp

incoherentPhotonNucleusLuminosity.cpp inputParameters.cpp nucleus.cpp readinluminosity.cpp starlight.cpp starlightStandalone.cpp twophotonluminosity.cpp **Functions** parameterlist add validationKey parameterbase toString operator<< parameter operator= ptr value name required setValue setName setRequired inputParameters ~inputParameters init configureFromFile baseFileName beam1Z beam1A beam2Z beam2A beamLorentzGamma beam1LorentzGamma beam2LorentzGamma ${\tt maxW}$ minW nmbWBins MaxRapidity phiSwitch kstarSwitch nmbRapidityBins ptCutEnabled ptCutMin ptCutMax etaCutEnabled etaCutMin etaCutMax productionMode nmbEvents prodParticleId randomSeed beamBreakupMode

interferenceEnabled
interferenceStrength
maxPtInterference
nmbPtBinsInterference

ptBinWidthInterference coherentProduction incoherentFactor minGammaEnergy maxGammaEnergy pythiaParams pythiaFullEventRecord xsecCalcMethod prodParticleType prodParticleDecayType interactionType protonEnergy setBaseFileName setBeam1Z setBeam1A setBeam2Z setBeam2A setBeamLorentzGamma setBeam1LorentzGamma setBeam2LorentzGamma setMaxW setMinW setNmbWBins SetMaxRapidity setphiSwitch setkstarSwitch setNmbRapidityBins setPtCutEnabled setPtCutMin setPtCutMax setEtaCutEnabled setEtaCutMin setEtaCutMax setProductionMode setNmbEvents setProdParticleId setRandomSeed setBeamBreakupMode setInterferenceEnabled setInterferenceStrength setMaxPtInterference setNmbPtBinsInterference setPtBinWidthInterference setCoherentProduction setIncoherentFactor setMinGammaEnergy setMaxGammaEnergy setPythiaParams setPythiaFullEventRecord setXsecCalcMethodsetProdParticleType setProdParticleDecayType setInteractionType setProtonEnergy setParameter print write

```
parameterValueKey
            instance
inputParser.h
      Included in files
            inputParameters.h
            inputParameters.cpp
            inputParser.cpp
      Functions
            inputParser
            inputParser
            parseFile/** Parse a file */
            parseString
            addIntParameter
            addUintParameter
            addFloatParameter
            addDoubleParameter
            addBoolParameter
            addStringParameter
            printParameterInfo
            validateParameters
            parameter
            operator==
            operator<
            printParameterInfo
            {\tt addParameter}
lorentzvector.h
      Included in files
            nBodyPhaseSpaceGen.h
            starlightparticle.h
            lorentzvector.cpp
      Functions
            lorentzVector
            ~lorentzVector
            SetXYZT
            SetPxPyPzE
            GetPx
            GetPy
            GetPz
            GetE
            operator +=
            operator -=
            M2
            BoostVector
            Boost
            operator <<
narrowResonanceCrossSection.h
      Included in files
            narrowResonanceCrossSection.cpp
            gammaavm.cpp
      Functions
```

narrowResonanceCrossSection
~narrowResonanceCrossSection

crossSectionCalculation

nBodyPhaseSpaceGen.h

Included in files

gammaavm.h

nBodyPhaseSpaceGen.cpp

Functions

Factorial

breakupMomentum

nBodyPhaseSpaceGen

~nBodyPhaseSpaceGen

setDecay

random

generateDecay

generateDecayAccepted

setMaxWeight

maxWeight

normalization

eventWeight

maxWeightObserved

resetMaxWeightObserved

estimateMaxWeight

eventAccepted

daughter

daughters

nmbOfDaughters

daughterMass

intermediateMass

 ${\tt breakupMom}$

cosTheta

phi

PIIT

print

operator <<

pickMasses

calcWeight

pickAngles

calcEventKinematics

eventAccepted

nucleus.h

Included in files

beam.h

beambeamsystem.h

twophotonluminosity.h

gammaaluminosity.h

incoherentPhotonNucleusLuminosity.cpp

nucleus.cpp

spectrumprotonnucleus.cpp

starlightdpmjet.cpp

starlightpythia.cpp

twophotonluminosity.cpp

Functions

nucleus

~nucleus

init

Ζ

```
Α
            nuclearRadius
            formFactor
            dipoleFormFactor
            thickness
            00
            rho0
            woodSaxonSkinDepth
            fritiofR0
            rws
photonNucleusCrossSection.h
      Included in files
            gammaaluminosity.h
            incoherentPhotonNucleusLuminosity.h
            incoherentVMCrossSection.h
            narrowResonanceCrossSection.h
            wideResonanceCrossSection.h
            gammaavm.cpp
            photonNucleusCrossSection.cpp
      Functions
            photonNucleusCrossSection
            ~photonNucleusCrossSection
            slopeParameter///< returns slope of t-distribution</pre>
            [(GeV/c)^{-2}]
            getChannelMass ///< returns mass of the produced</pre>
            system [GeV/c^2]
            getBNORM
            luminosity//< returns luminosity [10^{26} cm^{-2}]</pre>
            sec^{-1}]
            getbbs///< returns beamBeamSystem</pre>
            vmPhotonCoupling ///< vectormeson-photon coupling</pre>
            constant f v / 4 pi (cf. Eq. 10 in KN PRC 60 (1999)
            014903)
            getDefaultC
            maxPhotonEnergy///< returns max photon energy in lab</pre>
            frame [GeV] (for vectormesons only)
            crossSectionCalculation
            getcsgA
            photonFlux
            sigmagp
            sigma A
            sigma N
            breitWigner
            nepoint
pythiadecayer.h
      Included in files
            gammagammasingle.h
            pythiadecayer.cpp
      Functions
            pythiaDecayer
            ~pythiaDecayer
            init// Initialize
            addParticle // Add particle to current event
```

```
execute// Execute event and return starlight type
            event
            pythiaDecayer
            operator==
PythiaStarlight.h
      Included in files
            starlight.cpp
      Functions
            pythiaStarlight
            init
            getPythia
randomgenerator.h
      Included in files
            eventchannel.h
            gammaavm.h
            gammagammasingle.h
            nBodyPhaseSpaceGen.h
            inputParameters.cpp
            randomgenerator.cpp
            spectrum.cpp
      Functions
            SetSeed
            Rndom
            randomGenerator
            instance
readinluminosity.h
      Included in files
            eventchannel.h
            gammaavm.h
            gammagammaleptonpair.h
            gammagammasingle.h
            readinluminosity.cpp
      Functions
            readLuminosity
            ~readLuminosity
            read
reportingUtils.h
      Included in files
            inputParser.h
            nBodyPhaseSpaceGen.h
            beam.cpp
            beambeamsystem.cpp
            inputParameters.cpp
            main.cpp
            nucleus.cpp
            photonNucleusCrossSection.cpp
            pythiadecayer.cpp
            starlight.cpp
            starlightStandalone.cpp
      Functions
            getClassMethod___
            printErr
```

printWarn
printInfo
svnVersion
printSvnVersion
compileDir
printCompilerInfo
operator <<
progressIndicator
trueFalse
yesNo
onOff
enDisabled</pre>

spectrum.h

Included in files

spectrumprotonnucleus.h
starlightdpmjet.h
spectrum.cpp
starlightdpmjet.cpp

Functions

spectrum // Spectrum must be constructed with beambeam system, default constructor disallowed generateKsingle // Generate a table of photon energy probabilities. Use NK+1 logarithmic steps between Et min and Eg max generateKdouble // Generate a 2-D table of photon energy probabilities. Use NK+1 x NK+1 logarithmic steps between Et min and Eg max drawKsingle // Get the energy of a single gamma @return energy of the gamma drawKdouble // Get the energy of a single gamma @param egammal variable passed by reference to get the energy of the frst gamma @param egamma2 variable passed by reference to get the energy of the second gamma @return energy of the gamma setBeamBeamSystem // Set the beam beam system setMinGammaEnergy //Set the minimum gamma energy setMaxGammaEnergy / Set the maximum gamma energy setBmin //Set minimum impact parameter setBMax //Set maximum impact parameter generateBreakupProbabilities //Generate the hadron breakup probability table getSigma ---1.05? getTransformedNofe getFnSingle getFnDouble

sprectrumprotonnucleus.h

Included in files

spectrumprotonnucleus.cpp
starlightdpmjet.cpp
starlightpythia.cpp

Functions

spectrumProtonNucleus
getNucleonNucleonSigma --- 7.35?
generateBreakupProbabilities

getSigma

starlight.h

Included in files

main.cpp
starlight.cpp

starlightStandalone.cpp

Functions

starlight
~starlight
init
produceEvent
configFileName
nmbAttempts
nmbAccepted
luminosityTableIsValid

createEventChannel

starlightconstants.h

Included in files

eventchannel.h gammaavm.h gammagammasingle.h gammagammaleptonpair.h inputParameters.h nBodyPhaseSpaceGen.h photonNucleusCrossSection.h upcevent.h beam.cpp beambeamsystem.cpp gammaaluminosity.cpp gammagammaleptonpair.cpp gammagammasingle.cpp incoherentPhotonNucleusLuminosity.cpp incoherentVMCrossSection.cpp inputParameters.cpp narrowResonanceCrossSection.cpp nucleus.cpp photonNucleusCrossSection.cpp readinluminosity.cpp twophotonluminosity.cpp

Functions

N/A

starlightdpmjet.h

Included in files

starlight.cpp
starlightdpmjet.cpp

Functions

starlightDpmJet
init
produceEvent
produceSingleEvent
produceDoubleEvent
setSingleMode

wideResonanceCrossSection.cpp

setDoubleMode setMinGammaEnergy setMaxGammaEnergy setProtonMode starlightlimits.h Included in files gammagammaleptonpair.h readinluminosity.h twophotonluminosity.h **Functions** N/A starlightparticle.h Included in files pyhthiadecayer.h upcevent.h starlightparticle.cpp Functions starlightParticle ~starlightParticle setPdgCode getPdgCode setCharge getCharge setFirstParent getFirstParent setLastParent getLastParent setFirstDaughter getFirstDaughter setLastDaughter getLastDaughter getStatus setStatus setVertex getVertex starlightparticlecodes.h Included in files eventfilewriter.cpp starlightparticlescodes.cpp **Functions** jetsetToGeant//Converts a jetset code into a GEANT starlightpythia.h Included in files starlight.cpp starlightpythia.cpp Functions starlightPythia ~starlightPythia

produceSingleEvent
produceDoubleEvent

init

produceEvent setSingleMode setDoubleMode setMinGammaEnergy setMaxGammaEnergy setFullEventRecord

starlightStandalone.h

Included in files

main.cpp

starlightStandalone.cpp

Functions

starlightStandalone ~starlightStandalone init run configFileName eventDataFileName setConfigFileName setEventDataFileName

boostEvent

twophotonluminosity.h

Included in files

starlight.cpp
twophotonluminosity.cpp

Functions

upcevent.h

Included in files

eventchannel.h
filewriter.h
gammaavm.h
pythiadecayer.h
starlight.h
starlightpythia.h
starlight.cpp
upcevent.cpp

Functions

upcEvent
~upcEvent
addParticle
addVertex
addGamma
getParticles
getVertices
getGammaEnergies

```
operator=
operator+
boost
```

vector3.h

Included in files

 $\frac{\texttt{lorentzvector.h}}{\texttt{vector3.cpp}}$

Functions

vector3
~vector3
GetVector
SetVector
operator +=
operator =
operator -=
X
Y
Z
Mag2
Mag
operator <<</pre>

wideResonanceCrossSection.h

Included in files

gammaavm.cpp
wideResonanceCrossSection.cpp

Functions

wideResonanceCrossSection
~wideResonanceCrossSection
crossSectionCalculation