## **XPI Draft Specification**

Luke Dalessandro, Matthew Anderson, Maciej Brodowicz, Andrew Lumsdaine, and Thomas Sterling

Center for Research in Extreme Scale Technologies (CREST), Indiana University

December 16, 2013

**Version:** 1.0 (svn r305)

**Acknowledgement:** This material is based upon work supported by the Department of Energy under Award Number(s) [DE-SC0008809]

Disclaimer: This report was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor any agency thereof, nor any of their employees, makes any warranty, express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or any agency thereof. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or any agency thereof.

# **Contents**

1	Intr	oductio	on	2			
2	Overview and Conventions						
	2.1	Overv	view of XPI Execution	4			
	2.2	Comm	mon Terms	4			
	2.3	Interfa	ace Specification	5			
		2.3.1	XPI Interface Definitions				
		2.3.2	Action Specifications	7			
		2.3.3	Handle Type Specification				
3	Mis	Miscellaneous					
	3.1	Error 1	Handling	9			
	3.2		lization and Shutdown				
	3.3	High-l	-Level Interface Routines	10			
	3.4		n Management				
		3.4.1	C Actions				
		3.4.2	Fortran Actions				
4	Parc	Parcels 12					
	4.1	Parcel	l Generation	13			
	4.2		t Field Accessors				
	4.3		nuation Stack Management				
	4.4		ing a Parcel				
	4.5		y				
	4.6	11,	nced				
5	Glo	bal Ado	dress Space	20			
_	5.1		ess Space Properties				
		5.1.1	Atomicity				
		5.1.2	Alignment				
		5.1.3	Endianness				
	5.2		re Parcel Interface				
	5.3		tion-based Interface				
	J.0	5.3.1	Asynchronous Functions				
		5.3.2	Synchronous Functions				
	5.4		ess Space Representation				
			Address Arithmetic				

6	Thr	Threads 3							
	6.1	Actions	34						
		6.1.1 Builtin Actions	3.						
		6.1.2 Static Actions	3						
		6.1.3 Dynamic Actions	3						
		6.1.4 LCO Actions	30						
	6.2	Instantiation	30						
	6.3	Continuing	3						
	6.4	Thread Scheduling	3						
	6.5	Thread Suspension	3						
	6.6	Thread Resources	3						
	0.0	Tilleau Resources	3:						
7	Loca	al Control Objects	4						
	7.1	Properties	40						
		7.1.1 Strictly Serializable	40						
		7.1.2 Wait Free	40						
		7.1.3 Local Synchronous Memory	4						
		7.1.4 Polymorphic Actions	4						
		7.1.5 Predicates	4						
	7.2	Common Interface	4						
	7.2	Builtin LCOs	4						
	7.3	7.3.1 Future	4						
			4						
	<b>7</b> 4	7.3.2 Reduction							
	7.4	User LCOs	4						
		7.4.1 C Specification	4						
		7.4.2 Fortran Specification	50						
8	Proc	Processes							
	8.1	Instantiation & Destruction	5						
	8.2	Termination Detection	56						
	8.3	Key-Value Store	5'						
	8.4	Main Process	59						
	8.5	Hierarchy Inspection	59						
	8.6	<b>y</b> 1	6						
	0.0	Memory Management							
		8.6.1 Allocation & Distribution	6						
		8.6.2 Global Virtual Memory Mapping	6						
		8.6.3 Standard Library	64						
Αŗ	pen	dices	6						
A	χрі	Declarations	6'						
В	XPI	XPI Error Codes							
C	Exa	Examples							

# Chapter 1

# Introduction

XPI (eXtreme Parallex Interface) is a programming interface for parallel applications and systems based on the ParalleX execution model. XPI provides a simple abstraction layer to the family of ParalleX implementation HPX runtime system software. As HPX evolves, XPI insulates application codes from such changes, ensuring stability of experimental application codes. XPI serves both as a target for source-to-source compilers of high-level languages and as a readible low-level programming interface syntax. XPI is experimental and supports current on-going sponsored research projects. Its long term future is entirely dependent on its resulting value; an unknown at this time. But it is motivated by a short-term need to advance key project goals.

XPI is superficially similar to MPI while providing dramatically differing semantics in important areas. Its look and feel suggests MPI usage with library supported bindings to mainstream sequential languages (initially C bindings) through a familiar style of directives. Where MPI commands are prefaced with MPI\_, XPI commands prefaced with XPI\_. Like MPI-1, an initial basic set of commands are employed by XPI for early (and rapid) implementation, experimental programming, and experimentation. Through experience with use cases, a more mature XPI will evolve that facilitate usability, generality, and interoperability.

XPI provides a simple model of execution where *Threads*, invoked and managed by *Parcel* message-driven semantics and coordinated through a global network of *Local Control* synchronization *Objects* (LCOs), interact with an asynchronous, active global address space (*AGAS*). A hierarchy of XPI *Processes* provides a dynamic structure of contexts, name spacing, protection, and termination detection, where each process potentially spans multiple system hardware nodes (synchronous domains). Processes, threads, and LCOs are first class objects; parcels are not. Data structures (e.g., matrices, graphs), allocated in the global address space, may span an entire allocated system of many discrete subsystems (nodes). Processes and threads are ephemeral: they are created and eventually terminated dynamically. Though potentially expensive, both are free to migrate—or to be migrated—in space. Similarly, LCOs are first class objects, exist ephemerally, and may migrate as well. XPI permits optional static control and prespecified resource allocations but does not require them.

Chapter 2 of this report describes some terms and conventions used throughout, as well as presenting a brief overview of the principal semantic components of XPI based on, but not identical to, the ParalleX execution model of parallel processing. This introduces the ideas of computing threads, global address space, parcel message-driven computing, and parallel control state and continuations supported in part by local control objects. Chapter 3 provides some of the necessary syntax for setting up an XPI program, running it, and

ultimately terminating it. These miscellaneous commands are as ubiquitous in all XPI programs as they are tedious to compose and are reminiscent of many of their counterparts in MPI. Chapter 4 begins the substantive content of this report with an in-depth specification of Parcels, the unified constructs for invoking threads (and other actions) anywhere in the space (logically and physically) of the user application execution. Chapter 5 describes the execution environment in terms of the global address space and specifies commands for its management and use including asynchronous access, global loads and stores, address mapping, and interfaces to parcels and threads. Chapter 6 defines the thread commands and specifies their syntax for defining program actions. Chapter 7 presents the high-level parallel control space and the basis for continuations through Local Control Objects that perform synchronization and manage asynchronous system operation. Finally, Chapter 8 specifies the constructs for XPI Processes that serve as encapsulation of context, protection, and naming, ownership of physical resources, and termination detection. A Glossary of commands is included at the end of the report. This report is a work in progress. At any point in time it represents the best thinking on the evolving XPI syntax and functional semantics with the understanding that changes are anticipated in response to experience in its use and guidance from collaborators and friendly users.

# **Chapter 2**

## **Overview and Conventions**

## 2.1 Overview of XPI Execution

In the following detailed specification of the XPI syntax, and description of the related semantic constructs, a simple parallel programming model emerges. Actions (Section 6.1) are performed by instances of ephemeral threads which expose and exploit medium-grained parallelism. Each thread (Chapter 6) is the "active" result of the delivery of XPI's messaging construct, the parcel (Chapter 4), and is executed on a single locality within the contexts of its parent process (Chapter 8). Processes (Chapter 8) embody coarse-grained parallelism, providing return values and optional termination detection. Distributed sequential computation chains are expressed using the parcel's active continuation capabilities to chain together thread execution across localities. Thread and chain synchronization is established by the sequential ordering of a chain's threads, builtin compound atomic access to the global address space (Section 5.2), and user-defined local control object (LCO) operations (Chapter 7).

An XPI application is performed within the context of an asynchronous, single global virtual address space (Chapter 5). The mapping to physical memory resources is not partitioned or static. The phrase *active global address space* or AGAS is used to describe this model and differentiate it from alternatives such as distributed shared memory, partitioned global address space (PGAS), and cache-coherent global virtual memory. First class objects, including first-class XPI model objects like threads, processes, and LCOs, have global addresses and may be manipulated through them.

Processes are named objects. The process main encompasses the entire application, provides access to I/O objects, integrates lower level processes, its own threads, the fully global data, program code objects, and available physical resources provided by the operating system. All child processes (and their child processes, etc.) make up a hierarchical process tree with main at the root node. Each process has a *prime thread* which is instantiated when its host process is created.

### 2.2 Common Terms

**undefined** XPI defines a set of behaviors, i.e., actions an their results, along with a set of API usage errors. At the same time, there are API usage errors that exist but are unchecked. Such errors are considered to produce globally undefined behavior.

**implementation-defined** In some cases, the result of a particular operation results in implementation-defined behavior. XPI applications that depend on implementation-defined behavior sacrifice portability and maintainability, and may produce unexpected results as implementations change. It is valid, given a specific implementation, for the implementation-defined result to be *undefined* in the sense specified above.

**handle** A handle is an opaque reference to an implementation managed object. Handles need to be created and released using interface routines. Failing to destroy a handle may lead to leaked resources in an implementation. Handles do not have global addresses and handle values should not be shared between threads.

**value semantics** Implementation types that are designed to be allocated and released by the application programmer, and that are passed by copying their data (i.e., through a register, set of registers, or memopy) rather than by a reference have value semantics. An example of a type with value semantics is the XPI\_ADDR.

Developer's note. It may be a bad idea to expose value types to programmers, as this binds the compiled XPI binary to the specific version of the XPI headers that it was compiled with. At the same time, using handles to objects of these types is cumbersome, and using value types may expose static optimization opportunities to the compiler.

**action** An action is a thread entry point, (i.e., the target of a XPI\_PARCEL\_SEND). There are a number of different types of actions, along with language-specific rules for user-defined actions. See Section 6.1 for more information.

**parcel continuation** A parcel continuation is a parcel that will be automatically generated when an action completes. This is sometimes referred to as a *continuation action*, as all parcels encode actions. The parcel continuation is modeled as representing an entire continuation chain.

**sender** A thread that generates a parcel is considered the parcel's sender. In the basic model of XPI execution, parcel instances do not have receivers, XPI's active message semantics mean that a delivered parcel is in fact the thread that it spawns. This active-message abstraction can be broken through the use of the low-level parcel interface described in Chapter 4.

## 2.3 Interface Specification

#### 2.3.1 XPI Interface Definitions

The XPI interface is defined in three ways.

The first is a high-level interface definition describing the name of the interface routine, the parameters to the routine, and any errors that the routine may generate.

The second is a C API specification that deals with C-specific details, like assigning C types to parameters. The C API follows the high level interface definition as closely as

possible, but may require slightly different parameters to implement some of the high-level ideas.

The third is a FORTRAN API specification.

### **XPI Interface (XPI\_TYPE\_NAME\_OPERATION\_NAME)** ..... an example function

XPI\_TYPE\_NAME\_OPERATION\_NAME(p1, p2, p3)

IN p1 an input parameter

IN/OUT p2 a parameter that is both read and updated

OUT p3 (optional) an *optional* output-only parameter

[C] XPI\_Err XPI\_Type\_Name\_operation\_name(XPI\_Type1\_Name p1, Type2\* p2, Type3\* p3);

#### **Errors**

XPI\_ERR\_E1 an error condition

XPI ERR E2 a second error condition

XPI\_TYPE\_NAME\_OPERATION\_NAME shows an example of an interface specification. All interface names will be prefixed with XPI\_ followed by the name of the implementation type that this routine operates on (e.g., THREAD\_) and an underscore-separated list of words describing the operation (e.g., GET\_PROCESS).

#### **C** Conventions

The C API more-or-less implements the XPI specification directly.

Most C routines will return an XPI\_ERROR type that can be inspected for errors (Section 3.1 lists the entire set of XPI errors), the few that don't are routines that both (1) do not produce errors and (2) are much more convenient to use when they return their output, rather than XPI\_SUCCESS.

C function naming will use the uppercase  $xpi_-$ , combined with a capitalized type and lower-cased, underscore-separated operation name. In rare circumstances where a type is not appropriate,  $xpi_-$ operation\_name will be used (e.g.,  $xpi_-$ INIT).

Parameters marked IN/OUT and OUT in the XPI API will be passed by address, except in the case of XPI\_ADDR parameters, which are passed by-value with the understanding that the <code>OUT</code> value is the pointed-to value in the global address space. Routines that return new XPI\_ADDR values will take the XPI\_ADDR by reference.

The XPI interface may be specified using data type concepts that can't be represented as a single value in C, for instance a "list" of XPI\_ADDR-esses. In this case, the C API may expand the parameter list as necessary to describe the concept, e.g., adding a size-of-list parameter in the case of a list or array.

#### **Fortran Conventions**

*Developer's note.* Fortran conventions, and the Fortran interface, have not yet been implemented.

## 2.3.2 Action Specifications

XPI defines a number of builtin actions (see Section 6.1.1 for details) that an implementation must provide. Actions are XPI thread entry points similar to active message handler code, and are specified as parcel targets. An example of an action specification follows.

XPI Interface (XPI\_TYPE\_NAME\_OPERATION\_NAME) ...... an example action

XPI\_TYPE\_NAME\_OPERATION\_NAME\_ACTION(addr, in) CONTINUE(val)

IN addr the target's global address

IN in an input parameter

CONT val the future forwarded to the parcel continuation

The name of an action will contain the string suffix \_ACTION to distinguish it from regular runtime functions. Unlike function-based interfaces, actions may not have IN/OUT or OUT parameter, instead, they forward their "return" value to their continuation (see Section 6.3 for more details about continuations). The action definition describes the value passed to the parcel continuation using the CONTINUE and CONT keywords. The C identifier for the action will be in all caps to distinguish it from function-based alternatives. The C-API for an action will specify the continued type as a comment.

XPI\_TYPE\_NAME\_OPERATION\_NAME(addr, in, val)

IN addr the target's global address

IN in an input parameter

IN val (optional) a future representing the value forwarded to the par-

cel continuation

[C] XPI\_Err XPI\_Type\_Name\_operation\_name(XPI\_Addr addr, Type2 in, XPI\_Addr val);

Actions will often have an *asynchronous* function-based interface, that simplifies their use when application developers prefer a request-response style or programming, rather than the continuation-passing style provided with parcel continuations. These asynchronous functions will take a future (Section 7.3.1) that represents the completed response. These functions will have the same name as the action definition, without the \_ACTION suffix.

XPI\_TYPE\_NAME\_OPERATION\_NAME\_SYNC(addr, in)

IN addr the target's global address

IN in an input parameter

[C] XPI\_Err XPI\_Type\_Name\_operation\_name\_sync(XPI\_Addr addr, Type2 in);

In addition, some actions will have a *synchronous* function-based interface that presents a remote-procedure-call interface to the application developer. These actions will have the same name as the asynchronous function, with the string <code>\_SYNC</code> added to the operation name. These synchronous functions contain an implicit XPI\_THREAD\_WAIT semantics, though the implementation may not use one.

**Errors** 

XPI ERR E1 an error condition

XPI\_ERR\_E2 a second error condition

## 2.3.3 Handle Type Specification

Often, XPI exposes handles for local internal resources. Each resource type will have its own handle type, defined using the following format.

[C] typedef int XPI\_Type\_Name;

The XPI specification uses the identifier suffix \_HANDLE to make it clear that this is a specification for a type handle. The C declaration will be that of a typedef of the form XPI\_Type without the handle suffix, as the declaration makes it clear that this is a handle.

*Developer's note.* Fortran conventions are not yet complete.

# **Chapter 3**

## Miscellaneous

## 3.1 Error Handling

```
XPI Interface (XPI_ERROR) ..... error type
XPI_ERROR
```

[C] typedef int XPI\_Err;

[C]

XPI errors are represented as integer error codes. Success will always be indicated with XPI\_SUCCESS. Chapter B contains a list of the error codes currently in use, along with a reference to the context in which they are used. The detailed description of the code will be found in the referenced location.

Most XPI API routines will return an error code that can be evaluated.

### 3.2 Initialization and Shutdown

The following interface routines handle initialization and shutdown of the runtime system. They are native routines, and should not be used in the context of an XPI action.

This initializes the XPI runtime, using the passed arguments and the environment. C applications usually simply forward pointers to argc, argv, and envp (if available). XPI-specific arguments are removed from argc and argv, and the environment is updated as necessary.

```
XPI Interface (XPI_RUN) ...... run the XPI application

XPI RUN(args, result)
```

IN args (optional) a list of arguments

OUT result (optional) the result value of the main action (63)

[C] XPI\_Err XPI\_run(int argc, char\* argv[], int \*result);

XPI\_RUN encapsulates the creation of the main process along with its associated initial thread, the XPI\_MAIN thread. XPI\_RUN also manages the future required for XPI\_MAIN to return a value. This routine is synchronous, and will not return until the main process terminates.

```
XPI Interface (XPI_FINALIZE) ..... finalize execution XPI_FINALIZE
```

[C] XPI\_Err XPI\_finalize();

This terminates the execution of the XPI runtime, releasing resources acquired in XPI\_INIT and XPI\_RUN.

## 3.3 High-Level Interface Routines

The following routines are called from XPI code, but are not associated with any application objects and cannot be targeted as actions.

```
XPI Interface (XPI_ABORT) ...... abort execution
```

XPI\_ABORT(code, message)

IN code application-specific error code

IN message (optional) a message to print

[C] void XPI\_abort(int code, const char \*message) \_\_attribute\_\_((noreturn));

This unconditionally aborts the execution of an XPI application, returning control to the XPI\_RUN site with the result set to the passed code, and optionally printing the message. This should clean up resources associated with the running application.

This may be an expensive operation.

```
XPI Interface (XPI_VERSION) ...... query library version
```

XPI\_VERSION(major, minor, release)

OUT major the major version number
OUT minor the minor version number
OUT release the release number

[C] void XPI\_version(size\_t \*major, size\_t \*minor, size\_t \*release);

This queries the specification version number that the XPI implementation conforms to.

## 3.4 Action Management

Processes manage the user actions that are targeted by parcels

The following sections describe the language-specific details for writing user actions and registering them with the runtime.

#### 3.4.1 C Actions

User actions represented by statically compiled C functions must meet the following restricted programming interface.

- 1. C actions must have a return type of XPI\_ERROR. This error code can be used to communicate unexpected conditions to the XPI runtime.
- 2. A C action's parameter must be of **void**\* type, which will be bound to the parcel's argument data by the runtime.
- 3. A C action must terminate by returning an XPI\_ERROR, or XPI\_SUCCESS.
- 4. A C action must be registered using XPI\_REGISTER\_ACTION\_WITH\_KEY before being used in a parcel.

```
XPI Interface (XPI_REGISTER_ACTION_WITH_KEY) ..... register an action XPI_ACTION
```

```
[C] typedef XPI_Err (*XPI_Action)(void *args) /* CONT(...) */;
```

```
XPI_REGISTER_ACTION_WITH_KEY(function, key)
```

IN function language-specific address of the actionIN key application-specific unique key for this action

```
[C] XPI_Err XPI_register_action_with_key(XPI_Action action, char *key);
#define XPI_register_action(act) XPI_register_action_with_key(act, #act)
```

This registers an action with the runtime. It must be performed in order to send parcels to the action. It must be performed in a native C thread run on each locality, and may be performed as part of a static constructor. Builtin actions do not need to be registered before use, and have keys equivalent to their symbol names in C. The C interface provides a registration macro that uses the symbol name as a key. Registering two actions with the same key results in undefined behavior.

#### 3.4.2 Fortran Actions

Developer's note. Fortran bindings are not yet specified.

# **Chapter 4**

## **Parcels**

XPI models distributed computation using an active message and continuation model of execution, exposed via the parcel interface. A parcel encodes a chain of distributed execution, each link of which is an XPI thread (Chapter 6) resulting from an active message delivery. Parcels model five components.

- A target *action* (Section 6.1). This identifies the operation that should be performed on parcel delivery.
- A target *address* (Chapter 5). This global address establishes the location at which the target action *should* execute. With the exception of parcels targeting LCO actions (Section 6.1.4), and some primitive actions, the runtime may ignore this hint and execute the action at an arbitrary location.
- An *environment*. This is an untyped data block establishing the execution environment for the thread resulting from parcel delivery.
- The *argument* data. This is an untyped data block establishing the argument data passed to the action for the thread resulting from parcel delivery.
- A continuation stack. This is a stack of action, address, environment triples that encodes the set of continuation parcels that represents the *rest* of the computation for this chain of execution.

Programming with parcels is a low-level analog to programming in a continuation passing style, or with a continuation-based language. Semantics for such languages often model thread\_spawn and call/cc using a large step operational semantics, either in shared memory or eliding the messaging inherent in distributed execution. Parcels make this communication explicit, modeling thread\_spawn as XPI\_PARCEL\_SEND and call/cc as XPI\_CONTINUE, and allowing programmers—or languages targeting XPI—to manipulate their own continuation stack directly.

The parcel model does not restrict the programming language or style used to define actions—with the constraint that at least a native C interface must be available from the source language. In particular, actions defined using C execute using the standard C-ABI including stacks (though of course it is possible to write C-based actions in a continuation passing style locally).

### 4.1 Parcel Generation

XPI Interface (XPI\_PARCEL) ...... a handle to an XPI parcel XPI\_PARCEL\_HANDLE

[C] typedef int XPI\_Parcel;

Parcels are considered XPI implementation resources and are exposed to application developers through parcel handles. Attempted use of an invalid parcel handle will generally result in an XPI\_ERR\_INV\_PARCEL error.

XPI Interface (XPI\_PARCEL\_CREATE) ...... create a new empty parcel

XPI\_PARCEL\_CREATE(parcel)

OUT parcel a handle to the new parcel

[C] XPI\_Err XPI\_Parcel\_create(XPI\_Parcel \*parcel);

**Errors** 

XPI\_ERR\_NO\_MEM

not enough local resources to perform this operation

XPI\_PARCEL\_CREATE allocates a new parcel, and returns a handle for it. Allocated handles must be freed with XPI\_PARCEL\_FREE before a thread terminates, or the runtime resources associated with the parcel will leak. Handles are a scarce resource and XPI\_PARCEL\_CREATE will produce an XPI\_ERR\_NO\_MEM error if the request cannot be satisfied.

XPI Interface (XPI\_PARCEL\_CLONE) ...... create a copy of a parcel

XPI\_PARCEL\_CLONE(parcel, clone)

IN parcel a handle to the parcel to clone
OUT clone a handle to the new parcel

[C] XPI\_Err XPI\_Parcel\_clone(XPI\_Parcel parcel, XPI\_Parcel \*clone);

Errors

XPI ERR NO MEM

not enough local resources to perform this operation

XPI\_PARCEL\_CLONE allocates a new parcel, copies the data from the parcel into it including any continuation chain, and returns a handle for it. Allocated handles must be freed with XPI\_PARCEL\_FREE before a thread terminates, or the runtime resources associated with the parcel will leak. Handles are a scarce resource and XPI\_PARCEL\_CREATE will produce an XPI\_ERR\_NO\_MEM error if the request cannot be satisfied.

XPI Interface (XPI\_PARCEL\_FREE) ...... free a parcel

XPI PARCEL FREE(parcel)

IN parcel

a handle to the parcel to free

[C] XPI\_Err XPI\_Parcel\_free(XPI\_Parcel parcel);

Parcel handles are scarce resources and must be freed after use to avoid leaking the runtime resources allocated with them. It is not an error to attempt to free an invalid parcel handle. Parcel handles may be reissued, so freeing a handle twice may have unexpected results.

## 4.2 Target Field Accessors

XPI Interface (XPI\_PARCEL\_SET\_ADDR) ..... set a parcel's target address

XPI\_PARCEL\_SET\_ADDR(parcel, address)

IN parcel the parcel handle
IN address the target action

[C] XPI\_Err XPI\_Parcel\_set\_addr(XPI\_Parcel parcel, XPI\_Addr addr);

**Errors** 

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid

The target address is a global address (Chapter 5) and must have a valid mapping at the time that XPI\_PARCEL\_SEND or XPI\_CONTINUE is performed. XPI\_NULL is always a valid address, and indicates that there is no preferred processing location for this parcel.

```
XPI Interface (XPI_PARCEL_SET_ACTION) ...... set a parcel's target action
```

XPI\_PARCEL\_SET\_ACTION(parcel, action)

IN parcel the parcel handle
IN action the target action

[C] XPI\_Err XPI\_Parcel\_set\_action(XPI\_Parcel parcel, XPI\_Action action);

**Errors** 

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid

The action must correspond to an action (Section 6.1) that was registered with the XPI runtime using XPI\_REGISTER\_ACTION\_WITH\_KEY prior to XPI\_PARCEL\_SEND being called. An ACTION\_NULL action is always a valid action, and indicates that no further continuations should be processed.

```
XPI Interface (XPI_PARCEL_SET_ENV) ..... set a parcel's target environment data
```

XPI\_PARCEL\_SET\_ENV(parcel, data)

IN parcel the parcel handle

IN data the target environment data

[C] XPI\_Err XPI\_Parcel\_set\_env(XPI\_Parcel parcel, size\_t bytes, const void \*data);

**Errors** 

XPI ERR INV PARCEL the parcel handle is invalid

The parcel environment data is an untyped buffer available to the XPI thread that results from delivery of the parcel, through the XPI\_THREAD\_GET\_ENVIRONMENT routine.

*Rationale.* The environment data block is intended to support a continuation closure's environment bindings for the associate action's variables.

XPI Interface (XPI\_PARCEL\_SET\_DATA) ..... set a parcel's argument data

XPI\_PARCEL\_SET\_DATA(parcel, data)

IN parcel the parcel handle
IN data the argument data

[C] XPI\_Err XPI\_Parcel\_set\_data(XPI\_Parcel parcel, size\_t bytes, const void \*data);

**Errors** 

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid

The argument data is an untyped buffer available to the XPI thread that results from delivery of the parcel, and is bound to the thread's action argument parameter. This data is not modified by either the XPI\_PARCEL\_PUSH or XPI\_PARCEL\_POP operations.

*Rationale.* The argument data is intended to provide a continuation closure's argument binding. This buffer communicates the result of a thread to its continuation.

## 4.3 Continuation Stack Management

A parcel provides a stack push, and asynchronous pop, interface in order to manage the continuation stack.

XPI Interface (XPI\_PARCEL\_PUSH) ...... push the continuation stack

XPI PARCEL PUSH(parcel)

IN parcel a handle to the parcel

[C] XPI\_Err XPI\_Parcel\_push(XPI\_Parcel parcel);

**Errors** 

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid

XPI\_ERR\_NO\_MEM not enough local resources to perform this operation

XPI\_PARCEL\_PUSH allocates a new record, copies the current target action, address, and environment into the record, and pushes it onto the top of the stack. XPI\_PARCEL\_-PUSH resets with the target address, action, to XPI\_NULL, ACTION\_NULL, and NULL, respectively.

**XPI Interface (XPI\_PARCEL\_POP)** ...... pop the closure off the top of a parcel's stack

XPI\_PARCEL\_POP(parcel, complete)

IN parcel a handle to the parcel

IN complete (optional) the address of a future representing the completion of the

pop

[C] XPI\_Err XPI\_Parcel\_pop(XPI\_Parcel parcel, XPI\_Addr complete);

**Errors** 

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid

XPI\_PARCEL\_POP copies the data fields from the top of the continuation stack into the target action, address, and environment, freeing the previous environment buffer if necessary, and then pops the record off of the stack.

XPI\_PARCEL\_POP is a locally asynchronous operation. Its completion is signaled through the use of the complete future, which the calling thread should wait on. This future should be allocated with a size of 0.

Repeatedly popping the continuation stack without waiting for the previous XPI\_PARCEL\_POP operations to complete is not an error. The complete future is only necessary for inspecting the state of the parcel's fields.

. The state of a parcel's fields are unstable between the time of a XPI\_PARCEL\_POP and its completion. Overlapped XPI\_PARCEL\_POP operations may be pipelined, so only the most recent XPI\_PARCEL\_POP operation can be properly waited on.

Popping an empty stack is not an error, and has the side effect of resetting the target action, address, and environment fields to their default, freeing the previous environment buffer if necessary.

*Rationale.* While the continuation stack is modeled as a local block, the XPI\_PARCEL\_-POP operation is asynchronous so as to allow an XPI implementation to implement a continuation stack through a set of distributed "frames," which can optimize the bandwidth required for distributed operation.

## 4.4 Sending a Parcel

XPI Interface (XPI\_PARCEL\_SEND) ......send a parcel

XPI PARCEL SEND(parcel, complete, future)

IN parcel the parcel handle

IN complete (optional) the address of a future representing the local completion

of the send

IN future (optional) the address of a future representing the spawned thread's

global address

[C] XPI\_Err XPI\_Parcel\_send(XPI\_Parcel parcel, XPI\_Addr complete, XPI\_Addr future);

Errors

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid XPI\_ERR\_INV\_ADDR the target address is invalid

XPI\_PARCEL\_SEND sends a parcel, initiating the distributed chain of operation encoded by it.

Sending a parcel is a locally asynchronous operation. The parcel structure is unsafe to inspect or update until the local operation is complete. An application that wants to reuse parcel structures must provide a future as the complete parameter to XPI\_PARCEL\_SEND, and may wait for local completion using it.

In addition to waiting for the local send operation to complete, the sender is able to wait for remote completion of the send—along with its active message instantiation, by providing a future as the future parameter to XPI\_PARCEL\_SEND and waiting on it. In addition to signaling remote completion, this future will provide the global address of the thread that is spawned to execute the remote action. Such information can be used to query the status of the thread.

. Due to the active message nature of parcels, XPI\_PARCEL\_SEND is effectively equivalent to a thread\_spawn operation, in a distributed setting.

Advice to implementors. XPI\_PARCEL\_SEND permits optimized library implementations that may bypass the networking layer entirely, if possible. In particular, parcels targeting local addresses may merely be instantiated as local threads, or even run as part of a loop. The only restriction for a XPI\_PARCEL\_SEND implementation is that, if a program does not execute XPI\_PARCEL\_SELECT, then no thread should be able to observe semantics incompatible with the thread specification given in Chapter 6.

*Developer's note.* It's not clear that there is utility in this mechanism for getting the address of the spawned thread, however this functionality is consistent with initial XPI specification attempts and can be easily optimized at runtime, so we include it.

## 4.5 Apply

**XPI Interface (XPI\_APPLY)** ...... high-level asynchronous function call interface

XPI APPLY(target, action, data, future)

```
IN target target address
IN action target action
```

IN data the parameter data for the action

IN future (optional) a future to receive the continuation data

XPI\_APPLY\_SYNC(target, action, data)

IN	target	target address
IN	action	target action

IN data the parameter data for the action

**Errors** 

XPI ERR INV ADDR

the target global address is invalid

XPI\_APPLY encapsulates the steps required to assemble and send a parcel and continuation to effect a remote-procedure call. If the action does not continue a value, or if the continued value is to be ignored, then future should be set to XPI\_NULL.

### 4.6 Advanced

Some advanced programmers may need to inspect parcels manually, before they result in active threads. The interface for such inspection is given here. This functionality breaks the active message abstraction of parcels, and should be used carefully.

In particular, XPI\_PARCEL\_SEND is not obliged to interact with the network layer, if the XPI\_PARCEL\_SEND can be satisfied otherwise without effecting the semantics of the program, then the sent parcel may not be receivable with XPI\_PARCEL\_SELECT.

*Rationale.* It is expected that only low level system code will need to receive parcels explicitly. Such code is likely simply forwarding parcels, or relocating data for work balancing.

```
XPI Interface (XPI_PARCEL_SELECT) ..... explicitly receive a parcel
```

XPI PARCEL SELECT(match, parcels, matched)

IN match a pattern to match

IN/OUT parcels an n-element buffer to store matched parcel handles

OUT matched the number of parcels matched

This can be used to explicitly receive parcels from the network layer.

*Developer's note.* Currently, match is ignored. This routine simply receives the first parcel available at the locality at which it is called, and returns 1 for the matched value, assuming that there is at least one slot available in parcels.

```
XPI Interface (XPI_PARCEL_GET_ADDR) ..... get a parcel's target address
```

XPI\_PARCEL\_GET\_ADDR(parcel, parcel)

IN parcel the parcel handle
OUT parcel the target address

```
[C] XPI_Err XPI_Parcel_get_addr(XPI_Parcel parcel, XPI_Addr *addr);
```

Errors

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid

XPI Interface (XPI\_PARCEL\_GET\_ACTION) ...... get a parcel's target action

XPI\_PARCEL\_GET\_ACTION(parcel, action)

IN parcel the parcel handle
OUT action the target action

[C] XPI\_Err XPI\_Parcel\_get\_action(XPI\_Parcel parcel, XPI\_Action \*action);

Errors

XPI ERR INV PARCEL the parcel handle is invalid

XPI Interface (XPI\_PARCEL\_GET\_ENV) ...... get a parcel's target environment data

XPI\_PARCEL\_GET\_ENV(parcel, data)

IN parcel the parcel handle

OUT data the target environment data

[C] XPI\_Err XPI\_Parcel\_get\_env(XPI\_Parcel parcel, size\_t \*bytes, void \*\*data);

**Errors** 

XPI\_ERR\_INV\_PARCEL the parcel handle is invalid

XPI Interface (XPI\_PARCEL\_GET\_DATA) ..... get a parcel's argument data

XPI PARCEL GET DATA(parcel, data)

IN parcel the parcel handle

OUT data the parcel's argument data

[C] XPI\_Err XPI\_Parcel\_get\_data(XPI\_Parcel parcel, size\_t \*bytes, void \*\*data);

**Errors** 

XPI ERR INV PARCEL the parcel handle is invalid

# Chapter 5

# Global Address Space

The global address space is at the heart of parallel programming with XPI. It is a global virtual byte-addressable address space defined in terms of a native parcel interface in Section 5.2.

Explicit parcel programming can be inconvenient and potentially inefficient when messaging patterns that both match common usages and have hardware support. For example, the XPI\_AGAS\_LOAD\_ACTION is often used in conjunction with a future to perform a traditional, two-message, load operation. Where such patterns are common it makes sense to add function-based interfaces that simplify development and maintenance of code, and expose optimization opportunities.

Section 5.3.1 specifies a future-based (Section 7.3.1) asynchronous function-based interface that captures common patterns. Section 5.3.2 specifies a purely synchronous function-based interface to memory. Synchronous functions can restrict throughput, as they imply a strict ordering of memory accesses, however they are included with the intention of providing low overhead operations where such an ordering is logically required.

## 5.1 Address Space Properties

## 5.1.1 Atomicity

Primitive memory actions of the same size at the same global address are guaranteed to be performed atomically, i.e., a load action will never see data values corresponding to a partially completed store or compare-and-swap operation. This constraint implies that there exists some serial history of operations for each location, however XPI requires no ordering on parcels and thus this history is only observable with appropriate synchronization, e.g., through ordered use of the asynchronous function-based interface (Section 5.3.1) or sole use of the synchronous function-based interface (Section 5.3.2).

As with strict-aliasing in C, concurrent access to the same (or overlapping) location using types of a different size may produce an arbitrary value. The exception to this is that single-byte access to any location is always safe—in cases where a single-byte access is always atomic and can safely alias any global address.

## 5.1.2 Alignment

XPI's global memory space only supports accesses to aligned addresses, i.e., a 4-byte operation must be performed to a 4-byte aligned address, an 8-byte operation must be performed to an 8-byte aligned address, etc....

*Rationale.* Requiring aligned accesses to global memory may permit more efficient implementations of the address space, particularly with respect to the atomicity requirement. Unaligned accesses may be performed non-atomically with XPI\_PROCESS MEMCPY.

#### 5.1.3 Endianness

XPI's native parcel interface is defined to interact with the memory space in a little-endian manner.

*Rationale.* The memory space is defined as untyped bytes, but the native interface defines larger accesses as a result of performance and programmability concerns. Given the possibility of reading and writing some byte address using different native sizes—one of which must be single-byte access (Section 5.1.1), we must specify an endianness. The choice of little-endianness is arbitrary.

This is a consequence of defining the native memory interface in terms of a set of C-typed operations, e.g., uint64\_t, double, etc., rather than as byte-array (uint8\_t[]) operations. The interface is designed in such a manner to permit efficient library-based function call operations that act on machine registers, byte-arrays must have addresses and be passed by address.

#### 5.2 Native Parcel Interface

XPI's global address space defines an asynchronous memory interface that is accessed using parcels with a set of predefined, primitive system actions (Section 6.1.1).

XPI Interface (XPI\_AGAS\_LOAD) ..... load a value from the global address space

```
XPI_AGAS_LOAD_ACTION(addr) CONTINUE(val)
```

```
IN addr the global address from which to load CONT val the loaded value
```

```
[C] XPI_Err XPI_AGAS_LOAD_U8_ACTION() /* CONT(uint8_t val) */;
    XPI_Err XPI_AGAS_LOAD_U16_ACTION() /* CONT(uint16_t val) */;
    XPI_Err XPI_AGAS_LOAD_U32_ACTION() /* CONT(uint32_t val) */;
    XPI_Err XPI_AGAS_LOAD_U64_ACTION() /* CONT(uint64_t val) */;
    XPI_Err XPI_AGAS_LOAD_U128_ACTION() /* CONT(_uint128_t val) */;
    XPI_Err XPI_AGAS_LOAD_S8_ACTION() /* CONT(int8_t val) */;
    XPI_Err XPI_AGAS_LOAD_S16_ACTION() /* CONT(int16_t val) */;
    XPI_Err XPI_AGAS_LOAD_S32_ACTION() /* CONT(int32_t val) */;
    XPI_Err XPI_AGAS_LOAD_S64_ACTION() /* CONT(int64_t val) */;
    XPI_Err XPI_AGAS_LOAD_S128_ACTION() /* CONT(_int128_t val) */;
    XPI_Err XPI_AGAS_LOAD_F_ACTION() /* CONT(float val) */;
    XPI_Err XPI_AGAS_LOAD_D_ACTION() /* CONT(double val) */;
    XPI_Err XPI_AGAS_LOAD_D_ACTION() /* CONT(float _Complex val) */;
    XPI_Err XPI_AGAS_LOAD_F_ACTION() /* CONT(float _Complex val) */;
```

```
XPI_Err XPI_AGAS_LOAD_DC_ACTION() /* CONT(double _Complex val) */;
XPI_Err XPI_AGAS_LOAD_ADDR_ACTION() /* CONT(XPI_Addr val) */;
XPI_Err XPI_AGAS_LOAD_ADDRDIFF_ACTION() /* CONT(XPI_AddrDiff val) */;
```

#### **Errors**

XPI ERR INV ADDR

the address, addr, is not valid

This load action is an atypical in that the action does not return a value. It simply reads the local address, and transmits the read value to its continuation action. This is often a future's trigger action (Section 7.3.1), though any type-correct continuation is valid. Parcels specifying the load action with a null continuation perform no useful work and may be suppressed entirely by optimization.

Load operations can also be performed using the XPI\_AGAS\_LOAD and XPI\_AGAS\_-LOAD SYNC function-based interface.

**XPI Interface (XPI\_AGAS\_STORE)** ..... stores a value to the global address space

```
XPI_AGAS_STORE_ACTION(addr, val)
```

```
IN addr the global address targeted by the store
IN val the value to store
```

```
[C]
      XPI_Err XPI_AGAS_STORE_U8_ACTION(uint8_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_U16_ACTION(uint16_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_U32_ACTION(uint32_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_U64_ACTION(uint64_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_U128_ACTION(__uint128_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_S8_ACTION(int8_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_S16_ACTION(int16_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_S32_ACTION(int32_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_S64_ACTION(int64_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_S128_ACTION(__int128_t *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_F_ACTION(float *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_D_ACTION(double *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_FC_ACTION(float _Complex *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_DC_ACTION(double _Complex *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_ADDR_ACTION(XPI_Addr *args) /* CONT() */;
      XPI_Err XPI_AGAS_STORE_ADDRDIFF_ACTION(XPI_AddrDiff *args) /* CONT() */;
```

#### **Errors**

Store operations atomically update the target location with the passed value. The store operation does not continue a value.

Store operations can also be performed using the XPI\_AGAS\_STORE and XPI\_AGAS\_-STORE\_SYNC function-based interface.

```
XPI Interface (XPI_AGAS_CAS) ...... atomic read-modify-write support
```

#### XPI AGAS CAS ACTION(addr, from, to) CONTINUE(actual)

IN	addr	the global address targeted by the operation
IN	from	the value expected at addr
IN	to	the new value for addr
CONT	actual	the actual value that was seen

```
[C]
      /* args[0] == from value, and args[1] == to value */
      XPI_Err XPI_AGAS_CAS_U8_ACTION(uint8_t args[2])
      /* CONT(uint8_t actual) */;
      XPI_Err XPI_AGAS_CAS_U16_ACTION(uint16_t args[2])
         /* CONT(uint16_t actual) */;
      XPI_Err XPI_AGAS_CAS_U32_ACTION(uint32_t args[2])
         /* CONT(uint32_t actual) */;
      XPI_Err XPI_AGAS_CAS_U64_ACTION(uint64_t args[2])
         /* CONT(uint64_t actual) */;
      XPI_Err XPI_AGAS_CAS_U128_ACTION(__uint128_t args[2])
         /* CONT(__uint128_t actual) */;
      XPI_Err XPI_AGAS_CAS_S8_ACTION(int8_t args[2])
         /* CONT(int8_t actual) */;
      XPI_Err XPI_AGAS_CAS_S16_ACTION(int16_t args[2])
         /* CONT(int16_t actual) */;
      XPI_Err XPI_AGAS_CAS_S32_ACTION(int32_t args[2])
         /* CONT(int32_t actual) */;
      XPI_Err XPI_AGAS_CAS_S64_ACTION(int64_t args[2])
         /* CONT(int64_t actual) */;
      XPI_Err XPI_AGAS_CAS_S128_ACTION(__int128_t args[2])
         /* CONT(__int128_t actual) */;
      XPI_Err XPI_AGAS_CAS_F_ACTION(float args[2])
         /* CONT(float actual) */;
      XPI_Err XPI_AGAS_CAS_D_ACTION(double args[2])
         /* CONT(double actual) */;
      XPI_Err XPI_AGAS_CAS_FC_ACTION(float _Complex args[2])
         /* CONT(float _Complex actual) */;
      XPI_Err XPI_AGAS_CAS_DC_ACTION(double _Complex args[2])
         /* CONT(double _Complex actual) */;
      XPI_Err XPI_AGAS_CAS_ADDR_ACTION(XPI_Addr args[2])
         /* CONT(XPI_Addr actual) */;
      XPI_Err XPI_AGAS_CAS_ADDRDIFF_ACTION(XPI_AddrDiff args[2])
         /* CONT(XPI_AddrDiff actual) */;
```

#### **Errors**

The compare-and-swap action is used to perform a conditional atomic read-modify-write to a global address. As with a traditional shared-memory compare-and-swap operation, XPI\_AGAS\_CAS compares the current value of addr with from and if they are equal, updates the value of addr to the value specified as to. XPI\_AGAS\_CAS continues the actual value that was seen at addr so that the action's continuation can act appropriately.

Compare-and-swap operations can be performed using the XPI\_AGAS\_CAS and XPI\_-AGAS\_CAS\_SYNC function-based interface.

Advice to users. While function-based interfaces to compare-and-swap exists as XPI\_AGAS\_CAS and XPI\_AGAS\_CAS\_SYNC, the common shared-memory use of compare-and-swap in a loop to complete an atomic read-modify-write operation is not naturally suited to a function-based interface in XPI as it has the potential for excessive inter-node network traffic. In XPI, the XPI\_AGAS\_CAS\_ACTION is typically used directly, and paired with a continuation that checks the result of compare-and-swap locally, at the same locality.

The common *hazard pointer* design pattern used to avoid the  $A \longrightarrow B \longrightarrow A$  problem associated with implementations of linked data structures using compare-and-swap

requires an architecture to support compare-and-swap operations larger than that of the native address size. Depending on the size of the implementation-defined size of an XPI\_ADDR, this may not be possible to implement with XPI\_AGAS\_CAS. When algorithms can not tolerate  $A \longrightarrow B \longrightarrow A$  occurrences custom local-control-objects must be used (Chapter 7).

## 5.3 Function-based Interface

To assist with programmability as well as to enable potential optimizations, XPI defines a higher-level, asynchronous function-based interface that relies on *future* Local Control Objects to return data where necessary, or to order execution as desired. Furthermore, synchronous accesses to global memory are occasionally necessary, and may provide an optimization opportunity, so XPI provides a synchronous interface to memory.

A program that uses only synchronous, function-based access to global memory should have sequentially consistent global address semantics.

Advice to users. Applications developers should avoid synchronous access to global memory unless it is unavoidable, as it introduces overheads due to waiting, and prevents continued execution of independent statements. However programmers can expect that the synchronous interface will outperform the equivalent asynchronous code described above.

## 5.3.1 Asynchronous Functions

```
XPI_AGAS_LOAD(addr, future)
         ΙN
                                           the global address from which to load
                   addr
         IN
                   future
                                           a future representing the loaded value
  [C]
        XPI_Err XPI_Agas_load_u8(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_u16(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_u32(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_u64(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_u128(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_s8(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_s16(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_s32(XPI_Addr addr, XPI_Addr future);
         XPI Err XPI Agas load s64 (XPI Addr addr, XPI Addr future);
         XPI_Err XPI_Aqas_load_s128(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_f(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_d(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_fc(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_dc(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_addr(XPI_Addr addr, XPI_Addr future);
         XPI_Err XPI_Agas_load_addrdiff(XPI_Addr addr, XPI_Addr future);
[C11]
         #define XPI_Agas_load(addr, val, future)
            _Generic((val),
                   uint8_t
                               :XPI_Agas_load_u8,
                   uint16_t :XPI_Agas_load_u16,
uint32_t :XPI_Agas_load_u32,
uint64_t :XPI_Agas_load_u64,
                   uint64_t
                               :XPI_Agas_load_u64,
                   __uint128_t :XPI_Agas_load_u128,
```

```
:XPI_Agas_load_s8,
                  int16 t
                             :XPI_Agas_load_s16,
                  int32_t :XPI_Agas_load_s32,
int64_t :XPI_Agas_load_s64,
                    _int128_t :XPI_Agas_load_s128,
                  float.
                              :XPI_Agas_load_f,
                               :XPI_Agas_load_d,
                  double
                   float _Complex :XPI_Agas_load_fc,
                   double _Complex :XPI_Agas_load_dc) (addr, future)
       XPI_AGAS_STORE(addr, val, future)
        IN
                   addr
                                          the global address targeted by the store
        ΙN
                   val
                                          the value to store
        IN
                   future (optional)
                                          a future that can be used for ordering
  [C]
        XPI_Err XPI_Agas_store_u8(XPI_Addr addr, uint8_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_u16(XPI_Addr addr, uint16_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_u32(XPI_Addr addr, uint32_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_u64(XPI_Addr addr, uint64_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_u128(XPI_Addr addr, __uint128_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_s8(XPI_Addr addr, int8_t val, XPI_Addr future);
        XPI_Err XPI_Aqas_store_s16(XPI_Addr addr, int16_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_s32(XPI_Addr addr, int32_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_s64(XPI_Addr addr, int64_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_s128(XPI_Addr addr, __int128_t val, XPI_Addr future);
        XPI_Err XPI_Agas_store_f(XPI_Addr addr, float val, XPI_Addr future);
        XPI_Err XPI_Agas_store_d(XPI_Addr addr, double val, XPI_Addr future);
        XPI_Err XPI_Agas_store_fc(XPI_Addr addr, float _Complex val, XPI_Addr future);
        XPI_Err XPI_Agas_store_dc(XPI_Addr addr, double _Complex val, XPI_Addr future);
        XPI_Err XPI_Agas_store_addr(XPI_Addr addr, XPI_Addr val, XPI_Addr future);
        XPI_Err XPI_Agas_store_addrdiff(XPI_Addr addr, XPI_AddrDiff val, XPI_Addr future);
[C11]
        #define XPI_Agas_store(addr, val, future)
           _Generic((val),
                            :XPI_Agas_store_u8,
:XPI_Agas_store_u16,
                  uint8 t
                  uint16_t
                  uint32_t :XPI_Agas_store_u32,
                  uint64_t :XPI_Agas_store_u64,
                  __uint128_t :XPI_Agas_store_u128,
                  int8_t :XPI_Agas_store_s8,
                  int16_t
                             :XPI_Agas_store_s16,
                  int32_t :XPI_Agas_store_s32,
int64_t :XPI_Agas_store_s64,
                   __int128_t :XPI_Agas_store_s128,
                  float
                               :XPI_Agas_store_f,
                               :XPI_Agas_store_d,
                  double
                   float _Complex :XPI_Agas_store_fc,
                  double _Complex :XPI_Agas_store_dc) (addr, val, future)
       XPI AGAS CAS(addr, from, to, future)
        IN
                   addr
                                          the global address targeted by the operation
        IN
                                          the value expected at addr
                   from
        IN
                                          the new value for addr
                   to
        ΙN
                                          a future representing the actual value seen
                   future
```

int8\_t

```
[C]
        XPI_Err XPI_Agas_cas_u8(XPI_Addr addr, uint8_t from, uint8_t to,
                          XPI_Addr future);
        XPI_Err XPI_Agas_cas_u16(XPI_Addr addr, uint16_t from, uint16_t to,
                          XPI_Addr future);
        XPI_Err XPI_Agas_cas_u32(XPI_Addr addr, uint32_t from, uint32_t to,
                          XPI_Addr future);
        XPI_Err XPI_Agas_cas_u64(XPI_Addr addr, uint64_t from, uint64_t to,
                           XPI_Addr future);
        XPI_Err XPI_Agas_cas_u128(XPI_Addr addr, __uint128_t from, __uint128_t to,
                           XPI_Addr future);
        XPI_Err XPI_Agas_cas_s8(XPI_Addr addr, int8_t from, int8_t to,
                          XPI_Addr future);
        XPI_Err XPI_Agas_cas_s16(XPI_Addr addr, int16_t from, int16_t to,
                          XPI_Addr future);
        XPI_Err XPI_Agas_cas_s32(XPI_Addr addr, int32_t from, int32_t to,
                           XPI_Addr future);
        XPI_Err XPI_Agas_cas_s64(XPI_Addr addr, int64_t from, int64_t to,
                           XPI_Addr future);
        XPI_Err XPI_Agas_cas_s128(XPI_Addr addr, __int128_t from, __int128_t to,
                           XPI_Addr future);
        XPI_Err XPI_Agas_cas_f(XPI_Addr addr, float from, float to,
                         XPI_Addr future);
        XPI_Err XPI_Agas_cas_d(XPI_Addr addr, double from, double to,
                         XPI_Addr future);
        XPI_Err XPI_Agas_cas_fc(XPI_Addr addr, float _Complex from,
                          float _Complex to, XPI_Addr future);
        XPI_Err XPI_Agas_cas_dc(XPI_Addr addr, double _Complex from,
                          double _Complex to,
                          XPI_Addr future);
        XPI_Err XPI_Agas_cas_addr(XPI_Addr addr, XPI_Addr from, XPI_Addr to,
                           XPI_Addr future);
        XPI_Err XPI_Agas_cas_addrdiff(XPI_Addr addr, XPI_AddrDiff from, XPI_AddrDiff to,
                              XPI_Addr future);
[C11]
        #define XPI_Agas_cas(addr, from, to, future)
           _Generic((from),
                  uint8_t
                            :XPI_Agas_cas_u8,
                  uint16_t :XPI_Agas_cas_u16,
                  uint32 t
                           :XPI_Agas_cas_u32,
                  uint64_t :XPI_Agas_cas_u64,
                  __uint128_t :XPI_Agas_cas_u128,
                  int8_t
                           :XPI_Agas_cas_s8,
                  int16_t
                              :XPI_Agas_cas_s16,
                  int32_t
                              :XPI_Agas_cas_s32,
                  int64_t
                              :XPI_Agas_cas_s64,
                  __int128_t :XPI_Agas_cas_s128,
                  float
                            :XPI_Agas_cas_f,
                  double
                              :XPI_Agas_cas_d,
                  float _Complex :XPI_Agas_cas_fc,
                  double _Complex :XPI_Agas_cas_dc) (addr, from, to, future)
      5.3.2 Synchronous Functions
       XPI_AGAS_LOAD_SYNC(addr)
        IN
                  addr
                                         the global address from which to load
```

XPI\_Err XPI\_Agas\_load\_u8\_sync(XPI\_Addr addr, uint8\_t \*val);

[C]

```
XPI_Err XPI_Agas_load_u16_sync(XPI_Addr addr, uint16_t *val);
        XPI_Err XPI_Agas_load_u32_sync(XPI_Addr addr, uint32_t *val);
        XPI_Err XPI_Agas_load_u64_sync(XPI_Addr addr, uint64_t *val);
        XPI_Err XPI_Agas_load_u128_sync(XPI_Addr addr, __uint128_t *val);
        XPI_Err XPI_Agas_load_s8_sync(XPI_Addr addr, int8_t *val);
        XPI_Err XPI_Agas_load_s16_sync(XPI_Addr addr, int16_t *val);
        XPI_Err XPI_Agas_load_s32_sync(XPI_Addr addr, int32_t *val);
        XPI_Err XPI_Agas_load_s64_sync(XPI_Addr addr, int64_t *val);
        XPI_Err XPI_Agas_load_s128_sync(XPI_Addr addr, __int128_t *val);
        XPI_Err XPI_Agas_load_f_sync(XPI_Addr addr, float *val);
        XPI_Err XPI_Agas_load_d_sync(XPI_Addr addr, double *val);
        XPI_Err XPI_Agas_load_fc_sync(XPI_Addr addr, float _Complex *val);
        XPI_Err XPI_Agas_load_dc_sync(XPI_Addr addr, double _Complex *val);
        XPI_Err XPI_Agas_load_addr_sync(XPI_Addr addr, XPI_Addr *val);
        XPI_Err XPI_Agas_load_addrdiff_sync(XPI_Addr addr, XPI_AddrDiff *val);
[C11]
        #define XPI_Agas_load_sync(addr, val)
           _Generic((val),
                  uint8 t
                              :XPI_Agas_load_u8_sync,
                  uint16_t
                              :XPI_Agas_load_u16_sync,
                  uint32_t
                              :XPI_Agas_load_u32_sync,
                              :XPI_Agas_load_u64_sync,
                  uint64_t
                  __uint128_t :XPI_Agas_load_u128_sync,
                  int8_t
                              :XPI_Agas_load_s8_sync,
                  int16_t
                              :XPI_Agas_load_s16_sync,
                              :XPI_Agas_load_s32_sync,
                  int32_t
                              :XPI_Agas_load_s64_sync,
                  int64_t
                              :XPI_Agas_load_s128_sync,
                   _int128_t
                  float
                               :XPI_Agas_load_f_sync,
                  double
                               :XPI_Agas_load_d_sync,
                  float _Complex :XPI_Agas_load_fc_sync, \
                  double _Complex :XPI_Agas_load_dc_sync) (addr, val)
       XPI_AGAS_STORE_SYNC(addr, val)
                                          the global address targeted by the store
        ΙN
                   addr
        IN
                   val
                                          the value to store
  [C]
        XPI_Err XPI_Agas_store_u8_sync(XPI_Addr addr, uint8_t val);
        XPI_Err XPI_Agas_store_u16_sync(XPI_Addr addr, uint16_t val);
        XPI_Err XPI_Agas_store_u32_sync(XPI_Addr addr, uint32_t val);
        XPI_Err XPI_Agas_store_u64_sync(XPI_Addr addr, uint64_t val);
        XPI Err XPI Agas store u128 sync(XPI Addr addr, uint128 t val);
        XPI_Err XPI_Agas_store_s8_sync(XPI_Addr addr, int8_t val);
        XPI_Err XPI_Agas_store_s16_sync(XPI_Addr addr, int16_t val);
        XPI_Err XPI_Agas_store_s32_sync(XPI_Addr addr, int32_t val);
        XPI_Err XPI_Agas_store_s64_sync(XPI_Addr addr, int64_t val);
        XPI_Err XPI_Agas_store_s128_sync(XPI_Addr addr, __int128_t val);
        XPI_Err XPI_Agas_store_f_sync(XPI_Addr addr, float val);
        XPI_Err XPI_Agas_store_d_sync(XPI_Addr addr, double val);
        XPI_Err XPI_Agas_store_fc_sync(XPI_Addr addr, float _Complex val);
        XPI_Err XPI_Agas_store_dc_sync(XPI_Addr addr, double _Complex val);
        XPI_Err XPI_Agas_store_addr_sync(XPI_Addr addr, XPI_Addr val);
        XPI_Err XPI_Agas_store_addrdiff_sync(XPI_Addr addr, XPI_AddrDiff val);
[C11]
        #define XPI_Agas_store_sync(addr, val)
           _Generic((val),
                  uint8_t
                              :XPI_Agas_store_u8_sync,
```

```
:XPI_Agas_store_u32_sync,
                  uint32_t
                  uint64_t
                           :XPI_Agas_store_u64_sync,
                   _uint128_t :XPI_Agas_store_u128_sync,
                           :XPI_Agas_store_s8_sync,
                  int8_t
                  int16_t
                             :XPI_Agas_store_s16_sync,
                  int32_t
                             :XPI_Agas_store_s32_sync,
                  int64_t
                              :XPI_Agas_store_s64_sync,
                  __int128_t :XPI_Agas_store_s128_sync,
                  float
                              :XPI_Agas_store_f_sync,
                  double
                              :XPI_Agas_store_d_sync,
                  float _Complex :XPI_Agas_store_fc_sync,
                  double _Complex :XPI_Agas_store_dc_sync) (addr, val)
       XPI_AGAS_CAS_SYNC(addr, from, to)
        IN
                  addr
                                         the global address targeted by the operation
        IN
                  from
                                         the value expected at addr
        IN/OUT to
                                         in:the new value for addr, out:actual value seen
  [C]
        XPI_Err XPI_Agas_cas_u8_sync(XPI_Addr addr, uint8_t from, uint8_t *to);
        XPI_Err XPI_Agas_cas_u16_sync(XPI_Addr addr, uint16_t from, uint16_t *to);
        XPI_Err XPI_Agas_cas_u32_sync(XPI_Addr addr, uint32_t from, uint32_t *to);
        XPI_Err XPI_Agas_cas_u64_sync(XPI_Addr addr, uint64_t from, uint64_t *to);
        XPI_Err XPI_Agas_cas_u128_sync(XPI_Addr addr, __uint128_t from,
                               __uint128_t *to);
        XPI_Err XPI_Agas_cas_s8_sync(XPI_Addr addr, int8_t from, int8_t *to);
        XPI_Err XPI_Agas_cas_s16_sync(XPI_Addr addr, int16_t from, int16_t *to);
        XPI_Err XPI_Agas_cas_s32_sync(XPI_Addr addr, int32_t from, int32_t *to);
        XPI_Err XPI_Agas_cas_s64_sync(XPI_Addr addr, int64_t from, int64_t *to);
        XPI_Err XPI_Agas_cas_s128_sync(XPI_Addr addr, __int128_t from,
                               __int128_t *to);
        XPI_Err XPI_Agas_cas_f_sync(XPI_Addr addr, float from, float *to);
        XPI_Err XPI_Agas_cas_d_sync(XPI_Addr addr, double from, double *to);
        XPI_Err XPI_Agas_cas_fc_sync(XPI_Addr addr, float _Complex from,
                              float _Complex *to);
        XPI_Err XPI_Agas_cas_dc_sync(XPI_Addr addr, double _Complex from,
                              double _Complex *to);
        XPI_Err XPI_Agas_cas_addr_sync(XPI_Addr addr, XPI_Addr from,
                               XPI_Addr *to);
        XPI_Err XPI_Agas_cas_addrdiff_sync(XPI_Addr addr, XPI_AddrDiff from,
                                  XPI_AddrDiff *to);
[C11]
        #define XPI_Agas_cas_sync(addr, from, to)
           _Generic((from),
                  uint8_t
                             :XPI_Agas_cas_u8_sync,
                           :XPI_Agas_cas_u16_sync,
                  uint16_t
                  uint32_t :XPI_Agas_cas_u32_sync,
                  uint64_t :XPI_Agas_cas_u64_sync,
                   __uint128_t :XPI_Agas_cas_u128_sync,
                  int8 t
                            :XPI_Agas_cas_s8_sync,
                  int16_t
                             :XPI_Agas_cas_s16_sync,
                  int32_t
                            :XPI_Agas_cas_s32_sync,
                  int64_t
                              :XPI_Agas_cas_s64_sync,
                   __int128_t :XPI_Agas_cas_s128_sync,
                  float
                              :XPI_Agas_cas_f_sync,
                  double
                              :XPI_Agas_cas_d_sync,
```

:XPI\_Agas\_store\_u16\_sync,

uint16\_t

```
float _Complex :XPI_Agas_cas_fc_sync,
double _Complex :XPI_Agas_cas_dc_sync) (addr, from, to)
```

## 5.4 Address Space Representation

All library-based interfaces to memory require an address representation that can be manipulated by the application programmer. XPI's global address space is designed as an untyped, byte-addressable virtual address space. XPI provides the most general address representation, an opaque address structure. Such structures can be used as the target of a parcel (Chapter 4), and can be manipulation using XPI library routines to create new structures. Address structures are not handles because they have value semantics.

*Rationale.* At this time, we do not wish to formally bound the size of the global address space, or the address representation—as this may impact the network layer implementation, thus XPI does not currently use a simple integer representation. If, in the future, the size of the XPI virtual address becomes bounded this decision can be revisited.

We expect addresses and address computation to be ubiquitous, however we do not wish to require that either a) users manage memory associated with the addressing structures themselves, or b) the system garbage collect addresses, so we choose not to represent addresses as handles.

Advice to users. Users should not assume that the interface routines provided for address computations are library routines, as an implementation may choose to implement them as macros for performance reasons.

The XPI address space is designed to mimic traditional "C-style" virtual memory, and thus we define mechanisms for address structure comparison and arithmetic. To do this, XPI requires that conforming implementatations define a signed integer type large enough to represent the difference between any two addresses in the global address space.

Rationale. Given that XPI does not fix bounds for the size of the global address space, we do not know how large a difference may exist between two addresses. XPI does not define address differences as structs as this is both inconvenient for programmers and semantically unnecessary, given that the global address space is a flat, byte-addressable space in which the difference between two addresses can be represented concisely as a signed integer.

XPI Interface (XPI\_ADDRDIFF) ...... a global address difference handle

XPI ADDRDIFF

[C] typedef /\* implementation defined signed int \*/ XPI\_AddrDiff;

The XPI\_ADDRDIFF type will be typedefed to a signed integer type large enough to represent the difference between any two addresses in the global address space. As a signed integer, all standard signed integer operations are defined on XPI\_ADDRDIFF values. Note that, in C, signed integer underflow/overflow is undefined, so applications must take care with respect to computations on XPI\_ADDRDIFF-typed values.

**Errors** 

XPI\_ERR\_OUT\_OF\_RANGE the integer index is out of the range supported by the implementation

This interprets the integer as an index into the byte array representation of the global virtual address space, and initializes a structure suitable for use as a global address. Arbitrarily large addresses cannot be generated this way, further address arithmetic will be required to produce very large addresses.

obj

```
XPI Interface (XPI_NULL) ..... the null global virtual address
```

[C]extern XPI\_Addr XPI\_NULL;

The XPI\_NULL global virtual address is defined such that, when compared to an address initialized with the integer, 0.

Advice to users. The implementation of XPI\_NULL is left to the discretion of the XPI implementation, and thus portable XPI code should make no assumptions about it. In particular, XPI\_NULL should not have its address taken, as it may be implemented as a macro.

#### 5.4.1 Address Arithmetic

Advice to users. XPI's global address space is typed as bytes, thus all address arithmetic is performed in terms of bytes. This differs from traditional C-language pointer arithmetic, where, while addresses are byte-based, arithmetic is done in terms of the underlying pointer type.

Furthermore, pointer arithmetic in C is only defined in terms of pointers into the same array, or one-off-the-end. This is not currently a restriction for XPI address arithmetic, where the distance between any two addresses in the address space may be computed.

XPI Interface (XPI\_ADDR\_ADD) ...... adjust an address by an offset

XPI\_ADDR\_ADD(base, offset, result)

IN base the base address to adjust

IN offset the offset by which to adjust the baseOUT result and address representing base+offset

[C] XPI\_Addr XPI\_Addr\_add(XPI\_Addr base, XPI\_AddrDiff offset);

XPI\_ADDR\_ADD returns the global address that is offset bytes from base. This computation is not checked for overflow, however using an invalid address as a parcel target in XPI\_PARCEL\_SEND will result in an error. Note that offset may be negative.

**XPI Interface (XPI\_ADDR\_SUB)** ..... compute the difference between two addresses

XPI\_ADDR\_SUB(lhs, rhs, diff)

IN Ihs the left-hand side IN rhs the right-hand side

OUT diff the difference between lhs and rhs (i.e., lhs-rhs)

[C] XPI\_AddrDiff XPI\_Addr\_sub(XPI\_Addr lhs, XPI\_Addr rhs);

XPI\_ADDR\_SUB determines the distance between two addresses within the global address space. The XPI\_ADDRDIFF integer type is defined to be large enough to represent the difference between any two representable addresses, thus XPI\_ADDR\_SUB is total.

*Advice to users.* XPI\_ADDR\_SUB is a natural comparator for addresses.

$$\label{eq:XPI_ADDR_SUB} \text{XPI\_ADDR\_SUB(lhs, rhs, diff)} \implies \left\{ \begin{array}{ll} \text{diff} = 0 & \textit{iff} & \text{lhs} = \text{rhs} \\ \text{diff} < 0 & \textit{iff} & \text{lhs} < \text{rhs} \\ \text{diff} > 0 & \textit{iff} & \text{lhs} > \text{rhs} \end{array} \right.$$

*Developer's note.* XPI\_ADDR\_SUB-as-comparator usage depends on the fact that subtraction is a valid operation on any two representable addresses in XPI, as opposed to C where subtraction is only defined within the same array, or one-off-the-end.

XPI\_ADDR\_ADD and XPI\_ADDR\_SUB, combined with the native memory interface (Section 5.2) provide the basic mechanisms necessary to implement array and struct operations in XPI. As with any such attempt to impose structure on a fundamentally untyped, low-level address space, XPI applications must select a reasonable means for representing types and structures in memory. As of the current version, XPI does not define its own type system, thus application programmers are free to choose their own.

This document chooses to use the type system underlying the C language implementation on which the XPI application is being executed.

Rationale. It is expected that this decision will be in line with the majority of XPI applications. Such a decision allows application code to use C language types and operators (e.g., struct, sizeof, offsetof) to perform offset computations in many situations.

**Example 5.1** *Consider an array of points, defined by the C-struct* point\_t.

```
typedef struct {
   double x, y, z;
} point_t;
```

The following shows a simple example of iterating through this array in C, setting each double element to 0.

```
point_t points[1000];

for (int i = 0; i < 1000; ++i) {
   points[i].x = 0.0;
   points[i].y = 0.0;
   points[i].z = 0.0;
}</pre>
```

If the point array is instead stored in XPI's global address space, the same results can be achieved using the same C point\_t, sizeof (point\_t) to determine the current element of the array, offsetof (point\_t,  $\{x,y,z\}$ ) to determine the field offset, and the XPI\_ADDRDIFF type.

Advice to users. The XPI code above depends on the extended C11 interface for synchronous memory references.

**XPI Interface (XPI\_ADDR\_MOD)** ...... compute the integer mod of the address

XPI ADDR MOD(addr, denom, remainder)

INaddrthe addressINdenomthe denominator

OUT remainder the mod result (i.e., addr%denom)

[C] unsigned int XPI\_Addr\_mod(XPI\_Addr addr, unsigned int denom);

XPI\_ADDR\_MOD performs the integer modulus operation on a global address. As with the analogous C-pointer operation, XPI\_ADDR\_MOD is often used by low level code to map addresses to array indexes.

```
XPI Interface (XPI_ADDR_DIV) ...... compute the integer div of the address XPI ADDR DIV(addr, denom, quotient)
```

IN addr the address
IN denom the denominator

OUT quotient the div result (i.e., addr/denom)

[C] unsigned int XPI\_Addr\_div(XPI\_Addr addr, unsigned int denom);

XPI\_ADDR\_DIV performs integer division on a global address. Division is an uncommon operation but is included for completeness.

# Chapter 6

## **Threads**

Threads model active computation in XPI. A thread is generated by the runtime as the result of a parcel delivery. A thread is managed and scheduled by its associated process, has synchronous access to its global address, the parcel argument data, the target address, and the data environment associated with the parcel from which it was instantiated. Furthermore, a thread may inspect and modify the continuation parcel that will be sent upon its termination. A user LCO thread has additional access to the local virtual address for the LCO's user data.

## 6.1 Actions

An XPI action represents the code executed as a result of delivering a parcel (Chapter 4). Note that an XPI thread is distinct from the action that is being performed; the thread being a runtime instance executing the action.

Many actions will represent statically compiled, user-defined functionality (Section 6.1.2), however parcels may carry their own code description as part of their payload. Such parcels target native process actions (Chapter 8) provided as part of the runtime that are responsible for the transformation of the action description into appropriate executable code at the target locality.

*Developer's note.* Just-in-time compilation and self-modifying code functionality is not yet available.

In addition to user-defined actions, XPI provides builtin actions to perform specific, predefined operations that have no user-defined equivalents. These builtin actions exist where XPI defines asynchronous, parcel-based access to runtime functionality.

Ultimately, all actions serve the same role as parcel target actions in XPI.

XPI Interface (ACTION\_NULL) ..... the NULL action ACTION\_NULL

[C] extern XPI\_Action XPI\_ACTION\_NULL;

The NULL action. When used as the action field in a parcel, the NULL action indicates that the processing of this parcel, and any continuation, should terminate.

### 6.1.1 Builtin Actions

This XPI specification predefines a number of builtin actions that act upon the XPI model itself, e.g., XPI\_PROCESS\_CREATE\_CHILD\_ACTION, XPI\_THREAD\_SET\_PRIORITY\_ACTION, ....

Many of these are *primitive* actions that represent asynchronous, parcel-based operations on low-level model components for which we anticipate platform-specific hardware support to be provided. These primitive actions have no equivalent, higher level implementation.

Other builtin actions, such as XPI\_PROCESS\_MEMCPY, can be described through the composition of primitive actions and are not strictly necessary. These higher-level actions are included both to augment the programmability of the XPI specification, as well as to convey high-level semantic information to the XPI runtime that may result in performance improvements through the use of platform specific hardware or internal runtime information.

Advice to users. Often XPI defines equivalent, higher-level, synchronous and asynchronous, function-based interfaces that provide similar behavior to builtin actions when paired with common continuations. The canonical example of this is the duality between the parcel interface to global memory and the asynchronous function-based interface to global memory (Section 5.3.1).

### 6.1.2 Static Actions

Static actions are user-defined actions that are written in a supported language, precompiled, and registered with the runtime through the XPI\_REGISTER\_ACTION\_WITH\_-KEY routine. As XPI thread entry points, static actions must respect a constrained, language-dependent interface and will execute with XPI thread semantics.

XPI threads are asynchronous and can not be *joined* in the sense of a traditional POSIX thread and do not return values in a traditional sense. Instead, action results are transmitted to continuation parcels. Secondly, all parameters to actions are passed by-value. This reflects the distributed nature of XPI systems. Global addresses may be passed to actions to simulate traditional reference semantics, however updates to such locations must be correctly synchronized. Finally, XPI actions may signal errors to the runtime, however these errors are not delivered to the parcel's sender.

Many of a program's actions will be written by the application developer. Within the XPI framework, such user actions are managed by an XPI process. Details for writing and registering actions can be found in Section 3.4.

### 6.1.3 Dynamic Actions

Most generic actions represent statically compiled code, however parcels may carry their own code description as part of their payload. Such parcels target process actions provided as part of the runtime that are responsible for the transformation of the code description into appropriate executable code at the target locality.

*Developer's note.* Dynamic user actions require complex, code generation support from the XPI runtime, and are not currently supported.

#### 6.1.4 LCO Actions

Chapter 7 describes the special semantics associated with local control object (LCO) actions. In particular, all threads executing LCO actions are strictly serializable on a per-LCO basis.

### 6.2 Instantiation

A parcel specifies (1) a (potentially XPI\_NULL) target address, (2) a target action, (3) the argument data block, and (4) the environment data block. In addition, a parcel contains a continuation block that models a stack of continuation parcels.

The runtime spawns a thread in response to a parcel arrival. This thread will be spawned executing the target action, with its data argument set to the argument data block (or a copy of it). The thread may query its global address, the target address, the environment data, or the continuation parcel using the synchronous functions in this section. The runtime sets the thread's continuation parcel to the result of XPI\_PARCEL\_POP on the generating parcel.

**XPI Interface (XPI\_THREAD\_GET\_SELF)** ...... get the calling thread's global address XPI\_THREAD\_GET\_SELF(addr)

OUT addr the global address of the calling thread

[C] XPI\_Addr XPI\_Thread\_get\_self();

XPI\_THREAD\_GET\_SELF can be used to get the global address corresponding to the local thread. All threads are guaranteed to have an address, thus this call will neither fail nor produce XPI\_NULL.

 $\textbf{XPI Interface (XPI\_THREAD\_GET\_ADDRESS)} \quad .... \quad get \ the \ target \ address$ 

XPI THREAD GET ADDRESS(addr)

OUT addr the target address

[C] XPI\_Addr XPI\_Thread\_get\_addr();

XPI\_THREAD\_GET\_ADDRESS this gets the target address that was set in the instantiating parcel. This address may be XPI\_NULL if that is how the parcel was created, but this call will always return successfully.

XPI Interface (XPI\_THREAD\_GET\_ENVIRONMENT) ..... get the environment data

XPI THREAD GET ENVIRONMENT(data)

OUT data the environment data

[C] void\* XPI\_Thread\_get\_env();

XPI\_THREAD\_GET\_ENVIRONMENT returns a pointer to the environment block that was set in the instantiating parcel. This address may be NULL if there was no environment set, but the call will always be successful.

```
XPI Interface (XPI_THREAD_GET_CONTINUATION) ...... get continuation parcel

XPI_THREAD_GET_CONTINUATION(parcel)

OUT parcel a handle for the continuation parcel

[C] XPI_Parcel XPI_Thread_get_cont();
```

XPI\_THREAD\_GET\_CONTINUATION gets a handle for the thread's continuation parcel. Updates using this handle will change the thread's continuation action. For example, XPI\_PARCEL\_PUSH will add to the front of the continuation chain for the thread.

Repeated calls to XPI\_THREAD\_GET\_CONTINUATION within a thread must return equivalent handles.

The handle to the continuation parcel should not be freed using XPI\_PARCEL\_FREE. Threads that would like to terminate their continuation early should push the null action (ACTION\_NULL) onto their continuation stack.

### 6.3 Continuing

Every thread has a continuation dynamically specified as part of its instantiating parcel, and will dynamically generate a continuation parcel as it terminates. Threads "continue" data by setting the argument data field for their continuation parcel. XPI contains some helper functions that allow this data to be set directly, without explicit use of the continuation parcel.

```
XPI Interface (XPI_CONTINUE) the continue primitive

XPI_CONTINUE(sizes, vals)

IN sizes an n-element list of sizes describing vals

IN vals an n-element list of values to pass to the continuation

[C] void XPI_continue(size_t n, size_t sizes[], const void * vals[]);

void XPI_continue1(size_t size, const void *val);
```

The C implementation provides two options for continuing, XPI\_CONTINUE behaves as specified in the XPI declaration. Many actions will only continue simple scalar values and can use continue1 directly for this purpose.

Only the data from the last use of XPI\_CONTINUE will be used as the continuation parcel's argument data.

### 6.4 Thread Scheduling

XPI provides a thread-scheduling interface for lower-level use. This interface is defined through a native action interface. A standard, asynchronous function interface is also provided that allows senders to order their operations with respect to the target thread's changes.

```
XPI Interface (XPI_THREAD_SET_PRIORITY) ..... set the priority for the target thread XPI_THREAD_SET_PRIORITY_ACTION(priority)
```

```
IN
              priority
                                        new priority
[C]
     XPI_Err XPI_THREAD_SET_PRIORITY_ACTION(size_t *priority) /* CONT() */;
     XPI_THREAD_SET_PRIORITY_SYNC(priority, address)
      IN
              priority
                                        new priority
      IN
              address
                                        global address of the target thread
[C]
      XPI_Err XPI_Thread_set_priority_sync(XPI_Addr address, size_t priority);
    XPI Interface (XPI_THREAD_SET_STATE) ...... change the state of the target thread
     XPI THREAD SET STATE ACTION(state)
      IN
              state
                                        requested state
typedef enum {
       XPI_THREAD_STATE_ACTIVE,
       XPI_THREAD_STATE_SUSPENDED,
       XPI_THREAD_STATE_DEPLETED,
       XPI THREAD STATE TERMINATED
      } XPI_Thread_State;
      XPI_Err XPI_THREAD_SET_STATE_ACTION(XPI_Thread_State *state); /* CONT() */
     XPI THREAD SET STATE SYNC(state, address)
      IN
                                        requested state
              state
      IN
              address
                                        global address of the target thread
[C]
      XPI_Err XPI_Thread_set_state_sync(XPI_Addr address, XPI_Thread_State state);
```

### 6.5 Thread Suspension

Threads often need to wait for the completion of concurrent activities. Waiting is managed using local control objects (LCOs), which act as a mechanism to delay processing until certain conditions are met. More information about LCOs and their use can be found in Chapter 7.

XPI provides threads with a *wait*-based synchronization interface that allows them to suspend execution until a set of LCOs fires. When these routines return, the designated (or one of the designated) LCO's trigger event is guaranteed to have occurred, but no guarantees are made about the state of the LCO's predicate when this parcel arrives. This is a natural consequence of the design choice that LCOs may fire more than once.

These routines are synchronous, and act on the local thread of execution.

```
XPI Interface (XPI_THREAD_WAIT) ...... wait until an LCO fires

XPI_THREAD_WAIT(Ico, value)

IN Ico global address of an LCO for which to wait

OUT value the value produced by the LCO
```

[C] XPI\_Err XPI\_Thread\_wait(XPI\_Addr lco, void \*value);

This blocks execution until the LCO fires. From an operational perspective, the runtime implicitly captures the thread's current live state and suspends it. When the designated thread fires, the thread is resumed and provided the local address of the LCO's value.

**XPI Interface (XPI\_THREAD\_WAIT\_ALL)** ...... wait until all of a set of LCOs are fired

XPI\_THREAD\_WAIT\_ALL(lcos, values)

IN lcos list of global addresses corresponding to LCOs on which

to wait

OUT values list of the values produced by the LCOs

[C] XPI\_Err XPI\_Thread\_wait\_all(size\_t n, XPI\_Addr lco[], void\* values[]);

This blocks until all of the LCOs in lcos have fired. Operationally, this behaves in the same manner as XPI\_THREAD\_WAIT, except that the thread is not resumed until all of the designated LCOs have fired, and is provided with the values of all of the LCOs in the values array.

### 6.6 Thread Resources

**XPI Interface (XPI\_THREAD\_GET\_PROCESS)** ... get the global address corresponding to a thread's process

XPI THREAD\_GET\_PROCESS\_ACTION CONTINUE(process)

CONT process global address of the thread's process

[C] XPI\_Err XPI\_THREAD\_GET\_PROCESS\_ACTION() /\* CONT(XPI\_Addr process) \*/;

XPI\_THREAD\_GET\_PROCESS(address, future)

IN address global address of the target thread

IN future a future representing the global address of the thread's

process

[C] XPI\_Err XPI\_Thread\_get\_process(XPI\_Addr address, XPI\_Addr future);

XPI\_THREAD\_GET\_PROCESS\_SYNC(address, process)

IN address global address of the target thread

OUT process the global address of the thread's process

[C] XPI\_Err XPI\_Thread\_get\_process\_sync(XPI\_Addr address, XPI\_Addr \*process);

### Chapter 7

# **Local Control Objects**

A Local Control Object (LCO) is a synchronization object that allows XPI applications to suspend continuation execution until arbitrary conditions are met. While LCOs are allocated as part of the global virtual address space, their physical memory allocations are guaranteed to exist in one synchronous domain. This invariant will be maintained even if the LCO needs to be relocated.

### 7.1 Properties

### 7.1.1 Strictly Serializable

One of the major characteristics of an LCO is that the system guarantees that threads executing LCO actions do so in a *strictly serializable* manner, with respect to the target LCO.

*Rationale.* Strict serializability ensures that real-time ordering of LCO action execution is maintained. This is slightly more restrictive a constraint relative to pure serializability and can prevent numerous programmer errors due to false assumptions, as threads may communicate through synchronized memory accesses or multiple LCOs concurrently.

*Advice to implementors.* We anticipate the continued adoption of transactional memory hardware within synchronous domains. This hardware is ideal for providing the synchronization guarantees laid out here.

Without such hardware, XPI library implementations will be restricted to LCO boundary-style synchronization that can execute inside the runtime before and after LCO action execution. We do not at this time expect to provide an XPI software interface (e.g., XPI\_LOCAL\_READ and XPI\_LOCAL\_WRITE macros, etc.) for fine-grained, library-based synchronization of LCO actions.

#### 7.1.2 Wait Free

LCO actions are prohibited from using the thread suspension interface in Section 6.5.

*Rationale.* This wait-free property limits the possibility for deadlock. The strict serializability (Section 7.1.1) interferes with asynchronous request-response programming, as it introduces dependencies that can be expensive to track and recover from, and

is neither supported in the current generation of hardware transactional memory systems nor likely in future systems.

Advice to implementors. XPI implementations are encouraged to provide a debugging option that detects erroneous uses of the wait interface (Section 6.5), or XPI-defined synchronous or asynchronous function-based operations, from within LCO actions, and reports such events during execution. This behavior is not required.

Advice to users. LCO actions should not use any asynchronous or synchronous function-based interfaces defined in this specification (e.g., the global memory interfaces provided in Section 5.3.1 or Section 5.3.2) as they imply a wait operation. This restriction does not affect the LCO's ability to initiate asynchronous work with XPI\_PARCEL\_SEND, however it does not allow LCO actions to reuse parcel handles across multiple waits.

### 7.1.3 Local Synchronous Memory

LCOs are defined to be entirely resident in one synchronous domain, thus LCO actions can be, and are required to be in all implementations, provided with the local virtual address of the LCO data. LCO actions cannot read from the global address space, due to the limitation that they are not allowed to wait.

The consequence of this property is that an LCO must not have its global address mapping modified during the execution of an LCO action, as the executing thread is accessing it's physical (i.e., synchronous) addresses.

Advice to implementors. An implementation must merely ensure that LCO address remapping conforms to the LCO's strict serialization. This naturally satisfies the previous constraint, and can permit concurrent relocation in some circumstances.

### 7.1.4 Polymorphic Actions

LCOs are special in that every LCO type, either system-specified or user-defined, supports a specific superset of LCO actions, but provides its own concrete implementations for these actions.

*Rationale.* As with most object-oriented systems, it is beneficial to separate interface from implementation, and to provide polymorphic behavior. This permits user-implemented LCOs that interact in the same manner as builtin LCOs.

### 7.1.5 Predicates

LCOs send pending continuations when their predicate is met. An LCO's predicate is automatically evaluated by the XPI runtime after its XPI\_LCO\_TRIGGER is processed, and during XPI\_LCO\_GET\_VALUE processing.

### 7.2 Common Interface

The following are valid for all LCOs, but have polymorphic behavior. This behavior is defined by the XPI specification for builtin LCO types, e.g., futures (Section 7.3.1), and have user-defined behavior for user-defined LCO types (Section 7.4).

```
XPI Interface (XPI_LCO_GET_VALUE)

XPI_LCO_GET_VALUE_ACTION CONTINUE(value)

CONT value the LCO value
```

XPI\_Err XPI\_LCO\_GET\_VALUE\_ACTION() /\* CONT(void \*data) \*/;

XPI\_LCO\_GET\_VALUE, along with XPI\_LCO\_TRIGGER are the two primary LCO actions. The XPI\_LCO\_GET\_VALUE action either continues the value of the LCO, or suspends its continuation until the value is available. The continued data type is dependent on the concrete class of the LCO.

XPI\_LCO\_GET\_VALUE has neither an asynchronous nor synchronous function-based version, as it's functionality is based directly on the parcel continuation. The thread's wait interface (Section 6.5) can be used to wrap XPI\_LCO\_GET\_VALUE in a synchronous interface.

Advice to users. Application developers can use XPI\_PARCEL\_SEND's optional spawned thread address future parameter to determine that the XPI\_LCO\_GET\_-VALUE has occurred. The strict serializable and wait-free properties of LCO threads makes this an adequate signal.

```
XPI Interface (XPI_LCO_TRIGGER) ...... trigger an LCO
    XPI LCO TRIGGER ACTION(value)
      IN
              value (optional)
                                       an optional trigger value
XPI_Err XPI_LCO_TRIGGER_ACTION(void *data) /* CONT() */;
    XPI LCO TRIGGER(value, Ico, future)
      IN
              value (optional)
                                       an optional trigger value
      IN
                                       address of the Ico to trigger
              lco
      IN
              future (optional)
                                       future to be used for ordering
XPI_Err XPI_LCO_trigger(XPI_Addr lco, const void *data, XPI_Addr future);
    XPI LCO TRIGGER SYNC(value, Ico)
      IN
              value (optional)
                                       an optional trigger value
      IN
              Ico
                                       address of the Ico to trigger
XPI_Err XPI_LCO_trigger_sync(XPI_Addr lco, const void *data);
```

With XPI\_LCO\_GET\_VALUE, XPI\_LCO\_TRIGGER forms the primary interface to an LCO. This action triggers the LCO to potentially change state. The LCO's predicate is automatically tested after the trigger executes, and if it evaluates as true, all of the LCO's pending continuations are released.

Unlike XPI\_LCO\_GET\_VALUE, XPI\_LCO\_TRIGGER provides both asynchronous and synchronized function-based interfaces.

```
XPI Interface (XPI_LCO_GET_SIZE) ..... get the size of an LCO, in bytes
     XPI_LCO_GET_SIZE_ACTION CONTINUE(size)
      CONT
              size
                                       the size of the user-portion of the LCO
[C]
      XPI_Err XPI_LCO_GET_SIZE_ACTION() /* CONT(size_t size) */;
     XPI LCO GET SIZE(Ico, future)
      IN
                                       global address of the LCO to query
              lco
      IN
              future
                                       future representing the size of the user-portion of the LCO
XPI_Err XPI_LCO_get_size(XPI_Addr lco, XPI_Addr future);
     XPI_LCO_GET_SIZE_SYNC(Ico, future)
      IN
              lco
                                       global address of the LCO to query
      OUT
              future
                                       the size of the user-portion of the LCO
XPI_Err XPI_LCO_get_size_sync(XPI_Addr lco, size_t *size);
        This action is used to read the size, in bytes, of the LCO structure. This will not include
    any additional bytes allocated by the process in order to provide support for LCO semantics
    for this object.
    XPI Interface (XPI_LCO_HAD_GET_VALUE) ......
     XPI_LCO_HAD_GET_VALUE_ACTION CONTINUE(value)
      CONT
              value
                                       true if any threads have performed XPI_LCO_GET_-
                                       VALUE on the target LCO
XPI_Err XPI_LCO_HAD_GET_VALUE_ACTION() /* CONT(bool) */;
     XPI LCO HAD GET VALUE(Ico, future)
      IN
              lco
                                       global address of the LCO to query
      IN
              future
                                       future representing the result of the query
[C]
      XPI_Err XPI_LCO_had_get_value(XPI_Addr lco, XPI_Addr future);
     XPI_LCO_HAD_GET_VALUE_SYNC(lco, value)
      IN
              lco
                                       global address of the LCO to query
      OUT
              value
                                       the result of the query
XPI_Err XPI_LCO_had_get_value_sync(XPI_Addr lco, bool *value);
```

XPI\_LCO\_HAD\_GET\_VALUE allows the application programmer to determine if any XPI\_LCO\_GET\_VALUE actions have been performed on the target LCO.

*Rationale.* This action is included in order to allow an application developer to effectively use process termination detection (Section 8.2) in a recursive design, where one process provides work for the next process by attaching continuations (XPI\_PROCESS\_ATTACH) to LCOs in the next process.

The next process can begin by querying the state of its LCOs with XPI\_LCO\_HAD\_-GET\_VALUE to determine if it should terminate the recursive algorithm.

```
XPI Interface (XPI_LCO_FREE) ......
    XPI LCO FREE ACTION
XPI_Err XPI_LCO_FREE_ACTION() /* CONT() */;
    XPI LCO FREE(Ico, future)
     IN
                                   global address of the LCO to free
            lco
     IN
            future
                                   future useful for ordering
XPI_Err XPI_LCO_free(XPI_Addr lco, XPI_Addr future);
    XPI LCO FREE SYNC(Ico)
     IN
                                   global address of the LCO to query
XPI_Err XPI_LCO_free_sync(XPI_Addr lco);
```

XPI\_LCO\_FREE frees an LCO. It is strictly serializable with respect to other LCO actions. This means that it is safe to have an XPI\_LCO\_FREE\_ACTION waiting on the LCO that it is to free. The trigger that releases all waiters will serialize before the free, thus all the pending waiting continuations will be sent.

Of course, it is possible to introduce races where an application frees an LCO top early. Programmers are responsible for ensuring that application logic prevents this from occurring.

### 7.3 Builtin LCOs

### **7.3.1** Future

Future LCOs have a special place in XPI, as they represent the results of asynchronous computation and are used throughout the XPI interface as a means of ordered synchronization.

### Allocation

```
[C] struct XPI_Process_Future_New {
    size_t count;
    size_t bytes;
    XPI_Distribution distribution;
};

XPI_Err XPI_PROCESS_FUTURE_NEW_ACTION(struct XPI_Process_Future_New *arg)
    /* CONT(XPI_Addr address) */;
```

### XPI\_PROCESS\_FUTURE\_NEW(count, bytes, process, future)

IN count the number of futures to allocateIN bytes size of the buffer for the LCOs

IN process address of the process

IN future (optional) a future representing the address of the array

```
[C] XPI_Err XPI_Process_future_new(XPI_Addr process, size_t count, size_t bytes,
XPI_Distribution distribution,
XPI_Addr future);
```

### XPI\_PROCESS\_FUTURE\_NEW\_SYNC(count, bytes, process, address)

IN count the number of futures to allocate
IN bytes size of the buffer for the LCOs

IN process address of the process
OUT address the address of the array

These three routines are used for future allocation. As with all LCOs, futures are allocated in the global namespace.

The asynchronous function-based version of XPI\_PROCESS\_FUTURE\_NEW requires a future that has been allocated with the action or synchronous version, and thus is of limited use.

Futures should be freed using the XPI\_LCO\_FREE action interface.

**Trigger** The trigger functionality for a future takes a single value, and makes the value available using the XPI\_LCO\_GET\_VALUE action.

**Get Value** The get value functionality for a future simply continues the value of the future to the pending continuations once it is available.

### 7.3.2 Reduction

The reduction LCO suspends execution of waiting continuations until it has seen the expected number of XPI\_LCO\_TRIGGER events. This LCO will compute a reduction (as designated in XPI\_PROCESS\_REDUCTION\_NEW) of the trigger values, and continue the reduced value in XPI\_LCO\_GET\_VALUE.

#### Allocation

# **XPI\_PROCESS\_REDUCTION\_NEW)** ..... allocate an array of reductions XPI\_PROCESS\_REDUCTION\_OPERATOR

[C] typedef void (\*XPI\_reduction\_operator) (const void \*lhs, const void \*rhs, void \*result);

```
XPI PROCESS REDUCTION NEW ACTION(count, bytes, inputs, op) CONTINUE(address)
```

IN count the number of lcos to allocate
 IN bytes size of the value type for the LCOs
 IN inputs the number of inputs to the reduction

IN op the binary reduction operator

CONT address the address of the array

### XPI PROCESS REDUCTION NEW(count, bytes, inputs, op, process, future)

IN count the number of lcos to allocateIN bytes size of the value type for the LCOsIN inputs the number of inputs to the reduction

IN op the binary reduction operator

IN process address of the process

IN future (optional) a future representing the address of the array

### XPI\_PROCESS\_REDUCTION\_NEW\_SYNC(count, bytes, inputs, op, process, future)

IN count the number of lcos to allocateIN bytes size of the value type for the LCOsIN inputs the number of inputs to the reduction

```
IN op the binary reduction operator
IN process address of the process
OUT future (optional) the address of the array
```

The binary reduction operator, op, must be both commutative and associative. User LCOs (Section 7.4) can be used to define more complex reductions. A NULL operator can be used to implement a local barrier.

**Trigger** The trigger for the builtin reduction calls the relevant reduction operator with the address of the existing value and the address of the trigger data argument.

**Get Value** The get value functionality for a reduction simply continues the reduced value to the pending continuations once it has been computed.

### 7.4 User LCOs

Special considerations need to be taken for the development of user-defined LCOs, due in particular to their unique capability to polymorphic actions. These considerations are language specific.

User LCOs need to handle five events.

- The initialization event handler. Initialization occurs during XPI\_PROCESS\_LCO\_MALLOC, after local memory has been allocated but before the global address is available. As with standard object-oriented design, initialization is a chance to initialize the LCO's state.
- The trigger event handler. The trigger event handler is used inside the XPI\_LCO\_-TRIGGER action to update the private state of the LCO.
- The get value event handler. The get value event handler is used inside the XPI\_LCO\_GET\_VALUE action to provide the value of the lco to XPI\_LCO\_GET\_VALUE continuations.
- The get size event handler. The get size event handler is used inside the XPI\_LCO\_-GET\_SIZE action to return the size of the value of the LCO.
- The predicate evaluation event handler. The predicate evaluation is used by the XPI runtime in both the XPI\_LCO\_TRIGGER action, after the trigger event handler has executed, and in XPI\_LCO\_GET\_VALUE action, before the parcel continuation is suspended.

### 7.4.1 C Specification

The per-object function pointer table pattern common in many C-based object-oriented designs is used to specify the behavior of a user LCO in C. At LCO allocation-time (XPI\_PROCESS\_LCO\_MALLOC), handlers for each of the five events listed above must be provided to the runtime.

XPI Interface (XPI\_PROCESS\_LCO\_MALLOC) ...... allocate an array of LCOs
XPI LCO DESCRIPTOR

```
[C] typedef struct {
    void (*init) (void * const lco, const void * const data);
    void (*trigger) (void * const lco, const void * const data);
    bool (*eval) (const void * const lco);
    const void * (*get_value) (const void * const lco);
    size_t (*get_size) (const void * const lco);
} XPI_LCO_Descriptor;
```

The previous interface is used to describe the user LCO event handlers. These handlers are run inside of LCO actions, and thus can assume strictly serializable semantics with respect to the lco state and any data inputs.

- init This handles initialization of the LCO.
- trigger This handles the XPI\_LCO\_TRIGGER action, and should update the LCO's state.
- get\_value This is called to evaluate the LCO's predicate. It should not change the state of the LCO. The implementation may cache the result once it returns true.
- get\_size This should return the size of the value of the LCO.
- get\_value This should return the address of the computed value of the LCO. This will only be called when eval has returned true, and should point to memory of at least get\_size bytes. The return address or value may be cached by the implementation.

LCO handlers must not dynamically allocate data.

*Rationale.* LCOs may migrate within the distributed memory of a machine, and do not currently support serialization.

XPI PROCESS LCO MALLOC ACTION(count, size, handlers, distribution) CONTINUE(address)

IN	count	the number of LCOs to allocate
IN	size	number of bytes required for LCO state
IN	handlers	user LCO event handlers
IN	distribution	the distribution for the array
CONT	address	global address of the allocated LCO

```
struct XPI_Process_LCO_Malloc_Descriptor {
       size_t count;
       size_t size;
       XPI_LCO_Descriptor handlers;
       XPI_Distribution distribution;
       size_t init_data_size;
        const void * const init_data;
      XPI_Err XPI_PROCESS_LCO_MALLOC_ACTION(struct XPI_Process_LCO_Malloc_Descriptor *arg)
         /* CONT(XPI_Addr address) */;
     XPI PROCESS LCO MALLOC(count, size, handlers, distribution, process, future)
      IN
                                          the number of LCOs to allocate
               count
      IN
                                          number of bytes required for LCO state
               size
      IN
               handlers
                                          user LCO event handlers
      IN
               distribution
                                          the distribution for the array
      IN
               process
                                          global address of the allocating process
      IN
               future
                                          a future representing the global address of the allocated
                                          LCO
[C]
      XPI_Err XPI_Process_lco_malloc(XPI_Addr process,
                               size_t count, size_t size,
                               XPI_LCO_Descriptor handlers,
                               XPI_Distribution distribution,
                               size_t init_data_size, const void * const init_data,
                               XPI_Addr future);
     XPI PROCESS LCO MALLOC SYNC(count, size, handlers, distribution, process, address)
      IN
                                          the number of LCOs to allocate
               count
      IN
               size
                                          number of bytes required for LCO state
      IN
               handlers
                                          user LCO event handlers
      IN
               distribution
                                          the distribution for the array
      IN
               process
                                          global address of the allocating process
      OUT
                                          the address of the allocated LCO
               address
[C]
      XPI_Err XPI_Process_lco_malloc_sync(XPI_Addr process,
                                   size_t count, size_t size,
                                   XPI_LCO_Descriptor handlers,
                                   XPI_Distribution distribution,
                                   size_t init_data_size, const void * const init_data,
                                   XPI_Addr *address);
```

This action, and its corresponding function-based interface, deal with the special allocation requirements for LCOs. In particular, LCOs must specify the set of event handlers required by the User LCO interface.

LCOs should be freed using the standard XPI\_LCO\_FREE action.

### 7.4.2 Fortran Specification

*Developer's note.* Fortran bindings are not yet available, and may never be appropriate for LCO development.

### **Chapter 8**

### **Processes**

XPI processes manage and partition application resources, and provide a source of distributed control, serving as the largest granularity of parallelism in the system. Processes are first-class objects in the global address space.

Processes are organized into a tree structure. The XPI *main* process is always the root process in the process tree, and has some special properties, described thoroughly in Section 8.4. Processes provide optional termination detection.

### 8.1 Instantiation & Destruction

Processes are always instantiated as children of parent processes.

```
XPI Interface (XPI_PROCESS_CREATE_CHILD) ...... create a child process
```

XPI\_PROCESS\_CREATE\_CHILD\_ACTION(terminate) CONTINUE(address)

IN terminate address of an LCO that will be triggered at termina-

tion

CONT address the address of the new process

```
[C] XPI_Err XPI_PROCESS_CREATE_CHILD_ACTION(void *terminate)  /* \  \  \text{CONT}(\text{XPI}\_\text{Addr address}) \  \  */;
```

The XPI\_PROCESS\_CREATE\_CHILD\_ACTION creates a new process as the child of the target, parent process. The address of the new process is continued to the parcel continuation, which will be executed as the initial action within the context of the new process.

The termination address should either be XPI\_NULL, or the address of an LCO that will be triggered when the process terminates. If the termination address is not XPI\_NULL, then the process will implement automatic termination detection (Section 8.2), otherwise it will not.

Advice to users. Processes often compute some sort of return value. This should be implemented using the continuation chain that XPI\_PROCESS\_CREATE\_CHILD is instantiated with.

#### **Example 8.1** *Creating a process*

In this example, we will define an action, action\_my\_external, that spawns a new process as the child of its parent process, and enable termination detection for the new process. action\_my\_external will wait for the new process to terminate.

This example, as well as Example 8.3 and Example 8.2, relies on the following action-registration code.

```
XPI_Err action_my_process(XPI_Addr *process) /* CONT(int) */;
XPI_Err action_my_get_address(XPI_Addr *process) /* CONT(XPI_Aaddr) */;
/* register the local actions we need with the runtime */
static __attribute__((constructor)) void
init() {
    XPI_register_action((XPI_Action)action_my_process);
    XPI_register_action((XPI_Action)action_my_get_address);
}
```

The process itself is described by the action\_my\_process action, which can have arbitrarily complex behavior but generates an int as a result—this can be considered part of the process' type.

```
XPI_Err
action_my_process(XPI_Addr *process) {
   int result;
   :
   :
   XPI_continue1(sizeof(result), &result);
   return XPI_SUCCESS;
}
```

The declaration for the action\_my\_external simply conforms to the C action interface. action\_my\_external does not use its argument data, though a real application likely would. action\_my\_external starts by getting the global address of the thread, and the process.

```
1    XPI_Err
2    action_my_external(void* args __attribute__((unused))) {
3         XPI_Addr self = XPI_Thread_get_self();
4         XPI_Addr parent; XPI_Thread_get_process_sync(self, &parent);
```

It then creates a future that will be sent as the termination data argument to the XPI\_PRO-CESS\_CREATE\_CHILD action, indicating that we would like this process to employ a termination detection algorithm.

It then creates the parcel chain that describes the behavior of the process itself. In this case, we are simply creating the action defined by action\_my\_process, registered as "process", and then pushing the XPI\_PROCESS\_CREATE\_CHILD on the chain.

```
XPI_Parcel_push(p);
XPI_Parcel_set_addr(p, parent);
XPI_Parcel_set_action(p, XPI_PROCESS_CREATE_CHILD_ACTION);
XPI_Parcel_set_data(p, sizeof(XPI_Addr), &get_terminate);
```

Finally, action\_my\_external sends the request out, and waits for the future to be triggered, indicating that termination of the child process has been detected.

Note that termination detection cannot retrieve a value from the process. Combining termination detection with a return value requires a separation of concerns, as described in Example 8.3.

### **Example 8.2** *Returning the address of a process*

Example 8.1 demonstrates the example of creating a child process that depends on termination detection, and waiting for it to complete. It can be useful for the spawning thread to get the address of the child process, before the child process completes. In such a situation we can push an additional action onto the new process' chain that returns the new process' address to an externally-allocated LCO.

The action\_my\_get\_address below does exactly this (using the same action registration code as Example 8.1).

```
XPI Err
action_my_get_address(XPI_Addr *process) {
   /* environment consists of an LCO address to send the process */
  void *env = XPI_Thread_get_env();
  if (!env)
     return XPI_SUCCESS;
  XPI_Addr lco = *(XPI_Addr*)env;
   if (XPI_Addr_sub(lco, XPI_NULL) != 0)
     return XPI_SUCCESS;
   /* trigger the LCO from the environment with the address */
  XPI_Parcel p;
  XPI_Parcel_create(&p);
  XPI_Parcel_set_addr(p, lco);
  XPI_Parcel_set_action(p, XPI_LCO_TRIGGER_ACTION);
  XPI_Parcel_set_data(p, sizeof(XPI_Addr), process);
  XPI_Parcel_send(p, XPI_NULL, XPI_NULL);
  XPI_Parcel_free(p);
   /* continue the address on */
  XPI_continue1(sizeof(XPI_Addr), process);
  return XPI_SUCCESS;
```

Given this implementation, we can modify action\_my\_external to (1) allocate a future to receive the address once it's available, (2) push the action\_my\_get\_address action onto parcel p's continuation stack before action\_my\_process, and (3) wait for the address to be returned.

```
XPI_Err
action_my_external(void* args __attribute__((unused))) {
  XPI_Addr self = XPI_Thread_get_self();
  XPI_Addr parent; XPI_Thread_get_process_sync(self, &parent);
  XPI_Addr get_child;
  XPI_Process_future_new_sync(parent, /* process */
                      1, /* count */
                       sizeof(XPI_Addr), /* bytes */
                       XPI_LOCAL, /* distribution */
                       &get_child);
  XPI_Parcel_push(p);
  XPI_Parcel_set_addr(p, parent);
  XPI_Parcel_set_action(p, (XPI_Action)action_my_get_address);
  XPI_Parcel_set_env(p, sizeof(XPI_Addr), &get_child);
  XPI_Parcel_send(p, XPI_NULL, XPI_NULL);
  XPI_Parcel_free(p);
  XPI_Addr child;
  XPI_Thread_wait(get_child, &child);
  return XPI_SUCCESS;
}
```

**Example 8.3** Returning a value from a process Example 8.2 shows the basic tools required to return a value from a process. The process creator allocates a future, and provides the appropriate XPI\_LCO\_TRIGGER parcel as part of the XPI\_PROCESS\_CREATE\_CHILD continuation stack. Recall that the action\_my\_process action continues the computed result value.

```
XPI_Err
action_my_process(XPI_Addr *process) {
   int result;
   :
   :
   XPI_continue1(sizeof(result), &result);
   return XPI_SUCCESS;
}
```

In order to retrieve this, action\_my\_external must (1) allocate an appropriate future to receive the result, (2) push XPI\_LCO\_TRIGGER onto the process' continuation stack—before action\_my\_process so that it is the "final operation" within the process, and (3) wait for the result.

```
XPI_Err
action_my_external(void* args __attribute__((unused))) {
   XPI_Addr self = XPI_Thread_get_self();
   XPI_Addr parent; XPI_Thread_get_process_sync(self, &parent);
```

```
XPI_Addr get_result;
      XPI_Process_future_new_sync(parent, /* process */
                                /* count */
                          1,
                           sizeof(int), /* bytes */
                           XPI_LOCAL, /* distribution */
                           &get result);
      XPI_Parcel p;
      XPI_Parcel_create(&p);
      XPI_Parcel_set_addr(p, get_result);
      XPI_Parcel_set_action(p, XPI_LCO_TRIGGER_ACTION);
      XPI_Parcel_send(p, XPI_NULL, XPI_NULL);
      XPI_Parcel_free(p);
      int result;
      XPI_Thread_wait(get_result, &result);
      return XPI_SUCCESS;
   XPI Interface (XPI_PROCESS_FREE) ...... frees a process
    XPI_PROCESS_FREE_ACTION
XPI_Err XPI_PROCESS_FREE_ACTION() /* CONT() */;
    XPI_PROCESS_FREE(process, future)
     IN
                                     the process being freed
             process
                                     a future to be used for ordering
     IN
             future (optional)
XPI_Err XPI_Process_free(XPI_Addr process, XPI_Addr future);
    XPI_PROCESS_FREE_SYNC(process)
     IN
             process
                                     the process being freed
[C]
     XPI_Err XPI_Process_free_sync(XPI_Addr process);
```

XPI\_PROCESS\_FREE frees the target process. It may be performed by a thread in the context of the to-be-destroyed process. Any continuation actions associated with the XPI\_PROCESS\_FREE thread will be performed in the context of the process' parent. Any active threads or parcels within the context of the process at the time of the XPI\_PROCESS\_FREE will result in undefined behavior, as will the use of either the synchronous or asynchronous function-based interface from within the context of the process.

Orphaned children of a destroyed process are reparented to the main process.

**Example 8.4** Freeing a process In most cases requiring termination detection, freeing a process should be done by sending a XPI\_PROCESS\_FREE action to the process once termination is detection. An optional way to do this is by suspending a XPI\_PROCESS\_FREE action on the LCO used to signal termination.

In Example 8.2 we use action\_my\_get\_address to retrieve the address of the child process in action\_my\_process. Using the infrastructure from this example, we can modify action\_my\_process to correctly free the process by spawning a parcel chain that waits for the get\_address LCO and then continues with XPI\_PROCESS\_FREE.

```
XPI_Err
action_my_external(void* args __attribute__((unused))) {
  XPI_Addr self = XPI_Thread_get_self();
  XPI_Addr parent; XPI_Thread_get_process_sync(self, &parent);
  XPI_Addr child;
  XPI_Thread_wait (get_child, &child);
  XPI_Parcel q;
  XPI_Parcel_create(&q);
  XPI_Parcel_set_addr(q, child);
  XPI_Parcel_set_action(q, XPI_PROCESS_FREE_ACTION);
  XPI_Parcel_push (q);
  XPI_Parcel_set_addr(q, get_terminate);
  XPI_Parcel_set_action(q, XPI_LCO_GET_VALUE_ACTION);
  XPI_Parcel_send(q, XPI_NULL, XPI_NULL);
  XPI_Parcel_free(q);
  XPI_Thread_wait(get_terminate, NULL);
  return XPI_SUCCESS;
```

In a process that does not use termination detection, it often makes sense to push the XPI\_-PARCEL\_FREE action as the last action performed within the context of the process itself, or, as with the termination detection case, suspending a XPI\_PARCEL\_FREE parcel targeting the child on a return result LCO.

### 8.2 Termination Detection

Processes provide termination detection. A process is considered to be terminated when it has (1) no sent-but-not yet instantiated parcels within the process, (2) no active threads, and (3) no continuations waiting on LCOs.

When termination is detected, the process will craft and send an XPI\_LCO\_TRIGGER parcel to the address specified during XPI\_PROCESS\_CREATE\_CHILD, if it was non-XPI\_NULL. Termination detection does not continue any data through the XPI\_LCO\_TRIGGER. A process that relies on termination detection is only invoked for the purposes of its side effects.

XPI Interface (XPI\_PROCESS\_ATTACH) ...... attach a continuation to a process

### XPI\_PROCESS\_ATTACH\_ACTION

```
[C] XPI_Err XPI_PROCESS_ATTACH_ACTION() /* CONT() */;
```

External threads may attach continuations to an active process using the XPI\_PRO-CESS\_ATTACH action. The XPI\_PROCESS\_ATTACH action's thread occurs in the context of the sender's process, and the continuation parcel occurs in the context of the target process.

This transition between processes is *atomic*, i.e., there does not exist a time at which XPI\_PROCESS\_ATTACH has completed and the continuation parcel has not yet been sent in the context of the target process. This ensures that no thread or parcel becomes orphaned as a side effect of termination detection.

Of course, if the target process is terminated before the XPI\_PROCESS\_ATTACH continuation is sent, a runtime error will occur. It is the responsibility of the application programmer to ensure that the target process does not terminate in this circumstance.

### 8.3 Key-Value Store

XPI processes provide a hierarchical key-value store for XPI applications that would like to use named global data. Key-values are not mutable once set.

*Rationale.* The key-value store is intended to provide the capability for XPI actions to access global data without requiring XPI developers to thread global addresses throughout parcel continuation data. Global data typically consists of a global address for a static resource, such as a process-wide color map for a graph. In traditional C applications these are managed directly by the compiler and linker.

```
XPI Interface (XPI_PROCESS_CREATE_VALUE) ...... create a key-value entry
```

### XPI\_PROCESS\_CREATE\_VALUE(key, value, process, future)

IN	key	the key for the entry
IN	value	the value for the entry
IN	process	global address of the allocating process
IN	future	a future that can be used for ordering

XPI\_PROCESS\_CREATE\_VALUE\_SYNC(key, value, process)

IN key the key for the entry

IN value the value for the entry

IN process global address of the allocating process

[C] XPI\_Err XPI\_Process\_create\_value\_sync(XPI\_Addr process, const char \*const name, size\_t size, const void \*value);

Creates the key-value mapping in the target process. The mapping may not be modified, and is not inherited by child processes. This allows child processes to override the mapping if necessary.

XPI Interface (XPI\_PROCESS\_READ\_VALUE) ..... reads a key-value entry

XPI\_PROCESS\_READ\_VALUE\_ACTION(key) CONTINUE(i)

IN key the key for the entry

CONT i the value for the entry

[C] XPI\_Err XPI\_PROCESS\_READ\_VALUE\_ACTION(char \*name) /\* CONT(void\*) \*/;

XPI\_PROCESS\_READ\_VALUE(key, process, future)

IN key the key for the entry

IN process global address of the allocating process

IN future a future that represents the value

XPI\_PROCESS\_READ\_VALUE\_SYNC(key, process, result)

IN key the key for the entry

IN process global address of the allocating process

OUT result the stored value

Queries the target process to retrieve the value for the specified key. This does not perform a search through the process tree. The synchronous version of this routine must ensure that there is enough space available in the result buffer for the value.

### 8.4 Main Process

The XPI *main* process is the root of the process hierarchy, and has some special properties with respect to XPI execution. The main process has a designated initial continuation, the main action, that must be provided by the application developer. This action cannot be targeted by application parcels, and thus has no XPI\_MAIN definition suitable for registration, but merely has the C and Fortran specifications for XPI\_MAIN.

This is not implemented by XPI. It merely describes the interface that XPI applications are required to provide as the initial action for the main process.

The main process initially owns the entire global address space mapping. As the process hierarchy evolves, applications can allocate parts of this space in other, child processes using the allocation and distribution interface. Ownership is exclusive, but reverts back to parent processes as children are terminated.

The main process serves as the reparenting target for orphaned process, serving a role similar to the *init* process in Unix-like systems. A reparented process maintains the structure of it's subtree in the original hierarchy, and will promote its allocated memory into that that of the main process when it terminates.

Terminating the main process terminates the entire XPI application, as any orphaned processes cannot be reparented. The main process will terminate itself if it has no child processes nor active threads.

### 8.5 Hierarchy Inspection

The process hierarchy can be traversed using the following tree-style traversal routines.

Advice to users. These routines are not synchronized in any manner. Applications requiring synchronized process hierarchy traversals must provide their own synchronization structures on top of this interface.

```
XPI Interface (XPI_PROCESS_GET_PARENT) ..... get a process' parent process
    XPI PROCESS GET PARENT ACTION CONTINUE(parent)
     CONT
              parent
                                       the parent process address
XPI_Err XPI_PROCESS_GET_PARENT_ACTION() /* CONT(XPI_Addr parent) */;
    XPI_PROCESS_GET_PARENT(process, future)
     IN
                                       the process being queried
              process
     IN
              future
                                       a future representing the process address
[C]
     XPI_Err XPI_Process_get_parent(XPI_Addr process, XPI_Addr future);
```

XPI\_PROCESS\_GET\_PARENT\_SYNC(process, parent) IN process the process being queried OUT parent the parent process address [C] XPI\_Err XPI\_Process\_get\_parent\_sync(XPI\_Addr process, XPI\_Addr \*parent); This gets the address of a processes' parent process. The main process will return XPI\_-NULL. An orphaned process will return the address of the main process—see Section 8.4 for details. **XPI Interface (XPI\_PROCESS\_GET\_N\_CHILDREN)** ... get a process' number of children XPI PROCESS GET N CHILDREN ACTION CONTINUE(n) CONT the number of children of the process [C] XPI\_Err XPI\_PROCESS\_GET\_N\_CHILDREN\_ACTION() /\* CONT(size\_t n) \*/; XPI PROCESS GET N CHILDREN(process, future) IN process the process being queried IN future a future representing the number of children of the process [C] XPI\_Err XPI\_Process\_get\_n\_children(XPI\_Addr process, XPI\_Addr future); XPI\_PROCESS\_GET\_N\_CHILDREN\_SYNC(process, future) IN process the process being queried OUT future the number of children of the process [C] XPI\_Err XPI\_Process\_get\_n\_children\_sync(XPI\_Addr process, size\_t \*n); This retrieves the number of children for a process. XPI Interface (XPI PROCESS GET CHILD) ...... get a process' child process XPI\_PROCESS\_GET\_CHILD\_ACTION(i) CONTINUE(child) IN i the index CONT child the address of the i-th child XPI\_Err XPI\_PROCESS\_GET\_CHILD\_ACTION(size\_t \*i) /\* CONT(XPI\_Addr child) \*/; XPI PROCESS GET CHILD(i, process, future) IN i the index the process being queried IN process IN a future representing the address of the *i*-th child future [C] XPI\_Err XPI\_Process\_get\_child(XPI\_Addr process, size\_t i, XPI\_Addr future);

```
XPI_PROCESS_GET_CHILD_SYNC(i, process, child)
```

IN i the index

IN process the process being queried
OUT child the address of the *i*-th child

[C] XPI\_Err XPI\_Process\_get\_child\_sync(XPI\_Addr process, size\_t i, XPI\_Addr \*child);

This retrieves the i-th child of a process. If i is out of the range of valid child indices, this will return XPI\_NULL.

### 8.6 Memory Management

#### 8.6.1 Allocation & Distribution

XPI defines a *C*-like, malloc, free interface for global memory allocation. The allocation interface provides hints to suggest allocation distributions to the runtime. Actual allocation distributions may not match the hint, and are not static.

XPI Interface (XPI\_PROCESS\_GLOBAL\_MALLOC) ...... allocate global memory

```
XPI PROCESS GLOBAL MALLOC ACTION(size, count, distribution) CONTINUE(result)
```

IN size the number of bytes to allocate

IN count the number of array elements to allocate

IN distribution an initial distribution hint

CONT result the global address of the allocation

```
[C] struct XPI_Global_Malloc_Descriptor {
    size_t count;
    size_t size;
    XPI_Distribution distribution;
};

XPI_Err XPI_PROCESS_GLOBAL_MALLOC_ACTION(struct XPI_Global_Malloc_Descriptor *arg)
    /* CONT(XPI_Addr address) */;
```

### XPI\_PROCESS\_GLOBAL\_MALLOC(size, count, distribution, process, future)

```
IN size the number of bytes to allocate
```

IN count the number of array elements to allocate

IN distribution an initial distribution hint

IN process the process which should allocate the memory

IN future representing the global address of the allocation

XPI PROCESS GLOBAL MALLOC SYNC(size, count, distribution, process, future)

IN	size	the number of bytes to allocate
IN	count	the number of array elements to allocate
IN	distribution	an initial distribution hint
IN	process	the process which should allocate the memory

OUT future the global address of the allocation

Allocates a *size*-byte region in global memory. The distribution parameter provides a hint to the implementation of how this allocation should be initially distributed. This operation is currently defined to be synchronous.

```
XPI Interface (XPI_PROCESS_GLOBAL_FREE) ..... free a global memory region
```

```
XPI_PROCESS_GLOBAL_FREE_ACTION(address)
```

IN address the global memory to free

[C] XPI\_Err XPI\_PROCESS\_GLOBAL\_FREE\_ACTION(XPI\_Addr \*address) /\* CONT() \*/;

XPI\_PROCESS\_GLOBAL\_FREE(address, process, future)

IN address the global memory to free

IN process where the memory was allocated

IN future (optional) a future to be used for ordering

```
XPI_PROCESS_GLOBAL_FREE_SYNC(address, process)
```

IN address the global memory to free

IN process where the memory was allocated

[C] XPI\_Err XPI\_Process\_global\_free\_sync(XPI\_Addr process, XPI\_Addr address);

Frees a region of globally allocated memory. The address must be the result of an XPI\_PROCESS\_GLOBAL\_MALLOC\_ACTION call. This call is asynchronous, however the future can be used to wait until the operation has completed globally. It is not an error to free XPI\_NULL.

*Rationale.* XPI relies on relocatable data and execution to account for load imbalances that introduce latency or waiting. It's philosophy is that data distributions for exascale applications will be most effectively managed by the runtime. XPI acknowledges that, in many cases, the programmer will know what a reasonable distribution of the data will be in advance, and thus XPI provides the hint-based allocation scheme, to minimize overheads due to distribution warm up.

Advice to users. Users may not assume that the requested distribution has been satisfied, nor should they assume that the distribution remains consistent throughout the execution of the code.

### 8.6.2 Global Virtual Memory Mapping

The global address space is a virtual address space, implying that there exists a virtual—physical address mapping layer in the hardware or runtime. It is active because this mapping can be modified dynamically at runtime by either the system automatically, or explicitly by the application. This is important because, unlike cache-based shared memory systems, we expect the physical address to encode location information.

```
XPI Interface (XPI PROCESS PIN) ...... pin a global memory region
     XPI PROCESS PIN ACTION(process, base, extent) CONTINUE(result)
      IN
                                         the process managing the memory region
               process
      IN
                                         the base global address to pin
               base
      IN
                                         the extent to pin
               extent
      CONT
               result
                                         the local virtual address corresponding to base
struct XPI_Process_Pin_Descriptor {
       XPI Addr base;
       XPI_AddrDiff extent;
      XPI_Err XPI_PROCESS_PIN_ACTION(struct XPI_Process_Pin_Descriptor *arg)
         /* CONT(void* address) */;
     XPI PROCESS PIN(process, base, extent, future)
      IN
                                         the process managing the memory region
               process
      IN
                                         the base global address to pin
               base
      IN
               extent
                                         the extent to pin
      IN
               future
                                         a future representing the local virtual address correspond-
                                         ing to base
[C]
      XPI_Err XPI_Process_pin(XPI_Addr process, XPI_Addr base, XPI_AddrDiff extent,
                         XPI_Addr address);
     XPI PROCESS PIN SYNC(process, base, extent)
      IN
                                         the process managing the memory region
               process
      IN
                                         the base global address to pin
               base
      IN
               extent
                                         the extent to pin
XPI_Err XPI_Process_pin_sync(XPI_Addr process, XPI_Addr base,
                             XPI_AddrDiff extent, void **result);
        Pins a global address range. The entire range should be part of a single allocation, and
```

XPI Interface (XPI\_PROCESS\_UNPIN) ...... unpin a global memory region

XPI PROCESS UNPIN ACTION(process, address)

resident locally.

IN process managing the memory region

IN address to unpin

[C] XPI\_Err XPI\_PROCESS\_UNPIN\_ACTION(XPI\_Addr \*address) /\* CONT() \*/;

XPI PROCESS UNPIN(process, address, future)

IN process managing the memory region

IN address to unpin

IN future (optional) a future to be used for ordering

[C] XPI\_Err XPI\_Process\_unpin(XPI\_Addr process, XPI\_Addr address, XPI\_Addr future);

XPI\_PROCESS\_UNPIN\_SYNC(process, address)

IN process managing the memory region

IN address to unpin

[C] XPI\_Err XPI\_Process\_unpin\_sync(XPI\_Addr process, XPI\_Addr address);

This action releases a previously pinned region to the system. The *address* must correspond to the global base address of a previously pinned region.

### 8.6.3 Standard Library

XPI Interface (XPI\_PROCESS\_MEMCPY) ........... copy data within global memory

XPI PROCESS MEMCPY ACTION(process, from, to, bytes) CONTINUE(from)

IN process the process responsible for the operation

IN from the global address to copy fromIN to the global address to copy fromIN bytes the number of bytes to copy

CONT from the from address

```
[C] struct XPI_Process_Memcpy_Descriptor {
    XPI_Addr from;
    XPI_Addr to;
    size_t bytes;
};

XPI_Err XPI_PROCESS_MEMCPY_ACTION(struct XPI_Process_Memcpy_Descriptor *arg)
    /* CONT(XPI_Addr from) */;
```

### XPI\_PROCESS\_MEMCPY(process, from, to, bytes, future)

IN process the process responsible for the operation
IN from the global address to copy from

IN to the global address to copy from

IN bytes the number of bytes to copy

IN future (optional) a future representing the *from* address

### XPI\_PROCESS\_MEMCPY\_SYNC(process, from, to, bytes)

IN	process	the process responsible for the operation
IN	from	the global address to copy from
IN	to	the global address to copy from
IN	bytes	the number of bytes to copy

Copies bytes in the global address space asynchronously. The from and to ranges may overlap. The future provides strong ordering if needed.

# Appendices

# Appendix A

# **XPI Declarations**

XPI_INIT
XPI_RUN
XPI_FINALIZE 10
XPI_ABORT 10
XPI_VERSION
XPI_REGISTER_ACTION_WITH_KEY11
XPI_PARCEL_CREATE
XPI_PARCEL_CLONE
XPI_PARCEL_FREE
XPI_PARCEL_SET_ADDR
XPI_PARCEL_SET_ACTION
XPI_PARCEL_SET_ENV
XPI_PARCEL_SET_DATA 15
XPI_PARCEL_PUSH
XPI_PARCEL_POP
XPI_PARCEL_SEND
XPI_APPLY 17
XPI_PARCEL_SELECT
XPI_PARCEL_GET_ADDR
XPI_PARCEL_GET_ACTION
XPI_PARCEL_GET_ENV
XPI_PARCEL_GET_DATA
XPI_AGAS_LOAD
XPI_AGAS_STORE
XPI_AGAS_CAS
XPI_ADDR_INIT
XPI_ADDR_ADD
XPI_ADDR_SUB 33
XPI_ADDR_MOD
XPI_ADDR_DIV
XPI_THREAD_GET_SELF
XPI_THREAD_GET_ADDRESS
XPI_THREAD_GET_ENVIRONMENT
XPI THREAD GET CONTINUATION

XPI_CONTINUE
XPI_THREAD_SET_PRIORITY
XPI_THREAD_SET_STATE 38
XPI_THREAD_WAIT
XPI_THREAD_WAIT_ALL 39
XPI_THREAD_GET_PROCESS
XPI_LCO_GET_VALUE 42
XPI_LCO_TRIGGER
XPI_LCO_GET_SIZE
XPI_LCO_HAD_GET_VALUE
XPI_LCO_FREE
XPI_PROCESS_FUTURE_NEW
XPI_PROCESS_REDUCTION_NEW
XPI_PROCESS_LCO_MALLOC
XPI_PROCESS_CREATE_CHILD
XPI_PROCESS_FREE
XPI_PROCESS_ATTACH
XPI_PROCESS_CREATE_VALUE
XPI_PROCESS_READ_VALUE
XPI_PROCESS_GET_PARENT 59
XPI_PROCESS_GET_N_CHILDREN 60
XPI_PROCESS_GET_CHILD
XPI_PROCESS_GLOBAL_MALLOC 61
XPI_PROCESS_GLOBAL_FREE
XPI_PROCESS_PIN
XPI_PROCESS_UNPIN
XPI_PROCESS_MEMCPY

# Appendix B

# **XPI Error Codes**

XPI\_ERR\_NO\_MEM 12, 13, 19

XPI\_ERR\_INV\_PARCEL 15, 16, 17, 18, 19, 20, 21, 24, 25, 26, 27

XPI\_ERR\_INV\_ADDR 21, 22, 28

XPI\_ERR\_OUT\_OF\_RANGE 33

## Appendix C

# **Examples**

### **Example C.1** Fetch-and-add Via Compare-and-swap

```
1 #include <assert.h>
 2 #include <xpi.h>
 3
 4 XPI_Err action_post_load64(uint64_t*);
5 XPI_Err action_post_cas64(uint64_t*);
7 /** Register all of the local actions that we need to use. */
8 static __attribute__((constructor))
9 void
10 \; local\_init() \; \{
11
      XPI_register_action((XPI_Action)action_post_load64);
12
      XPI_register_action((XPI_Action)action_post_cas64);
13 }
14
15 /**
16
   * post_cas64_env
17
18
   * The environment for the action_post_cas64. It's free variables are the
19
    * value we expected to see during the cas itself, and the value we're trying
20
   * to add, for use when our cas fails and we need to do it again.
21
22 typedef struct {
23
      uint64_t expected;
24
      int64_t val;
25 } post_cas64_env;
26
27
28
    * do_continue_cas
29
30
   * This local utility function sets up a single instance of the CAS/post-cas
31
    \star loop for the current thread using its continuation. It is used from
32
   * post-load and post-cas.
33
34 static XPI_Err
35 do_continue_cas(post_cas64_env *env) {
36
      XPI_Addr addr = XPI_Thread_get_addr();
37
      XPI_Parcel c = XPI_Thread_get_cont();
38
39
      XPI_Parcel_push(c);
40
      XPI_Parcel_set_addr(c, addr);
      XPI_Parcel_set_action(c, (XPI_Action)action_post_cas64);
```

```
42
       XPI_Parcel_set_env(c, sizeof(post_cas64_env), env);
43
44
       XPI_Parcel_push(c);
45
       XPI_Parcel_set_addr(c, addr);
46
       XPI_Parcel_set_action(c, (XPI_Action)XPI_AGAS_CAS_U64_ACTION);
47
48
       uint64_t to = env->expected + env->val;
49
50
       const void* args[] = {
51
         &env->expected,
52
          &to
53
       };
54
55
       size_t sizes[] = {
56
          sizeof(uint64_t),
57
          sizeof(uint64_t)
58
       };
59
60
       XPI_continue(2, sizes, args);
61
62
       return XPI_SUCCESS;
63
   }
64
65
   /**
66
    * action_post_cas64
67
68
    * After using the builtin AGAS_CAS, this post-cas continuation checks to see
69
    * if the value was updated successfully (i.e., the actual value that we saw
70
   * was the expected value). If it was, then we can continue the fetched value,
71
    * otherwise we go through another CAS/post-cas loop.
72
    */
73 XPI_Err
74 action_post_cas64(uint64_t *actual) {
75
       post_cas64_env *env = (post_cas64_env*)XPI_Thread_get_env();
76
77
       if (*actual == env->expected) {
78
          XPI_continue1(sizeof(uint64_t), actual);
79
          return XPI_SUCCESS;
80
       }
81
82
       env->expected = *actual;
83
       return do_continue_cas(env);
84
85
86 /**
87
    * action_post_load64
88
89
    * The first time we try to do the CAS, we need to read the value from the
90
    * location first. This post_load64 happens after a LOAD_U64 and just uses the
91
    * do_continue_cas utility to perform a single instance of the CAS/post_cas
92
    * loop.
93
    */
94 XPI_Err
95 action_post_load64(uint64_t *from) {
96
      int64_t val = *(int64_t*)XPI_Thread_get_env();
97
       post cas64 env env = { *from, val };
98
       return do_continue_cas(&env);
99
   }
100
```

```
101 /**
102 * fetch-and-add via compare-and-swap
103 *
104 * This is not the most efficient way to perform a fetch-and-add, but is how we
105 * would do it if the only atomic memory primitive we have is
     * compare-and-swap. Essentially, the sender allocates a local future for the
106
107
     * "fetched" value, and then starts a CAS/post-cas loop at the global address'
    * locality, until the cas succeeds. It actually uses the LOAD/post-load
108
109
     * combination to get the value for the first iteration.
110
111 uint64_t
112 fadd64_via_cas64_sync(XPI_Addr addr, int64_t val) {
113
      /* Allocate a future that we use to receive the fetched value. */
114
       XPI_Addr process;
115
       XPI_Thread_get_process_sync(XPI_Thread_get_self(), &process);
116
117
       XPI Addr f;
       XPI_Process_future_new_sync(process, 1, sizeof(int64_t), XPI_LOCAL, &f);
118
119
120
       /* Create the async chain that triggers the future when complete. */
121
       XPI_Parcel p;
122
       XPI_Parcel_create(&p);
123
       XPI_Parcel_set_addr(p, f);
124
       XPI_Parcel_set_action(p, XPI_LCO_TRIGGER_ACTION);
125
126
       XPI_Parcel_push(p);
127
       XPI_Parcel_set_addr(p, addr);
128
       XPI_Parcel_set_action(p, (XPI_Action)action_post_load64);
129
       XPI_Parcel_set_env(p, sizeof(val), &val);
130
131
       XPI_Parcel_push(p);
132
       XPI_Parcel_set_addr(p, addr);
133
       XPI_Parcel_set_action(p, XPI_AGAS_LOAD_U64_ACTION);
134
135
       XPI_Parcel_send(p, XPI_NULL, XPI_NULL);
136
       XPI_Parcel_free(p);
137
138
       /* wait for the result, and return it */
139
       uint64_t result;
140
       XPI_Thread_wait(f, &result);
141
       return result;
142
```