#### Contents

- Introduction
- 2. System Structures



- 3. Process Concept
  - 4. Multithreaded Programming
  - 5. Process Scheduling
  - 6. Synchronization
  - 7. Deadlocks
  - 8. Memory-Management Strategies
  - 9. Virtual-Memory Management
  - 10. File System
  - 11. Mass-Storage Structures
  - 12. I/O Systems
  - 13. Protection, Security, Distributed Systems


# **Chapter 3 Process Concept**

- Objective:
  - Process Concept & Definitions
- Process Classification:
  - Operating system processes executing system code
  - User processes executing system code
  - User processes executing user code

- Example: Special Processes in Unix
  - PID 0 Swapper (i.e., the scheduler)
    - Kernel process
    - No program on disks correspond to this process
  - PID 1 *init* responsible for bringing up a Unix system after the kernel has been bootstrapped. (/etc/rc\* & init or /sbin/rc\* & init)
    - User process with superuser privileges
  - PID 2 pagedaemon responsible for paging
    - Kernel process


- Process
  - A Basic Unit of Work from the Viewpoint of OS
  - Types:
    - Sequential processes: an activity resulted from the execution of a program by a processor
    - Multi-thread processes
  - An Active Entity
    - Program Code A Passive Entity
    - Stack and Data Segments
  - The Current Activity context
    - PC, Registers, Contents in the Stack and Data Segments

Process State





- Process Control Block (PCB)
  - Process State
  - Program Counter
  - CPU Registers
  - CPU Scheduling Information
  - Memory Management Information
  - Accounting Information
  - I/O Status Information

 PCB: The repository for any information that may vary from process to process




- Process Control Block (PCB) An Unix Example
  - Droc[i] 不論 run 或 wait 都要知道
    - Everything the system must know even when the process is swapped out.
      - pid, priority, state, timer counters, etc.
  - .U
    - Things the system should know when a process is running
      - signal disposition, statistics accounting, files[], etc.






### **Process Scheduling**

- The goal of multiprogramming
  - Maximize CPU/resource utilization!
- The goal of time sharing
  - Allow each user to interact with his/her program!




# Process Scheduling – A Queueing Diagram



## Process Scheduling – Schedulers

在個人電腦可能不存在系統裡

Long-Term (/Job) Scheduler



Goal: Select a good mix of I/O-bound and

eg. 科學計算: CPU-bound process

eg. PowerPoint

- Remarks:
  - 1. Control the degree of multiprogramming
  - Can take more time in selecting processes because of a longer interval between executions
  - May not exist physically

## Process Scheduling – Schedulers

- Short-Term (/CPU) Scheduler
  - Goal: Efficiently allocate the CPU to one of the ready processes according to some criteria.
- Mid-Term Scheduler PID 2
  - Swap processes in and out memory to control the degree of multiprogramming

當發現有些 process 進來佔用 CPU 時,導致整個 OS 效能不彰 -> 將他 swap out

## Process Scheduling – Context Switches

一個 process 目前的 state: program counter, register...

希望 pure 越小越好

最常需要置換的 東西存在 CPU 和 MMU 裡面

#### Context Switch ~ Pure Overheads

- Save the state of the old process and load the state of the newly scheduled process.
  - The context of a process is usually reflected in PCB and others, e.g., .u in Unix.

**Process Control Block** 

#### ssues:


The cost depends on hardware support

luxury approach

- e.g. processes with <u>multiple register sets</u> or computers with advanced memory management.
- Threads, i.e., light-weight process (LWP), are introduced to break this bottleneck!

16

- Process Creation & Termination
  - Restrictions on resource usage
  - Passing of Information
  - Concurrent execution



- Process Duplication
  - A copy of parent address space + context is made for child, except the returned value from fork():
    - Child returns with a value 0
    - Parent returns with process id of child
  - No shared data structures between parent and child – Communicate via shared files, pipes, etc.
  - Use execve() to load a new program
  - fork() vs vfork() (Unix)

A Unix Example:

```
if (pid = fork()) == 0) {
  /* child process */
   execlp("/bin/ls", "ls", NULL);
} else if (pid < 0) {
  fprintf(stderr, "Fork Failed");
  exit(-1);
} else {
  /* parent process */
  wait(NULL);
```

A Win32 API Example: STARTUPINFO si; // properties, e.g., window size, handles to infile PROCESS.INFORMATION pi; // a handle and ID's to the newly // created process & its threads if (!CreateProcess(NULL, //use command line "c:\\WINDOWS\\system32\\mspaint.exe", // command line NULL, // don't inherit process handle NULL, // don't inherit thread handle FALSE, // disable handle inheritance 0, // no creation flags NULL, // use parent's environment block NULL, // use parent's existing directory &si, &pi)) { fprintf(stderr, "Create Process Failed"); return -1; WaitForSingleObject(pi.hProcess, INFINITE);

- Termination of Child Processes
  - Reasons:
    - Resource usages, needs, etc.
  - Restrictions:
    - Parent-child, superusers, etc.
  - Waiting of child processes
    - Zombie processes and orphans
  - Kill, exit, wait, abort, signal, etc.
- Cascading Termination

### Interprocess Communication

- Cooperating processes can affect or be affected by the other processes
  - Independent Processes
- Reasons:
  - Information Sharing, e.g., files
  - Computation Speedup, e.g., parallelism.
  - Modularity, e.g., functionality dividing
  - Convenience, e.g., multiple work


### Interprocess Communication


- Why Inter-Process Communication (IPC)?
  - Exchanging of Data and Control Information!

- Why Process Synchronization?
  - Protect critical sections!
  - Ensure the order of executions!

### Interprocess Communication


- Shared Memory
  - Max Speed & Comm Convenience
- Message Passing
  - No Access Conflict & Easy Implementation





## Interprocess Communication – Shared Memory

- A Consumer-Producer Example:
  - Bounded buffer or unbounded buffer
    - Supported by inter-process communication (IPC) or by hand coding



buffer[0...n-1]
Initially,
 in=out=0;

### Interprocess Communication – Shared Memory

```
Producer:
       while (1) {
          /* produce an item nextp */
            while (((in+1) % BUFFER_SIZE) == out)
Synchonization
                   ; /* do nothing */
            buffer[in] = nextp;
            in = (in+1) % BUFFER_SIZE;
            0, 1, ..., BUFFER SIZE - 1
```

## Interprocess Communication – Shared Memory

```
Consumer:
    while (1) {
        while (in == out)
            ; /* do nothing */
        nextc = buffer[ out ];
        out = (out+1) % BUFFER_SIZE ;
        /* consume the item in nextc */
    }
```

## Interprocess Communication – Message Passing

- Logical Implementation of Message Passing
  - Fixed/variable msg size, symmetric/asymmetric communication, direct/indirect communication, automatic/explicit buffering, send by copy or reference, etc.

## Interprocess Communication – Message Passing

- Classification of Communication by Naming
  - Processes must have a way to refer to each other!
  - Types
    - Direct Communication
    - Indirect Communication

## Interprocess Communication — Direct Communication

- Process must explicitly name the recipient or sender of a communication
  - Send(P, msg), Receive(Q, msg)
- Properties of a Link:
  - a. Communication links are established automatically.
  - b. Two processes per a link
  - c. One link per pair of processes
  - d. Bidirectional or unidirectional

## Interprocess Communication — Direct Communication

- Issue in Addressing:
  - Symmetric or asymmetric addressing
     Send(P, msg), Receive(id, msg)
- Difficulty:
  - Process naming vs modularity

## Interprocess Communication — Indirect Communication


 Two processes can communicate only if the process share a mailbox (or ports)

#### Properties:

- 1. A link is established between a pair of processes only if they share a mailbox.
- 2. n processes per link for  $n \ge 1$ .
- 3. n links can exist for a pair of processes for n >= 1.
- 4. Bidirectional or unidirectional

## Interprocess Communication — Indirect Communication

- ssues:
  - a. Who is the recipient of a message?



- b. Owners vs Users
  - Process → owner as the sole recipient?
  - OS → Let the creator be the owner?
     Privileges can be passed?
     Garbage collection is needed?

# Interprocess Communication — Synchronization

- Blocking or Nonblocking (Synchronous versus Asynchronous)
  - Blocking send
  - Nonblocking send
  - Blocking receive
  - Nonblocking receive
  - Rendezvous blocking send & receive

# Interprocess Communication — Buffering

- The Capacity of a Link = the # of messages could be held in the link.
  - Zero capacity(no buffering)
    - Msg transfer must be synchronized rendezvous!
  - Bounded capacity
    - Sender can continue execution without waiting till the link is full
  - Unbounded capacity
    - Sender is never delayed!
- The last two items are for asynchronous communication and may need acknowledgement

# Interprocess Communication — Buffering

- Special cases:
  - a. Msgs may be lost if the receiver can not catch up with msg sending
    → synchronization
  - Senders are blocked until the receivers have received msgs and replied by reply msgs
    - → A Remote Procedure Call (RPC) framework

# Interprocess Communication — Exception Conditions

- Process termination
  - a. Sender Termination → Notify or terminate the receiver!
  - b. Receiver Termination
    - a. No capacity → sender is blocked.
    - Buffering → messages are accumulated.

# Interprocess Communication — Exception Conditions

- Ways to Recover Lost Messages (due to hardware or network failure):
  - OS detects & resends messages.
  - Sender detects & resends messages.
  - OS detects & notifies the sender to handle it.
- Issues:
  - a. Detecting methods, such as the timeout!
  - Distinguish multiple copies if retransmitting is possible
- Scrambled Messages:
  - Usually OS adds checksums, such as CRC, inside messages & resend them as necessary!

## Example – POSIX

- Creation of a Shared Memory Object shm\_fd = shm\_open(name, O\_CREAT | O\_RDRW, 0666);
  - Implementation over memory-mapped files: name, RW, dir rights
- Size Config, Memory Map, Remove

  ftruncate(shm\_fd, 4096);

  ptr = mmap(0, SIZE, PROT\_WRITE, MAP\_SHARED, shm\_fd, 0);

  shm\_unlink(name);
- Access
  - sprintf(ptr, "%s", "Writing to shared mem");

### Example – Mach

- Mach A message-based OS from the Carnegie Mellon University
  - When a task is created, two special mailboxes, called ports, are also created.
    - The Kernel mailbox is used by the kernel to communicate with the tasks
    - The Notify mailbox is used by the kernel sends notification of event occurrences.

### Example - Mach

- Three system calls for message transfer:
  - msg\_send:
    - Options when mailbox is full:
    - a. Wait indefinitely
    - Return immediately
    - c. Wait at most for *n* ms
    - d. Temporarily cache a message.
      - a. A cached message per sending thread for a mailbox

<sup>\*</sup> One task can either own or receive from a mailbox.

#### Example - Mach

- msg\_receive
  - To receive from a mailbox or a set of mailboxes. Only one task can own & have a receiving privilege of it
    - \* options when mailbox is empty:
    - a. Wait indefinitely
    - b. Return immediately
    - c. Wait at most for *n* ms
- msg\_rpc
  - Remote Procedure Calls

#### Example - Mach

- port\_allocate
  - create a mailbox (owner)
  - port\_status ~ .e.g, # of msgs in a link
- All messages have the same priority and are served in a FIFO fashion for the same sender.
- Message Size
  - A fixed-length head + a variable-length data + two mailbox names
- Message copying: message copying -> remapping of addressing space
- System calls are carried out by messages.


### Example – Windows

- Advanced Local Procedure Call (ALPC) –
   Message Passing on the Same Processor
  - 1. The client opens a handle to a subsystem's *connection port* object.
  - 2. The client sends a connection request.
  - 3. The server creates a channel with two private *communication ports*, and returns the handle to one of them to the client.
  - 4. The client and server use the corresponding port handle to send messages or callbacks and to listen for replies.

#### Example – Windows

- Two Types of Message Passing Techniques
  - Small messages (<= 256 bytes)
    - Message copying
  - Large messages section object or API
    - To avoid memory copy
      - Sending and receiving of the pointer and size information of the object
      - Call API to directly read and write to the address space of a client for data not fitting in a section object
- A callback mechanism
  - When a response could not be made immediately.

- Socket
  - An endpoint for communication identified by an IP address concatenated with a port number
- Host X
- A client-server architecture




- Three types of sockets in Java
  - Connection-oriented (TCP) Socket class
  - Connectionless (UDP) DatagramSocket class
  - MulticastSocket class DatagramSocket subclass

```
Server
```

- Remote Procedure Call (RPC)
  - A way to abstract the procedure-call mechanism for use between systems with network connection.
  - Needs:
    - Ports to listen from the RPC daemon site and to return results, identifiers of functions to call, parameters to pack, etc.
    - Stubs at the client site
      - One for each RPC
      - Locate the proper port and marshall parameters.

- Needs (continued)
  - Stubs at the server site
    - Receive the message
    - Invoke the procedure and return the results.
- Issues for RPC
  - Data representation
    - External Data Representation (XDR)
      - Parameter marshalling
  - Semantics of a call
    - History of all messages processed
  - Binding of the client and server port
    - Matchmaker a rendezvous mechanism




- An Example for RPC
  - A Distributed File System (DFS)
    - A set of RPC daemons and clients
    - DFS port on a server on which a file operation is to take place:
      - Disk operations: read, write, delete, status, etc – corresponding to usual system calls

- Remote Method Invocation (RMI)
  - Allow a thread to invoke a method on a remote object.
    - boolean val = Server.someMethod(A,B)
  - **Implementation** 
    - Stub a proxy for the remote object
      - Parcel a method name and its marshalled parameters, etc.
    - Skeleton for the unmarshalling of parameters and invocation of the method and the sending of a parcel back

- Parameter Passing
  - Local (or Nonremote) Objects
    - Pass-by-copy an object serialization
  - Remote Objects Reside on a different Java virtual machine (JVM)
    - The stub for that remote object is passed.
  - Implementation of the interface java.io.Serializable

### Pipes

Child



- Implementation Issues
  - Unidirectional or Bidirectional?
  - Half or Full Duplex?
  - The Existence of a Relationship, e.g., Parent-Child?
  - Inter- or Intra-Machine?

## Pipes – Ordinary Pipes

- Ordinary Pipes The Read and Write Ends
  - A unidirectional pipe that is created by calling pipe(int fd[]) and usually followed by a fork() to allow Parent and Child to communicate with each other.
- Exampe: UNIX and Windows
  - Anonymous Pipe of Windows

```
int main(VOID) {
HANDLE ReadHandle, WriteHandle;
STARTINFO si;
PROCESS_INFORMATION pi;
SECURITY ATTRIBUTES sa = {
 sizeof(SECURITY_ATTRIBUTES),
 NULL, TRUE);
if (!CreatePipe(&ReadHandle,
   &WriteHandle, &sa, 0) {
CreateProcess(NULL, "child.exe",
 NULL, NULL,
 TRUE, /* inherit handles */
 0, NULL, NULL, &si, &pi);
```

## Pipes – Named Pipes

#### Motivation

- Bidirectional Pipes
- No requirement for a parent-child relationship
- Multiple Readers and Writers
- Existence After the Termination of Communicating Processes

#### Example

- FIFOS of UNIX mkfifo(), open(), close(), read(), write(); Half Dulex; Byte-Oriented Transmissions
- Pipes of Windows: CreateNamePipe(),
   ConnectNamePipe(); ReadFile(); Full Duplex,
   Byte/Message-Oriented Transmissions