Fuji Manual

v1.4.9

 ${\it sakurawald}$

August 30, 2024

Contents

1	Cor	ncept	1
	1.1	Configuration File	1
		1.1.1 Definition	1
		1.1.2 Types	1
	1.2		2
			2
		1.2.2 Properties	2
		1.2.3 Module Path	2
		1.2.4 How to enable/disable a module?	3
	1.3	Job	4
		1.3.1 Definition	4
		1.3.2 Cron Expression as Trigger Rule	4
	1.4	Regex	5
		1.4.1 Definition	5
		1.4.2 Reference	5
2	Per	mission	6
	2.1	Definition	6
	2.2	Types	6
	2.3	What is the permission system used by fuji?	7
		2.3.1 Explanation	7
		2.3.2 Set a string permission for a command	7
	2.4	Reference	7
3	Met	ta	8
	3.1	Definition	8
	3.2	Example	8
4	Cor	nfiguration	9
	4.1		9
			9
		4.1.1.1 quartz	9
		· · · · · · · · · · · · · · · · · · ·	9
		00	9
		1	9
			9
		1	Û

			4.1.1.3.1 default_language
	4.2	Modul	e-Control File
5	Mo	dule	12
Ŭ	5.1	config	
	0.1	5.1.1	Purpose
		5.1.2	Command
		0.1.2	5.1.2.1 /fuji reload
	5.2	langua	ge
	5.2	5.2.1	Purpose
			•
		5.2.2	Feature
		5.2.3	Difference
	5.3	-	older
		5.3.1	Purpose
		5.3.2	Placeholder
	5.4	an tpa	
		5.4.1	Purpose
		5.4.2	Command
			5.4.2.1 /tpa
			5.4.2.2 /tpahere
			5.4.2.3 /tpaacept
			5.4.2.4 /tpadeny
			5.4.2.5 /tpacancel
		5.4.3	Configuration
		0.4.0	5.4.3.1 timeout
	5.5	book	
	0.0	5.5.1	
		5.5.2	Command
			5.5.2.1 /back
		5.5.3	Configuration
			5.5.3.1 ignore_distance
	5.6	home.	
		5.6.1	Purpose
		5.6.2	Command
			5.6.2.1 /home
		5.6.3	Meta
	5.7	pvp .	
			Purpose
		5.7.2	Command
		J	5.7.2.1 /pvp
	5.8	afk	20
	0.0	5.8.1	Purpose
		5.8.2	Command
		0.0.4	5.8.2.1 /afk
		E 0 2	
		5.8.3	Configuration
			5.8.3.1 format
			5.8.3.2 afk_checker
			5.8.3.2.1 cron

			20
			20
			20
			20
		5.8.3.4.3 moveable	20
5.9	chat .		21
	5.9.1	Purpose	21
	5.9.2		21
	5.9.3		22
			22
	5.9.4	<i>'</i>	22
	5.9.5		22
	0.5.0		22
			$\frac{22}{22}$
		± •	22
			22
			22
			22
		•	22
			22
		5.9.5.1.3 spy	22
	5.9.6	Sub-Module	23
		5.9.6.1 display	23
		5.9.6.1.1 Placeholder	23
			23
			23
		•	23
			23
			23
	5.9.7		23
5 10			23 24
5.10			
F 11		•	24
5.11			25
		•	25
	5.11.2		25
		•	25
			25
		5.11.2.3 render	25
	5.11.3	Example	25
	5.11.4	Reference	25
5.12	tab_lis	t	26
			26
			26
			26
		•	$\frac{26}{26}$
	5 19 2		20 26
	0.14.0		20 26
			20 26

		5.12.3.1.2 How it works	26
		5.12.3.1.3 Example	26
		5.12.3.1.4 Sub-Module	26
			27
			27
			$\frac{2}{27}$
E 19	ntn	•	28
5.15			
			28
			28
	5.13.3		28
		7 -	28
			28
	5.13.4		28
		5.13.4.1 setup	28
5.14	works		29
	5.14.1	Purpose	29
		•	29
		·	29
			29
	0.11.1		29
		•	$\frac{26}{29}$
			28
F 1 F	1 (11		
5.15			30
		•	30
			30
		•	30
5.16	function	nal	31
	5.16.1	Purpose	31
	5.16.2	Sub-Module	31
		5.16.2.1 /workbench	31
			31
			31
		,	31
			$\frac{31}{31}$
			31
		, 010	31
		,	31
		<i>'</i>	31
5.17			32
		•	32
5.18	cleaner		33
	5.18.1	Purpose	33
	5.18.2	Command	33
			33
	5.18.3	<i>'</i>	33
			33
			33
		·	34

	5.18.3.3.1 ignoreItemEntity	34
	5.18.3.3.2 ignoreLivingEntity	34
		34
	· · · · · · · · · · · · · · · · · · ·	34
		34
		34
		34
F 10		
5.19		35
	•	35
		35
	,	35
5.20	command_permission	36
	5.20.1 Purpose	36
	5.20.2 How it works	36
	5.20.3 Example	36
5.21		37
		37
5 22	•	$\frac{38}{38}$
0.22		38
E 99	•	39
0.20		
	•	39
		39
		39
	*	39
5.24		40
	5.24.1 Purpose	40
	5.24.2 Example	40
5.25	command_warmup	41
	5.25.1 Purpose	41
5.26	command_cooldown	42
		42
5.27	·	43
		43
	•	43
		43
		43
	, , ,	
		43
		43
	<i>7</i> ♥	43
		43
	5.27.2.7 /sit	43
	5.27.2.8 /heal	43
	5.27.2.9 /lore	43
	5.27.2.10 /more	44
	5.27.2.11 ping	44
	7.2 0	44
		44
	·	$\frac{1}{44}$
		-

		5.27.2.15 /reply	44
			44
			44
			44
			44
			44
			$\frac{1}{44}$
			$\frac{44}{44}$
			$\frac{44}{44}$
		<i>'</i>	44
		/ 11	44
		/ 1	44
		<i>'</i>	44
		/ 1 1	44
		5.27.2.29 /near	44
		5.27.2.30 /jump	44
		5.27.2.31 /compass	44
5.28	comma		45
			45
5.29		•	46
			46
			46
5 30			47
0.00			47
		•	47
	5.30.3		48
			48
		1	48
5.31		•	49
	5.31.1	Purpose	49
	5.31.2	Configuration	49
		5.31.2.1 warmup_second	49
		5.31.2.2 interrupt_distance	49
			49
5.32	top_ch		50
			50
		•	50
	0.02.2		50
	5 22 2	,	50
	0.02.0		
		· · · · · · · · · · · · · · · · · · ·	50
			50
			50
		* * *	50
5.33			51
	5.33.1	•	51
	5.33.2	Command	51
		5.33.2.1 /skin	51
	5.33.3	Configuration	51

		5.33.3.1	$default_skin$	 	 	 			 	 51
		5.33.3.2	$random_skins$	 	 	 				 51
5.34	world_	download	er	 	 	 				 52
										52
			ation							52
	0.0	_	url_format							52
			port							52
			bytes_per_second_limit .							52
			context_cache_size							52
5 35	whitoli									53
0.00										53 53
r 20		_								
5.30										54
		_								54
	5.36.2		d							54
			/head							54
5.37										55
	5.37.1	Purpose		 	 	 			 	 55
	5.37.2	Comman	d	 	 	 				 55
		5.37.2.1	/profiler	 	 	 				 55
5.38	tester			 	 	 				 56
										56
			d							56
	0.00.		/tester							56
5 30	multin									57
0.00										57
		-	d Numeric Types							57
										57
F 40										
5.40										58
		_								58
	5.40.2		ule							58
			chat_speed_disabler							58
			$move_speed_disabler \ . \ .$							58
			$\max_{\text{player_disabler}}$							58
5.41	anti_bı	ıild		 	 	 			 	 59
	5.41.1	Purpose		 	 	 				 59
	5.41.2	Anti Typ	oes	 	 	 				 59
	5.41.3	Exapmle		 	 	 				 59
5.42										60
	5.42.1	Purpose		 	 	 				 60
		_	ule							60
			Sign							60
			Anvil							60
5.43	kit									61
0.40										61
		-								61
		-								
	0.45.5		d							61
٠			/kit	 	 	 	•	 •	 •	 61
5 44	temp l	nan								62

	5.44.1	Purpose		 	 	 	 	 62
	5.44.2	Command		 	 	 	 	 62
		5.44.2.1 /temp-b						
	5.44.3	Example						
5.45		$\operatorname{and_meta}$						
	5.45.1	Purpose		 	 	 	 	 63
		Sub-Module						
		5.45.2.1 run						
			Purpose					
		5.45.2.1.2	Command	 	 	 	 	 63
			.1.2.1 /run					
			Example					
		5.45.2.2 for_each						
			Purpose					
			Command					
			$.2.2.1$ /for_each					
			Example					
		5.45.2.3 chain .	•					
			Purpose					
			Command					
			.3.2.1 /chain .					
			Example					
		5.45.2.4 delay .						
			Purpose					
			Command					
			.4.2.1 /delay .					
			Example					
		5.45.2.5 json	_					
		*	Purpose					
			Command					
			.5.2.1 /json .					
			Exaxmple					
			Reference					
		5.45.2.6 attachm						
			Purpose					
			Command					
			.6.2.1 /attachn					
			Example					
		5.45.2.7 shell						
			Purpose					
			Example					
5.46	gamep							
9	_	Sub-Module						
		5.46.1.1 multi_ol						
			Purpose					
			Configuration					
			1.2.1 factor .					
		5.46.1.2 carpet.						
		1 7 7						_

	5.46.1.2.1 Sub-Module	70									
	5.46.1.2.1.1 fake_player_manager	70									
	5.46.1.2.1.2 better_info	71									
6	$\mathbf{Q\&A}$	72									
	6.1 Where is the configuration files?	72									
	6.2 What is .json file?	72									
	6.3 How can I edit a configuration file?	72									
	6.4 What is .dat file?	72									
	6.5 How to update fuji to a new version?	73									
	6.5.1 Backup the data	73									
	6.5.2 Test the new version in your test-environment	73									
	6.5.3 Apply the changes to production-environment	73									
	6.6 Fuji conflits with one of my mods	73									
	6.7 How can I report bugs or suggest new features?	73									
7	Transformer										
	7.1 Command Transformer	74									
	7.2 Command Generator	76									
8	Development	77									
	8.1 Setup the development environment	77									
9	Suggestion	78									
	9.1 Suggestion on server-side mods	78									
	9.1.1 Explanation										
	9.1.2 Server-side mode list										

Chapter 1

Concept

1.1 Configuration File

1.1.1 Definition

All files inside config/fuji directory are named configuration file

1.1.2 Types

Note: The types of configuration files

- 1. Control File A control file is used to control behaviours.
 - 1.1. Main-Control File The main-control file refers to the config/fuji/config.json file, which is used to enable/disable a module.
 - **1.2.** Module-Control File Some modules will have their own control file, which is used to control the behaviour of the module.
- 2. User-Data File User-data files are used to store the data generated by the user.

1.2 Module

1.2.1 Definition

A module is used to provide a specific purpose.

Example: The purpose of modules

- 1. ChatModule provides chat-format customization.
- 2. TpaModule provides /tpa command.

1.2.2 Properties

The properties of a module are as follows:

- 1. Can be disabled You can disable a module completely in main-control file by setting the value of its enable key to false.
- 2. Can work standalone The code of a module is self-contained, there is no reference to other modules.

1.2.3 Module Path

A module is identified by a unique module path.

Example: What a module-path looks like?

The module path of the module tpa is tpa.

The module path of the module history whose parent module is chat, is chat.history. You will see a list of enabled modules identified by their module path at the server-startup process.

A module can have sub-module.

The relationship between parent-module and sub-module is relative, and there is nothing special about sub-module.

1.2.4 How to enable/disable a module?

You can enable/disable a module in config/fuji/config.json by setting the value of its enable key to true/false

A module will be enabled if the following conditions are met:

- 1. The required dependency mods are installed.
- 2. Its parnet-module is enabled.
- 3. The value of its enable key is set to true.

Example: How to enable a sub-module?

To make the module chat.display enabled, you need to enable chat module first.

1.3 Job

1.3.1 Definition

A job is some things will be done repeatedly.

1.3.2 Cron Expression as Trigger Rule

A language named cron language is used to define when a job should be triggered.

Tip: Don't write cron expression by hand. Use generator!

A cron expression looks like 0 * * ? * *, which means trigger the job every minute.

You can use the generator to generate a cron expression: https://www.freeformatter.com/cron-expression-generator-quartz.html

1.4 Regex

1.4.1 Definition

Regex is a language used to define the pattern of strings.

1.4.2 Reference

- 1. https://regexr.com/
- 2. https://regex101.com/

Chapter 2

Permission

2.1 Definition

A permission is used to decide whether a player can do something or not.

2.2 Types

To make the discussion clearer, we define the types of permission as follows:

- 1. level permission A permission level is a non-negative number used in vanilla minecraft. The higher number means the higher authority.
- 2. string permission Usually, a string permission is introduced by a permission plugin, such as luckperms.

2.3 What is the permission system used by fuji?

2.3.1 Explanation

Fuji use the mojang's vanilla permission system, which is based on level permission.

As a convention, most of the commands registered by fuji, requires level permission to be 0 to use. Only a few of the commands require the level permission to be 4 to use.

2.3.2 Set a string permission for a command

By default, fuji only use the level permission as the requirement of a command. However, if you want to use string permission for a command, you can use command permission module, which is used to override the requirement of an existing command.

Example: Allow players to use /seed command

The command /seed provided by mojang requires level permission to be 3 to use. If you want to allow players to use /seed command, but you don't want to grant op for them. Then in this situation, you can grant the string permission for them: /lp group default permission set fuji.permission.seed true, which means that: set the requirement of command /seed to string permission fuji.permission.seed.

Example: Dis-allow players to use /list command

The command <code>/list</code> provided by mojang required <code>level</code> permission to be 0 to use. If you want to dis-allow players to use <code>/list</code> command, but because this command requires no <code>string</code> permission to use, so it's impossible to ban it via <code>luckperms</code>. In this situation, you can grant a <code>string</code> permission: <code>/lp</code> group <code>default</code> permission <code>set fuji.permission.list false</code> for them, which means that: set the requirement of command <code>/list</code> to string permission <code>fuji.permission.list</code>.

Example: Unset the override of requirement of the command

To undo the operation in the first example, just issue /lp group default permission unset fuji.permission.seed

2.4 Reference

1. https://minecraft.fandom.com/wiki/Permission_level

Chapter 3

Meta

3.1 Definition

A meta is a key-value pair.

Note:

Note that meta is introduced by luckperms mod, there is no meta in vanilla minecraft.

3.2 Example

Example: Set a meta for a gruop.

The home module supports the meta fuji.home.home_limit, which controls how many homes a player can create. To set the max homes limits to 3: /lp group default meta set fuji.home.home_limit 3

Example: Query all metas for a group.

/lp group default info

Chapter 4

Configuration

4.1 Main-Control File

4.1.1 common

The common options inside config/fuji/config.json will influence all modules.

4.1.1.1 quartz

Fuji use quartz library as scheduler, all the Job are managed by quartz. Quartz library use a language called cron language to define when to trigger a job.

4.1.1.1.1 logger_level

The logger level for quartz. The logger level from high to low are: OFF, FATAL, ERROR, WARN, INFO, DEBUG, TRACE, ALL.

Example: Enable all logs for quartz

Set the value to ALL to display all the messages from quartz. It's recommended to set at least WARN level, to avoid console spam.

4.1.1.2 backup

Fuji will back up the config/fuji directory automatically before it loads any module.

$4.1.1.2.1 \quad \text{max_slots}$

How many backup should we keep?

4.1.1.2.2 skip

The list of path resolver to skip in backup.

Insert head means skip the folder config/fuji/head.

${\bf 4.1.1.3}\quad {\bf language}$

4.1.1.3.1 default_language

The default language to use.

Fuji also supports multi-language based on player's client-side language if the server is able to do so. You need to enable language module to let fuji respect client-side's language settings.

Also, if the server can't support client-side's language, it will fallback to the deafult_language

4.2 Module-Control File

You can read more about module-control file for each module in Module

Chapter 5

Module

5.1 config

5.1.1 Purpose

This module provides the root command /fuji, which includes some operations on fuji itself.

5.1.2 Command

5.1.2.1 /fuji reload

Reload all configuration files and all modules.

Note: Module itself can't be hot reloaded

After you enable or disable a module, you must restart your server.

5.2 language

5.2.1 Purpose

This module provides client-side multi-language support.

Note: What is client-side language?

When the client joins a server, it will send its client options, including the client-side language value. The server can send messages in language used by the client later.

5.2.2 Feature

- 1. Client-Side Respect The client-side language will be respected if possible.
- 2. Lazy-load Only load the necessary language into the memory.

5.2.3 Difference

Disabled: All the players use the default_language.

Enabled: Fuji will try to respect the player's client-side language, if the server-side supports.

5.3 placeholder

5.3.1 Purpose

This module provides more placeholder for Text Placeholder API mod.

5.3.2 Placeholder

- 1. %fuji:player_mined% sum of mining blocks of a player
- 2. %fuji:server_mined% sum of mining blocks of a server
- 3. %fuji:player_placed% sum of placed blocks of a player
- 4. "fuji:server_placed" sum of placed blocks of a server
- 5. %fuji:player_killed% sum of killed entities of a player
- 6. %fuji:server_killed% sum of killed entities of a server
- 7. %fuji:player_moved% sum of moved distance of a player
- 8. %fuji:server_moved% sum of moved distance of a server
- 9. %fuji:player_playtime% sum of playtime of a player
- 10. %fuji:server_playtime% sum of playtime of a server
- 11. %fuji:health_bar% the health bar of a player
- 12. %fuji:rotate hello% rotate the string hello
- 13. %fuji:has_permission% check luckperms permission
- 14. %fuji:has_meta% get luckperms meta
- 15. %fuji:random_player% get a random online player
- 16. %fuji:random 1 5% get a random number from 1 to 5
- 17. %fuji:escape% escape a placeholder form the parser.

 An optional numebr argument is used as the levels to escape.
- 18. %fuji:date% get current date.

An optional string argument is used to set the **date formatter**, for example, **%fuji:date** HH:MM%.

See also: https://docs.oracle.com/javase/8/docs/api/java/text/SimpleDateFormat.html

Tip: Use placeholder in language file

It's allowed to write placeholders in language file.

Note: Some other mods that provide more placeholders

https://placeholders.pb4.eu/user/mod-placeholders/

5.4 tpa

5.4.1 Purpose

This module provides teleport request for players.

5.4.2 Command

- 5.4.2.1 /tpa
- **5.4.2.2** /tpahere
- 5.4.2.3 /tpaacept
- **5.4.2.4** /tpadeny
- 5.4.2.5 /tpacancel

5.4.3 Configuration

5.4.3.1 timeout

Tpa request expiration duration.unit is second

5.5 back

5.5.1 Purpose

This module allows player to teleport back to last teleport point or death point.

5.5.2 Command

5.5.2.1 /back

5.5.3 Configuration

$\bf 5.5.3.1 \quad ignore_distance$

If the player's teleportation destination is close enough, we ignore this teleportation.

5.6 home

5.6.1 Purpose

This module allows players to create their home.

5.6.2 Command

5.6.2.1 /home

5.6.3 Meta

1. fuji.home.home_limit The home number per player limit.

5.7 pvp

5.7.1 Purpose

This module provide pvp state toggle.

5.7.2 Command

5.7.2.1 /pvp

5.8 afk

5.8.1 Purpose

This module provides afk detection, afk event, afk name customization and afk effects.

5.8.2 Command

5.8.2.1 /afk

5.8.3 Configuration

5.8.3.1 format

The tab-name format when a player is afk

5.8.3.2 afk_checker

5.8.3.2.1 cron

The cron to define how the afk_checker is triggered.

5.8.3.3 afk_event

Execute commands on afk events.

```
Example: Kick a player if he enters afk state

"on_enter_afk": [
  "send-broadcast <gold>Player %player:name% is now afk",
  "kick %player:name% You are kicked beacause on afk."
]
```

5.8.3.4 effect

Afk effects are applied if a player enters afk state.

5.8.3.4.1 invulnerable

Immune to all damage?

5.8.3.4.2 targetable

Can be targeted by a hostile entity?

5.8.3.4.3 moveable

Can be moved if in afk state?

5.9 chat

5.9.1 Purpose

This module provides chat system customization.

5.9.2 Feature

- 1. You can create your own regex transformer to replace chat message sent by players.
- 2. You can insert any placeholder like %world:name%
- 3. You can insert player's prefix and suffix. Just insert %fuji:player_prefix% and %fuji:player_suffix%.
- 4. You can insert item, inv and ender to display your item, inventory and ender-chest.
- 5. You can insert **Steve** to mention another player named Steve.
- 6. You can insert **pos** to show the position.
- 7. You can use markdown language to define simple format.
- 8. You can use mini-message language to define complex format.
- 9. Besides the server chat format, each player can also set their per-player chat format.
- 10. This module doesn't **cancel** the vanilla chat events, so it can work with other chat related mods.

Note: Set prefix and suffix for players

Luckperms is required to set prefix and suffix.

After you installed luckperms mod, just issue /lp group default meta setprefix <yellow>[awesome] to assign prefix.

Don't forget to change the format in chat module, and issue /fuji reload

Tip: Write complex style using mini-language

You can use mini-language to write complex style Text.

See more:

- 1. https://docs.advntr.dev/minimessage/format.html
- 2. https://placeholders.pb4.eu/user/quicktext

5.9.3 Command

5.9.3.1 /chat

5.9.4 Placeholder

- 1. %fuji:pos% player current position
- 2. %fuji:player_prefix% player prefix
- 3. %fuji:player_suffix% player suffix

5.9.5 Configuration

5.9.5.1 format

The server chat format for all players.

5.9.5.1.1 rewrite

The regex language list used to rewrite the player chat message.

You can use regex language to transform player's chat input (only chat message, no command usage).

5.9.5.1.2 mention_player

If you insert Steve in chat message, then the player named Steve will get audio mention.

5.9.5.1.2.1 sound

The type of **sound** used to notify the mentioned player.

Tip: Query all identifiers of sound

/playsound ...

5.9.5.1.2.2 volume

5.9.5.1.2.3 pitch

5.9.5.1.2.4 repeat_count

The sound repeat count.

$\bf 5.9.5.1.2.5 \quad interval_ms$

The interval between each repeat.

5.9.5.1.3 spy

Log chat information into server-console.

5.9.6 Sub-Module

5.9.6.1 display

5.9.6.1.1 Placeholder

- 1. %fuji:item% display player's main-hand item.
- 2. %fuji:inv% display player's inventory.
- 3. %fuji:ender% display player's ender-chest.

5.9.6.1.2 Configuration

5.9.6.1.2.1 expiration_duration_s

For each display data, how long should we save in the memory. Note that if a player shares its inventory items, then fuji will save a copy of his inventory data in the memory.

5.9.6.2 history

New joined players can see the historical chat messages.

5.9.6.2.1 Configuration

5.9.6.2.1.1 buffer_size

How many chat messages should we save, so that we can send for a new-joined player.

5.9.7 Reference

- 1. Text Placeholder API default placeholders
- 2. Luckperms prefix, suffix and meta

$5.10 \mod$

5.10.1 Purpose

This module provides motd customization.

5.11 nametag

5.11.1 Purpose

This module provides nametag customization.

5.11.2 Configuration

5.11.2.1 update_cron

The cron used for the job to **update** the properties of **display entity**.

5.11.2.2 style

Define the style for the nametag display entity.

5.11.2.3 render

Define the nametag render behaviour.

```
Note: The explanation of each field in style and render
```

You can refer to the minecraft wiki about **display entity**: https://minecraft.wiki/w/Display

5.11.3 Example

Example: Set background to blue color

"background": -16776961

Example: Set half transparency

"text_opacity": 128

Example: Scale the size of text into double

```
"scale": {
    "x": 2.0,
    "y": 2.0,
    "z": 2.0
```

5.11.4 Reference

1. https://minecraft.wiki/w/Display

5.12 tab_list

5.12.1 Purpose

This module provides tab list customization.

5.12.2 Configuration

5.12.2.1 update_cron

The cron used for the job to update the tab list.

5.12.2.2 style

The style for tab list.

5.12.3 Sub-Module

5.12.3.1 sort

5.12.3.1.1 Purpose

If enable this module, the player names in tab list will be sorted by weight.

The default weight is 0, the range of weight is [0, 675], which means you can set at most 676 sort groups.

5.12.3.1.2 How it works

The tab list sort method is client-side decided. So the workaround is to send virtual-player entry to the client-side, and hide the real player in client-side's tablist.

In this case, the client-side will find that, all command target selector will display the virtual-player. And you can see the virtual-player in client-side's Player Reporting UI.

Note: The virtaul player has no perforamnce issue

The virtual-player is just an entry listed in tab list, when the client ask the server tab list, the server lie with the virtual-player list.

There is not a real player entity in the server side, so no extra performance problem.

The sync method is event-based, and cached, so the performance is good.

5.12.3.1.3 Example

Example: Set a weight for a group

Issue the command /lp group default meta set fuji.tab_list.sort.weight 1 After you set a new weight, you should issue /fuji reload or re-connect to refresh the tab-list.

5.12.3.1.4 Sub-Module

${\bf 5.12.3.1.4.1 \quad sync_game_profile}$

Whether to copy the game profile from real-player to virtual-player.

5.12.3.2 faker

5.12.3.2.1 Purpose

This module is used to send random fake data to client.

5.13 rtp

5.13.1 Purpose

Provides random teleportation.

5.13.2 Feature

- 1. Per dimension configurable.
- 2. Ignore fluid blocks, such as water and lava.
- 3. Ignore powered snow.

5.13.3 Command

5.13.3.1 /rtp

5.13.3.1.1 Argument

1. -dimension target dimension

Tip: Improve the performance on rtp

- 1. It's highly recommended to pre-gen the world chunks. To gen a new chunk during rtp requires about 2 10 seconds. If a chunk is pre-gen, then it will be fast.
- 2. It's highly recommended to pre-gen the world chunks. To gen a new chunk during rtp requires about 2 10 seconds. If a chunk is pre-gen, then it will be fast.

5.13.4 Configuration

5.13.4.1 setup

Teleport setup per dimension. Dimensions that are not in the list will be disabled to rtp.

5.14 works

5.14.1 Purpose

This module provides a bill-board gui for players to show their works.

5.14.2 Concept

A work is a teleporation point.

The types of work are as follows:

- 1. Non-Production-Work the project don't produce any resource (e.g. bone, string, coal).
- 2. Production-Work the project produce some resource.

Tip: The main difference between non-production work and production-work

For a production-work, fuji provides the production sample to count the hopper and minecart-hopper

Tip: About the production counter

- 1. You can use the production counter provided by production work to sample the output.
- 2. This module works with carpet-fabric's hopper counter. You can use both of them at the same time.
- 3. The hopper counter provided by this module will not destroy the item.

5.14.3 Command

1. /works

5.14.4 Configuration

5.14.4.1 sample_time_ms

For a production-work, how long should we sample it?

5.14.4.2 sample_distance_limit

For a production-work, how large the radius should we considered as the work's production.

5.14.4.3 sample_counter_top_n

For a production-work, we only display the topN output items.

5.15 deathlog

5.15.1 Purpose

This module logs the inventory on player death.

5.15.2 Command

1. /deathlog

5.15.3 Example

Example: Query the logs for a player

/deathlog view Steve

Example: Restore a death log for a player

/deathlog restore Steve 0 Steve

Tip: The death log index number is clickable

You can click the number to quickly restore the logged inventory to your inventory.

5.16 functional

5.16.1 Purpose

This module allows players to open a virtual-gui for functional-block.

5.16.2 Sub-Module

- 5.16.2.1 /workbench
- 5.16.2.2 /enchantment
- 5.16.2.3 /grindstone
- 5.16.2.4 /stonecutter
- 5.16.2.5 /anvil
- 5.16.2.6 /cartography
- 5.16.2.7 /enderchest
- 5.16.2.8 /smithing
- 5.16.2.9 /loom

5.17 system_message

5.17.1 Purpose

This module provides **system message** customization.

Note: What is system message?

Here are some messages that are system message:

- 1. player join and leave server message
- 2. player advancement message
- 3. player death message
- 4. player command feedback
- 5. player whitelist message

Note: Server-side message and Client-side message

It should be noted that, no all messages inside mojang's official language file are server-side message. If a message is client-side message, which means that the message is only used in client-side, then the module will have no effects on this message.

5.18 cleaner

5.18.1 Purpose

This module provides the entity cleaner to remove specified entities automatically.

Note: Only use this module to clean some edge-case entity

Since the vanilla minecraft also has a cleaner to remove the item stack in the ground, so it's recommended to only use this module to clean some weak-loading entities, like: the sand item stack . . .

5.18.2 Command

5.18.2.1 /cleaner clean

Note: The cleaner will keep silent if cleans nothing

If the cleaner cleans nothing, then it will keep silent. (Which means you will not see any message in console, or in-game chat)

Tip: See what is cleaned in cleaner broadcast.

Hover your mouse on the cleaner broadcast, you can see what has been removed.

5.18.3 Configuration

5.18.3.1 cron

The cron used to define the job to trigger /cleaner clean.

5.18.3.2 key2age

The key is translatable key, which you can query in en_us.json language file in minecraft 1.21.

The translatable key of entity starts with entity.minecraft.

The translatable key of item starts with item.minecraft and block.minecraft.

The age is the existence time of the entity, the unit of age is game tick, which means 20 age = 20 ticks = 1 second.

The cleaner will only remove the entities whose translatable key equals key, and age greater equals the defined age, and the entity must not in the ignore list.

Example: Clean the sand-block entity lives longer than 60sec

"block.minecraft.sand": 1200

5.18.3.3 ignore

Entities match the ignore list will not be cleaned.

Note: The built-in safety rule

The cleaner will **always ignore** the following types:

- 1. player
- 2. any block attached entity (e.g. leash_knot)
- 3. any vehicle entity (e.g. minecart, boat ...)

5.18.3.3.1 ignoreItemEntity

Should we ignore all item entity.

5.18.3.3.2 ignoreLivingEntity

Should we ignore all living entity.

If you want the cleaner to remove monster or animals, you should enable this option.

5.18.3.3.3 ignoreNamedEntity

Should we ignore named entity. (With name tag, or name changed by anvil.)

${\bf 5.18.3.3.4}\quad {\bf ignore Entity With Vehicle}$

Like entity riding in some other entity, e.g. minecraft, pig or spider

${\bf 5.18.3.3.5} \quad {\bf ignore Entity With Passengers}$

5.18.3.3.6 ignore Glowing Entity

5.18.3.3.7 ignoreLeashedEntity

5.19 command_scheduler

5.19.1 Purpose

This module allows you to define jobs using cron express to run commands.

5.19.2 Command

5.19.2.1 /command-scheduler trigger

Immediately trigger a job.

5.20 command_permission

5.20.1 Purpose

This module provides the customization of the requirement of all commands.

5.20.2 How it works

The vanilla minecraft use a command system named brigadier.

All the commands are registered, parsed and executed by brigadier.

In this system, all commands are build into a tree structure, that is to say, all commands are a direct or in-direct child of the **root command node**.

Example: What is the path of a specific command node?

For example, the command /gamemode creative Steve is composed by 3 command node:

- 1. literal command node = "gamemode"
- 2. argument command node = a gamemode argument
- 3. argument command node = a player argument

We say that the command path of /gamemode creative Steve, is ["gamemode", "gamemode", "target"].

Also, each **command node** has its **requirement**, which is a **predicate** to check if the **command source** can use the command node.

Tip: Query all the registered command path

/lp group default permission set fuji.permission...

5.20.3 Example

Example: Allow everyone to use /op command

/lp group default permission set fuji.permission.op true

5.21 command_rewrite

5.21.1 Purpose

This module allows you to use regex language to rewrite the command line a player issued.

5.22 command_alias

5.22.1 Purpose

This module allows you to define command alias, which redirect to the existing command node.

Note: A command node is identified by path

See also: ${\tt https://minecraft.fandom.com/wiki/Commands}$

5.23 command_attachment

5.23.1 Purpose

This module allows you to attach commands into itemstack.

5.23.2 Command

5.23.2.1 /command-attachment

Note: The same item-stack shares the-same instance

If you hold stick * 64 in your mainhand, then all the sticks share the same attached commands.

5.23.3 Example

Example: Create a magic-stick which will heal player when click.

Hold a stick item in your main hand.

/command-attachment attach-one heal

Example: Create a magic-stick giving you dimaond when left click (with use limit 3 times) and giving you gold when right click (with use limit 5 times).

Hold a stick item in your main hand.

```
/command-attachment attach-one --maxUseTimes 3 --interactType LEFT give
%player:name% minecraft:diamond 1
/command-attachment attach-one --maxUseTimes 5 --interactType RIGHT give
%player:name% minecraft:gold_ingot 1
```

Example: Query the attached commands in the mainhand item

```
/command-attachment attach-one --maxUseTimes 3 --destroyItem false give
%player:name% minecraft:apple 1
```

5.24 command_interactive

5.24.1 Purpose

This module allows you to write commands in **sign block**.

5.24.2 Example

Example: Basic usage

/say hi %player:name% line 2 empty line 3 empty line 4 empty

Example: Add a prefix description text

prefix /say first
/say the second
/say hi %player:name%
/say the last command

Example: Concat commands between lines

prefix /say this is the first /say and the second line 4 empty

Tip:

- 1. You need to press shift + right click to edit an interactive sign
- 2. The command is executed as the player.

${\bf 5.25} \quad {\bf command_warmup}$

5.25.1 Purpose

This module adds a warmup countdown before command usage.

Note: The difference between command warmup and command cooldown

command warmup is before command usage, while command cooldown is after command usage.

5.26 command_cooldown

5.26.1 Purpose

This module adds a cooldown countdown after the command usage.

5.27 command_toolbox

5.27.1 Purpose

This module provides some simple commands. (misc commands)

5.27.2 Sub-Module

- 5.27.2.1 /bed
- 5.27.2.2 /extinguish
- 5.27.2.3 /feed
- 5.27.2.4 /fly
- 5.27.2.5 /god
- 5.27.2.6 /hat
- 5.27.2.7 /sit
- 5.27.2.8 /heal
- 5.27.2.9 /lore

Example: Set lore for item in mainhand

/lore set <rainbow>the first line<newline><bold><green>the second

```
5.27.2.10 \quad / \text{more}
```

- 5.27.2.14 /repair
- 5.27.2.15 /reply
- 5.27.2.16 /seen
- 5.27.2.17 /suicide
- 5.27.2.18 /top
- 5.27.2.19 /send_message
- 5.27.2.20 /send_broadcast
- 5.27.2.21 /send_actionbar
- 5.27.2.22 /send_title
- 5.27.2.23 /send_toast

Example: Send title to a player

```
/send-title Steve --mainTitle "<rainbow>Hello" --subTitle "<blue>World" --fadeInTicks 60 --stayTicks 60 --fadeOutTicks 60
```

Example: Send title to online players

/foreach send-title %player:name% --mainTitle "<rainbow>Hello %player:name%"

- 5.27.2.24 /trashcan
- 5.27.2.25 /tppos
- 5.27.2.26 /warp
- 5.27.2.27 /burn
- 5.27.2.28 /help_op
- 5.27.2.29 /near
- 5.27.2.30 /jump
- **5.27.2.31** /compass

5.28 command_spy

5.28.1 Purpose

Log command issue into console.

5.29 command_event

5.29.1 Purpose

Execute commands on specific events.

5.29.2 Example

5.30 world

5.30.1 Purpose

Provides a unified world management.

5.30.2 Concept

Example: What is the difference between world, dimension and dimension type?

Well, in the early stage of minecraft, a **world** only support **single-dimension**, which means 1 world only contains 1 dimension.

But now, 1 world supports multi dimension. Sometimes, you will see **world** and **dimension** means the same thing.

But clearer, we say: 1 world can contain 1 or more dimension, and each dimension has its dimension type.

Usually, you can say a mod adds extra dimension type and creates an extra dimension with that dimension type instead of creating extra world.

See also: https://minecraft.wiki/w/Dimension_definition

See also: https://minecraft.wiki/w/Dimension_type

Tip: The dimension and dimension types in vanilla minecraft

In vanilla minecraft, 1 world contains 3 dimensions:

- 1. minecraft:overworld
- 2. minecraft:the_nether
- 3. minecraft:the_end

You can see the dimensions of a world in world/level.dat file.

A dimension type is used to create dimensions, the vanilla minecraft has the following dimension type:

- 1. minecraft:overworld
- 2. minecraft:overworld_caves
- 3. minecraft:the_nether
- 4. minecraft:the_end

The file server properties is used for the only and default world.

5.30.3 Configuration

5.30.3.1 blacklist

The dimensions in the blacklist will not be operated by this module. Use blacklist to avoid misoperation.

5.30.4 Example

Example: Create an extra the_nether dimension

/world create my_nether minecraft:the_nether

Example: Delete the extra dimension

/world delete fuji:my_nether

Example: Reset the extra dimension with random seed

/world reset fuji:my_nether

Tip: Specify a seed for dimension

/world create my_nether minecraft:the_nether --seed 1234567890
/world reset fuji:my_nether --use-the-same-seed

Tip: Make a resource-world that automatically reset every day

You can use command-scheduler module to execute world reset command automatically.

5.31 teleport_warmup

5.31.1 Purpose

This module adds a warmup cooldown before player-teleportation.

A teleportation will be interrupted if:

- 1. the player runs too far.
- 2. the player gets damage.
- 3. the player is in combat.

5.31.2 Configuration

5.31.2.1 warmup_second

The second to wait before the teleportation.

5.31.2.2 interrupt_distance

How far should we cancel the teleportation.

5.31.2.3 dimension

Only allowed in the following dimensions.

Warning: Dimensions that created by other mods may have special behaviour

Some other mods will add extra dimension (like, the mod the-bumblezone-fabric). Their dimension portal may work in a different way, so this module may not be compatible with these mods.

In the default options, we only allow this module works in the vanilla minecraft dimensions.

5.32 top_chunks

5.32.1 Purpose

This module compute a **laggy score** for all loaded chunks, and return the topN lagged chunks. Higher score means more lagged.

5.32.2 Command

5.32.2.1 /chunks

5.32.3 Configuration

5.32.3.1 top

The top chunks to show in /chunks command

5.32.3.2 nearest_distance

For a chunk, how much the radius used to search the nearest player around the chunk.

5.32.3.3 hide_location

Should we hide the chunk-position for a lagged-chunk? Hide chunk location to avoid grief or privacy purpose.

5.32.3.4 type2score

The dict to define how lagged a type(entity/entity_block) should be.

For example: this.put("entity.minecraft.zombie", 4); means that if there are 15 zombies inside a chunk, then the chunk gets score 15 * 4 = 60.

Any other types not inside the dict use the score defined for type default.

5.33 skin

5.33.1 Purpose

This module provides skin management.

5.33.2 Command

5.33.2.1 /skin

5.33.3 Configuration

5.33.3.1 default_skin

The default skin used for player who has no skin set.

5.33.3.2 random_skins

Random skin for fake-player, if you enable the local skin for fake-player.

5.34 world_downloader

5.34.1 Purpose

This module allows a player to download nearby chunks.

5.34.2 Configuration

5.34.2.1 url_format

The url format used to broadcast

5.34.2.2 port

${\bf 5.34.2.3} \quad {\bf bytes_per_second_limit}$

Max download speed limit for each connection.

5.34.2.4 context_cache_size

Max download request allowed in the memory at the same time.

5.35 whitelist

5.35.1 Purpose

This module makes the mojang vanilla whitelist system only compares the $\mathbf{username}$ and \mathbf{ignore} \mathbf{UUD} .

Warning: Only enable this module in offline-mode server

If you are hosting a online-mode server, you will never need to enable this module.

5.36 head

5.36.1 Purpose

This module allows players to buy heads from head-database.

5.36.2 Command

5.36.2.1 /head

5.37 profiler

5.37.1 Purpose

This module shows server health status, such as os, vm, cpu, ram, tps, mspt and gc.

Warning:

Enable this module requires spark mod installed.

5.37.2 Command

5.37.2.1 /profiler

5.38 tester

5.38.1 Purpose

This module is only used for development. If you are a developer, you can register new commands into this module for test-purpose.

5.38.2 Command

5.38.2.1 /tester

Warning:

You should not use this module at your production-environment, because it almost does nothing useful.

5.39 multiplier

5.39.1 Purpose

This module provides some numeric multiplier.

5.39.2 Supported Numeric Types

- 1. damage damage to player
- 2. experience experience a player gained

5.39.3 Example

Example: Double the damage from zombie to a player

/lp group default meta set fuji.multiplier.damage.minecraft:zombie 2

Example: Cancel the fall damage

/lp group default meta set fuji.multiplier.damage.minecraft:fall 0

Example: Double all damage to a player

/lp group default meta set fuji.multiplier.damage.all 2

Example: Double all experience a player gained

/lp group default meta set fuji.multiplier.experience.all 2

Example: Half all damage to a player

/lp group default meta set fuji.multiplier.damage.all 0.5

5.40 disabler

5.40.1 Purpose

This module provides some disabler to disable checkers inside vanilla minecraft.

5.40.2 Sub-Module

5.40.2.1 chat_speed_disabler

Disable Kicked for spamming.

5.40.2.2 move_speed_disabler

Disable moved too quickly and vehicle too quickly check.

Warning: The movement anti-cheat inside vanilla minecraft is bad

Inside the vanilla minecraft server, there is a checker used to check if the player moves correctly. However, this checker usually makes wrong detection, and force setback the player, which makes the client-side gameplay feel lagged.

5.40.2.3 max_player_disabler

Disable the max players limit of the server.

5.41 anti_build

5.41.1 Purpose

This module allows you to ban the interaction with some item/block/entity.

5.41.2 Anti Types

The types supported by this module are as follows:

- 1. break_block
- 2. place_block
- 3. interact_item
- 4. interact_block
- 5. interact_entity

```
Tip: Query identifiers

To query block identifier, issue /setblock ~~~...
To query entity identifier, issue /summon ...
To query item identifier, issue /give ...
```

5.41.3 Exapmle

```
Example: Ban TNT
```

add minecraft:tnt into place_block list

```
Example: Ban TNT but allow a specific player to use
```

/lp user <player> permission set fuji.anti_build.place_block.bypass.minecraft:tr

5.42 color

5.42.1 Purpose

This module provides colorize for things.

5.42.2 Sub-Module

- 5.42.2.1 Sign
- 5.42.2.2 Anvil

5.43 kit

5.43.1 Purpose

This module allows you to make kits.

5.43.2 Concept

A **kit** is a set of itemstack.

5.43.3 Command

5.43.3.1 /kit

$5.44 \ temp_ban$

5.44.1 Purpose

This module provides temp-ban.

5.44.2 Command

5.44.2.1 /temp-ban

5.44.3 Example

Example:

/temp-ban player Steve 12h30m15s bad boy

5.45 command_meta

5.45.1 Purpose

This module provides commands to operate on commands.

5.45.2 Sub-Module

5.45.2.1 run

5.45.2.1.1 Purpose

This module provides /run command, which can run a command with context.

5.45.2.1.2 Command

5.45.2.1.2.1 /run

5.45.2.1.3 Example

Example: Give random diamonds to all online players

/run as console give @a minecraft:diamond %fuji:random 8 32%

Example: Give all online players random diamonds

/run as console foreach give %fuji:escape player:name% minecraft:diamond
%fuji:escape fuji:random 8 32%

Example: Execute a commands as a player

/run as player Steve back

Example: Execute a commands as fake-op

/run as fake-op Steve give %player:name% minecraft:apple 1

5.45.2.2 for each

5.45.2.2.1 Purpose

This module provides /foreach command.

If a command is only targeted for single player, you can use /foreach to apply it for each player.

5.45.2.2.2 Command

5.45.2.2.1 /for_each

5.45.2.2.3 Example

Example:

/foreach say hello %player:name%

Tip: Escape the placeholder properly

If you use foreach in scheduler module, then you should escape (Write %fuji:escape player:name% instead of %player:name%) the placeholder.

It's because the command-scheduler module will try to parse the placeholder, and you need to escape the placeholder, so that the placeholder can be parsed by /foreach command. Here is an example about escape the foreach command in scheduler command list: /foreach give %fuji:escape player:name% minecraft:diamond 16

5.45.2.3 chain

5.45.2.3.1 Purpose

A chain command allows you to run another 2 commands, the first is any command, and the second is the chain command.

Note: The return value of a command

In vanilla minecraft, the return value of command, are failed, pass and success.

5.45.2.3.2 Command

5.45.2.3.2.1 /chain

5.45.2.3.3 Example

Example: A nested chain.

/chain say 1 chain say 2 chain say 3

Example: A breakable chain.

/chain bad command here chain say 2

5.45.2.4 delay

5.45.2.4.1 Purpose

Delay command allows you to execute a command in specific seconds.

5.45.2.4.2 Command

5.45.2.4.2.1 /delay

5.45.2.4.3 Example

Example: A basic usage

/delay 3 say three seconds passed

Example: A nested delay

/delay 1 delay 2 delay 3 say 6 seconds passed.

5.45.2.5 json

5.45.2.5.1 Purpose

Provides a unified json editor.

5.45.2.5.2 Command

5.45.2.5.2.1 /json

5.45.2.5.3 Example

Example: Read a key

/json read "config/fuji/config.json" "\$.common.quartz.logger_level"

Example: List keys

/json read "config/fuji/config.json" "\$.modules.keys()

Example: Set a key

/json write "config/fuji/config.json" "\$.common.quartz.logger_level" NULL null

5.45.2.5.4 Reference

1. https://goessner.net/articles/JsonPath/

5.45.2.6 attachment

5.45.2.6.1 Purpose

Provides a unified attachment facility, which can attach any data to any object.

5.45.2.6.2 Command

5.45.2.6.2.1 /attachment

5.45.2.6.3 Example

Example: Set a attachment

/attachment set news today hello world

Example: Get a attachment

/attachment get news today

5.45.2.7 shell

5.45.2.7.1 Purpose

This module provides /shell command, which executes the command line in your host shell.

Danger: This is a dangerous module

This module is a powerful and dangerous module, not recommended to enable it.

5.45.2.7.2 Example

Example: Create a file using placeholder

/shell touch %player:name%.dangerous

Example: Execute a program in the host os

/shell emacs

Example: Possible to download a virus from Internet and execute it!

/shell ...

5.46 gameplay

5.46.1 Sub-Module

5.46.1.1 multi_obsidian_platform

5.46.1.1.1 Purpose

This module makes the every ender portal frame generate its own obsidian platform.

makes every EnderPortal generate its own Obsidian Platform (Up to 128 in survival-mode.

You can even use creative-mode to build more Ender Portal and more ObsidianPlatform.

Please note that: all the obsidian-platform are vanilla-respect, which means they have the same chunk-layout and the same behaviour as vanilla obsidian-platform which locates in (100,50,0))

5.46.1.1.2 Configuration

5.46.1.1.2.1 factor

The coordination-convertion factor between overworld and the_end. In vanilla minecraft, the factor between overworld and the_nether is 8.

5.46.1.2 carpet

5.46.1.2.1 Sub-Module

5.46.1.2.1.1 fake_player_manager

Purpose

Enable this module requires carpet-fabric mod installed. This module provides some management for fake-player.

Command

/player who = query the owner of the fake-player.

 $/player\ renew = renew\ all\ of\ your\ fake-players.$

Configuration

caps_limit_rule

How many fake-player can each player spawn (in different time)? The tuple means (day_of_week, minutes_of_the_day, max_fake_player_per_player). The range of day_of_week is [1,7]. The range of minutes_of_the_day is [0, 1440]. For example: (1, 0, 2) means if the days_of_week i = 1, and minutes_of_the_day i = 0, then the max_fake_player_per_player now is 2. Besides, you can add multi rules, the rules are checked from up to down. The first rule that matches current time will be used to decide the max_fake_player_per_player. You can issue /player who to see the owner of the fake-player. Only the owner can operates the fake-player. (Op can bypass this limit)

renew_duration_ms

How long should we renew when a player issue 'player renew The command 'player renew allows the player to manually renew all of his fake-player. If a fake-player don't gets renew, then it will expired and get killed. Use-case: to avoid some long-term alive fake-player.

transform_name

The rule to transform the name of fake-player. Use-case: add prefix or suffix for fake-player. use_local_random_skins_for_fake_player

Should we use local skin for fake-player? Enable this can prevent fetching skins from mojang official

CHAPTER 5. MODULE 71

server each time the fake-player is spawned. This is mainly used in some network situation if your network to mojang official server is bad.

$\mathbf{5.46.1.2.1.2} \quad \mathbf{better_info}$

Purpose

Add nbt query for /info block command. Add the command /info entity.

$\mathbf{Q} \& \mathbf{A}$

6.1 Where is the configuration files?

As a convention, all the files are placed in config/fuji/ directory.

6.2 What is .json file?

A json file is a text file, whose name normally ends with .json.

6.3 How can I edit a configuration file?

To ensure the readable and transparent, most of the files are saved as pure text format. You can open them with a text editor.

Tip: Use a moderen text editor.

Some files may have a large number of lines, so it's highly recommended to use a modern text editor, which can highlight symbols and reveal the structure of the file, such as:

- 1. Visual Studio Code
- 2. Visual Studio Code Web Online Editor
- 3. Vim
- 4. Emacs
- 5. Sublime Text

6.4 What is .dat file?

The file whose name ends with .dat are the vanilla minecraft NBT format file. To open such a file, you need to use a NBT Editor, such as NBTExplorer.

CHAPTER 6. Q&A

6.5 How to update fuji to a new version?

6.5.1 Backup the data

Back up the config/fuji directory.

6.5.2 Test the new version in your test-environment

Put the new version of fuji into mods/ directory, start the server, and adjust the configuration to what you want.

Warning: Don't test new changes directly in your production-environment

It's highly recommended to setup a test-environment for a network-maintainer, so that you can test and tweak installed mods into what you want, and avoid un-expected situations.

6.5.3 Apply the changes to production-environment

Now, it's ready to apply the changes to your production-environment.

6.6 Fuji conflits with one of my mods.

You can disable the conflicting module. If possible, create an issue at fuji issue page, so that we can solve this later.

6.7 How can I report bugs or suggest new features?

You can create an issue at fuji issue page

Transformer

7.1 Command Transformer

The following commands can be transformed:

- 1. /blockcycling = /give player minecraft:debug_stick
- 2. /blockinfo = /data get block
- 3. /blocknbt = /data get block
- 4. /entityinfo = /data get entity
- 5. /entitynbt = /data get entity
- 6. /customrecipe = recipe editor
- 7. $/\exp = /\exp(-i\alpha x)$
- 8. /gm, /gms, /gms = /gamemode
- 9. /findbiome = /locate biome
- 10. /tempfly = use luckperms temporal permission
- 11. /flyspeed = /attribute player minecraft:generic.flying_speed
- 12. /walkspeed = /attribute player minecraft:movement_speed
- 13. /maxhealth = /attribute player minecraft:generic.max_health
- 14. /groundclean = /kill @e[type=...]
- 15. /spawner = interact spawner block with spawn egg
- 16. /spawnmob = /summon
- 17. /shoot = /summon with motion
- 18. /smite, /thunder = /summon minecraft:lighting_bolt

- 19. /stats, /statsedit = all stats files are located in world/stats
- $20.\ /\mathrm{tree} = \mathrm{use}\ \mathrm{tree}\ \mathrm{brush}\ \mathrm{from}\ \mathrm{world-edit}\ \mathrm{mod}$
- 21. /unbreakable = /enchant player minecraft:unbreaking
- 22. /item_maker = /give
- 23. /replaceblock = /setblock
- 24. chunks loading/unloading commands = These commands will not bring performance improvements.
- 25. /note = /attachment get note
- 26. $/\dots$ all = /foreach \dots
- $27.\ /\mathrm{cuff} = \mathrm{use}$ anti-build module with string permission
- 28. /cheque = use command-attachment module to make magic item

7.2 Command Generator

You can generate complex and powerful commands using:

- 1. https://www.digminecraft.com/generators/
- 2. https://minecraft.tools/en/public-gallery.php

Development

8.1 Setup the development environment

1. Clone the source:

```
git clone https://github.com/sakurawald/fuji-fabric.git
```

2. Change the working-directory:

```
cd fuji-fabric
```

3. Compile the source:

./gradlew build

Suggestion

9.1 Suggestion on server-side mods

9.1.1 Explanation

Here is some mods that existing and recommended to use, which can make your life easier in fabric server-side crafting.

Note that fuji doesn't require these mods installed to work, and some of these mods have the same functionality as fuji.

If you want to taste something different, and if some of the mods provides a better experience than fuji, then you can just disable the module in fuji, and go use it.

Tip: Decide according to your situation

The suggestion is personal, you can make decision according to your preference.

9.1.2 Server-side mode list

- 1. skin restorer
- 2. head index
- 3. carpet
- 4. ledger
- 5. styled chat
- 6. styled nickname
- 7. styled sidebar
- 8. styled player list
- 9. universal shop
- 10. image2map
- 11. inv view
- 12. universal graves
- 13. **sit**
- 14. lithium
- 15. krypton
- 16. luckperms
- 17. spark
- 18. enclosure
- 19. essential commands
- 20. world-edit
- 21. chunky
- 22. tab
- 23. blue map
- 24. mini motd
- 25. husk homes