SICKO Coefficient Explained

The SICKO Coefficient (S_c) is used assess the true value of infection in C. elegans by accounting for animals that have died prior to the experiment with and without infection.

Variables

 D_W = Number of worms that **Died** during **Washing**

 D_{TO} = **Total** number of worms that **Died** while **Observed**

 D_{TIO} = Total number of worms that **Died** and were **Infected** while **Observed**

 T_{IO} = **Total** number of worms that were **Infected** while **Observed**

 T_{AW} = **Total** number of worms that are **Alive** after **Washing**

 T_{NC} = **Total** number of worms in condition **Not Censored**

N =Specified day **N** of experiment

 $D_{IOi} =$ Worms that **Died** and were **Infected** while **Observed** on Day (i)

Calculated Variables

 $D_{IO}(N) = \text{Cumulative sum of worms that Died}$ and were Infected while Observed up to Day (N)

$$D_{IO}(N) = \sum_{i=1}^{N} D_{IOi}$$

 D_{IW} = Projected number of worms that **Died** during **Washing** due to **Infection**

$$D_{IW} = D_W \left(\frac{D_{TIO}}{D_{TO}} \right)$$

 P_I = **Projected** number of **Infected** Worms

$$P_I = \left(\frac{T_{IO}}{T_{NC}}\right) T_{AW} + D_{IW}$$

SICKO Coefficent of Day (N)

$$S_c(N) = \left(\frac{1}{\sqrt{1 - \frac{P_I}{T_{AW}}}}\right) \left(\frac{P_I}{|P_I - (D_{IW} + D_{IO}(N))|}\right)$$