Package 'bfpwr'

February 24, 2025

Version 0.1.5

Date 2025-02-24
Author Samuel Pawel [aut, cre] (https://orcid.org/0000-0003-2779-320X)
Maintainer Samuel Pawel <samuel.pawel@uzh.ch></samuel.pawel@uzh.ch>
Title Power and Sample Size Calculations for Bayes Factor Analysis
Description Implements z-test, t-test, and normal moment prior Bayes factors based on summary statistics, along with functionality to perform corresponding power and sample size calculations as described in Pawel and Held (2025) <doi:10.1080 00031305.2025.2467919="">.</doi:10.1080>
License GPL-3
Encoding UTF-8
Imports lamW
Suggests roxygen2, tinytest, knitr
VignetteBuilder knitr
NeedsCompilation no
RoxygenNote 7.3.1
<pre>URL https://github.com/SamCH93/bfpwr</pre>
<pre>BugReports https://github.com/SamCH93/bfpwr/issues</pre>
Contents
bf01 2 binbf01 2 nbinbf01 6 nmbf01 8 nnmbf01 10 ntbf01 1 pbf01 1 pbinbf01 1 plot.power.bftest 16

bf01

bf01			z-t	est	В	ay	es	fa	ctc	or																			
Index																													31
	tbf01	•		•	•		•	•			•	•	•	•	 •	•	•	•	•		•	•	•	•	 •	•	•	•	 28
	ptbf01																												
	print.power.bftest																												 26
	powertbf01																												 24
	powernmbf01																												
	powerbinbf01																												 21
	powerbf01																												
	pnmbf01																												 18

Description

This function computes the Bayes factor that quantifies the evidence that the data (in the form of an asymptotically normally distributed parameter estimate with standard error) provide for a point null hypothesis with a normal prior assigned to the parameter under the alternative. The standard error is assumed to be known.

Usage

```
bf01(estimate, se, null = 0, pm, psd, log = FALSE)
```

Arguments

estimate	Parameter estimate
se	Standard error of the parameter estimate
null	Parameter value under the point null hypothesis. Defaults to 0
pm	Mean of the normal prior assigned to the parameter under the alternative
psd	Standard deviation of the normal prior assigned to the parameter under the alternative. Set to \emptyset to obtain a point prior at the prior mean
log	Logical indicating whether the natural logarithm of the Bayes factor should be returned. Defaults to FALSE

Value

Bayes factor in favor of the null hypothesis over the alternative (BF $_{01}$ > 1 indicates evidence for the null hypothesis, whereas BF $_{01}$ < 1 indicates evidence for the alternative)

Author(s)

Samuel Pawel

```
bf01(estimate = 0.2, se = 0.05, null = 0, pm = 0, psd = 2)
```

binbf01 3

binbf01 Binomial Bayes factor

Description

This function computes the Bayes factor for testing a binomial proportion p based on x observed successes out of n trials. Two types of tests are available:

- Test of a point null hypothesis: The Bayes factor quantifies the evidence for H_0 : $p = p_0$ against H_1 : $p \neq p_0$. A beta prior is assigned to the proportion p under the alternative hypothesis H_1 .
- Test of a directional null hypothesis: The Bayes factor quantifies the evidence for H_0 : $p \le p_0$ against H_1 : $p > p_0$. A beta prior that is truncated to the range $[0, p_0]$ under the null H_0 and to $(p_0, 1]$ under the alternative H_1 is assigned to the proportion p under the corresponding hypothesis.

Usage

```
binbf01(
    x,
    n,
    p0 = 0.5,
    type = c("point", "direction"),
    a = 1,
    b = 1,
    log = FALSE
)
```

Arguments

X	Number of successes
^	Trumoer of successes
n	Number of trials
p0	Tested binomial proportion. Defaults to 0.5
type	Type of test. Can be "point" or "directional". Defaults to "point"
а	Number of successes parameter of the beta prior distribution. Defaults to 1
b	Number of failures parameter of the beta prior distribution. Defaults to 1
log	Logical indicating whether the natural logarithm of the Bayes factor should be returned. Defaults to FALSE

Value

Bayes factor in favor of the null hypothesis over the alternative ($BF_{01} > 1$ indicates evidence for the null hypothesis, whereas $BF_{01} < 1$ indicates evidence for the alternative)

4 nbf01

Author(s)

Samuel Pawel

See Also

```
pbinbf01, nbinbf01
```

Examples

```
## example on Mendelian inheritance from ?stats::binom.test
binbf01(x = 682, n = 925, p0 = 3/4, a = 1, b = 1, type = "point")
## 18.6 => strong evidence for the hypothesized p = 3/4 compared to other p

## with directional hypothesis
binbf01(x = 682, n = 925, p0 = 3/4, a = 1, b = 1, type = "direction")
## 1.5 => only anecdotal evidence for p <= 3/4 over p > 3/4

## Particle-counting experiment from Stone (1997) with point null
binbf01(x = 106298, n = 527135, p0 = 0.2, a = 1, b = 1, type = "point")
## 8.1 => moderate evidence for the alternative over the null

## Coin flip experiment from Bartos et al. (2023) with point null
binbf01(x = 178079, n = 350757, p0 = 0.5, a = 5100, b = 4900, type = "point")
## => 1/1.72e+17 extreme evidence in favor of the alternative over the null
```

nbf01

Sample size determination for z-test Bayes factor

Description

This function computes the required sample size to obtain a Bayes factor (bf01) more extreme than a threshold k with a specified target power.

Usage

```
nbf01(
    k,
    power,
    usd,
    null = 0,
    pm,
    psd,
    dpm = pm,
    dpsd = psd,
    nrange = c(1, 10^5),
    lower.tail = TRUE,
    integer = TRUE,
```

nbf01 5

```
analytical = TRUE,
...
)
```

Arguments

k	Bayes factor threshold
power	Target power
usd	Unit standard deviation, the (approximate) standard error of the parameter estimate based on $n=1,$ see details
null	Parameter value under the point null hypothesis. Defaults to 0
pm	Mean of the normal prior assigned to the parameter under the alternative in the analysis
psd	Standard deviation of the normal prior assigned to the parameter under the alternative in the analysis. Set to \emptyset to obtain a point prior at the prior mean
dpm	Mean of the normal design prior assigned to the parameter. Defaults to the same value as the analysis prior ${\tt pm}$
dpsd	Standard deviation of the normal design prior assigned to the parameter. Defaults to the same value as the analysis prior psd
nrange	Sample size search range over which numerical search is performed. Defaults to $c(1,10^{\circ}5)$
lower.tail	Logical indicating whether $Pr(BF_{01} \le k)$ (TRUE) or $Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE
integer	Logical indicating whether only integer valued sample sizes should be returned. If TRUE the required sample size is rounded to the next larger integer. Defaults to TRUE
analytical	Logical indicating whether analytical (if available) or numerical method should be used. Defaults to \ensuremath{TRUE}
	Other arguments passed to stats::uniroot

Details

It is assumed that the standard error of the future parameter estimate is of the form $se = usd/\sqrt{n}$. For example, for normally distributed data with known standard deviation sd and two equally sized groups of size n, the standard error of an estimated standardized mean difference is $se = sd\sqrt{2/n}$, so the corresponding unit standard deviation is $usd = sd\sqrt{2}$. See the vignette for more information.

Value

The required sample size to achieve the specified power

Note

A warning message will be displayed in case that the specified target power is not achievable under the specified analysis and design priors. 6 nbinbf01

Author(s)

Samuel Pawel

See Also

```
pbf01, powerbf01, bf01
```

Examples

nbinbf01

Sample size determination for binomial Bayes factor

Description

This function computes the required sample size to obtain a binomial Bayes factor (binbf01) more extreme than a threshold k with a specified target power.

Usage

```
nbinbf01(
    k,
    power,
    p0 = 0.5,
    type = c("point", "direction"),
    a = 1,
    b = 1,
    dp = NA,
    da = a,
    db = b,
    dl = 0,
    du = 1,
```

nbinbf01

```
lower.tail = TRUE,
nrange = c(1, 10^4),
...
)
```

Arguments

power Target power p0 Tested binomial proportion. Defaults to 0.5 type Type of test. Can be "point" or "directional". Defaults to "point" a Number of successes parameter of the beta analysis prior distribution. Defaults to 1 b Number of failures parameter of the beta analysis prior distribution. Defaults to 1 dp Fixed binomial proportion assumed for the power calculation. Set to NA to use a truncated beta design prior instead (specified via the da, db, dl, and du arguments). Defaults to NA da Number of successes parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior db Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior dl Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to 0 du Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to 1 lower.tail Logical indicating whether $P(BF_{01} \le k)$ (TRUE) or $Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE nrange Sample size search range over which numerical search is performed. Defaults to $c(1, 10^{\circ}4)$ Other arguments passed to stats::uniroot	k	Bayes factor threshold
Type of test. Can be "point" or "directional". Defaults to "point" Number of successes parameter of the beta analysis prior distribution. Defaults to 1 b Number of failures parameter of the beta analysis prior distribution. Defaults to 1 dp Fixed binomial proportion assumed for the power calculation. Set to NA to use a truncated beta design prior instead (specified via the da, db, dl, and du arguments). Defaults to NA da Number of successes parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior db Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior dl Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to \emptyset du Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to \emptyset lower.tail Logical indicating whether $P(BF_{01} \le k)$ (TRUE) or $P(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE nrange Sample size search range over which numerical search is performed. Defaults to $C(1, 10^4)$	power	Target power
Number of successes parameter of the beta analysis prior distribution. Defaults to 1 b Number of failures parameter of the beta analysis prior distribution. Defaults to 1 dp Fixed binomial proportion assumed for the power calculation. Set to NA to use a truncated beta design prior instead (specified via the da, db, d1, and du arguments). Defaults to NA da Number of successes parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior db Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior d1 Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to \emptyset du Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to 1 lower.tail Logical indicating whether $\Pr(BF_{01} \leq k)$ (TRUE) or $\Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE nrange Sample size search range over which numerical search is performed. Defaults to $c(1, 10^4)$	p0	Tested binomial proportion. Defaults to 0.5
Number of failures parameter of the beta analysis prior distribution. Defaults to 1 dp Fixed binomial proportion assumed for the power calculation. Set to NA to use a truncated beta design prior instead (specified via the da, db, d1, and du arguments). Defaults to NA da Number of successes parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior db Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior d1 Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to θ du Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to 1 lower.tail Logical indicating whether $Pr(BF_{01} \le k)$ (TRUE) or $Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE	type	Type of test. Can be "point" or "directional". Defaults to "point"
Fixed binomial proportion assumed for the power calculation. Set to NA to use a truncated beta design prior instead (specified via the da, db, d1, and du arguments). Defaults to NA da	a	* *
a truncated beta design prior instead (specified via the da, db, d1, and du arguments). Defaults to NA Number of successes parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to \emptyset Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to \emptyset Logical indicating whether $\Pr(BF_{01} \le k)$ (TRUE) or $\Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE	b	* 1
Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior db Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior dl Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to \emptyset du Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to 1 lower.tail Logical indicating whether $Pr(BF_{01} \le k)$ (TRUE) or $Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE nrange Sample size search range over which numerical search is performed. Defaults to $c(1, 10^4)$	dp	a truncated beta design prior instead (specified via the da, db, d1, and du argu-
only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior	da	Is only taken into account if dp = NA. Defaults to the same value a as specified
taken into account if dp = NA. Defaults to 0 du	db	only taken into account if dp = NA. Defaults to the same value b as specified for
taken into account if dp = NA. Defaults to 1 lower.tail Logical indicating whether $Pr(BF_{01} \le k)$ (TRUE) or $Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE nrange Sample size search range over which numerical search is performed. Defaults to c(1, 10^4)	dl	• •
should be computed. Defaults to TRUE nrange Sample size search range over which numerical search is performed. Defaults to c(1, 10^4)	du	**
to c(1, 10 ⁴)	lower.tail	
Other arguments passed to stats::uniroot	nrange	
	• • •	Other arguments passed to stats::uniroot

Value

The required sample size to achieve the specified power

Author(s)

Samuel Pawel

See Also

```
pbinbf01, binbf01
```

8 nmbf01

Examples

```
## sample size parameters
pow < -0.9
p0 <- 3/4
a <- 1
b <- 1
k <- 1/10
## Not run:
## sample sizes for directional testing
(nH1 <- nbinbf01(k = k, power = pow, p0 = p0, type = "direction", a = a,
                 b = b, da = a, db = b, dl = p0, du = 1))
(nH0 \leftarrow nbinbf01(k = 1/k, power = pow, p0 = p0, type = "direction", a = a,
                 b = b, da = a, db = b, dl = 0, du = p0, lower.tail = FALSE))
nseq \leftarrow seq(1, 1.1*max(c(nH1, nH0)), length.out = 100)
powH1 < - pbinbf01(k = k, n = nseq, p0 = p0, type = "direction", a = a,
                  b = b, da = a, db = b, dl = p0, du = 1)
powH0 \leftarrow pbinbf01(k = 1/k, n = nseq, p0 = p0, type = "direction", a = a,
                  b = b, da = a, db = b, dl = 0, du = p0, lower.tail = FALSE)
matplot(nseq, cbind(powH1, powH0), type = "s", xlab = "n", ylab = "Power", lty = 1,
        ylim = c(0, 1), col = c(2, 4), las = 1)
abline(h = pow, lty = 2)
abline(v = c(nH1, nH0), col = c(2, 4), lty = 2)
legend("topleft", legend = c("H1", "H0"), lty = 1, col = c(2, 4))
## sample sizes for point null testing
(nH1 \leftarrow nbinbf01(k = k, power = pow, p0 = p0, type = "point", a = a,
                 b = b, da = a, db = b)
(nH0 < - nbinbf01(k = 1/k, power = pow, p0 = p0, type = "point", a = a,
                 b = b, dp = p0, lower.tail = FALSE, nrange = c(1, 10^5))
nseq \leftarrow seq(1, max(c(nH1, nH0)), length.out = 100)
powH1 \leftarrow pbinbf01(k = k, n = nseq, p0 = p0, type = "point", a = a,
                  b = b, da = a, db = b, dl = 0, du = 1)
powH0 \leftarrow pbinbf01(k = 1/k, n = nseq, p0 = p0, type = "point", a = a,
                  b = b, dp = p0, lower.tail = FALSE)
matplot(nseq, cbind(powH1, powH0), type = "s", xlab = "n", ylab = "Power", lty = 1,
        ylim = c(0, 1), col = c(2, 4), las = 1)
abline(h = pow, lty = 2)
abline(v = c(nH1, nH0), col = c(2, 4), lty = 2)
legend("topleft", legend = c("H1", "H0"), lty = 1, col = c(2, 4))
## End(Not run)
```

nmbf01

Normal moment prior Bayes factor

Description

This function computes the Bayes factor that quantifies the evidence that the data (in the form of an asymptotically normally distributed parameter estimate with standard error) provide for a point null hypothesis with a normal moment prior assigned to the parameter under the alternative.

nmbf01

Usage

```
nmbf01(estimate, se, null = 0, psd, log = FALSE)
```

Arguments

estimate	Parameter estimate
se	Standard error of the parameter estimate
null	Parameter value under the point null hypothesis. Defaults to 0
psd	Spread of the normal moment prior assigned to the parameter under the alternative. The modes of the prior are located at $\pm\sqrt{2}\rm psd$
log	Logical indicating whether the natural logarithm of the Bayes factor should be returned. Defaults to FALSE

Details

A normal moment prior has density $f(x \mid \text{null}, \text{psd}) = N(x \mid \text{null}, \text{psd}^2) \times (x - \text{null})/\text{psd}^2$ with $N(x \mid m, v)$ the normal density with mean m and variance v evaluated at x.

Value

Bayes factor in favor of the null hypothesis over the alternative (BF $_{01}$ > 1 indicates evidence for the null hypothesis, whereas BF $_{01}$ < 1 indicates evidence for the alternative)

Author(s)

Samuel Pawel

References

Johnson, V. E. and Rossell, D. (2010). On the use of non-local prior densities in Bayesian hypothesis tests. Journal of the Royal Statistical Society: Series B (Statistical Methodology), 72(2):143–170. doi:10.1111/j.14679868.2009.00730.x

Pramanik, S. and Johnson, V. E. (2024). Efficient alternatives for Bayesian hypothesis tests in psychology. Psychological Methods, 29(2):243–261. doi:10.1037/met0000482

See Also

```
nmbf01, pnmbf01, nnmbf01, powernmbf01
```

```
nmbf01(estimate = 0.25, se = 0.05, null = 0, psd = 0.5/sqrt(2)) # mode at 0.5
```

nnmbf01

nnmbf01

Sample size determination for normal moment prior Bayes factor

Description

This function computes the required sample size to obtain a normal moment prior Bayes factor (nbf01) more extreme than a threshold k with a specified target power.

Usage

```
nnmbf01(
    k,
    power,
    usd,
    null = 0,
    psd,
    dpm,
    dpsd,
    nrange = c(1, 10^5),
    lower.tail = TRUE,
    integer = TRUE,
    ...
)
```

Arguments

k	Bayes factor threshold
power	Target power
usd	Unit standard deviation, the (approximate) standard error of the parameter estimate based on $n=1,$ see details
null	Parameter value under the point null hypothesis. Defaults to 0
psd	Spread of the normal moment prior assigned to the parameter under the alternative in the analysis. The modes of the prior are located at $\pm\sqrt{2}\rm psd$
dpm	Mean of the normal design prior assigned to the parameter
dpsd	Standard deviation of the normal design prior assigned to the parameter. Set to 0 to obtain a point prior at the design prior mean
nrange	Sample size search range over which numerical search is performed. Defaults to $c(1, 10^5)$
lower.tail	Logical indicating whether $\text{Pr}(BF_{01} \leq \text{k})$ (TRUE) or $\text{Pr}(BF_{01} > \text{k})$ (FALSE) should be computed. Defaults to TRUE
integer	Logical indicating whether only integer valued sample sizes should be returned. If TRUE the required sample size is rounded to the next larger integer. Defaults to TRUE
	Other arguments passed to stats::uniroot

ntbf01 11

Details

It is assumed that the standard error of the future parameter estimate is of the form $se = usd/\sqrt{n}$. For example, for normally distributed data with known standard deviation sd and two equally sized groups of size n, the standard error of an estimated standardized mean difference is $se = sd\sqrt{2/n}$, so the corresponding unit standard deviation is $usd = sd\sqrt{2}$. See the vignette for more information.

Value

The required sample size to achieve the specified power

Author(s)

Samuel Pawel

See Also

```
nmbf01, pnmbf01, powernmbf01
```

Examples

```
nnmbf01(k = 1/10, power = 0.9, usd = 1, null = 0, psd = 0.5/sqrt(2), dpm = 0.5, dpsd = 0)
```

ntbf01

Sample size calculations for t-test Bayes factor

Description

This function computes the required sample size to obtain a t-test Bayes factor (tbf01) more extreme than a threshold k with a specified target power.

Usage

```
ntbf01(
    k,
    power,
    null = 0,
    plocation = 0,
    pscale = 1/sqrt(2),
    pdf = 1,
    type = c("two.sample", "one.sample", "paired"),
    alternative = c("two.sided", "less", "greater"),
    dpm = plocation,
    dpsd = pscale,
    lower.tail = TRUE,
    integer = TRUE,
    nrange = c(2, 10^4),
    ...
)
```

12 ntbf01

Arguments

k Bayes factor threshold

power Target power

null Standardized mean difference under the point null hypothesis. Defaults to 0

plocation t prior location. Defaults to 0 pscale t prior scale. Defaults to 1/sqrt(2)

pdf t prior degrees of freedom. Defaults to 1 (a Cauchy prior)

type Type of t-test. Can be "two.sample" (default), "one.sample", or "paired" alternative Direction of the test. Can be either "two.sided" (default), "less", or "greater".

The latter two truncate the analysis prior to negative and positive effects, respectively. If set to "less" or "greater", the power is only computed based on data

with effect estimates in the direction of the alternative

dpm Mean of the normal design prior assigned to the standardized mean difference.

Defaults to the analysis prior location

dpsd Standard deviation of the normal design prior assigned to the standardized mean

difference. Set to 0 to obtain a point prior at the design prior mean. Defaults to

the analysis prior scale

lower.tail Logical indicating whether $Pr(BF_{01} \le k)$ (TRUE) or $Pr(BF_{01} > k)$ (FALSE)

should be computed. Defaults to TRUE

integer Logical indicating whether only integer valued sample sizes should be returned.

If TRUE the required sample size is rounded to the next larger integer. Defaults

to TRUE

nrange Sample size search range over which numerical search is performed. Defaults

to c(2, 10⁴)

... Other arguments passed to stats::uniroot

Value

The required sample size to achieve the specified power

Author(s)

Samuel Pawel

See Also

```
ptbf01, powertbf01, tbf01
```

pbf01

pbf01	Cumulative distribution function of the z-test Bayes factor

Description

This function computes the probability of obtaining a Bayes factor (bf01) more extreme than a threshold k with a specified sample size.

Usage

```
pbf01(k, n, usd, null = 0, pm, psd, dpm = pm, dpsd = psd, lower.tail = TRUE)
```

Arguments

k	Bayes factor threshold
n	Sample size
usd	Unit standard deviation, the (approximate) standard error of the parameter estimate based on $n=1,$ see details
null	Parameter value under the point null hypothesis. Defaults to 0
pm	Mean of the normal prior assigned to the parameter under the alternative in the analysis
psd	Standard deviation of the normal prior assigned to the parameter under the alternative in the analysis. Set to 0 to obtain a point prior at the prior mean
dpm	Mean of the normal design prior assigned to the parameter. Defaults to the same value as the analysis prior pm
dpsd	Standard deviation of the normal design prior assigned to the parameter. Defaults to the same value as the analysis prior psd
lower.tail	Logical indicating whether $Pr(BF_{01} \le k)$ (TRUE) or $Pr(BF_{01} > k)$ (FALSE) should be computed. Defaults to TRUE

Details

It is assumed that the standard error of the future parameter estimate is of the form $se = usd/\sqrt{n}$. For example, for normally distributed data with known standard deviation sd and two equally sized groups of size n, the standard error of an estimated standardized mean difference is $se = sd\sqrt{2/n}$, so the corresponding unit standard deviation is $usd = sd\sqrt{2}$. See the vignette for more information.

Value

The probability that the Bayes factor is less or greater (depending on the specified lower.tail) than the specified threshold k

Author(s)

Samuel Pawel

14 pbinbf01

See Also

```
nbf01, powerbf01, bf01
```

Examples

```
## point alternative (psd = 0)
pbf01(k = 1/10, n = 200, usd = 2, null = 0, pm = 0.5, psd = 0)
## normal alternative (psd > 0)
pbf01(k = 1/10, n = 100, usd = 2, null = 0, pm = 0.5, psd = 2)
## design prior is the null hypothesis (dpm = 0, dpsd = 0)
pbf01(k = 10, n = 1000, usd = 2, null = 0, pm = 0.3, psd = 2, dpm = 0, dpsd = 0, lower.tail = FALSE)
## draw a power curve
nseq \leftarrow round(exp(seq(log(10), log(10000), length.out = 100)))
plot(nseq, pbf01(k = 1/10, n = nseq, usd = 2, null = 0, pm = 0.3, psd = 0), type = "1",
     xlab = "n", ylab = bquote("Pr(BF"["01"] <= 1/10 * ")"), ylim = c(0, 1),
     log = "x", las = 1)
## standardized mean difference (usd = sqrt(2), effective sample size = per group size)
n <- 30
pbf01(k = 1/10, n = n, usd = sqrt(2), null = 0, pm = 0, psd = 1)
## z-transformed correlation (usd = 1, effective sample size = n - 3)
n <- 100
pbf01(k = 1/10, n = n - 3, usd = 1, null = 0, pm = 0.2, psd = 0.5)
## log hazard/odds ratio (usd = 2, effective sample size = total number of events)
nevents <- 100
pbf01(k = 1/10, n = nevents, usd = 2, null = 0, pm = 0, psd = sqrt(0.5))
```

pbinbf01

Cumulative distribution function of the binomial Bayes factor

Description

This function computes the probability of obtaining a binomial Bayes factor (binbf01) more extreme than a threshold k with a specified sample size.

Usage

```
pbinbf01(
    k,
    n,
    p0 = 0.5,
    type = c("point", "direction"),
    a = 1,
```

pbinbf01 15

```
b = 1,
dp = NA,
da = a,
db = b,
dl = 0,
du = 1,
lower.tail = TRUE
```

Arguments

k	Bayes factor threshold
n	Number of trials
p0	Tested binomial proportion. Defaults to 0.5
type	Type of test. Can be "point" or "directional". Defaults to "point"
a	Number of successes parameter of the beta analysis prior distribution. Defaults to 1
b	Number of failures parameter of the beta analysis prior distribution. Defaults to 1
dp	Fixed binomial proportion assumed for the power calculation. Set to NA to use a truncated beta design prior instead (specified via the da, db, d1, and du arguments). Defaults to NA
da	Number of successes parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior
db	Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior
dl	Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if $dp = NA$. Defaults to \emptyset
du	Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to 1
lower.tail	Logical indicating whether $\text{Pr}(BF_{01} \leq \text{k})$ (TRUE) or $\text{Pr}(BF_{01} > \text{k})$ (FALSE) should be computed. Defaults to TRUE

Value

The probability that the Bayes factor is less or greater (depending on the specified lower.tail) than the specified threshold k

Author(s)

Samuel Pawel

See Also

binbf01, nbinbf01

16 plot.power.bftest

Examples

```
## compute probability that BF > 10 under the point null
b <- 1
p0 < -3/4
k <- 10
nseq <- seq(1, 1000, length.out = 100)
powH0 < - pbinbf01(k = k, n = nseq, p0 = p0, type = "point", a = a, b = b,
                  dp = p0, lower.tail = FALSE)
plot(nseq, powH0, type = "s", xlab = "n", ylab = "Power")
## compare to normal approximation
pm \leftarrow a/(a + b) # prior mean under H1
psd <- sqrt(a*b/(a + b)^2/(a + b + 1)) # prior standard deviation under H1
pownormH0 <- pbf01(k = k, n = nseq, usd = sqrt(p0*(1 - p0)), null = p0,
                   pm = pm, psd = psd, dpm = p0, dpsd = 0, lower.tail = FALSE)
lines(nseq, pownormH0, type = "s", col = 2)
legend("right", legend = c("Exact", "Normal approximation"), lty = 1,
       col = c(1, 2)
## compute probability that BF < 1/10 under the p|H1 \sim Beta(a, b) alternative
a <- 10
b <- 5
p0 <- 3/4
k < -1/10
powH1 \leftarrow pbinbf01(k = k, n = nseq, p0 = p0, type = "point", a = a, b = b,
                  da = a, db = b, dl = 0, du = 1)
plot(nseq, powH1, type = "s", xlab = "n", ylab = "Power")
## compare to normal approximation
pm \leftarrow a/(a + b) # prior mean under H1
psd \leftarrow sqrt(a*b/(a + b)^2/(a + b + 1)) \# prior standard deviation under H1
pownormH1 \leftarrow pbf01(k = k, n = nseq, usd = sqrt(pm*(1 - pm)), null = p0,
                   pm = pm, psd = psd, dpm = pm, dpsd = psd)
lines(nseq, pownormH1, type = "s", col = 2)
legend("right", legend = c("Exact", "Normal approximation"), lty = 1,
       col = c(1, 2))
## probability that directional BF <= 1/10 under uniform [3/4, 1] design prior
pow <- pbinbf01(k = 1/10, n = nseq, p0 = 3/4, type = "direction", a = 1, b = 1,
                da = 1, db = 1, dl = 3/4, du = 1)
plot(nseq, pow, type = "s", xlab = "n", ylab = "Power")
```

plot.power.bftest

Plot method for class "power.bftest"

Description

Plot method for class "power.bftest"

plot.power.bftest 17

Usage

```
## S3 method for class 'power.bftest'
plot(
    x,
    nlim = c(2, 500),
    ngrid = 100,
    type = "l",
    plot = TRUE,
    nullplot = TRUE,
    ...
)
```

Arguments

X	Object of class "power.bftest"
nlim	Range of sample sizes over which the power should be computed. Defaults to $c(2, 500)$
ngrid	Number of grid point for which power should be computed. Defaults to 100
type	Type of plot. Defaults to "1" (line-plot)
plot	Logical indicating whether data should be plotted. If FALSE only the data used for plotting are returned.
nullplot	Logcal indicating whether a second plot with the power in favor of the null (using a Bayes factor threshold of 1/k) should be created. Defaults to TRUE
	Other arguments (for consistency with the generic)

Value

Plots power curves (if specified) and invisibly returns a list of data frames containing the data underlying the power curves

Author(s)

Samuel Pawel

See Also

```
powerbf01, powertbf01, powernmbf01
```

```
ssd1 <- powerbf01(k = 1/6, power = 0.95, pm = 0, psd = 1/sqrt(2), dpm = 0.5, dpsd = 0)
plot(ssd1, nlim = c(1, 8000))

power1 <- powerbf01(k = 1/2, n = 120, pm = 0, psd = 1/sqrt(2), dpm = 0.5, dpsd = 0)
plot(power1, nlim = c(1, 1000))</pre>
```

18 pnmbf01

pnmbf01	Cumulative distribution function of the normal moment prior Bayes factor

Description

This function computes the probability of obtaining a normal moment prior Bayes factor (nmbf01) more extreme than a threshold k with a specified sample size.

Usage

```
pnmbf01(k, n, usd, null = 0, psd, dpm, dpsd, lower.tail = TRUE)
```

Arguments

k	Bayes factor threshold
n	Sample size
usd	Unit standard deviation, the (approximate) standard error of the parameter estimate based on $n=1,$ see details
null	Parameter value under the point null hypothesis. Defaults to 0
psd	Spread of the normal moment prior assigned to the parameter under the alternative in the analysis. The modes of the prior are located at $\pm\sqrt{2}\text{psd}$
dpm	Mean of the normal design prior assigned to the parameter
dpsd	Standard deviation of the normal design prior assigned to the parameter. Set to 0 to obtain a point prior at the design prior mean
lower.tail	Logical indicating whether $Pr(BF_{01} \le {\sf k})$ (TRUE) or $Pr(BF_{01} > {\sf k})$ (FALSE) should be computed. Defaults to TRUE

Details

It is assumed that the standard error of the future parameter estimate is of the form $se = usd/\sqrt{n}$. For example, for normally distributed data with known standard deviation sd and two equally sized groups of size n, the standard error of an estimated standardized mean difference is $se = sd\sqrt{2/n}$, so the corresponding unit standard deviation is $usd = sd\sqrt{2}$. See the vignette for more information.

Value

The probability that the Bayes factor is less or greater (depending on the specified lower.tail) than the specified threshold k

Author(s)

Samuel Pawel

powerbf01 19

See Also

```
nmbf01, nnmbf01, powernmbf01
```

Examples

powerbf01

Power and sample size calculations for z-test Bayes factor

Description

Compute probability that z-test Bayes factor is smaller than a specified threshold (the power), or determine sample size to obtain a target power.

Usage

```
powerbf01(
    n = NULL,
    power = NULL,
    k = 1/10,
    sd = 1,
    null = 0,
    pm,
    psd,
    type = c("two.sample", "one.sample", "paired"),
    dpm = pm,
    dpsd = psd,
    nrange = c(1, 10^5)
)
```

Arguments

n Sample size (per group for two-sample tests). Has to be NULL if power is specified. Defaults to NULL

power Target power. Has to be NULL if n is specified. Defaults to NULL

k Bayes factor threshold. Defaults to 1/10, Jeffreys' threshold for 'strong evidence' against the null hypothesis

20 powerbf01

sd	Standard deviation of one observation (for type = "two.sample" or type = "one.sample") or of one difference within a pair of observations (type = "paired"). Is assumed to be known. Defaults to 1
null	Mean difference under the point null hypothesis. Defaults to 0
pm	Mean of the normal prior assigned to the mean difference under the alternative in the analysis
psd	Standard deviation of the normal prior assigned to the mean difference under the alternative in the analysis. Set to 0 to obtain a point prior at the prior mean
type	The type of test. One of "two.sample", "one.sample", "paired". Defaults to "two.sample"
dpm	Mean of the normal design prior assigned to the mean difference. Defaults to the same value as the analysis prior pm
dpsd	Standard deviation of the normal design prior assigned to the mean difference. Defaults to the same value as the analysis prior psd
nrange	Sample size search range over which numerical search is performed (only taken into account when n is NULL). Defaults to c(1, 10^5)

Details

This function provides a similar interface as stats::power.t.test. It also assumes that the data are continuous and that the parameter of interest is either a mean or a (standardized) mean difference. For some users, the low-level functions nbf01 (to directly compute the sample size for a fixed power) and pbf01 (to directly compute the power for a fixed sample size) may also be useful because they can be used for other data and parameter types.

Value

Object of class "power.bftest", a list of the arguments (including the computed one) augmented with method and note elements

Note

A warning message will be displayed in case that the specified target power is not achievable under the specified analysis and design priors.

Author(s)

Samuel Pawel

See Also

plot.power.bftest, nbf01, pbf01, bf01

powerbinbf01 21

Examples

```
## determine power
powerbf01(n = 100, pm = 0, psd = 1, dpm = 0.5, dpsd = 0)
## determine sample size
powerbf01(power = 0.99, pm = 0, psd = 1, dpm = 0.5, dpsd = 0)
```

powerbinbf01

Power and sample size calculations for binomial Bayes factor

Description

Compute probability that binomial Bayes factor (binbf01) is smaller than a specified threshold (the power), or determine sample size to obtain a target power.

Usage

```
powerbinbf01(
    n = NULL,
    power = NULL,
    k = 1/10,
    p0 = 0.5,
    type = c("point", "direction"),
    a = 1,
    b = 1,
    dp = NA,
    da = a,
    db = b,
    dl = 0,
    du = 1,
    nrange = c(1, 10^4)
)
```

Arguments

n	Sample size. Has to be NULL if power is specified. Defaults to NULL
power	Target power. Has to be NULL if n is specified. Defaults to NULL
k	Bayes factor threshold. Defaults to 1/10, Jeffreys' threshold for 'strong evidence' against the null hypothesis
p0	Tested binomial proportion. Defaults to 0.5
type	Type of test. Can be "point" or "directional". Defaults to "point"
а	Number of successes parameter of the beta analysis prior distribution. Defaults to 1
b	Number of failures parameter of the beta analysis prior distribution. Defaults to 1

22 powerbinbf01

dp	Fixed binomial proportion assumed for the power calculation. Set to NA to use a truncated beta design prior instead (specified via the da, db, dl, and du arguments). Defaults to NA
da	Number of successes parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value a as specified for the analysis prior
db	Number of failures parameter of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to the same value b as specified for the analysis prior
dl	Lower truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to \emptyset
du	Upper truncation limit of of the truncated beta design prior distribution. Is only taken into account if dp = NA. Defaults to 1
nrange	Sample size search range over which numerical search is performed (only taken into account when n is NULL). Defaults to c(1, 10^3)

Details

This function provides a similar interface as stats::power.prop.test. For some users, the low-level functions nbinbf01 (to directly compute the sample size for a fixed power) and pbinbf01 (to directly compute the power for a fixed sample size) may also be useful.

Value

Object of class "power.bftest", a list of the arguments (including the computed one) augmented with method and note elements

Author(s)

Samuel Pawel

See Also

plot.power.bftest, pbinbf01, nbinbf01, binbf01

```
## determine sample size
(nres <- powerbinbf01(power = 0.8, p0 = 0.2, type = "direction", dl = 0.2))
## Not run:
plot(nres, nlim = c(1, 250), ngrid = 250, type = "s")
## End(Not run)
## determine power
(powres <- powerbinbf01(n = 100, type = "point"))
## Not run:
plot(powres)</pre>
```

powernmbf01 23

```
## End(Not run)
```

powernmbf01 Power and sample size calculations for normal moment prior Bayes factor

Description

Compute probability that normal moment prior Bayes factor is smaller than a specified threshold (the power), or determine sample size to obtain a target power.

Usage

```
powernmbf01(
    n = NULL,
    power = NULL,
    k = 1/10,
    sd = 1,
    null = 0,
    psd,
    type = c("two.sample", "one.sample", "paired"),
    dpm,
    dpsd,
    nrange = c(1, 10^5)
)
```

Arguments

n	Sample size (per group for two-sample tests). Has to be NULL if power is specified. Defaults to NULL
power	Target power. Has to be NULL if n is specified. Defaults to NULL
k	Bayes factor threshold. Defaults to 1/10, Jeffreys' threshold for 'strong evidence' against the null hypothesis
sd	Standard deviation of one observation (for type = "two.sample" or type = "one.sample") or of one difference within a pair of observations (type = "paired"). Is assumed to be known. Defaults to 1
null	Parameter value under the point null hypothesis. Defaults to 0
psd	Spread of the normal moment prior assigned to the parameter under the alternative in the analysis. The modes of the prior are located at $\pm\sqrt{2}$ psd
type	The type of test. One of "two.sample", "one.sample", "paired". Defaults to "two.sample"
dpm	Mean of the normal design prior assigned to the parameter
dpsd	Standard deviation of the normal design prior assigned to the parameter. Set to 0 to obtain a point prior at the design prior mean
nrange	Sample size search range over which numerical search is performed (only taken into account when n is NULL). Defaults to $c(1, 10^5)$

24 powertbf01

Details

This function provides a similar interface as stats::power.t.test. It also assumes that the data are continuous and that the parameter of interest is either a mean or a (standardized) mean difference. For some users, the low-level functions nnmbf01 (to directly compute the sample size for a fixed power) and pnmbf01 (to directly compute the power for a fixed sample size) may also be useful because they can be used for other data and parameter types.

Value

Object of class "power.bftest", a list of the arguments (including the computed one) augmented with method and note elements

Author(s)

Samuel Pawel

See Also

```
plot.power.bftest, nnmbf01, pnmbf01, nmbf01
```

Examples

```
## determine power
powernmbf01(n = 100, psd = 1, dpm = 0.5, dpsd = 0)
## determine sample size
powernmbf01(power = 0.99, psd = 1, dpm = 0.5, dpsd = 0)
```

powertbf01

Power and sample size calculations for t-test Bayes factor

Description

Compute probability that t-test Bayes factor is smaller than a specified threshold (the power), or determine sample size to obtain a target power.

Usage

```
powertbf01(
  n = NULL,
  power = NULL,
  k = 1/10,
  null = 0,
  plocation = 0,
  pscale = 1/sqrt(2),
  pdf = 1,
  type = c("two.sample", "one.sample", "paired"),
```

powertbf01 25

```
alternative = c("two.sided", "less", "greater"),
dpm = plocation,
dpsd = pscale,
nrange = c(2, 10^4)
)
```

Arguments

n Sample size (per group)

power Target power. Has to be NULL if n is specified. Defaults to NULL

k Bayes factor threshold. Defaults to 1/10, Jeffreys' threshold for 'strong evi-

dence' against the null hypothesis

null Standardized mean difference under the point null hypothesis. Defaults to 0

plocation t prior location. Defaults to 0 pscale t prior scale. Defaults to 1/sqrt(2)

pdf t prior degrees of freedom. Defaults to 1 (a Cauchy prior)

type Type of t-test. Can be "two.sample" (default), "one.sample", or "paired"

alternative Direction of the test. Can be either "two.sided" (default), "less", or "greater".

The latter two truncate the analysis prior to negative and positive effects, respectively. If set to "less" or "greater", the power is only computed based on data

with effect estimates in the direction of the alternative

dpm Mean of the normal design prior assigned to the standardized mean difference.

Defaults to the analysis prior location

dpsd Standard deviation of the normal design prior assigned to the standardized mean

difference. Set to 0 to obtain a point prior at the design prior mean. Defaults to

the analysis prior scale

nrange Sample size search range over which numerical search is performed (only taken

into account when n is NULL). Defaults to c(2, 10⁴)

Details

This function provides a similar interface as stats::power.t.test. For some users, the low-level functions ntbf01 (to directly compute the sample size for a fixed power) and ptbf01 (to directly compute the power for a fixed sample size) may also be useful.

Value

Object of class "power.bftest", a list of the arguments (including the computed one) augmented with method and note elements

Author(s)

Samuel Pawel

See Also

```
plot.power.bftest, ptbf01, ntbf01, tbf01
```

26 print.power.bftest

Examples

```
## determine power powertbf01(n = 146, k = 1/6, dpm = 0.5, dps = 0, alternative = "greater") ## determine sample size powertbf01(power = 0.95, k = 1/6, dpm = 0.5, dps = 0, alternative = "greater")
```

print.power.bftest

Print method for class "power.bftest"

Description

Print method for class "power.bftest"

Usage

```
## S3 method for class 'power.bftest'
print(x, digits = getOption("digits"), ...)
```

Arguments

```
x Object of class "power.bftest"digits Number of digits for formatting of numbers... Other arguments (for consistency with the generic)
```

Value

Prints text summary in the console and invisibly returns the "power.bftest" object

Note

Function adapted from stats:::print.power.htest written by Peter Dalgaard

Author(s)

Samuel Pawel

See Also

powerbf01

```
powerbf01(power = 0.95, pm = 0, psd = 1, dpm = 0.5, dpsd = 0)
powerbf01(power = 0.95, pm = 0, psd = 1, dpm = 0.5, dpsd = 0, type = "one.sample")
powerbf01(power = 0.95, pm = 0, psd = 1, dpm = 0.5, dpsd = 0, type = "paired")
powerbf01(power = 0.95, pm = 1, psd = 0, dpm = 0.8, dpsd = 0, type = "paired")
```

ptbf01 27

ptbf01

Cumulative distribution function of the t-test Bayes factor

Description

This function computes the probability of obtaining a t-test Bayes factor (tbf01) more extreme than a threshold k with a specified sample size.

Usage

```
ptbf01(
  k,
 n,
 n1 = n,
 n2 = n,
  null = 0,
  plocation = 0,
  pscale = 1/sqrt(2),
  pdf = 1,
  dpm = plocation,
  dpsd = pscale,
  type = c("two.sample", "one.sample", "paired"),
  alternative = c("two.sided", "less", "greater"),
  lower.tail = TRUE,
  drange = "adaptive",
)
```

Arguments

k	Bayes factor threshold
n	Sample size (per group)
n1	Sample size in group 1 (only required for two-sample t -test with unequal group sizes)
n2	Sample size in group 2 (only required for two-sample t -test with unequal group sizes)
null	Standardized mean difference under the point null hypothesis. Defaults to 0
plocation	t prior location. Defaults to \emptyset
pscale	t prior scale. Defaults to 1/sqrt(2)
pdf	t prior degrees of freedom. Defaults to 1 (a Cauchy prior)
dpm	Mean of the normal design prior assigned to the standardized mean difference. Defaults to the analysis prior location
dpsd	Standard deviation of the normal design prior assigned to the standardized mean difference. Set to 0 to obtain a point prior at the design prior mean. Defaults to the analysis prior scale

28 tbf01

Value

The probability that the Bayes factor is less or greater (depending on the specified lower.tail) than the specified threshold k

Author(s)

Samuel Pawel

See Also

```
tbf01, ntbf01, powertbf01
```

tbf01 29

Description

This function computes the Bayes factor that forms the basis of the informed Bayesian *t*-test from Gronau et al. (2020). The Bayes factor quantifies the evidence that the data provide for the null hypothesis that the standardized mean difference (SMD) is zero against the alternative that the SMD is non-zero. A location-scale *t*-distribution is assumed for the SMD under the alternative hypothesis. The Jeffreys-Zellner-Siow (JZS) Bayes factor (Rouder et al., 2009) is obtained as a special case by setting the location of the prior to zero and the prior degrees of freedom to one, which is the default.

The data are summarized by t-statistics and sample sizes. The following types of t-statistics are accepted:

- Two-sample *t*-test where the SMD represents the standardized mean difference between two group means (assuming equal variances in both groups)
- One-sample *t*-test where the SMD represents the standardized mean difference to the null value
- Paired t-test where the SMD represents the standardized mean change score

Usage

```
tbf01(
    t,
    n,
    n1 = n,
    n2 = n,
    plocation = 0,
    pscale = 1/sqrt(2),
    pdf = 1,
    type = c("two.sample", "one.sample", "paired"),
    alternative = c("two.sided", "less", "greater"),
    log = FALSE,
    ...
)
```

Arguments

```
t-statistic
t
                   Sample size (per group)
n
                  Sample size in group 1 (only required for two-sample t-test with unequal group
n1
                   Sample size in group 2 (only required for two-sample t-test with unequal group
n2
                   sizes)
plocation
                   t prior location. Defaults to 0
                   t prior scale. Defaults to 1/sqrt(2)
pscale
pdf
                   t prior degrees of freedom. Defaults to 1 (a Cauchy prior)
                   Type of t-test. Can be "two.sample" (default), "one.sample", or "paired"
type
```

30 tbf01

alternative	Direction of the test. Can be either "two.sided" (default), "less", or "greater". The latter two truncate the analysis prior to negative and positive effects, respectively.
log	Logical indicating whether the natural logarithm of the Bayes factor should be returned. Defaults to FALSE
	Additional arguments passed to stats::integrate

Details

The Bayes factor is implemented as in equation (5) in Gronau et al. (2020), and using suitable truncation in case of one-sided alternatives. Integration is performed numerically with stats::integrate.

Value

Bayes factor in favor of the null hypothesis over the alternative (BF₀₁ > 1 indicates evidence for the null hypothesis, whereas BF₀₁ < 1 indicates evidence for the alternative)

Author(s)

Samuel Pawel

References

Rouder, J. N., Speckman, P. L., Sun, D., Morey, R. D., Iverson, G. (2009). Bayesian *t* tests for accepting and rejecting the null hypothesis. Psychonomic Bulletin & Review, 16(2):225-237. doi:10.3758/PBR.16.2.225

Gronau, Q. F., Ly., A., Wagenmakers, E.J. (2020). Informed Bayesian *t*-Tests. The American Statistician, 74(2):137-143. doi:10.1080/00031305.2018.1562983

See Also

```
powertbf01, ptbf01, ntbf01
```

```
## analyses from Rouder et al. (2009):
## values from Table 1
tbf01(t = c(0.69, 3.20), n = 100, pscale = 1, type = "one.sample")
## examples from p. 232
tbf01(t = c(2.24, 2.03), n = 80, pscale = 1, type = "one.sample")
## analyses from Gronau et al. (2020) section 3.2:
## informed prior
tbf01(t = -0.90, n1 = 53, n2 = 57, plocation = 0.350, pscale = 0.102, pdf = 3, alternative = "greater", type = "two.sample")
## default (one-sided) prior
tbf01(t = -0.90, n1 = 53, n2 = 57, plocation = 0, pscale = 1/sqrt(2), pdf = 1, alternative = "greater", type = "two.sample")
```

Index

```
bf01, 2, 4, 6, 13, 14, 20
binbf01, 3, 6, 7, 14, 15, 21, 22
nbf01, 4, 10, 14, 20
nbinbf01, 4, 6, 15, 22
nmbf01, 8, 9, 11, 18, 19, 24
nnmbf01, 9, 10, 19, 24
ntbf01, 11, 25, 28, 30
pbf01, 6, 13, 20
pbinbf01, 4, 7, 14, 22
plot.power.bftest, 16, 20, 22, 24, 25
pnmbf01, 9, 11, 18, 24
powerbf01, 6, 14, 17, 19, 26
powerbinbf01, 21
powernmbf01, 9, 11, 17, 19, 23
powertbf01, 12, 17, 24, 28, 30
print.power.bftest, 26
ptbf01, 12, 25, 27, 30
tbf01, 11, 12, 25, 27, 28, 28
```