

MEMORY: SMALLER PAGETABLES

Shivaram Venkataraman

CS 537, Spring 2019

ADMINISTRIVIA

- Project 2a is due **Friday**
- Project 1b grades this week
- Midterm makeup
- Discussion today: xv6 scheduler walk through

OFFICE HOURS?



OFFICE HOURS?



OFFICE HOURS

- I. One question per student at a time
2. Please be prepared before asking questions.
3. The TAs might not be able to fix your problem
4. Up to 10 mins per student.

Search Piazza?

Discussion section: Using gdb

Extra office hours in the afternoon and evening tomorrow till 8pm!

AGENDA / LEARNING OUTCOMES

Memory virtualization

How we reduce the size of page tables?


What can we do to handle large address spaces?

RECAP

PAGING TRANSLATION STEPS

For each mem reference:

1. extract **VPN** (virt page num) from **VA** (virt addr)
2. calculate addr of **PTE** (page table entry)
3. read **PTE** from memory
4. extract **PFN** (page frame num)
5. build **PA** (phys addr)
6. read contents of **PA** from memory



DISADVANTAGES OF PAGING


Additional memory reference to page table → Very inefficient

- Page table must be stored in memory
- MMU stores only base address of page table

Storage for page tables may be substantial

- Simple page table: Requires PTE for all pages in address space
Entry needed even if page not allocated ?

STRATEGY: CACHE PAGE TRANSLATIONS



PAGING TRANSLATION STEPS

For each mem reference:


1. extract **VPN** (virt page num) from **VA** (virt addr)
2. check TLB for **VPN**

if miss:

3. calculate addr of **PTE** (page table entry)
4. read **PTE** from memory, **add to TLB**
5. extract **PFN** from TLB (page frame num)
6. build **PA** (phys addr)
7. read contents of **PA** from memory

hit

TLB ACCESSES: SEQUENTIAL EXAMPLE



TLB SUMMARY

Pages are great, but accessing page tables for every memory access is slow

Cache recent page translations → TLB

- Hardware performs TLB lookup on every memory access

TLB performance depends strongly on workload

- Sequential workloads perform well
- Workloads with temporal locality can perform well

In different systems, hardware or OS handles TLB misses

TLBs increase cost of context switches

- Flush TLB on every context switch
- Add ASID to every TLB entry

LFU
Random

DISADVANTAGES OF PAGING

Additional memory reference to page table → Very inefficient

- Page table must be stored in memory
- MMU stores only base address of page table

Storage for page tables may be substantial

- Simple page table: Requires PTE for all pages in address space
Entry needed even if page not allocated ?

SMALLER PAGE TABLES

QUIZ: HOW BIG ARE PAGE TABLES?

1. PTE's are **2 bytes**, and **32** possible virtual page numbers

= **64 bytes**

2. PTE's are **2 bytes**, virtual addrs are **24 bits**, pages are **16 bytes**

$$2^{20} \times 2 = 2^{21} \text{ bytes}$$

3. PTE's are **4 bytes**, virtual addrs are **32 bits**, and pages are **4 KB**

$$2^{20} \times 4 = 2^{22} = 4 \text{ MB}$$

4. PTE's are **4 bytes**, virtual addrs are **64 bits**, and pages are **4 KB**

$$2^{52} \times 4 = 2^{54} =$$


How big is each page table?

Linear Page Table
= 4 bits
= 20 bits VPN

= 12 bits
offset

= 12 bits
offset

WHY ARE PAGE TABLES SO LARGE?



MANY INVALID PT ENTRIES

how to avoid
storing these?

PFN	valid	prot
10	1	r-x
-	0	-
23	0	rw-
-	0	-
-	0	-
-	0	-
-	0	-
...many more invalid...		
-	0	-
-	0	-
-	0	-
-	0	-
28	1	rw-
4	1	rw-

AVOID SIMPLE LINEAR PAGE TABLES?

Use more complex page tables, instead of just big array

Any data structure is possible with software-managed TLB

- Hardware looks for vpn in TLB on every memory access
- If TLB does not contain vpn, TLB miss
 - Trap into OS and let OS find vpn->ppn translation
 - OS notifies TLB of vpn->ppn for future accesses

size
array =
Num
VP N

OTHER APPROACHES

- I. Segmented Pagetables
2. Multi-level Pagetables
 - Page the page tables
 - Page the pagetables of page tables...
3. Inverted Pagetables

VALID PTES ARE CONTIGUOUS

A hand-drawn diagram illustrating a page table structure. The table has three columns: PFN (Physical Frame Number), valid, and prot (Protection). The rows show memory addresses 10, 23, and 28, along with several invalid entries indicated by dashes. The protection levels shown are r-x, rw-, and -.

PFN	valid	prot
10	0	r-x
23	0	rw-
-	0	-
-	0	-
-	0	-
-	0	-
...many more invalid...		
-	0	-
-	0	-
-	0	-
-	0	-
28	0	-
4	0	rw-
		rw-

Annotations include:

- A bracket on the left labeled "heap" with arrows pointing to address 10 and address 23.
- A bracket on the right labeled "stack" with arrows pointing to address 28 and address 4.
- A bracket below the table labeled "how to avoid storing these?" with an arrow pointing to the invalid entries.

Note “hole” in addr space:
valids vs. invalids are clustered

How did OS avoid allocating holes in phys
memory?

Segmentation


COMBINE PAGING AND SEGMENTATION

Divide address space into segments (code, heap, stack)

- Segments can be variable length

Divide each segment into fixed-sized pages

Logical address divided into three portions



seg # (4 bits)	page number (8 bits)	page offset (12 bits)
----------------	----------------------	-----------------------

Implementation

- Each segment has a page table
- Each segment track base (physical address) and bounds of the **page table**


24 bit
addresses

QUIZ: PAGING AND SEGMENTATION



seg	base	bounds	R	W
0	0x002000	0xff	1	0
1	0x000000	0x00	0	0
2	0x001000	0x0f	1	1

0x002070 read: 0x004 070
0x202016 read: 0x003 016
0x104c84 read: ERROR PPN
0x010424 write: ERROR P: 10 B: x0f
0x210014 write: P: 10 B: x0f ERROR
0x203568 read:



ADVANTAGES OF PAGING AND SEGMENTATION

Advantages of Segments

- Supports sparse address spaces.
- Decreases size of page tables. If segment not used, not need for page table

Advantages of Pages

- No external fragmentation
- Segments can grow without any reshuffling
- Can run process when some pages are swapped to disk (next lecture)

Advantages of Both

- Increases flexibility of sharing: Share either single page or entire segment

DISADVANTAGES OF PAGING AND SEGMENTATION

Potentially large page tables (for each segment)

- Must allocate each page table contiguously
 - More problematic with more address bits
 - Page table size?

Assume 2 bits for segment, 18 bits for page number, 12 bits for offset

Each page table is:

$$\begin{aligned} &= \text{Number of entries} * \text{size of each entry} \\ &= \text{Number of pages} * 4 \text{ bytes} \\ &= 2^{18} * 4 \text{ bytes} = 2^{20} \text{ bytes} = 1 \text{ MB!!!} \end{aligned}$$

OTHER APPROACHES

- I. Segmented Pagetables
2. Multi-level Pagetables
 - Page the page tables
 - Page the pagetables of page tables...
3. Inverted Pagetables


MULTILEVEL PAGE TABLES

Goal: Allow each page tables to be allocated non-contiguously


Idea: Page the page tables

- Creates multiple levels of page tables; outer level “page directory”
- Only allocate page tables for pages in use
- Used in x86 architectures (hardware can walk known structure)

MULTILEVEL PAGE TABLES



MULTILEVEL



QUIZ: MULTILEVEL

page directory

PPN	valid
0x3	1
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
0x92	1

page of PT (@PPN:0x3)

PPN	valid
0x10	1
0x23	1
-	0
-	0
-	0
0x80	1
0x59	1
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0

page of PT (@PPN:0x92)

PPN	valid
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
-	0
0x55	1
0x45	1

translate 0xFEED0

Page dir = 0xF
 Page PT = 0x92
 valid = 0xE
 offset = 0x55
 PPN = 0x55
 0x55 E D0
 0x55 E D0

20-bit address:



ADDRESS FORMAT FOR MULTILEVEL PAGING

30-bit address:



Page
size

How should logical address be structured? How many bits for each paging level?

Goal?

- Each page table fits within a page
- PTE size * number PTE = page size

Assume PTE size = 4 bytes

Page size = 2^{12} bytes = 4KB

Number of entries

→ # bits for selecting inner page =




=
4KB

Remaining bits for outer page:

$$- 30 - \underline{10} - \underline{12} = \underline{8} \text{ bits}$$

PROBLEM WITH 2 LEVELS?

Problem: page directories (outer level) may not fit in a page



How large is virtual address space with 4 KB pages, 4 byte PTEs,
(each page table fits in page)

4KB / 4 bytes → 1K entries per level

1 level: $2^{22} \approx 2^{10} \cdot 2^{12} = 4\text{ MB}$

2 levels: 4GB

3 levels: 4TB

FULL SYSTEM WITH TLBS

On TLB miss: *lookups with more levels more expensive*

Assume 3-level page table

Assume 256-byte pages

Assume 16-bit addresses

Assume ASID of current process is 211

ASID	VPN	PFN	Valid
211	0xbb	0x91	1
211	0xff	0x23	1
122	0x05	0x91	1
211	0x05	0x12	0

How many physical accesses for each instruction? (Ignore ops changing TLB)

(a) 0xAA10: movl 0x1111, %edi

(b) 0xBB13: addl \$0x3, %edi

(c) 0x0519: movl %edi, 0xFF10

INVERTED PAGE TABLE

Only need entries for virtual pages w/ valid physical mappings

Naïve approach:

Search through data structure $\langle \text{ppn}, \text{vpn}+\text{asid} \rangle$ to find match

Too much time to search entire table

Better:

Find possible matches entries by hashing $\text{vpn}+\text{asid}$

Smaller number of entries to search for exact match

Managing inverted page table requires software-controlled TLB

SUMMARY: BETTER PAGE TABLES

Problem: Simple linear page tables require too much contiguous memory

Many options for efficiently organizing page tables

If OS traps on TLB miss, OS can use any data structure

- Inverted page tables (hashing)

If Hardware handles TLB miss, page tables must follow specific format

- Multi-level page tables used in x86 architecture
- Each page table fits within a page

SWAPPING

MOTIVATION

OS goal: Support processes when not enough physical memory

- Single process with very large address space
- Multiple processes with combined address spaces


User code should be independent of amount of physical memory

- Correctness, if not performance

Virtual memory: OS provides illusion of more physical memory


Why does this work?

- Relies on key properties of user processes (workload) and machine architecture (hardware)



Virtual Memory





Virtual Memory



LOCALITY OF REFERENCE

Leverage **locality of reference** within processes

- **Spatial:** reference memory addresses **near** previously referenced addresses
- **Temporal:** reference memory addresses that have referenced in the past
- Processes spend majority of time in small portion of code
 - Estimate: 90% of time in 10% of code


Implication:

- Process only uses small amount of address space at any moment
- Only small amount of address space must be resident in physical memory

MEMORY HIERARCHY

Leverage **memory hierarchy** of machine architecture

Each layer acts as “backing store” for layer above



SWAPPING INTUITION

Idea: OS keeps unreferenced pages on disk

- Slower, cheaper backing store than memory

Process can run when not all pages are loaded into main memory

OS and hardware cooperate to make large disk seem like memory

- Same behavior as if all of address space in main memory

Requirements:

- OS must have **mechanism** to identify location of each page in address space → in memory or on disk
- OS must have **policy** for determining which pages live in memory and which on disk

VIRTUAL ADDRESS SPACE MECHANISMS


Each page in virtual address space maps to one of three locations:

- Physical main memory: Small, fast, expensive
- Disk (backing store): Large, slow, cheap
- Nothing (error): Free

Extend page tables with an extra bit: present

- permissions (r/w), valid, present
- Page in memory: present bit set in PTE
- Page on disk: present bit cleared
 - PTE points to block on disk
 - Causes trap into OS when page is referenced

Disk



Phys Memory



PFN	valid	prot	present
10	0	r-x	-
-	0	-	-
23	0	rw-	0
-	0	-	-
-	0	-	-
-	0	-	-
-	0	-	-
-	0	-	-
-	0	-	-
-	0	-	-
28	0	-	-
4	1	rw-	0
		rw-	-

What if access vpn 0xb?

VIRTUAL MEMORY MECHANISMS

First, hardware checks TLB for virtual address

- if TLB hit, address translation is done; page in physical memory

Else ...

- Hardware or OS walk page tables
- If PTE designates page is present, then page in physical memory
(i.e., present bit is cleared)

Else

- Trap into OS (not handled by hardware)
- OS selects victim page in memory to replace
 - Write victim page out to disk if modified (add dirty bit to PTE)
- OS reads referenced page from disk into memory
- Page table is updated, present bit is set
- Process continues execution

NEXT STEPS

Project 2a: Due Friday

Discussion section:

How to use gdb

xv6 scheduler walk through

Next class: More Swapping!