MEMORY: SWAPPING

Shivaram Venkataraman CS 537, Spring 2019

ADMINISTRIVIA

- Project 2b is out. Due Feb 27th, 11:59
- Project Ib grades are out

LESSONS FROM P2A?

- I. Start early!
- 2. Sketch out a design?
- 3. Synthesize ideas from various sources: TAs, stackoverflow.com, gdb, discussion videos
- 4. Handling edge cases, string handling

AGENDA / LEARNING OUTCOMES

Memory virtualization

How we support virtual mem larger than physical mem?

What are mechanisms and policies for this?

RECAP

PAGING TRANSLATION STEPS

For each mem reference:

I. extract **VPN** (virt page num) from **VA** (virt addr)

2. check TLB for **VPN**

if miss:

- 3. calculate addr of **PTE** (page table entry)
- 4. read PTE from memory, add to TLB
- 5. extract **PFN** from TLB (page frame num)
- 6. build **PA** (phys addr)
- 7. read contents of **PA** from memory

Sty Styles

COMBINE PAGING AND SEGMENTATION

Divide address space into segments (code, heap, stack)

Segments can be variable length
 Divide each segment into fixed-sized pages
 Logical address divided into three portions

stack)


seg # (4 bits) page number (8 bits) page offset (12 bits)

Implementation


- Each segment has a page table
- Each segment track base (physical address) and bounds of the page table

MULTILEVEL PAGE TABLES

30-bit address:



ADDRESS FORMAT FOR MULTILEVEL PAGING



How should logical address be structured? How many bits for each paging level? Goal? page jes

- Each page table fits within a page
- PTE size * number PTE = page size Assume PTE size = 4 bytes Page size = 2^12 bytes = 4KB

→ # bits for selecting inner page = [v http://www.

Remaining bits for outer page:

$$-30-[5]-[2]=8$$
 bits





PROBLEM WITH 2 LEVELS?

fx g Mysus ble

page offset (12 bits)

Problem: page directories (outer level) may not fit in a page


outer page? inner page (10 bits)

Solution:

Split page directories into pieces

3 levels: 1024 x 1024 x 1024 x 4K = 242=47B

Use another page dir to refer to the page dir pieces.



FULL SYSTEM WITH TLBS

On TLB miss: lookups with more levels more expensive	ASID	VPN	PFN	Valid
Assume 3-level page table Assume 256-byte pages Assume 16-bit addresses	211	0xbb	0x91	_
Assume 256-byte pages = 100 v P	211	0xff	0x23	
Assume 16-bit addresses $\% \sqrt{N^2}$	122	0x05	0x91	5
Assume ASID of current process is 211	211	0x05	0x12	0
How many physical accesses for each instruction? (Ignore ops changing TLB) (a) 0xAA10: movl 0x1111, %edi TLB with access to mem acc TLB list 1 mem access 0x9113				
(b) 0xBB13: addl \$0x3, %edi	•		8 1100	
TLB list I mem access 0x9113				
(c) 0x0519: movl %edi, 0xFF10		instr	<u> </u>	

https://tinyurl.com/cs537-sp19-bunny1



INVERTED PAGE TABLE

Only need entries for virtual pages w/ valid physical mappings

Naïve approach:

Search through data structure <ppn, vpn+asid> to find match Too much time to search entire table

Better:

Find possible matches entries by hashing vpn+asid Smaller number of entries to search for exact match

Managing inverted page table requires software-controlled TLB

SUMMARY: BETTER PAGE TABLES

Problem: Simple linear page tables require too much contiguous memory

Many options for efficiently organizing page tables

If OS traps on TLB miss, OS can use any data structure

Inverted page tables (hashing)

If Hardware handles TLB miss, page tables must follow specific format

- Multi-level page tables used in x86 architecture
- Each page table fits within a page

SWAPPING

MOTIVATION

OS goal: Support processes when not enough physical memory


- Single process with very large address space
- Multiple processes with combined address spaces


User code should be independent of amount of physical memory


Correctness, if not performance

Virtual memory: OS provides illusion of more physical memory Why does this work?

 Relies on key properties of user processes (workload) and machine architecture (hardware)







akof (skr);

LOCALITY OF REFERENCE


Leverage locality of reference within processes

- Spatial: reference memory addresses near previously referenced addresses
- Temporal: reference memory addresses that have referenced in the past
- Processes spend majority of time in small portion of code
 - Estimate: 90% of time in 10% of code

Implication:

- Process only uses small amount of address space at any moment
- Only small amount of address space must be resident in physical memory

MEMORY HIERARCHY



SWAPPING INTUITION

Idea: OS keeps unreferenced pages on disk

Slower, cheaper backing store than memory

Process can run when not all pages are loaded into main memory

OS and hardware cooperate to make large disk seem like memory

Same behavior as if all of address space in main memory

Requirements:

- OS must have mechanism to identify location of each page in address space → in memory or on disk
- OS must have policy for determining which pages live in memory and which on disk


SWAPPING MECHANISMS

Each page in virtual address space maps to one of three locations:


- Physical main memory: Small, fast, expensive
- Disk (backing store): Large, slow, cheap
- Nothing (error): Free

Extend page tables with an extra bit: present

- permissions (r/w), valid, present
- Page in memory: present bit set in PTE
- Page on disk: present bit cleared
 - PTE points to block on disk
 - Causes trap into OS when page is referenced







What if access vpn 0xb?

VIRTUAL MEMORY MECHANISMS

First, hardware checks TLB for virtual address

- if TLB hit, address translation is done; page in physical memory

Else ...

- Hardware or OS walk page tables
- If PTE designates page is present, then page in physical memory (i.e., present bit is cleared)

Else

- Trap into OS (not handled by hardware)
- OS selects victim page in memory to replace
 - Write victim page out to disk if modified (add dirty bit to PTE)
- OS reads referenced page from disk into memory
- Page table is updated, present bit is set
- Process continues execution

SWAPPING POLICIES

SWAPPING POLICIES age faults

Goal: Minimize number of page faults

- Page faults require milliseconds to handle (reading from disk)
- Implication: Plenty of time for OS to make good decision

OS has two decisions

Page selection

When should a page (or pages) on disk be brought into memory?

Page replacement

Which resident page (or pages) in memory should be thrown out to disk?

PAGE SELECTION

Demand paging: Load page only when page fault occurs

- Intuition: Wait until page must absolutely be in memory
- When process starts: No pages are loaded in memory
- Problems: Pay cost of page fault for every newly accessed page

Prepaging (anticipatory, prefetching): Load page before referenced

- OS predicts future accesses (oracle) and brings pages into memory early
- Works well for some access patterns (e.g., sequential)
- Problems?

Hints: Combine above with user-supplied hints about page references

- User specifies: may need page in future, don't need this page anymore, or sequential access pattern, ...
- Example: madvise() in Unix






PAGE REPLACEMENT

Which page in main memory should selected as victim?

- Write out victim page to disk if modified (dirty bit set)
- If victim page is not modified (clean), just discard

OPT: Replace page not used for longest time in future

- Advantages: Guaranteed to minimize number of page faults
- Disadvantages: Requires that OS predict the future; Not practical, but good for comparison



PAGE REPLACEMENT

FIFO: Replace page that has been in memory the longest

- Intuition: First referenced long time ago, done with it now
- Advantages: Fair: All pages receive equal residency; Easy to implement
- Disadvantage: Some pages may always be needed

LRU: Least-recently-used: Replace page not used for longest time in past

- Intuition: Use past to predict the future
- Advantages: With locality, LRU approximates OPT
- Disadvantages:
 - · Harder to implement, must track which pages have been accessed
 - Does not handle all workloads well

PAGE REPLACEMENT EXAMPLE

Page reference string: ABCABDADBCB





PAGE REPLACEMENT COMPARISON

Add more physical memory, what happens to performance? LRU, OPT:

- Guaranteed to have fewer (or same number of) page faults
- Smaller memory sizes are guaranteed to contain a subset of larger memory sizes
- Stack property: smaller cache always subset of bigger

FIFO:

- Usually have fewer page faults
- Belady's anomaly: May actually have more page faults!

FIFO PERFORMANCE MAY DECREASE!

Consider access stream: ABCDABEABCDE

Consider physical memory size: 3 pages vs. 4 pages

How many misses with FIFO?

IMPLEMENTING LRU

Software Perfect LRU

- OS maintains ordered list of physical pages by reference time
- When page is referenced: Move page to front of list
- When need victim: Pick page at back of list
- Trade-off: Slow on memory reference, fast on replacement

Hardware Perfect LRU

- Associate timestamp register with each page
- When page is referenced: Store system clock in register
- When need victim: Scan through registers to find oldest clock
- Trade-off: Fast on memory reference, slow on replacement (especially as size of memory grows)

In practice, do not implement Perfect LRU

- LRU is an approximation anyway, so approximate more
- Goal: Find an old page, but not necessarily the very oldest

CLOCK ALGORITHM


Hardware

- Keep use (or reference) bit for each page frame
- When page is referenced: set use bit

Operating System

- Page replacement: Look for page with use bit cleared (has not been referenced for awhile)
- Implementation:
 - Keep pointer to last examined page frame
 - Traverse pages in circular buffer
 - Clear use bits as search
 - Stop when find page with already cleared use bit, replace this page

CLOCK: LOOK FOR A PAGE



CLOCK EXTENSIONS

Replace multiple pages at once

- Intuition: Expensive to run replacement algorithm and to write single block to disk
- Find multiple victims each time and track free list

Use dirty bit to give preference to dirty pages

- Intuition: More expensive to replace dirty pages
 Dirty pages must be written to disk, clean pages do not
- Replace pages that have use bit and dirty bit cleared

SUMMARY: VIRTUAL MEMORY

Abstraction: Virtual address space with code, heap, stack

Address translation

- Contiguous memory: base, bounds, segmentation
- Using fixed sizes pages with page tables

Challenges with paging

- Extra memory references: avoid with TLB
- Page table size: avoid with multi-level paging, inverted page tables etc.

Larger address spaces: Swapping mechanisms, policies (LRU, Clock)

NEXT STEPS

Project 2b: Out now

Next class: New module on Concurrency