# **Virtual Memory**


### **Background (Cont.)**

- Virtual memory separation of user logical memory from physical memory
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - Allows for more efficient process creation
  - More programs running concurrently
  - Less I/O needed to load or swap processes

### **Background (Cont.)**


- Virtual address space logical view of how process is stored in memory
  - Usually start at address 0, contiguous addresses until end of space
  - Meanwhile, physical memory organized in page frames
  - MMU must map logical to physical
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation

#### **Virtual Memory That is Larger Than Physical Memory**



#### **Demand Paging**

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
  - Less I/O needed, no unnecessary I/O
  - Less memory needed
  - Faster response
  - More users
- Similar to paging system with swapping (diagram on right)
- □ Page is needed ⇒ reference to it
  - invalid reference ⇒ abort
  - □ not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a pager




#### **Basic Concepts**

- With swapping, pager guesses which pages will be used before swapping out again
- Instead, pager brings in only those pages into memory
- How to determine that set of pages?
  - Need new MMU functionality to implement demand paging
- □ If pages needed are already memory resident
  - No difference from non demand-paging
- □ If page needed and not memory resident
  - Need to detect and load the page into memory from storage
    - Without changing program behavior
    - Without programmer needing to change code


#### **Valid-Invalid Bit**

- With each page table entry a valid–invalid bit is associated
  (v ⇒ in-memory memory resident, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:



During MMU address translation, if valid–invalid bit in page table entry is i ⇒ page fault

#### Page Table When Some Pages Are Not in Main Memory




#### **Page Fault**

If there is a reference to a page, first reference to that page will trap to operating system:

#### page fault


- 1. Operating system looks at another table to decide:
  - □ Invalid reference ⇒ abort
  - Just not in memory
- 2. Find free frame
- 3. Swap page into frame via scheduled disk operation
- Reset tables to indicate page now in memory Set validation bit = v
- 5. Restart the instruction that caused the page fault

### **Steps in Handling a Page Fault**



#### **Aspects of Demand Paging**


- Extreme case start process with no pages in memory
  - OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault
  - And for every other process pages on first access
  - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
  - Pain decreased because of locality of reference
- Hardware support needed for demand paging
  - Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Instruction restart



#### Page Replacement

- Prevent over-allocation of memory by modifying pagefault service routine to include page replacement
- ☐ Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory

### **Need For Page Replacement**




#### Page and Frame Replacement Algorithms

- ☐ Frame-allocation algorithm determines
  - How many frames to give each process
  - Which frames to replace
- □ Page-replacement algorithm
  - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
  - String is just page numbers, not full addresses
  - Repeated access to the same page does not cause a page fault
  - Results depend on number of frames available
- In all our examples, the reference string of referenced page numbers is

### First-In-First-Out (FIFO) Algorithm

- □ Reference string: **7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1**
- □ 3 frames (3 pages can be in memory at a time per process)




15 page faults

- □ Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
  - Adding more frames can cause more page faults!
    - Belady's Anomaly
- How to track ages of pages?
  - Just use a FIFO queue


#### **Optimal Algorithm**

- Replace page that will not be used for longest period of time
  - 9 is optimal for the example
- How do you know this?
  - Can't read the future
- Used for measuring how well your algorithm performs



#### Least Recently Used (LRU) Algorithm


- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page



- □ 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?

#### **Thrashing**

- If a process does not have "enough" pages, the page-fault rate is very high
  - Page fault to get page
  - Replace existing frame
  - But quickly need replaced frame back
  - This leads to:
    - Low CPU utilization
    - Operating system thinking that it needs to increase the degree of multiprogramming
    - Another process added to the system
- □ Thrashing = a process is busy swapping pages in and out



- □ What happens, if CPU want to access "Page 2" of each process
  - Increase in Page fault rate and most of the time will spent in bringing pages in and out of the RAM.
  - This process is referred to THRASHING

## **Thrashing (Cont.)**

