In the name of Allah

Midterm Overview

Zohre Soorani Mahdi Haghverdi Hussein Husseini Hosna Rajaei



November 14, 2023

Content

Computer Abstraction and Technology

Operations of the Computer Hardware

Operands of the Computer Hardware

Memory Operands Constant or Immedidate Operands

Representing Instructions

Logical Operations

Instuctions for Making Decisions

Suporting Precedures in Computer Hardware

MIPS Addressing for 32-Bit Immediates and Addresses

A C Sort Example to Put It All Together

Midterm Overview 1 / 47

Computer Abstraction and Technology

Computer Abstraction and Technology

Operations of the Computer Hardware

Operations of the Computer Hardware

Figure: Arithmatic Instructions in MIPS

Category	Instruction	Example	Meaning	Comments
	add	add \$s1,\$s2,\$s3	\$s1 = \$s2 + \$s3	Three register operands
Arithmetic	subtract	sub \$s1,\$s2,\$s3	\$s1 = \$s2 - \$s3	Three register operands
	add immediate	addi \$s1,\$s2,20	\$s1 = \$s2 + 20	Used to add constants

load upper immed	lui \$s1, 20	\$s1 = 20 * 2 ¹⁶	Loads constant in upper 16 bits
store byte	sb \$s1, 20(\$s2)	Memory[\$s2 + 20] = \$s1	Byte from register to memory
load byte unsigned	lbu \$s1, 20(\$s2)	\$s1 = Memory[\$s2 + 20]	Byte from memory to register
load byte	lb \$s1, 20(\$s2)	\$s1 = Memory[\$s2 + 20]	Byte from memory to register
store word	sw \$s1, 20(\$s2)	Memory[\$s2 + 20] = \$s1	Word from register to memory
load word	lw \$s1, 20(\$s2)	\$s1 = Memory[\$s2 + 20]	Word from memory to register

Table: Data Transfer Instructions in MIPS

Figure: Logical Instructions in MIPS

	and	and	\$s1,\$s2,\$s3	\$s1 = \$s2 & \$s3	Three reg. operands; bit-by-bit AND
	or	or	\$s1,\$s2,\$s3	\$s1 = \$s2 \$s3	Three reg. operands; bit-by-bit OR
	nor	nor	\$s1,\$s2,\$s3	\$s1 = ~ (\$s2 \$s3)	Three reg. operands; bit-by-bit NOR
Logical	and immediate	andi	\$s1,\$s2,20	\$s1 = \$s2 & 20	Bit-by-bit AND reg with constant
	or immediate	ori	\$s1,\$s2,20	\$s1 = \$s2 20	Bit-by-bit OR reg with constant
	shift left logical	s11	\$s1,\$s2,10	\$s1 = \$s2 << 10	Shift left by constant
	shift right logical	srl	\$s1,\$s2,10	\$s1 = \$s2 >> 10	Shift right by constant

Figure: Conditional Branch Instructions in MIPS

Conditional branch	branch on equal	beq	\$s1,\$s2,25	if (\$s1 == \$s2) go to PC + 4 + 100	Equal test; PC-relative branch
	branch on not equal	bne	\$s1,\$s2,25	if (\$s1!= \$s2) go to PC + 4 + 100	Not equal test; PC-relative
	set on less than	slt	\$s1,\$s2,\$s3	if (\$s2 < \$s3) \$s1 = 1; else \$s1 = 0	Compare less than; for beq, bne
	set on less than unsigned	sltu	\$s1,\$s2,\$s3	if (\$s2 < \$s3) \$s1 = 1; else \$s1 = 0	Compare less than unsigned
	set less than immediate	slti	\$s1,\$s2,20	if (\$s2 < 20) \$s1 = 1; else \$s1 = 0	Compare less than constant
	set less than immediate unsigned	sltiu	ı \$s1,\$s2,20	if (\$s2 < 20) \$s1 = 1; else \$s1 = 0	Compare less than constant unsigned

Figure: Unconditional Jump Instructions in MIPS

Unconditional -	jump	j	2500	go to 10000	Jump to target address
	jump register	jr	\$ra	go to \$ra	For switch, procedure return
	jump and link	jal	2500	\$ra = PC + 4; go to 10000	For procedure call

Example - Compiling a Complex C Assignment into MIPS

A somewhat complex statement contains the five variables f, g, h, i, and j: f = (g + h) - (i + j); What might a C compiler produce?

Answer

- add t0, g, h # temporary variable t0 contains g + h
- add t1, i, j # temporary variable t1 contains i + j
- sub f, t0, t1 # f gets t0 t1, which is (g + h) (i + j)

Operands of the Computer Hardware

Example - Compiling a C Assignment Using Registers

It is the compiler's job to associate program variables with registers.

Take, for instance, the assignment statement from our earlier example:

$$f = (g + h) - (i + j);$$

The variables f, g, h, i, and j are assigned to the registers s0, s1, s2, s3, and s4, respectively.

What is the compiled MIPS code?

Answer

- add \$t0, \$s1, \$s2 # register \$t0 contains g + h
- add \$t1, \$s3, \$s4 # register \$t1 contains i + j
- sub \$s0, \$t0, \$t1 # f gets <math>\$t0 \$t1, which is (g + h) (i + j)

Example - Compiling Using Load and Store

Assume variable h is associated with register \$s2 and the base address of the array A is in \$s3.

What is the MIPS assembly code for the C assignment state ment below?

A[12] = h + A[8];

Answer

- lw \$t0, 32(\$s3) # Temporary reg \$t0 gets A[8]
- add \$t0, \$s2, \$t0 # Temporary reg \$t0 gets h + A[8]
- sw \$t0, 48(\$s3) # Stores h + A[8] back into A[12]

Constant or Immedidate Operands

- addi \$s3, \$s3, 4 # \$s3 = \$s3 + 4

Representing Instructions

Instructions Big Picture

Name	Format	Example					Comments	
Field Size		6 bit	5 bit	5 bit	5 bit	5 bit	6 bit	All MIPS instructions are 32 bits long
R-format	R	op	rs	rt	$_{\mathrm{rd}}$	shamt	funct	Arithmetic instruction format
add	R	0	18	19	17	0	32	add \$s1,\$s2,\$s3
I-format	I	op	rs	rt		address		Data transfer format
lw	I	35	18	17		100		lw \$s1,100(\$s2)
J-format	J	op	address			Unconditional Branch		
j	J	8	300					jump to address

Logical Operations

Logical Operations Big Picture

Logical operations	C operators	Java operators	MIPS instructions
Shift left	<<	<<	sll
Shift right	>>	>>>	srl
Bit-by-bit AND	&	&	and, andi
Bit-by-bit OR			or, ori
Bit-by-bit NOT	~	~	nor

Instuctions for Making Decisions

Instructions for Making Decisions

- beq register1, register2, L1
 This instruction means go to the statement labeled L1 if the value in register1 equals the value in register2.
 The mnemonic beq stands for branch if equal.
- bne register1, register2, L1

 It means go to the statement labeled L1 if the value in register1 does not equal the value in register2.

 The magnetic bre stands for branch if not equal
 - The mnemonic bne stands for branch if not equal.

Example - Compiling *if-then-else* into Conditional Branches

In the following code segment, f, g, h, i, and j are variables.

If the five variables, f through j, correspond to the five registers \$s0 through \$s4,

what is the compiled MIPS code for this C if statement?

```
1 if i == j:
2     f = g + h
3 else:
4     f = g - h
```

Answer

```
1 bne $s3, $s4, Else  # go to Else if i != j
2 add $s0, $s1, $s2  # f = g + h (skipped if i != j)
3  j  Exit  # go to Exit
4 Else:
5  sub $s0, $s1, $s2  # f = g - h (skipped if i = j)
6 Exit:
```

Example - Compiling a while Loop in C

Here is a traditional loop in C:

```
1 while (save[i] == k){
2     i += 1;
3 }
```

Assume that i and k correspond to registers \$s3 and \$s5 and the base of the array save is in \$s6.

What is the MIPS assembly code corresponding to this C segment?

Answer

```
$t1,$s3,2
                                  # Temp reg $t1 = i * 4
  Loop:
          sll
                  $t1,$t1,$s6
                                  # $t1 = address of save[i]
          add
                  $t0,0($t1)
                                  # Temp reg $t0 = save[i]
          ٦w
                                  # go to Exit if save[i] != k
                  $t0,$s5, Exit
          bne
5
          addi
                  $s3,$s3,1
                                  # i = i + 1
6
                  Loop
                                  # go to Loop
  Exit:
```

Suporting Precedures in Computer Hardware

Six Steps

- 1. Put parameters in a place where the procedure can access them.
- 2. Transfer control to the procedure.
- 3. Acquire the storage resources needed for the procedure.
- 4. Perform the desired task.
- 5. Put the result value in a place where the calling program can access it.
- 6. Return control to the point of origin, since a procedure can be called from several points in a program.

Provided Registers

MIPS software follows the following convention for procedure calling in allocating its 32 registers

- \$a0-\$a3: four argument registers in which to pass parameters
- \$v0-\$v1: two value registers in which to return values
- \$ra: one return address register to return to the point of origin

Provided Registers (Cont'd)

- In addition to allocating these registers, MIPS assembly language includes an instruction just for the procedures:
- It jumps to an address and simultaneously saves the address of the following instruction in register \$ra.
- The *jump-and-link* instruction (jal) is simply written:
- jal ProcedureAddress

Provided Registers (Cont'd)

- The *link* portion of the name means that an address or link is formed that points to the calling site to allow the procedure to return to the proper address. This "link", stored in register \$ra (register 31), is called the return address.
- The return address is needed because the same procedure could be called from several parts of the program.
- To support such situations, computers like MIPS use jump register instruction (jr), introduced above to help with case statements, meaning an unconditional jump to the address specified in a register:
- jr \$ra

Example - Compiling a C Procedure That Doesn't Call Another Procedure

```
1 int leaf_example (int g, int h, int i, int j)
2 {
3    int f;
4    f = (g + h) - (i + j);
5    return f;
6 }
```

Answer

```
leaf example:
   addi $sp, $sp, -12
                       # adjust stack to make room for 3 items
        $t1, 8($sp)
                        # save register $t1 for use afterwards
   sw
      $t0, 4($sp) # save register $t0 for use afterwards
   SW
   SW
      $s0, 0($sp)
                        # save register $s0 for use afterwards
   add
        $t0, $a0, $a1 # register $t0 contains g + h
        $t1, $a2, $a3  # register $t1 contains i + j
   add
        $s0, $t0, $t1 # f = $t0 - $t1, which is (g + h-)(i + j)
   sub
   add
        $v0. $s0. $zero # returns f ($v0 = $s0 + 0)
```

Answer (Cont'd)

```
lw $s0, 0($sp)  # restore register $s0 for caller
lw $t0, 4($sp)  # restore register $t0 for caller
lw $t1, 8($sp)  # restore register $t1 for caller
addi $sp, $sp, 12  # adjust stack to delete 3 items

jr $ra  # jump back to calling routine
```

Example - Compiling a Recursive C Procedure, Showing Nested Procedure Linking

```
1 int fact (int n)
2 {
3     if (n < 1) {
4         return 1;
5     }
6     else {
7         return (n * fact(n - 1));
8     }
9 }</pre>
```

Answer

```
fact:
   addi $sp, $sp, -8 # adjust stack for 2 items
        $ra, 4($sp) # save the return address
   sw
        $a0.0(\$sp) # save the argument n
   SW
   slti $t0, $a0, 1  # test for n < 1</pre>
   beg $t0, $zero, L1 # if n >= 1, go to L1
   addi $v0, $zero, 1 # return 1
   addi $sp, $sp, 8 # pop 2 items off stack
   jr $ra
                   # return to caller
```

Answer (Cont'd)

```
L1:
                     addi a0, 
                                                                                    # call fact with (n - 1)
                     ial fact
                     lw $a0, 0($sp) # return from jal: restore argument n
                     lw $ra, 4($sp)  # restore the return address
                     addi $sp, $sp, 8 # adjust stack pointer to pop 2 items
                    mul $v0, $a0, $v0 # return n * fact (n - 1)
                     jr $ra
                                                                                                                    # return to the caller
```

MIPS Addressing for 32-Bit Immediates and Addresses


Example - Loading a 32-Bit Constant

What is the MIPS assembly code to load this 32-bit constant into register \$s0? 0000 0000 0011 1101 0000 1001 0000 0000

Answer

- Immediate addressing where the operand is a constant within the instruct tion itself


Immediate addressing




- Register addressing where the operand is a register




- Base or displacement addressing where the operand is at the memory location whose address is the sum of a register and a constant in the instruction




- PC-relative addressing where the branch address is the sum of the PC and a constant in the instruction



- Pseudodirect addressing where the jump address is the 26 bits of the instruction concatenated with the upper bits of the PC





A C Sort Example to Put It All Together