Cubeviz User Manual

September 13, 2013

Contents

1	Intr	Introduction :						
2	Inst							
3	Getting Started							
	3.1	Embed	dded Matplotlib	5				
	3.2	Cube l	Information	5				
	3.3	Cube l	Menu	5				
	3.4	Updat	e Button	6				
	3.5	Toolba	ar	7				
	3.6	Plot N	Menu	8				
4	Col	orbar (Options Window	9				
	4.1	Auton	natic Selection	9				
	4.2	Fixed	Colorbar	9				
	4.3		al Selection	9				
5	Tut	orial		10				
	5.1	2D Cu	ıbes	10				
		5.1.1	Load a File	10				
		5.1.2	Screen Layout	11				
		5.1.3	Adapting the Layout	12				
		5.1.4	Change the Plot Type	12				
		5.1.5	Pick a Color Scheme	13				
		5.1.6	Switching to quickplot	14				
		5.1.7	Contours, Coastlines and More	14				
		5.1.8	Choose a Projection	15				
		5.1.9	Matplotlib Interactions	16				

		5.1.10	Saving your Image	16
	5.2	More (Complex Cubes	16
		5.2.1	Arranging Dimensions	17
		5.2.2	Moving through a Dimension	18
		5.2.3	Setting the Colorbar	19
	5.3	More 1	Dimensions	20
		5.3.1	Selecting a Cube from a File	20
		5.3.2	Working with Collapsed Dimensions	20
6	Kev	board	Shortcuts	22

1 Introduction

Cubeviz is a lightweight visulisation tool designed for use with Iris and Cartopy. It allows you to quickly and easily load a file, and then view plots of the cubes within it.

You are able to select which cube from the file you would like to plot, and, for cubes with more than 2 dimensions, you are able to choose to plot any 2D slice of the cube.

Further, you have numerous options regarding how the cube will be plotted, from the type of graph, to drawing coastlines, all of which are explained in this manual.

This manual will help you get help you get started with Cubeviz, and guide you through the features that it offers. For hints whilst using the program, hold your mouse over the relevant section to produce a tool tip describing its function.

2 Installation

3 Getting Started




Figure 1: This figure shows the main window of the application, broken down into its key components.

The main window can be broken down into a few main segments;

- 1. Embedded Matplotlib Display: Where the plot is displayed.
- 2. Cube Information: Displays a summary of the cube and the slice, and shows the data within the slice.
- 3. Cube Menu: Allows selection of which slice is plotted.
- 4. Update Button: Replots the cube.
- 5. Toolbar: Numerous Actions such as open and save.
- 6. Plot Menu: Allows selection of how the cube is plotted.

3.1 Embedded Matplotlib

The plot is displayed in an embedded matplotlib window. This means that all of the functionality that you would have using matplotlib from terminal will still be present here.

For example, by clicking the magnifying glass icon in the matplotlib toolbar, you are able to zoom in on any area of the plot by dragging a rectangle around the section that you would like to enlarge. Equally, you are also able to enlarge a region by specifying the range over which the graph will be plotted. This is done by clicking on the green tick, clicking ok, and then specifying the max and min of the axes range.

You can also pan and zoom by clicking the pan button, can save using the save button, and can adjust the position of the plot using the configure subplots button.

If you mouse over the plot, you will discover that the current posistion of the mouse will be displayed to the right of the toolbar.

3.2 Cube Information

This pannel contains all of the information about the cube. There are three tabs to select from, Full Cube, Cube Slice, and Slice Data.

- Full Cube: This tab will show you the summary of the cube that is currently loaded.
- Cube Slice: This tab will display the summary of the slice of the cube that is currently being plotted. (note that this will be the same as the full cube if the cube has fewer than 3 dimensions).
- Slice Data: This tab will display the raw data contained within the current slice in the form of a table.

3.3 Cube Menu

The Cube Options sections is split into 4 parts.

- Select Cube: This drop down box allows you to select which cube you would like to view from the list of cubes in the current file. If there is only one cube in the file, this box will be disabled.
- Axes Dimensions: These 2 drop down boxes contain the coordinates that will be placed on the axes of the plot. For example, if the boxes

contained height and time, then the application will produce a plot of height against time.

You are able to choose any of the dimensions from the drop down box.

The order of the two boxes is not important, (i.e. a selection of latitude and longitude will produce the same result as longitude and latitude.

• Sliced Dimension: This is the dimension in which the slices will be taken. The next and previous slice buttons will move along slices in this dimension, and setting the colorbar across all slices refers to this dimension.

The top box contains the dimension that is currently being sliced, while the box below it contains the value apon which that dimension will be collapsed for this slice.

You are able to select the desired dimension using the drop down box, and can choose which slice along this dimension is taken by using either the slider or the drop down box.

• Collapsed Dimensions: The remaining dimensions are placed in this area. The names of the remaining dimensions will apear alongside a drop down list.

To obtain a 2D cube which can be plotted, the program will collapse these dimensions down onto the values specified in the boxes. You are able to select which value to collapse onto by using the drop down boxes.

• *N.B:* For cubes which contain anonymous dimensions, you will find that the coordinate name will be set to *ANONYMOUS* (with a number atatched to distinguish between multiple anonymous coordinates.)

The application will function as normal with these coordinates, however it will fill the drop down boxes with the numbers 0 - (n-1) (where n is the size of the dimension) instead of the values of the coordinate as these do not exist for anonymous dimensions.

3.4 Update Button

This button will cause the plot to be redrawn. The changes that you make to the plot will not be executed until the update button is pressed.

3.5 Toolbar

The main toolbar contains numerous options and actions:

- Open: Brings up a file browser from which you are able to select a to file open
- Save: Opens a window which allows you to save the current image in a specified location with a specified name in a number of different file types including jpeg and png
- Previous Slice: Only enabled if the cube has three or more dimensions. This will move you to the slice with a coordinate index of the sliced dimension which is one lower than the current index.
- Next Slice: Only enabled if the cube has three or more dimensions. This will move you to the slice with a coordinate index of the sliced dimension which is one higher than the current index.
- Source Code: Clicking this button will open up a new window containing code that is able to recreate the currently displayed image.
- Coastlines: Toggle the plotting of coastlines on and off. This will be disabled if the plot is not detected to be a lat/lon plot.
- Gridlines: Toggle whether gridlines should be drawn onto the plot.
- Contour Labels: Toggle the labelling of the contours. Only enabled if the plot type is Contour.
- Country Boundaries: Toggle the marking of country borders.

 Will only be enabled if the plot is detected to be lat/lon.

 Note: This will also give a more detailed representation of the coast-lines, but will slow down the plotting of the graph.
- Rivers and Lakes: Toggle the marking on of major lakes and rivers. This will only be enabled if the plot is detected to be lat/lon.
- Colorbar Range: Opens a window giving you options about how the colorbar is set. See section 4 for more details.
- *Plot Menu:* This will toggle the plot menu on and off. See section 3.6 for more details on the Plot Menu.

- *About:* Gives brief general and copywrite information about the application.
- Exit: Closes the application.

3.6 Plot Menu

This menu contains options which affect the visual appearence of the plot.

The menu can be toggled on and off by clicking the plot menu button in the toolbar.

- *Plot Type:* This option allows you to select the type of graph you would like to plot. Choose from Contour, Filled Contour and prolormesh (Block Plot).
- *Plot Projection:* This option allows you to select the type of plot projection that you would like.

N.B. At the time of writing, some bugs in Cartopy make many of the projections very temperemental. (This is known about and being fixed)

Some of the projections will return just a dot. If this is the case then you should be able to zoom in on them (see section 3.1)

Others will plot data in areas outside of the earth or will have a discontinuity part way across.

Some may even cause the application to stop working. In this case, exit the application using, clicking 'force close' if required, and then restart the program.

Which projections fail depends on the plot type being used and on the data being plotted. If in doubt, leave the projection as automatic.

- Color Scheme: This option allows you to select a color scheme for the plot. The colour schemes available are the brewer palletes that were compatible with Iris at the time of writing.
- No. of Contours: This option allows you to select the number of contours to plot.

This option will be disabled if the plot type is prolormesh.

If the Color Scheme has fewer colors than the number of contours, then multiple contours will be set to one color.

4 Colorbar Options Window

In this window, you are able to change which values the colorbar will be set between. The current maximum and minimum of the range will be shown in the max and min boxes.



Figure 2: This figure shows the main window of the application, broken down into its key components.

4.1 Automatic Selection

By default, the application will scan through the values in the current slice, and find the maximum and the minimum values. It will then set the lowest color to the minimum value, and the highest color to the maximum value, and fill in everything else.

4.2 Fixed Colorbar

If you are looking to compare different slices, it may be useful for the colorbar to be constant, instead of changing itself from slice to slice. To do this, it often makes sense to set the colorbar to the max and min of the entire set of slices, instead of just the current slice, and that is exactly what is done by this option.

For a good example of where this is useful, see the tutorial section 5.2.3.

4.3 Manual Selection

Alternatively, you might wish to set your own range. To do this, simply click Manual Selection and then enter your chosen values into the boxes.

5 Tutorial

In this short tutorial, I will step you through how to load your first cubes, and then introduce the options available to you in Cubeviz.

The files used in this tutorial are from the Iris-Sample-Data.

If you do not have these files already, then they can be found at https://github.com/SciTools/iris-sample-data

5.1 2D Cubes

We will start with a simple 2D cube which holds data on gloabl air temperature.

5.1.1 Load a File




Figure 3: Click here to open a new file.

To load this file, simply click on the 'Open' button found at the top left of the screen. This will open a file browser. From here, navigate to your version of the iris-sample-data folder, select the file named 'A1B.2098.pp' and click open.




Figure 4: Select the A1B.2098.pp cube

5.1.2 Screen Layout

The cube should now be loaded, and should have been plotted on the left of your screen. To the right of the screen, you will see that the axes dimension boxes and the select cube box have been filled, but not the Sliced Dimension box. This is because the cube has only 2 dimensions.




Figure 5: Clear here to view the data in the cube.

If you look to the bottom left of the window, you will be able to see the a summary of the cube. You are currently in the Full Cube tab. This will

show you the summary of the cube you have loaded. You can switch to the Sliced Cube tab by clicking on the tab, however you will notice that there is no change to the cube summary. This is because this cube has only 2 dimensions and so does not need to be sliced before plotting.

Click on the slice data tab to show a table containing the data contained within the currently plotted slice.

5.1.3 Adapting the Layout

Depending on how you are using the aplication, you may wish to resize elements of the window. Firstly, the whole window can be resized as standard, but the program will also allow you to resize some of its internal components. You can change the size of the data table and plot by clicking as indicated on the diagram and dragging either up or down as desired.




Figure 6: Drag where the arrows are to change the layout of the window. Click on Plot Menu to toggle the Plot Menu on and off.

Likewise, you are able to click as indicated here and drag left or right to change the size of the cube options section.

Finally, the plot menu can be toggle on or off by clicking the 'Plot Menu' button.

5.1.4 Change the Plot Type

Changing the plot type is simple. Just click on the drop down list labeled Plot Type, and select the type of plot you would like.




Figure 7: Click here to change the plot type.

After having made any changes, you will need to click update (shortcut rtrn) before the plot will be redrawn with the new options.

5.1.5 Pick a Color Scheme

Again, simply click on the marked drop down list and pick from the list.

The application currently uses the brewer color palletes that are compatible with Iris.




Figure 8: Click here to change the colors used in the plot.

5.1.6 Switching to quickplot

So far, we have not been using any of the Iris plotting tools. Instead, we have simply been plotting the raw data. This has the advantage of being very fast, but comes without much of the functionality offered by Iris and Cartopy. Lets switch now to using iris.quickplot for creating the images. This can be done by clicking on the plot method button and selecting using quickplot from the drop down list. Click update to replot the graph.




Figure 9: Click here to change the plot method.

5.1.7 Contours, Coastlines and More

Now that we are using quickplot, you will notice that there are more options enabled in the toolbar. The ones available for this cube are coastlines, country boundaries, rivers and lakes and contour labels if the plot type is Contour.

You also have the option to change the number of contours plotted using the slider.

Try turning these options on and off now to get a feel for them. (remeber that you will need to click update before the plot is redrawn)




Figure 10: This range of options will affect what is plotted on the image.

5.1.8 Choose a Projection

Just as simple to change. Click on the Select Projection box, and make a choice.




Figure 11: Clicking here will change the progrection that is being used.

However, at the time of writing, some bugs in Cartopy make many of the projections very tempremental. (This is known about and being fixed)

As such, a few of the projections have temporarily been removed from

the program. You may also see other bugs when using projections. It would be greatly appreciated if you could report any bugs that you find.

5.1.9 Matplotlib Interactions

In just the same way as if you had plotted the graph through the terminal, you have all of the same options with you matplotlib image. The standard toolbar can be found below the image and provides functionality for zooming, dragging etc.




Figure 12: These options are the same as those found in a standard matplotlib toolbar.

5.1.10 Saving your Image

You can save your image either by clicking the save button on the matplotlib toolbar, or by clicking save on the main toolbar. In both cases you will open a file browser which will allow you to save the image as normal.

You can save the image in numerous formats including png and jpeg.

5.2 More Complex Cubes

In this next example, we are going to load a 4 dimensional cube. Following the same method as before, this time load the 'A1B_north_america.nc' file.

5.2.1 Arranging Dimensions

If we now look at the cube information section, and flick between the tabs, we can see that there is now a difference between the full cube and cube slice summaries.




Figure 13: Inspect the current slice using these buttons.

Looking closer at the Sliced Cube tab, we can see that the Axes Dimensions correspond to the dimensions of this cube slice, and that the other two dimensions have been collapsed down to the value shown on the boxes (although if the coordinate is time then there may be differences as Iris transforms the time values)

We can now try changing the Axes dimensions.

Click on the latitude axes dimension and change it to be time. Now click update (or press rtrn) to plot the new graph.




Figure 14: Change the coordinate from latitude to time.

Notice that now many of the options have been removed. For example you now cannot plot coastlines or change the projection. This is because the plot is no longer a lat/lon plot, so these options would make no sense.

5.2.2 Moving through a Dimension

To move through the slices, you can either select the slice you would like to see using the slider or the drop down list, or you can use the next and previous slice buttons (shortcuts 6 and 4) to step through the slices.




Figure 15: Use these to move through the slices.

5.2.3 Setting the Colorbar

As you are moving through the slices, you may have noticed that for every new slice, the colorbar updates. This makes it difficult to compare between the slices, as red in one slice may not be the same temperature as red in any other slice.

To change this, click on the Colorbar Range button.




Figure 16: Click here to open the colorbar dialog box.

This will open a new window. In this window, check the box next to Fix across all Slices. You will notice that the values in the max and min boxes will change.

Closing this and again moving through the slices, you will notice that it is now much easier to compare between slices, as a particular color will now always correspond to the same temperature.




Figure 17: Clicking here will fix the colorbar over all of the slices.

What we have done here is to scan through all of the slices, and set red to be the maximum value across all of the slices, and blue to be the minimum across all of the slices.

You are also able to specify your own range for the colorbar by clicking the manual botton in the Colorbar Range window and then changing the max and min values. Try this now a see what effect this has.

5.3 More Dimensions

For the last section al the tutorial, try opening a four dimensional cube. One such cube is 'uk_hires.pp', again found in the Iris Sample Data folder.

5.3.1 Selecting a Cube from a File

Looking at the Select Cube box, you will see that unlike in the last example, this box is now enabled. Click it, and you will see that you now have a choice of the 2 cubes contained within this file. (remembering still that the update button must be pressed before the graph will be redrawn)




Figure 18: Click here to change the current cube within the file.

5.3.2 Working with Collapsed Dimensions

Switch back to the air_potential_temperatur cube. You should now be able to see that we have filled one of our collapsed dimension slots. Checking the Cube Slice tab, you will see that the cube has been collapsed down onto the value specified next to the collapsed dimension name.

To change this value, simply select a new one from the drop down list. To change which dimensions are collapsed, just pick the dimensions that you would like to plot as before.

That's it! You have now seen all of the features availiable to you, and hopefully feel ready to start using Cubeviz.

If you have any further questions or have any problems, please contact \dots

6 Keyboard Shortcuts

Table 1: Keyboard Shortcuts

rable 1: Hej board blieftedtb					
Action	Shorcut				
Open	Cntl + O				
Save	Cntl + S				
Update	rtrn				
Previous Slice	4				
Next Slice	6				
Coastlines	\mathbf{C}				
Gridlines	G				
Contour Labels	${ m L}$				
Country Boundaries	В				
Rivers and Lakes	\mathbf{R}				
Colorbar Range	O				
Plot Menu	M				
Exit	Esc				