Stress Drop Reading Group


Week 1

July 15th, 2024

How to average stress drop?

Assumptions

- (a) $\Delta u_2(x_1, x_3) = 0 \& \Delta \vec{u} \perp \vec{e_2}$ (no fault opening)
- (b) Slip in single direction $(\overrightarrow{e_1})$ is dominant.
- (c) Planar fault *S* embedded in linear elastic infinite homogeneous medium



Stress drop (vector):
$$\Delta \vec{\sigma}(x_1, x_3) = \overrightarrow{\tau^i}(x_1, x_3) - \overrightarrow{\tau^f}(x_1, x_3)$$

It is obvious that $\Delta \vec{\sigma}$ varies spatially on the fault plane. How to average?

Rupture domain: $\Sigma = {\vec{x} \in S : |\Delta \vec{u}(\vec{x})| \neq 0}$


Truncated domain: $\Sigma = {\vec{x} \in S : |\Delta \vec{u}(\vec{x})| > th \times \max_{S}(|\Delta \vec{u}|)}$ (for practical purpose)

$$\Delta \bar{\sigma} = \frac{\int_{S} \Delta \vec{\sigma} \cdot \vec{w} \, dS}{\int_{S} \vec{e_1} \cdot \vec{w} \, dS} \quad \Rightarrow \quad \text{How would we choose weight } \vec{w} ?$$

How to average stress drop?

(1) Moment-based stress drop, $\overline{\Delta \sigma_M}$

- Average of stress drop weighted by the slip distribution \vec{E}^{12} due to uniform stress drop in the overall slip direction $\vec{e_1}$ over the same ruptured domain ($\vec{w} = \vec{E}^{12}$).
- Equal to seismologically estimated stress drop, $\frac{M_0}{\int_{\Sigma} E_1^{12} dS} \approx C \frac{M_0}{\rho^3} = C \frac{M_0}{A^{3/2}}$
- For circular rupture, $\overline{\Delta \sigma_M}$ emphasizes stress change in the middle of the ruptured domain.



How to average stress drop?

(2) Spatially averaged stress drop, $\overline{\Delta \sigma_A}$

•
$$\overline{\Delta \sigma_A} = \frac{1}{A} \int_{\Sigma} \Delta \sigma_1 dS \ (\overrightarrow{w} = \overrightarrow{e_1})$$

• Equal to difference between average stress levels on the fault before and after earthquake.

(3) Energy-based stress drop, $\overline{\Delta \sigma_E}$

- Average of stress drop weighted by the final slip $\Delta \vec{u}$ at each point $(\vec{w} = \Delta \vec{u})$.
- Relevant stress drop for calculating radiation ratio, $\eta_R = E_R / \Delta W_0 = \frac{2\mu E_R}{\Delta \sigma M_0}$
- $\overline{\Delta \sigma_E} \geq \overline{\Delta \sigma_M}$

Relation between $\overline{\Delta \sigma_E}$ and strain energy ΔW

Total strain energy:
$$\Delta W = \left(\frac{\tau^i + \tau^f}{2}\right) \overline{\Delta u} A$$


Partial strain energy change: $\Delta W_0 = E_G + E_R$

Radiation ratio (efficiency):
$$\eta_R = E_R / \Delta W_0 = \frac{2\mu E_R}{\Delta \sigma M_0}$$


Introduce $\lambda \in [0, 1]$ to represent continuous set of static solutions between initial $(\lambda = 0)$ and final state $(\lambda = 1)$.

$$\overrightarrow{\delta_{vp}}(\lambda, \vec{x}) = \lambda \Delta \vec{u}, \ \overrightarrow{\tau_{vp}}(\lambda, \vec{x}) = \lambda \vec{\tau}^f + (1 - \lambda) \vec{\tau}^i$$

$$\Delta W = \int_0^1 \frac{dW}{d\lambda} d\lambda = \int_0^1 \int_{\Sigma} \overrightarrow{\tau_{vp}} \cdot \frac{d\overrightarrow{\delta_{vp}}}{d\lambda} dS d\lambda$$
$$\Delta W = \int_{\Sigma} \left\{ \frac{1}{2} \Delta \vec{\sigma} + \vec{\tau}^i \right\} \cdot \Delta \vec{u} dS$$




(a)




Relation between $\overline{\Delta \sigma_E}$ and strain energy ΔW


$$\Delta W_0 = \Delta W - \int_{\Sigma} \vec{\tau}^f \cdot \Delta \vec{u} \, dS = \frac{1}{2} \int_{\Sigma} \Delta \vec{\sigma} \cdot \Delta \vec{u} \, dS$$

$$\Delta W_0 = \frac{1}{2} \left[\frac{\int_{\Sigma} \Delta \vec{\sigma} \cdot \Delta \vec{u} \, dS}{\int_{\Sigma} \Delta u_1 dS} \right] \int_{\Sigma} \Delta u_1 dS = \frac{1}{2} \overline{\Delta \sigma_E} \, \overline{\Delta u_1} A$$






Comparison of $\overline{\Delta \sigma}$ for heterogeneous ruptures



Comparison of $\overline{\Delta \sigma}$ for heterogeneous ruptures




Energy partitioning and shear stress evolution

Radiated energy:
$$E_R = \frac{1}{2} \int_{\Sigma} (\vec{\tau}^i - \vec{\tau}^f) \cdot \Delta \vec{u} \, dS + \int_0^{t^{fin}} dt \int_{\Sigma} \frac{d\vec{\tau}}{dt} \cdot \vec{\delta} dS$$


$$\approx \frac{1}{2} \int_{\Sigma} (\tau_1^i - \tau_1^f) \cdot \Delta u_1 dS + \int_0^{t^{fin}} dt \int_{\Sigma} \frac{d\tau_1}{dt} \delta_1 dS$$

Radiation ratio:
$$\eta_R = 1 + \frac{2\mu}{\overline{\Delta\sigma_E}M_0} \int_0^{t^{fin}} dt \int_{\Sigma} \frac{d\tau_1}{dt} \delta_1 dS$$

ightarrow Sign of $rac{d au_1}{dt}$ determines whether $\eta_R>1$ or $\eta_R<1$




Energy partitioning and shear stress evolution



Apparent stress, σ_{app}

•
$$\sigma_{app} = \eta \bar{\sigma} = \frac{\mu E_R}{M_0}$$
 (Madariaga, 1977)

- Does not require an estimate of source dimension.
- Q) Can we use σ_{app} instead of $\Delta \sigma$? How much uncertainty in E_R ?
- Q) How does source complexity (e.g., rupture directivity) influence E_R and σ_{app} ?




$$E_R = \frac{I}{4\pi^2 \rho \beta^5} \int_0^\infty \left| \omega \cdot \dot{M}(\omega) \right|^2 d\omega$$

 $\dot{M}(\omega)$: Displacement source spectra

I: Average mean-squared S-wave radiation pattern coefficient (2/5)

Baltay et al. (2011)

Example of earthquake with significantly varying rakes



Questions

- 1. Which stress drop average should we pursue to estimate in observational seismology? Would it depend on specific focus of the research?
- 2. Heterogeneity of stress drop on the fault leads to partially very low and high parts.
 - Does it imply that small earthquakes that break those parts would have correspondingly low or high stress drops? Implication for self-similarity?
- 3. Considering the paradigm of elastic rebound theory, does the average stress drop matter or strong locked patch with locally high stress drop matter?