The Python/C API

发布 3.8.2

Guido van Rossum and the Python development team

三月 16, 2020

Python Software Foundation Email: docs@python.org

Contents

| 1 | 1.1 1.2 1.3 1.4 1.5 | 代码标准 3 包含文件 3 有用的宏 4 对象、类型和引用计数 4 异常 4 5 5 | 3 4 5 8 |
|---|----------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------|
| | 1.6 1.7 | 嵌入 Python | |
| 2 | 稳定的 | 的应用程序二进制接口 13 | 3 |
| 3 | The V | Very High Level Layer | 5 |
| 4 | 引用证 | 十数 | 1 |
| 5 | 异常分 5.1 5.2 5.3 5.4 5.5 5.6 5.7 5.8 5.9 5.10 | 地理 23 Printing and clearing 25 抛出异常 24 Issuing warnings 26 Querying the error indicator 27 Signal Handling 28 Exception Classes 29 Exception Objects 29 Unicode Exception Objects 30 Recursion Control 31 标准异常 31 标准警告类别 33 | 3467899111 |
| 6 | 工具 6.1 6.2 6.3 6.4 6.5 6.6 6.7 6.8 6.9 | 操作系统实用程序35系统功能37过程控制39导入模块40Data marshalling support43语句解释及变量编译44字符串转换与格式化55反射52编解码器注册与支持功能52 | 5 7 9 0 4 1 2 |
| 7 | 抽象》 7.1 | 对象层 对象协议 | |

| | 7.2 | 数字协议 | 61 |
|----|----------|----------------------------------------------------------------|------|
| | 7.3 | 序列协议 | 63 |
| | 7.4 | 映射协议 | |
| | 7.5 | 迭代器协议 | |
| | 7.6 | 缓冲协议 | |
| | 7.7 | 旧缓冲协议 | 72 |
| 8 | 目.休首 | 的对象层 | 75 |
| O | 8.1 | - 基本対象 | |
| | 8.2 | 数值对象 | |
| | 8.3 | 序列对象 | |
| | 8.4 | 容器对象 | 108 |
| | 8.5 | 函数对象 | 111 |
| | 8.6 | 其他对象 | 114 |
| 9 | T., 242. | Partin Pinchard and Thomas | 121 |
| 9 | 9.1 | l lization, Finalization, and Threads 在 Python 初始化之前 | 131 |
| | 9.1 | 在 Pyulon 初始化之前 | |
| | 9.2 | 王月乱且又里 | |
| | 9.4 | Process-wide parameters | |
| | 9.5 | Thread State and the Global Interpreter Lock | |
| | 9.6 | Sub-interpreter support | |
| | 9.7 | 异步通知 | |
| | 9.8 | 分析和跟踪 | |
| | 9.9 | 高级调试器支持 | 146 |
| | 9.10 | Thread Local Storage Support | 147 |
| 10 | D 41 | 3m LA 7L at 1101 | 1.40 |
| 10 | | on 初始化配置 PyWideStringList | 149 |
| | | PyStatus | |
| | | PyPreConfig | |
| | | Preinitialization with PyPreConfig | |
| | | PyConfig | |
| | | Initialization with PyConfig | |
| | | Isolated Configuration | |
| | | Python Configuration | |
| | 10.9 | 路径配置 | 160 |
| | 10.10 | Py_RunMain() | 162 |
| | 10.11 | Multi-Phase Initialization Private Provisional API | 162 |
| 11 | 内存管 | 等和 | 165 |
| 11 | | 概述 | |
| | | 原始内存接口 | |
| | 11.3 | 内存接口 | |
| | 11.4 | 对象分配器 | 168 |
| | 11.5 | 默认内存分配器 | 169 |
| | 11.6 | Customize Memory Allocators | |
| | 11.7 | The pymalloc allocator | |
| | 11.8 | tracemalloc C API | |
| | 11.9 | 示例 | 172 |
| 12 | 计负点 | 实现支持 | 173 |
| 12 | 12.1 | 文元文句 - 在堆中分配对象 | |
| | 12.1 | Common Object Structures | |
| | 12.3 | Type 对象 | |
| | | Number Object Structures | |
| | 12.5 | Mapping Object Structures | |
| | 12.6 | Sequence Object Structures | |
| | 12.7 | Buffer Object Structures | |

| D 片 | C.2 获取或以其他方式使用 Python 的条款和条件 | |
|-------------|--------------------------------------------------------------------------------------------------------------|-----------------------------------|
| | | |
| (| 历史和许可证 C.1 该软件的历史 (1) (1) (2) (2) (3) (3) (4) (4) (4) (4) (4) (4) (4) (4) (4) (4 | |
| B 7 | 文档说明 B.1 Python 文档贡献者 | 227 227 |
| A 7 | 术语对照表 | 215 |
| 13 A | API 和 ABI 版本管理 | 213 |
| 1 1 | 12.8 Async Object Structures 12.9 Slot Type typedefs 12.10 例子 12.11 使对象类型支持循环垃圾回收 | 206207 |

本手册描述了希望编写扩展模块并将 Python 解释器嵌入其应用程序中的 C 和 C++ 程序员可用的 API。同时可以参阅 extending-index ,其中描述了扩展编写的一般原则,但没有详细描述 API 函数。

Contents 1

2 Contents

CHAPTER 1

概述

Python 的应用编程接口(API)使得 C 和 C++ 程序员可以在多个层级上访问 Python 解释器。该 API 在 C++ 中同样可用,但为简化描述,通常将其称为 Python/C API。使用 Python/C API 有两个基本的理由。第一个理由是为了特定目的而编写 扩展模块;它们是扩展 Python 解释器功能的 C 模块。这可能是最常见的使用场景。第二个理由是将 Python 用作更大规模应用的组件;这种技巧通常被称为在一个应用中 embedding Python。

编写扩展模块的过程相对来说更易于理解,可以通过"菜谱"的形式分步骤介绍。使用某些工具可在一定程度上自动化这一过程。虽然人们在其他应用中嵌入 Python 的做法早已有之,但嵌入 Python 的过程没有编写扩展模块那样方便直观。

许多 API 函数在你嵌入或是扩展 Python 这两种场景下都能发挥作用;此外,大多数嵌入 Python 的应用程序也需要提供自定义扩展,因此在尝试在实际应用中嵌入 Python 之前先熟悉编写扩展应该会是个好主意。

1.1 代码标准

如果你想要编写可包含于 CPython 的 C 代码,你 **必须**遵循在 PEP 7 中定义的指导原则和标准。这些指导原则适用于任何你所要扩展的 Python 版本。在编写你自己的第三方扩展模块时可以不必遵循这些规范,除非你准备在日后向 Python 贡献这些模块。

1.2 包含文件

使用 Python/C API 所需要的全部函数、类型和宏定义可通过下面这行语句包含到你的代码之中:

#define PY_SSIZE_T_CLEAN
#include <Python.h>

这意味着包含以下标准头文件: <stdio.h>, <string.h>, <errno.h>, <limits.h>, <assert.h>和 <stdlib.h> (如果可用)。

注解: 由于 Python 可能会定义一些能在某些系统上影响标准头文件的预处理器定义,因此在包含任何标准头文件之前,你必须先包含 Python.h。

It is recommended to always define PY_SSIZE_T_CLEAN before including Python.h. See 语句解释及变量编译 for a description of this macro.

Python.h 所定义的全部用户可见名称(由包含的标准头文件所定义的除外)都带有前缀 Py 或者 _Py。以 _Py 打头的名称是供 Python 实现内部使用的,不应被扩展编写者使用。结构成员名称没有保留前缀。

注解: User code should never define names that begin with Py or _Py. This confuses the reader, and jeopardizes the portability of the user code to future Python versions, which may define additional names beginning with one of these prefixes.

头文件通常会与Python一起安装。在Unix上,它们位于以下目录: prefix/include/pythonversion/和 exec_prefix/include/pythonversion/,其中 prefix 和 exec_prefix 是由向 Python 的 configure 脚本传入的对应形参所定义,而 version 则为 '%d.%d' % sys.version_info[:2]。在 Windows 上,头文件安装于 prefix/include,其中 prefix 是向安装程序指定的安装目录。

要包含头文件,请将两个目录 (如果不同)都放到你所用编译器的包含搜索路径中。请不要将父目录放入搜索路径然后使用 #include <pythonX.Y/Python.h>; 这将使得多平台编译不可用,因为 prefix下平台无关的头文件需要包含来自 exec_prefix 下特定平台的头文件。

C++ users should note that although the API is defined entirely using C, the header files properly declare the entry points to be extern "C". As a result, there is no need to do anything special to use the API from C++.

1.3 有用的宏

Python 头文件中定义了一些有用的宏。许多是在靠近它们被使用的地方定义的(例如Py_RETURN_NONE)。 其他更为通用的则定义在这里。这里所显示的并不是一个完整的列表。

Py_UNREACHABLE()

这个可以在你有一个不打算被触及的代码路径时使用。例如,当一个 switch 语句中所有可能的 值都已被 case 子句覆盖了,就可将其用在 default: 子句中。当你非常想在某个位置放一个 assert (0) 或 abort () 调用时也可以用这个。

3.7 新版功能.

$Py_ABS(x)$

返回x的绝对值。

3.3 新版功能.

$Py_MIN(x, y)$

返回×和y当中的最小值。

3.3 新版功能.

$Py_MAX(x, y)$

返回×和y当中的最大值。

3.3 新版功能.

Py_STRINGIFY(X)

将 x 转换为 C 字符串。例如 Py_STRINGIFY (123) 返回 "123"。

3.4 新版功能.

Py_MEMBER_SIZE (type, member)

返回结构(type)member的大小,以字节表示。

3.6 新版功能.

$\textbf{Py_CHARMASK} \ (c)$

参数必须为 [-128, 127] 或 [0, 255] 范围内的字符或整数类型。这个宏将 c 强制转换为 unsigned char 返回。

4 Chapter 1. 概述

Py_GETENV(s)

Like getenv(s), but returns NULL if -E was passed on the command line (i.e. if Py_IgnoreEnvironmentFlag is set).

Py_UNUSED (arg)

Use this for unused arguments in a function definition to silence compiler warnings. Example: int func(int a, int Py_UNUSED(b)) { return a; }.

3.4 新版功能.

Py_DEPRECATED (version)

Use this for deprecated declarations. The macro must be placed before the symbol name.

示例:

```
Py_DEPRECATED(3.8) PyAPI_FUNC(int) Py_OldFunction(void);
```

在 3.8 版更改: MSVC support was added.

1.4 对象、类型和引用计数

大多数 Python/C API 函数都有一个或多个参数以及一个PyObject*类型的返回值。此类型是一个指针,指向表示一个任意 Python 对象的不透明数据类型。由于在大多数情况下(例如赋值、作用域规则和参数传递)Python 语言都会以同样的方式处理所有 Python 对象类型,因此它们由一个单独的 C 类型来表示是很适宜的。几乎所有 Python 对象都生存在堆上:你绝不会声明一个PyObject类型的自动或静态变量,只有PyObject*类型的指针变量可以被声明。唯一的例外是 type 对象;由于此种对象永远不能被释放,所以它们通常是静态PyTypeObject 对象。

所有 Python 对象(甚至 Python 整数)都有一个 type 和一个 $reference\ count$ 。对象的类型确定它是什么类型的对象(例如整数、列表或用户定义函数;还有更多,如 types 中所述)。对于每个众所周知的类型,都有一个宏来检查对象是否属于该类型;例如,当(且仅当)a 所指的对象是 Python 列表时 PyList_Check (a) 为真。

1.4.1 引用计数

The reference count is important because today's computers have a finite (and often severely limited) memory size; it counts how many different places there are that have a reference to an object. Such a place could be another object, or a global (or static) C variable, or a local variable in some C function. When an object's reference count becomes zero, the object is deallocated. If it contains references to other objects, their reference count is decremented. Those other objects may be deallocated in turn, if this decrement makes their reference count become zero, and so on. (There's an obvious problem with objects that reference each other here; for now, the solution is "don't do that.")

Reference counts are always manipulated explicitly. The normal way is to use the macro $Py_INCREF()$ to increment an object's reference count by one, and $Py_DECREF()$ to decrement it by one. The $Py_DECREF()$ macro is considerably more complex than the incref one, since it must check whether the reference count becomes zero and then cause the object's deallocator to be called. The deallocator is a function pointer contained in the object's type structure. The type-specific deallocator takes care of decrementing the reference counts for other objects contained in the object if this is a compound object type, such as a list, as well as performing any additional finalization that's needed. There's no chance that the reference count can overflow; at least as many bits are used to hold the reference count as there are distinct memory locations in virtual memory (assuming sizeof(Py_ssize_t) >= sizeof(void*)). Thus, the reference count increment is a simple operation.

It is not necessary to increment an object's reference count for every local variable that contains a pointer to an object. In theory, the object's reference count goes up by one when the variable is made to point to it and it goes down by one when the variable goes out of scope. However, these two cancel each other out, so at the end the reference count hasn't changed. The only real reason to use the reference count is to prevent the object from being deallocated as long as our variable is pointing to it. If we know that there is at least one other reference to the object that lives at least as long as our variable, there is no need to increment the reference count temporarily. An important situation where this

arises is in objects that are passed as arguments to C functions in an extension module that are called from Python; the call mechanism guarantees to hold a reference to every argument for the duration of the call.

However, a common pitfall is to extract an object from a list and hold on to it for a while without incrementing its reference count. Some other operation might conceivably remove the object from the list, decrementing its reference count and possibly deallocating it. The real danger is that innocent-looking operations may invoke arbitrary Python code which could do this; there is a code path which allows control to flow back to the user from a $Py_DECREF()$, so almost any operation is potentially dangerous.

A safe approach is to always use the generic operations (functions whose name begins with PyObject_, PyNumber_, PySequence_ or PyMapping_). These operations always increment the reference count of the object they return. This leaves the caller with the responsibility to call $Py_DECREF()$ when they are done with the result; this soon becomes second nature.

Reference Count Details

The reference count behavior of functions in the Python/C API is best explained in terms of *ownership of references*. Ownership pertains to references, never to objects (objects are not owned: they are always shared). "Owning a reference" means being responsible for calling Py_DECREF on it when the reference is no longer needed. Ownership can also be transferred, meaning that the code that receives ownership of the reference then becomes responsible for eventually decref'ing it by calling Py_DECREF() or Py_XDECREF() when it's no longer needed---or passing on this responsibility (usually to its caller). When a function passes ownership of a reference on to its caller, the caller is said to receive a *new* reference. When no ownership is transferred, the caller is said to *borrow* the reference. Nothing needs to be done for a borrowed reference.

Conversely, when a calling function passes in a reference to an object, there are two possibilities: the function *steals* a reference to the object, or it does not. *Stealing a reference* means that when you pass a reference to a function, that function assumes that it now owns that reference, and you are not responsible for it any longer.

Few functions steal references; the two notable exceptions are $PyList_SetItem()$ and $PyTuple_SetItem()$, which steal a reference to the item (but not to the tuple or list into which the item is put!). These functions were designed to steal a reference because of a common idiom for populating a tuple or list with newly created objects; for example, the code to create the tuple (1, 2, "three") could look like this (forgetting about error handling for the moment; a better way to code this is shown below):

```
PyObject *t;

t = PyTuple_New(3);
PyTuple_SetItem(t, 0, PyLong_FromLong(1L));
PyTuple_SetItem(t, 1, PyLong_FromLong(2L));
PyTuple_SetItem(t, 2, PyUnicode_FromString("three"));
```

Here, $PyLong_FromLong()$ returns a new reference which is immediately stolen by $PyTuple_SetItem()$. When you want to keep using an object although the reference to it will be stolen, use $Py_INCREF()$ to grab another reference before calling the reference-stealing function.

Incidentally, $PyTuple_SetItem()$ is the *only* way to set tuple items; $PySequence_SetItem()$ and $PyObject_SetItem()$ refuse to do this since tuples are an immutable data type. You should only use $PyTuple_SetItem()$ for tuples that you are creating yourself.

Equivalent code for populating a list can be written using PyList_New() and PyList_SetItem().

However, in practice, you will rarely use these ways of creating and populating a tuple or list. There's a generic function, $Py_BuildValue()$, that can create most common objects from C values, directed by a *format string*. For example, the above two blocks of code could be replaced by the following (which also takes care of the error checking):

```
PyObject *tuple, *list;

tuple = Py_BuildValue("(iis)", 1, 2, "three");
list = Py_BuildValue("[iis]", 1, 2, "three");
```

6 Chapter 1. 概述

It is much more common to use PyObject_SetItem() and friends with items whose references you are only borrowing, like arguments that were passed in to the function you are writing. In that case, their behaviour regarding reference counts is much saner, since you don't have to increment a reference count so you can give a reference away ("have it be stolen"). For example, this function sets all items of a list (actually, any mutable sequence) to a given item:

```
int
set_all(PyObject *target, PyObject *item)
{
    Py_ssize_t i, n;
    n = PyObject_Length(target);
    if (n < 0)
        return -1;
    for (i = 0; i < n; i++) {
        PyObject *index = PyLong_FromSsize_t(i);
        if (!index)
            return -1;
        if (PyObject_SetItem(target, index, item) < 0) {
            Py_DECREF(index);
            return -1;
        }
        Py_DECREF(index);
    }
    return 0;
}</pre>
```

The situation is slightly different for function return values. While passing a reference to most functions does not change your ownership responsibilities for that reference, many functions that return a reference to an object give you ownership of the reference. The reason is simple: in many cases, the returned object is created on the fly, and the reference you get is the only reference to the object. Therefore, the generic functions that return object references, like $PyObject_GetItem()$ and $PySequence_GetItem()$, always return a new reference (the caller becomes the owner of the reference).

It is important to realize that whether you own a reference returned by a function depends on which function you call only --- the plumage (the type of the object passed as an argument to the function) doesn't enter into it! Thus, if you extract an item from a list using $PyList_GetItem()$, you don't own the reference --- but if you obtain the same item from the same list using $PySequence_GetItem()$ (which happens to take exactly the same arguments), you do own a reference to the returned object.

Here is an example of how you could write a function that computes the sum of the items in a list of integers; once using PyList_GetItem(), and once using PySequence_GetItem().

(下页继续)

(续上页)

```
return total;
}
```

```
long
sum_sequence(PyObject *sequence)
    Py_ssize_t i, n;
    long total = 0, value;
    PyObject *item;
    n = PySequence_Length(sequence);
    if (n < 0)
        return -1; /* Has no length */
    for (i = 0; i < n; i++) {</pre>
        item = PySequence_GetItem(sequence, i);
        if (item == NULL)
            return -1; /* Not a sequence, or other failure */
        if (PyLong_Check(item)) {
            value = PyLong_AsLong(item);
            Py_DECREF (item);
            if (value == -1 && PyErr_Occurred())
                /* Integer too big to fit in a C long, bail out */
                return -1;
            total += value;
        }
        else {
            Py_DECREF(item); /* Discard reference ownership */
    return total;
```

1.4.2 类型

There are few other data types that play a significant role in the Python/C API; most are simple C types such as int, long, double and char*. A few structure types are used to describe static tables used to list the functions exported by a module or the data attributes of a new object type, and another is used to describe the value of a complex number. These will be discussed together with the functions that use them.

1.5 异常

Python 程序员只需要处理特定需要处理的错误异常;未处理的异常会自动传递给调用者,然后传递给调用者的调用者,依此类推,直到他们到达顶级解释器,在那里将它们报告给用户并伴随堆栈回溯。

For C programmers, however, error checking always has to be explicit. All functions in the Python/C API can raise exceptions, unless an explicit claim is made otherwise in a function's documentation. In general, when a function encounters an error, it sets an exception, discards any object references that it owns, and returns an error indicator. If not documented otherwise, this indicator is either NULL or -1, depending on the function's return type. A few functions return a Boolean true/false result, with false indicating an error. Very few functions return no explicit error indicator or have an ambiguous return value, and require explicit testing for errors with $PyErr_Occurred()$. These exceptions are always explicitly documented.

Exception state is maintained in per-thread storage (this is equivalent to using global storage in an unthreaded application). A thread can be in one of two states: an exception has occurred, or not. The function <code>PyErr_Occurred()</code> can be used to check for this: it returns a borrowed reference to the exception type object when an exception has occurred, and <code>NULL</code> otherwise. There are a number of functions to set the exception state: <code>PyErr_SetString()</code> is the most common (though not the most general) function to set the exception state, and <code>PyErr_Clear()</code> clears the exception state.

8 Chapter 1. 概述

The full exception state consists of three objects (all of which can be <code>NULL</code>): the exception type, the corresponding exception value, and the traceback. These have the same meanings as the Python result of <code>sys.exc_info()</code>; however, they are not the same: the Python objects represent the last exception being handled by a Python <code>try...except</code> statement, while the C level exception state only exists while an exception is being passed on between C functions until it reaches the Python bytecode interpreter's main loop, which takes care of transferring it to <code>sys.exc_info()</code> and friends.

Note that starting with Python 1.5, the preferred, thread-safe way to access the exception state from Python code is to call the function <code>sys.exc_info()</code>, which returns the per-thread exception state for Python code. Also, the semantics of both ways to access the exception state have changed so that a function which catches an exception will save and restore its thread's exception state so as to preserve the exception state of its caller. This prevents common bugs in exception handling code caused by an innocent-looking function overwriting the exception being handled; it also reduces the often unwanted lifetime extension for objects that are referenced by the stack frames in the traceback.

As a general principle, a function that calls another function to perform some task should check whether the called function raised an exception, and if so, pass the exception state on to its caller. It should discard any object references that it owns, and return an error indicator, but it should *not* set another exception --- that would overwrite the exception that was just raised, and lose important information about the exact cause of the error.

A simple example of detecting exceptions and passing them on is shown in the <code>sum_sequence()</code> example above. It so happens that this example doesn't need to clean up any owned references when it detects an error. The following example function shows some error cleanup. First, to remind you why you like Python, we show the equivalent Python code:

```
def incr_item(dict, key):
    try:
        item = dict[key]
    except KeyError:
        item = 0
    dict[key] = item + 1
```

Here is the corresponding C code, in all its glory:

```
incr_item(PyObject *dict, PyObject *key)
    /* Objects all initialized to NULL for Py_XDECREF */
    PyObject *item = NULL, *const_one = NULL, *incremented_item = NULL;
    int rv = -1; /* Return value initialized to -1 (failure) */
    item = PyObject_GetItem(dict, key);
    if (item == NULL) {
        /* Handle KeyError only: */
        if (!PyErr_ExceptionMatches(PyExc_KeyError))
            goto error;
        /* Clear the error and use zero: */
        PyErr_Clear();
        item = PyLong_FromLong(0L);
        if (item == NULL)
            goto error;
    const_one = PyLong_FromLong(1L);
    if (const_one == NULL)
        goto error;
    incremented_item = PyNumber_Add(item, const_one);
    if (incremented_item == NULL)
        goto error;
    if (PyObject_SetItem(dict, key, incremented_item) < 0)</pre>
        goto error;
```

(下页继续)

1.5. 异常 9

(续上页)

```
rv = 0; /* Success */
    /* Continue with cleanup code */

error:
    /* Cleanup code, shared by success and failure path */

    /* Use Py_XDECREF() to ignore NULL references */
    Py_XDECREF(item);
    Py_XDECREF(const_one);
    Py_XDECREF(incremented_item);

return rv; /* -1 for error, 0 for success */
}
```

This example represents an endorsed use of the goto statement in C! It illustrates the use of $PyErr_ExceptionMatches()$ and $PyErr_Clear()$ to handle specific exceptions, and the use of $Py_XDECREF()$ to dispose of owned references that may be NULL (note the 'X' in the name; $Py_DECREF()$ would crash when confronted with a NULL reference). It is important that the variables used to hold owned references are initialized to NULL for this to work; likewise, the proposed return value is initialized to $Py_DECREF()$ and only set to success after the final call made is successful.

1.6 嵌入 Python

The one important task that only embedders (as opposed to extension writers) of the Python interpreter have to worry about is the initialization, and possibly the finalization, of the Python interpreter. Most functionality of the interpreter can only be used after the interpreter has been initialized.

The basic initialization function is $Py_Initialize()$. This initializes the table of loaded modules, and creates the fundamental modules builtins, $__main__$, and sys. It also initializes the module search path (sys.path).

 $Py_Initialize()$ does not set the "script argument list" (sys.argv). If this variable is needed by Python code that will be executed later, it must be set explicitly with a call to $PySys_SetArgvEx(argc, argv, updatepath)$ after the call to $Py_Initialize()$.

On most systems (in particular, on Unix and Windows, although the details are slightly different), $Py_Initialize()$ calculates the module search path based upon its best guess for the location of the standard Python interpreter executable, assuming that the Python library is found in a fixed location relative to the Python interpreter executable. In particular, it looks for a directory named lib/pythonX. Y relative to the parent directory where the executable named python is found on the shell command search path (the environment variable PATH).

For instance, if the Python executable is found in /usr/local/bin/python, it will assume that the libraries are in /usr/local/lib/pythonX. Y. (In fact, this particular path is also the "fallback" location, used when no executable file named python is found along PATH.) The user can override this behavior by setting the environment variable PYTHONHOME, or insert additional directories in front of the standard path by setting PYTHONPATH.

The embedding application can steer the search by calling $Py_SetProgramName(file)$ before calling $Py_Initialize()$. Note that PYTHONHOME still overrides this and PYTHONPATH is still inserted in front of the standard path. An application that requires total control has to provide its own implementation of $Py_GetPath()$, $Py_GetPrefix()$, $Py_GetExecPrefix()$, and $Py_GetProgramFullPath()$ (all defined in Modules/getpath.c).

Sometimes, it is desirable to "uninitialize" Python. For instance, the application may want to start over (make another call to $Py_Initialize()$) or the application is simply done with its use of Python and wants to free memory allocated by Python. This can be accomplished by calling $Py_FinalizeEx()$. The function $Py_IsInitialized()$ returns true if Python is currently in the initialized state. More information about these functions is given in a later chapter. Notice that $Py_FinalizeEx()$ does *not* free all memory allocated by the Python interpreter, e.g. memory allocated by extension modules currently cannot be released.

10 Chapter 1. 概述

1.7 调试构建

Python can be built with several macros to enable extra checks of the interpreter and extension modules. These checks tend to add a large amount of overhead to the runtime so they are not enabled by default.

A full list of the various types of debugging builds is in the file Misc/SpecialBuilds.txt in the Python source distribution. Builds are available that support tracing of reference counts, debugging the memory allocator, or low-level profiling of the main interpreter loop. Only the most frequently-used builds will be described in the remainder of this section.

Compiling the interpreter with the Py_DEBUG macro defined produces what is generally meant by "a debug build" of Python. Py_DEBUG is enabled in the Unix build by adding --with-pydebug to the ./configure command. It is also implied by the presence of the not-Python-specific _DEBUG macro. When Py_DEBUG is enabled in the Unix build, compiler optimization is disabled.

除了前面描述的引用计数调试之外,还执行以下额外检查:

- 额外检查将添加到对象分配器。
- 额外的检查将添加到解析器和编译器中。
- Downcasts from wide types to narrow types are checked for loss of information.
- 许多断言被添加到字典和集合实现中。另外,集合对象需要 test_c_api() 方法。
- 输入参数的完整性检查被添加到框架创建中。
- 使用已知的无效模式初始化整型的存储,以捕获对未初始化数字的引用。
- 添加底层跟踪和额外的异常检查到虚拟机的运行时中。
- Extra checks are added to the memory arena implementation.
- 添加额外调试到线程模块。

这里可能没有提到的额外的检查。

Defining Py_TRACE_REFS enables reference tracing. When defined, a circular doubly linked list of active objects is maintained by adding two extra fields to every PyObject. Total allocations are tracked as well. Upon exit, all existing references are printed. (In interactive mode this happens after every statement run by the interpreter.) Implied by Py_DEBUG.

有关更多详细信息,请参阅 Python 源代码中的 Misc/Special Builds.txt。

1.7. 调试构建 11

12 Chapter 1. 概述

稳定的应用程序二进制接口

传统上, Python 的 C API 将随每个版本而变化。大多数更改都与源代码兼容,通常只添加 API,而不是更改现有 API 或删除 API (尽管某些接口会首先弃用然后再删除)。

不幸的是,API 兼容性没有扩展到二进制兼容性(ABI)。原因主要是结构定义的演变,在这里添加新字段或更改字段类型可能不会破坏 API,但可能会破坏 ABI。因此,每个 Python 版本都需要重新编译扩展模块(即使在未使用任何受影响的接口的情况下,Unix 上也可能会出现异常)。此外,在 Windows 上,扩展模块与特定的 pythonXY.dll 链接,需要重新编译才能与新的 pythonXY.dll 链接。

从 Python3.2 起,已经声明了一个 API 的子集,以确保稳定的 ABI。如果使用此 API(也被称为"受限 API")的扩展模块需要定义"Py_LIMITED_API"。许多解释器细节将从扩展模块中隐藏; 反过来,在任何 3.x 版本(x>=2)上构建的模块都不需要重新编译

在某些情况下,需要添加新函数来扩展稳定版 ABI。希望使用这些新 API 的扩展模块需要将 Py_LIMITED_API 设置为他们想要支持的最低 Python 版本的 PY_VERSION_HEX 值(例如: Python 3.3 为 0×03030000)(参见 API 和 ABI 版本管理)。此类模块将适用于所有后续 Python 版本,但无法在 旧版本上加载(因为缺少符号)。

从 Python 3.2 开始,受限 API 可用的函数集记录在 PEP 384。在 C API 文档中,不属于受限 API 的 API 元素标记为"不属于受限 API"。

The Very High Level Layer

The functions in this chapter will let you execute Python source code given in a file or a buffer, but they will not let you interact in a more detailed way with the interpreter.

Several of these functions accept a start symbol from the grammar as a parameter. The available start symbols are Py_eval_input, Py_file_input, and Py_single_input. These are described following the functions which accept them as parameters.

Note also that several of these functions take FILE* parameters. One particular issue which needs to be handled carefully is that the FILE structure for different C libraries can be different and incompatible. Under Windows (at least), it is possible for dynamically linked extensions to actually use different libraries, so care should be taken that FILE* parameters are only passed to these functions if it is certain that they were created by the same library that the Python runtime is using.

int Py_Main (int argc, wchar_t **argv)

The main program for the standard interpreter. This is made available for programs which embed Python. The *argc* and *argv* parameters should be prepared exactly as those which are passed to a C program's main () function (converted to wchar_t according to the user's locale). It is important to note that the argument list may be modified (but the contents of the strings pointed to by the argument list are not). The return value will be 0 if the interpreter exits normally (i.e., without an exception), 1 if the interpreter exits due to an exception, or 2 if the parameter list does not represent a valid Python command line.

Note that if an otherwise unhandled SystemExit is raised, this function will not return 1, but exit the process, as long as Py_InspectFlag is not set.

int Py_BytesMain (int argc, char **argv)

Similar to Py_Main() but argv is an array of bytes strings.

3.8 新版功能.

int **PyRun_AnyFile** (FILE *fp, const char *filename)

This is a simplified interface to PyRun_AnyFileExFlags() below, leaving closeit set to 0 and flags set to NULL.

int PyRun_AnyFileFlags (FILE *fp, const char *filename, PyCompilerFlags *flags)

This is a simplified interface to PyRun_AnyFileExFlags() below, leaving the closeit argument set to 0.

int PyRun_AnyFileEx (FILE *fp, const char *filename, int closeit)

This is a simplified interface to PyRun_AnyFileExFlags() below, leaving the flags argument set to NULL.

int PyRun_AnyFileExFlags (FILE *fp, const char *filename, int closeit, PyCompilerFlags *flags)

If fp refers to a file associated with an interactive device (console or terminal input or Unix pseudo-terminal), return the value of $PyRun_InteractiveLoop()$, otherwise return the result of $PyRun_SimpleFile()$. filename is decoded from the filesystem encoding (sys.getfilesystemencoding()). If filename is NULL, this function uses "???" as the filename.

int PyRun_SimpleString (const char *command)

This is a simplified interface to PyRun_SimpleStringFlags() below, leaving the PyCompilerFlags* argument set to NULL.

int PyRun_SimpleStringFlags (const char *command, PyCompilerFlags *flags)

Executes the Python source code from *command* in the __main__ module according to the *flags* argument. If __main__ does not already exist, it is created. Returns 0 on success or -1 if an exception was raised. If there was an error, there is no way to get the exception information. For the meaning of *flags*, see below.

Note that if an otherwise unhandled SystemExit is raised, this function will not return -1, but exit the process, as long as Py_InspectFlag is not set.

int **PyRun_SimpleFile** (FILE *fp, const char *filename)

This is a simplified interface to PyRun_SimpleFileExFlags() below, leaving closeit set to 0 and flags set to NULL.

int **PyRun_SimpleFileEx** (FILE *fp, const char *filename, int closeit)

This is a simplified interface to PyRun_SimpleFileExFlags () below, leaving flags set to NULL.

int PyRun_SimpleFileExFlags (FILE *fp, const char *filename, int closeit, PyCompilerFlags *flags)

Similar to <code>PyRun_SimpleStringFlags()</code>, but the Python source code is read from <code>fp</code> instead of an in-memory string. <code>filename</code> should be the name of the file, it is decoded from the filesystem encoding (<code>sys.getfilesystemencoding()</code>). If <code>closeit</code> is true, the file is closed before <code>PyRun_SimpleFileExFlags</code> returns.

注解: On Windows, fp should be opened as binary mode (e.g. fopen (filename, "rb"). Otherwise, Python may not handle script file with LF line ending correctly.

int PyRun_InteractiveOne (FILE *fp, const char *filename)

This is a simplified interface to PyRun_InteractiveOneFlags() below, leaving flags set to NULL.

int PyRun_InteractiveOneFlags (FILE *fp, const char *filename, PyCompilerFlags *flags)

Read and execute a single statement from a file associated with an interactive device according to the *flags* argument. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the filesystem encoding (sys.getfilesystemencoding()).

Returns 0 when the input was executed successfully, -1 if there was an exception, or an error code from the errorde.h include file distributed as part of Python if there was a parse error. (Note that errorde.h is not included by Python.h, so must be included specifically if needed.)

int PyRun_InteractiveLoop (FILE *fp, const char *filename)

This is a simplified interface to PyRun_InteractiveLoopFlags() below, leaving flags set to NULL.

int PyRun_InteractiveLoopFlags (FILE *fp, const char *filename, PyCompilerFlags *flags)

Read and execute statements from a file associated with an interactive device until EOF is reached. The user will be prompted using sys.ps1 and sys.ps2. *filename* is decoded from the filesystem encoding (sys.getfilesystemencoding()). Returns 0 at EOF or a negative number upon failure.

int (*PyOS_InputHook) (void)

Can be set to point to a function with the prototype int func (void). The function will be called when Python's interpreter prompt is about to become idle and wait for user input from the terminal. The return value is ignored. Overriding this hook can be used to integrate the interpreter's prompt with other event loops, as done in the Modules/_tkinter.c in the Python source code.

char* (*PyOS_ReadlineFunctionPointer) (FILE *, FILE *, const char *)

Can be set to point to a function with the prototype char *func(FILE *stdin, FILE *stdout, char *prompt), overriding the default function used to read a single line of input at the interpreter's

prompt. The function is expected to output the string *prompt* if it's not NULL, and then read a line of input from the provided standard input file, returning the resulting string. For example, The readline module sets this hook to provide line-editing and tab-completion features.

The result must be a string allocated by <code>PyMem_RawMalloc()</code> or <code>PyMem_RawRealloc()</code>, or <code>NULL</code> if an error occurred.

在 3.4 版更改: The result must be allocated by <code>PyMem_RawMalloc()</code> or <code>PyMem_RawRealloc()</code>, instead of being allocated by <code>PyMem_Malloc()</code> or <code>PyMem_RawRealloc()</code>.

- struct _node* PyParser_SimpleParseString (const char *str, int start)
 - This is a simplified interface to <code>PyParser_SimpleParseStringFlagsFilename()</code> below, leaving <code>filename</code> set to <code>NULL</code> and <code>flags</code> set to <code>0</code>.
- struct _node* PyParser_SimpleParseStringFlags (const char *str, int start, int flags)

 This is a simplified interface to PyParser_SimpleParseStringFlagsFilename() below, leaving filename set to NULL.
- struct _node* PyParser_SimpleParseStringFlagsFilename (const char *str, const char *filename, int start, int flags)

Parse Python source code from *str* using the start token *start* according to the *flags* argument. The result can be used to create a code object which can be evaluated efficiently. This is useful if a code fragment must be evaluated many times. *filename* is decoded from the filesystem encoding (sys.getfilesystemencoding()).

- struct _node* PyParser_SimpleParseFile (FILE *fp, const char *filename, int start)

 This is a simplified interface to PyParser_SimpleParseFileFlags() below, leaving flags set to 0.
- struct _node* PyParser_SimpleParseFileFlags (FILE *fp, const char *filename, int start, int flags)
 Similar to PyParser_SimpleParseStringFlagsFilename(), but the Python source code is read
- from fp instead of an in-memory string.
- PyObject* PyRun_String (const char *str, int start, PyObject *globals, PyObject *locals)

 Return value: New reference. This is a simplified interface to PyRun_StringFlags() below, leaving flags set to NULL.
- PyObject* PyRun_StringFlags (const char *str, int start, PyObject *globals, PyObject *locals, PyCompilerFlags *flags)

Return value: New reference. Execute Python source code from str in the context specified by the objects globals and locals with the compiler flags specified by flags. globals must be a dictionary; locals can be any object that implements the mapping protocol. The parameter start specifies the start token that should be used to parse the source code.

Returns the result of executing the code as a Python object, or NULL if an exception was raised.

- PyObject* PyRun_File (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals)

 Return value: New reference. This is a simplified interface to PyRun_FileExFlags() below, leaving closeit set to 0 and flags set to NULL.
- PyObject* PyRun_FileEx (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals, int closeit)

 Return value: New reference. This is a simplified interface to PyRun_FileExFlags () below, leaving flags

Return value: New reference. This is a simplified interface to *PyRun_FileExFlags()* below, leaving *flags* set to NULL.

- PyObject* PyRun_FileFlags (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals, PyCompilerFlags *flags)

 Return value: New reference. This is a simplified interface to PyRun FileFyFlags() below less
 - Return value: New reference. This is a simplified interface to PyRun_FileExFlags() below, leaving closeit set to 0.
- PyObject* PyRun_FileExFlags (FILE *fp, const char *filename, int start, PyObject *globals, PyObject *locals, int closeit, PyCompilerFlags *flags)

 Return value: New reference. Similar to PyRun_StringFlags(), but the Python source code is read

Return value: New reference. Similar to PyRun_StringFlags(), but the Python source code is read from fp instead of an in-memory string. filename should be the name of the file, it is decoded from the filesystem encoding (sys.getfilesystemencoding()). If closeit is true, the file is closed before PyRun_FileExFlags() returns.

PyObject* Py_CompileString (const char *str, const char *filename, int start)

Return value: New reference. This is a simplified interface to Py_CompileStringFlags () below, leaving *flags* set to NULL.

PyObject* Py_CompileStringFlags (const char *str, const char *filename, int start, PyCompiler-Flags *flags)

Return value: New reference. This is a simplified interface to *Py_CompileStringExFlags()* below, with *optimize* set to -1.

PyObject* Py_CompileStringObject (const char *str, PyObject *filename, int start, PyCompiler-Flags *flags, int optimize)

Return value: New reference. Parse and compile the Python source code in str, returning the resulting code object. The start token is given by start; this can be used to constrain the code which can be compiled and should be Py_eval_input, Py_file_input, or Py_single_input. The filename specified by filename is used to construct the code object and may appear in tracebacks or SyntaxError exception messages. This returns NULL if the code cannot be parsed or compiled.

The integer *optimize* specifies the optimization level of the compiler; a value of -1 selects the optimization level of the interpreter as given by -0 options. Explicit levels are 0 (no optimization; __debug__ is true), 1 (asserts are removed, __debug__ is false) or 2 (docstrings are removed too).

3.4 新版功能.

PyObject* Py_CompileStringExFlags (const char *str, const char *filename, int start, PyCompiler-Flags *flags, int optimize)

Return value: New reference. Like Py_CompileStringObject(), but filename is a byte string decoded from the filesystem encoding (os.fsdecode()).

3.2 新版功能.

PyObject* PyEval_EvalCode (PyObject *co, PyObject *globals, PyObject *locals)

Return value: New reference. This is a simplified interface to <code>PyEval_EvalCodeEx()</code>, with just the code object, and global and local variables. The other arguments are set to <code>NULL</code>.

PyObject* PyEval_EvalCodeEx (PyObject *co, PyObject *globals, PyObject *locals, PyObject *const *args, int argcount, PyObject *const *kws, int kwcount, PyObject *const *defs, int defcount, PyObject *kwdefs, PyObject *closure)

Return value: New reference. Evaluate a precompiled code object, given a particular environment for its evaluation. This environment consists of a dictionary of global variables, a mapping object of local variables, arrays of arguments, keywords and defaults, a dictionary of default values for *keyword-only* arguments and a closure tuple of cells.

PyFrameObject

The C structure of the objects used to describe frame objects. The fields of this type are subject to change at any time.

PyObject* PyEval_EvalFrame (PyFrameObject *f)

Return value: New reference. Evaluate an execution frame. This is a simplified interface to $PyEval_EvalFrameEx()$, for backward compatibility.

PyObject* PyEval_EvalFrameEx (PyFrameObject *f, int throwflag)

Return value: New reference. This is the main, unvarnished function of Python interpretation. The code object associated with the execution frame f is executed, interpreting bytecode and executing calls as needed. The additional throwflag parameter can mostly be ignored - if true, then it causes an exception to immediately be thrown; this is used for the throw() methods of generator objects.

在 3.4 版更改: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

int PyEval_MergeCompilerFlags (PyCompilerFlags *cf)

This function changes the flags of the current evaluation frame, and returns true on success, false on failure.

int Py_eval_input

The start symbol from the Python grammar for isolated expressions; for use with Py_CompileString().

int Py_file_input

The start symbol from the Python grammar for sequences of statements as read from a file or other source; for use with <code>Py_CompileString()</code>. This is the symbol to use when compiling arbitrarily long Python source code.

int Py_single_input

The start symbol from the Python grammar for a single statement; for use with Py_CompileString(). This is the symbol used for the interactive interpreter loop.

struct PyCompilerFlags

This is the structure used to hold compiler flags. In cases where code is only being compiled, it is passed as int flags, and in cases where code is being executed, it is passed as PyCompilerFlags *flags. In this case, from __future__ import can modify flags.

Whenever PyCompilerFlags *flags is NULL, cf_flags is treated as equal to 0, and any modification due to from __future__ import is discarded.

int cf_flags

Compiler flags.

int cf_feature_version

cf_feature_version is the minor Python version. It should be initialized to PY_MINOR_VERSION.

The field is ignored by default, it is used if and only if PyCF_ONLY_AST flag is set in *cf_flags*.

在 3.8 版更改: Added cf_feature_version field.

int CO FUTURE DIVISION

This bit can be set in *flags* to cause division operator / to be interpreted as "true division" according to **PEP 238**.

CHAPTER 4

引用计数

本节介绍的宏被用于管理 Python 对象的引用计数。

void **Py INCREF** (*PyObject* **o*)

增加对象o的引用计数。对象必须不为NULL;如果你不确定它不为NULL,可使用 $Py_XINCREF()$ 。

void **Py XINCREF** (*PyObject* **o*)

增加对象 o 的引用计数。对象可以为 NULL, 在此情况下该宏不产生任何效果。

void **Py DECREF** (*PyObject* *o)

减少对象o的引用计数。对象必须不为NULL;如果你不确定它不为NULL,可使用 $P_{Y_XDECREF}$ ()。如果引用计数降为零,将发起调用对象所属类型的释放函数(它必须不为NULL)。

警告:释放函数可导致任意 Python 代码被发起调用(例如当一个带有 __del__() 方法的类实例被释放时就是如此)。虽然此类代码中的异常不会被传播,但被执行的代码能够自由访问所有 Python 全局变量。这意味着任何可通过全局变量获取的对象在 $Py_DECREF()$ 被发起调用之前都应当处于完好状态。例如,从一个列表中删除对象的代码应当将被删除对象的引用拷贝到一个临时变量中,更新列表数据结构,然后再为临时变量调用 $Py_DECREF()$ 。

void Py XDECREF (PyObject *o)

减少对象 o 的引用计数。对象可以为 NULL,在此情况下该宏不产生任何效果;在其他情况下其效果与 $P_{Y_DECREF}()$ 相同,并会应用同样的警告。

void **Py_CLEAR** (*PyObject* *o)

减少对象o的引用计数。对象可以为 NULL ,在此情况下该宏不产生任何效果;在其他情况下其效果与 $\mathrm{Py_DECREF}$ ()相同,区别在于其参数也会被设为 NULL 。针对 $\mathrm{Py_DECREF}$ ()的警告不适用于所传递的对象,因为该宏会细心地使用一个临时变量并在减少其引用计数之前将参数设为 NULL 。

每当要减少在垃圾回收期间可能会被遍历的对象的引用计数时,使用该宏是一个好主意。

以下函数适用于 Python 的运行时动态嵌入: Py_IncRef (PyObject *o), Py_DecRef (PyObject *o)。它们分别只是Py_XINCREF () 和Py_XDECREF () 的简单导出函数版本。

以下函数或宏仅可在解释器核心内部使用: _Py_Dealloc(), _Py_ForgetReference(), _Py_NewReference() 以及全局变量 _Py_RefTotal。

CHAPTER 5

异常处理

The functions described in this chapter will let you handle and raise Python exceptions. It is important to understand some of the basics of Python exception handling. It works somewhat like the POSIX errno variable: there is a global indicator (per thread) of the last error that occurred. Most C API functions don't clear this on success, but will set it to indicate the cause of the error on failure. Most C API functions also return an error indicator, usually NULL if they are supposed to return a pointer, or -1 if they return an integer (exception: the PyArg_* () functions return 1 for success and 0 for failure).

Concretely, the error indicator consists of three object pointers: the exception's type, the exception's value, and the traceback object. Any of those pointers can be NULL if non-set (although some combinations are forbidden, for example you can't have a non-NULL traceback if the exception type is NULL).

When a function must fail because some function it called failed, it generally doesn't set the error indicator; the function it called already set it. It is responsible for either handling the error and clearing the exception or returning after cleaning up any resources it holds (such as object references or memory allocations); it should *not* continue normally if it is not prepared to handle the error. If returning due to an error, it is important to indicate to the caller that an error has been set. If the error is not handled or carefully propagated, additional calls into the Python/C API may not behave as intended and may fail in mysterious ways.

注解: The error indicator is **not** the result of <code>sys.exc_info()</code>. The former corresponds to an exception that is not yet caught (and is therefore still propagating), while the latter returns an exception after it is caught (and has therefore stopped propagating).

5.1 Printing and clearing

void PyErr_Clear()

Clear the error indicator. If the error indicator is not set, there is no effect.

void PyErr_PrintEx (int set_sys_last_vars)

Print a standard traceback to sys.stderr and clear the error indicator. Unless the error is a SystemExit, in that case no traceback is printed and the Python process will exit with the error code specified by the SystemExit instance.

Call this function **only** when the error indicator is set. Otherwise it will cause a fatal error!

If *set_sys_last_vars* is nonzero, the variables sys.last_type, sys.last_value and sys.last_traceback will be set to the type, value and traceback of the printed exception, respectively.

```
void PyErr_Print()
```

Alias for PyErr_PrintEx(1).

void PyErr_WriteUnraisable (PyObject *obj)

Call sys.unraisablehook() using the current exception and obj argument.

This utility function prints a warning message to sys.stderr when an exception has been set but it is impossible for the interpreter to actually raise the exception. It is used, for example, when an exception occurs in an __del__() method.

The function is called with a single argument *obj* that identifies the context in which the unraisable exception occurred. If possible, the repr of *obj* will be printed in the warning message.

An exception must be set when calling this function.

5.2 抛出异常

These functions help you set the current thread's error indicator. For convenience, some of these functions will always return a NULL pointer for use in a return statement.

```
void PyErr_SetString (PyObject *type, const char *message)
```

This is the most common way to set the error indicator. The first argument specifies the exception type; it is normally one of the standard exceptions, e.g. PyExc_RuntimeError. You need not increment its reference count. The second argument is an error message; it is decoded from 'utf-8'.

```
void PyErr_SetObject (PyObject *type, PyObject *value)
```

This function is similar to $PyErr_SetString()$ but lets you specify an arbitrary Python object for the "value" of the exception.

```
PyObject* PyErr_Format (PyObject *exception, const char *format, ...)
```

Return value: Always NULL. This function sets the error indicator and returns NULL. exception should be a Python exception class. The *format* and subsequent parameters help format the error message; they have the same meaning and values as in PyUnicode_FromFormat(). format is an ASCII-encoded string.

```
PyObject* PyErr_FormatV (PyObject *exception, const char *format, va_list vargs)
```

Return value: Always NULL. Same as PyErr_Format(), but taking a va_list argument rather than a variable number of arguments.

3.5 新版功能.

void PyErr_SetNone (PyObject *type)

This is a shorthand for PyErr_SetObject (type, Py_None).

int PyErr_BadArgument()

This is a shorthand for PyErr_SetString (PyExc_TypeError, message), where *message* indicates that a built-in operation was invoked with an illegal argument. It is mostly for internal use.

PvObject* PvErr NoMemory()

Return value: Always NULL. This is a shorthand for PyErr_SetNone (PyExc_MemoryError); it returns NULL so an object allocation function can write return PyErr_NoMemory(); when it runs out of memory.

PyObject* PyErr_SetFromErrno (PyObject *type)

Return value: Always NULL. This is a convenience function to raise an exception when a C library function has returned an error and set the C variable errno. It constructs a tuple object whose first item is the integer errno value and whose second item is the corresponding error message (gotten from strerror()), and then calls PyErr_SetObject(type, object). On Unix, when the errno value is EINTR, indicating an interrupted system call, this calls PyErr_CheckSignals(), and if that set the error indicator, leaves it set to that. The function always returns NULL, so a wrapper function around a system call can write return PyErr_SetFromErrno(type); when the system call returns an error.

PyObject* PyErr_SetFromErrnoWithFilenameObject (PyObject *type, PyObject *filenameObject)

Return value: Always NULL. Similar to PyErr_SetFromErrno(), with the additional behavior that if

filenameObject is not NULL, it is passed to the constructor of *type* as a third parameter. In the case of OSError exception, this is used to define the filename attribute of the exception instance.

PyObject* PyErr_SetFromErrnoWithFilenameObjects (PyObject *type, PyObject *filenameObject2)

Return value: Always NULL. Similar to PyErr_SetFromErrnoWithFilenameObject(), but takes a second filename object, for raising errors when a function that takes two filenames fails.

3.4 新版功能.

PyObject* PyErr_SetFromErrnoWithFilename (PyObject *type, const char *filename)

Return value: Always NULL. Similar to PyErr_SetFromErrnoWithFilenameObject(), but the filename is given as a C string. filename is decoded from the filesystem encoding (os.fsdecode()).

PyObject* PyErr_SetFromWindowsErr (int ierr)

Return value: Always NULL. This is a convenience function to raise WindowsError. If called with ierr of 0, the error code returned by a call to GetLastError() is used instead. It calls the Win32 function FormatMessage() to retrieve the Windows description of error code given by ierr or GetLastError(), then it constructs a tuple object whose first item is the ierr value and whose second item is the corresponding error message (gotten from FormatMessage()), and then calls PyErr_SetObject(PyExc_WindowsError, object). This function always returns NULL.

可用性: Windows。

PyObject* PyErr_SetExcFromWindowsErr (PyObject *type, int ierr)

Return value: Always NULL. Similar to PyErr_SetFromWindowsErr(), with an additional parameter specifying the exception type to be raised.

可用性: Windows。

PyObject* PyErr_SetFromWindowsErrWithFilename (int ierr, const char *filename)

Return value: Always NULL. Similar to PyErr_SetFromWindowsErrWithFilenameObject(), but the filename is given as a C string. filename is decoded from the filesystem encoding (os.fsdecode()).

可用性: Windows。

PyObject* PyErr_SetExcFromWindowsErrWithFilenameObject (PyObject *type, int ierr, Py-Object *filename)

Return value: Always NULL. Similar to PyErr_SetFromWindowsErrWithFilenameObject(), with an additional parameter specifying the exception type to be raised.

可用性: Windows。

PyObject* PyErr_SetExcFromWindowsErrWithFilenameObjects (PyObject *type, int ierr, PyObject *filename, PyObject *filename, PyObject *filename)

Return value: Always NULL. Similar to PyErr_SetExcFromWindowsErrWithFilenameObject(), but accepts a second filename object.

可用性: Windows。

3.4 新版功能.

PyObject* PyErr_SetExcFromWindowsErrWithFilename (PyObject *type, int ierr, constitution char *filename)

Return value: Always NULL. Similar to PyErr_SetFromWindowsErrWithFilename(), with an additional parameter specifying the exception type to be raised.

可用性: Windows。

PyObject* PyErr_SetImportError (PyObject *msg, PyObject *name, PyObject *path)

Return value: Always NULL. This is a convenience function to raise ImportError. msg will be set as the exception's message string. name and path, both of which can be NULL, will be set as the ImportError's respective name and path attributes.

3.3 新版功能.

5.2. 抛出异常 25

void PyErr_SyntaxLocationObject (*PyObject *filename*, int *lineno*, int *col_offset*)

Set file, line, and offset information for the current exception. If the current exception is not a SyntaxError, then it sets additional attributes, which make the exception printing subsystem think the exception is a SyntaxError.

3.4 新版功能.

void PyErr_SyntaxLocationEx (const char *filename, int lineno, int col_offset)

Like PyErr_SyntaxLocationObject(), but filename is a byte string decoded from the filesystem encoding (os.fsdecode()).

3.2 新版功能.

void PyErr_SyntaxLocation (const char *filename, int lineno)

Like PyErr_SyntaxLocationEx (), but the col_offset parameter is omitted.

void PyErr_BadInternalCall()

This is a shorthand for PyErr_SetString (PyExc_SystemError, message), where *message* indicates that an internal operation (e.g. a Python/C API function) was invoked with an illegal argument. It is mostly for internal use.

5.3 Issuing warnings

Use these functions to issue warnings from C code. They mirror similar functions exported by the Python warnings module. They normally print a warning message to *sys.stderr*; however, it is also possible that the user has specified that warnings are to be turned into errors, and in that case they will raise an exception. It is also possible that the functions raise an exception because of a problem with the warning machinery. The return value is 0 if no exception is raised, or -1 if an exception is raised. (It is not possible to determine whether a warning message is actually printed, nor what the reason is for the exception; this is intentional.) If an exception is raised, the caller should do its normal exception handling (for example, $P_{Y_DECREF}()$) owned references and return an error value).

int PyErr WarnEx (PyObject *category, const char *message, Py ssize t stack level)

Issue a warning message. The *category* argument is a warning category (see below) or NULL; the *message* argument is a UTF-8 encoded string. *stack_level* is a positive number giving a number of stack frames; the warning will be issued from the currently executing line of code in that stack frame. A *stack_level* of 1 is the function calling *PyErr WarnEx()*, 2 is the function above that, and so forth.

Warning categories must be subclasses of PyExc_Warning; PyExc_Warning is a subclass of PyExc_Exception; the default warning category is PyExc_RuntimeWarning. The standard Python warning categories are available as global variables whose names are enumerated at 标准警告类别.

For information about warning control, see the documentation for the warnings module and the -W option in the command line documentation. There is no C API for warning control.

PyObject* PyErr_SetImportErrorSubclass (PyObject *exception, PyObject *msg, PyObject *name, PyObject *path)

Return value: Always NULL. Much like PyErr_SetImportError() but this function allows for specifying a subclass of ImportError to raise.

3.6 新版功能.

```
int PyErr_WarnExplicitObject (PyObject *category, PyObject *message, PyObject *filename, int lineno, PyObject *module, PyObject *registry)
```

Issue a warning message with explicit control over all warning attributes. This is a straightforward wrapper around the Python function warnings.warn_explicit(), see there for more information. The *module* and *registry* arguments may be set to NULL to get the default effect described there.

3.4 新版功能.

```
int PyErr_WarnExplicit (PyObject *category, const char *message, const char *filename, int lineno, const char *module, PyObject *registry)
```

Similar to PyErr_WarnExplicitObject() except that message and module are UTF-8 encoded strings, and filename is decoded from the filesystem encoding (os.fsdecode()).

int PyErr_WarnFormat (*PyObject *category*, Py_ssize_t *stack_level*, const char *format, ...)

Function similar to PyErr_WarnEx(), but use PyUnicode_FromFormat() to format the warning message. *format* is an ASCII-encoded string.

3.2 新版功能.

int PyErr_ResourceWarning (PyObject *source, Py_ssize_t stack_level, const char *format, ...)

Function similar to PyErr_WarnFormat (), but category is ResourceWarning and it passes source to warnings. WarningMessage ().

3.6 新版功能.

5.4 Querying the error indicator

PyObject* PyErr_Occurred()

Return value: Borrowed reference. Test whether the error indicator is set. If set, return the exception type (the first argument to the last call to one of the PyErr_Set*() functions or to PyErr_Restore()). If not set, return NULL. You do not own a reference to the return value, so you do not need to Py_DECREF() it.

注解: Do not compare the return value to a specific exception; use <code>PyErr_ExceptionMatches()</code> instead, shown below. (The comparison could easily fail since the exception may be an instance instead of a class, in the case of a class exception, or it may be a subclass of the expected exception.)

int PyErr_ExceptionMatches (PyObject *exc)

Equivalent to PyErr_GivenExceptionMatches (PyErr_Occurred(), exc). This should only be called when an exception is actually set; a memory access violation will occur if no exception has been raised.

int PyErr_GivenExceptionMatches (PyObject *given, PyObject *exc)

Return true if the *given* exception matches the exception type in *exc*. If *exc* is a class object, this also returns true when *given* is an instance of a subclass. If *exc* is a tuple, all exception types in the tuple (and recursively in subtuples) are searched for a match.

```
void PyErr_Fetch (PyObject **ptype, PyObject **pvalue, PyObject **ptraceback)
```

Retrieve the error indicator into three variables whose addresses are passed. If the error indicator is not set, set all three variables to NULL. If it is set, it will be cleared and you own a reference to each object retrieved. The value and traceback object may be NULL even when the type object is not.

注解: This function is normally only used by code that needs to catch exceptions or by code that needs to save and restore the error indicator temporarily, e.g.:

```
PyObject *type, *value, *traceback;
PyErr_Fetch(&type, &value, &traceback);

/* ... code that might produce other errors ... */
PyErr_Restore(type, value, traceback);
}
```

void PyErr_Restore (PyObject *type, PyObject *value, PyObject *traceback)

Set the error indicator from the three objects. If the error indicator is already set, it is cleared first. If the objects are NULL, the error indicator is cleared. Do not pass a NULL type and non-NULL value or traceback. The exception type should be a class. Do not pass an invalid exception type or value. (Violating these rules will cause subtle problems later.) This call takes away a reference to each object: you must own a reference to each object before the call and after the call you no longer own these references. (If you don't understand this, don't use this function. I warned you.)

注解: This function is normally only used by code that needs to save and restore the error indicator temporarily. Use <code>PyErr_Fetch()</code> to save the current error indicator.

void PyErr_NormalizeException (PyObject**exc, PyObject**val, PyObject**tb)

Under certain circumstances, the values returned by $PyErr_Fetch$ () below can be "unnormalized", meaning that *exc is a class object but *val is not an instance of the same class. This function can be used to instantiate the class in that case. If the values are already normalized, nothing happens. The delayed normalization is implemented to improve performance.

注解: This function *does not* implicitly set the __traceback__ attribute on the exception value. If setting the traceback appropriately is desired, the following additional snippet is needed:

```
if (tb != NULL) {
   PyException_SetTraceback(val, tb);
}
```

void PyErr_GetExcInfo (PyObject **ptype, PyObject **pvalue, PyObject **ptraceback)

Retrieve the exception info, as known from <code>sys.exc_info()</code>. This refers to an exception that was *already caught*, not to an exception that was freshly raised. Returns new references for the three objects, any of which may be <code>NULL</code>. Does not modify the exception info state.

注解: This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr_SetExcInfo()</code> to restore or clear the exception state.

3.3 新版功能.

void PyErr_SetExcInfo (PyObject *type, PyObject *value, PyObject *traceback)

Set the exception info, as known from $sys.exc_info()$. This refers to an exception that was *already caught*, not to an exception that was freshly raised. This function steals the references of the arguments. To clear the exception state, pass NULL for all three arguments. For general rules about the three arguments, see $PyErr_Restore()$.

注解: This function is not normally used by code that wants to handle exceptions. Rather, it can be used when code needs to save and restore the exception state temporarily. Use <code>PyErr_GetExcInfo()</code> to read the exception state.

3.3 新版功能.

5.5 Signal Handling

int PyErr_CheckSignals()

This function interacts with Python's signal handling. It checks whether a signal has been sent to the processes and if so, invokes the corresponding signal handler. If the signal module is supported, this can invoke a signal handler written in Python. In all cases, the default effect for SIGINT is to raise the KeyboardInterrupt exception. If an exception is raised the error indicator is set and the function returns -1; otherwise the function returns 0. The error indicator may or may not be cleared if it was previously set.

void PyErr_SetInterrupt()

Simulate the effect of a SIGINT signal arriving. The next time <code>PyErr_CheckSignals()</code> is called, the Python signal handler for <code>SIGINT</code> will be called.

If SIGINT isn't handled by Python (it was set to signal.SIG_DFL or signal.SIG_IGN), this function does nothing.

int $PySignal_SetWakeupFd$ (int fd)

This utility function specifies a file descriptor to which the signal number is written as a single byte whenever a signal is received. *fd* must be non-blocking. It returns the previous such file descriptor.

The value -1 disables the feature; this is the initial state. This is equivalent to signal.set_wakeup_fd() in Python, but without any error checking. fd should be a valid file descriptor. The function should only be called from the main thread.

在 3.5 版更改: On Windows, the function now also supports socket handles.

5.6 Exception Classes

PyObject* PyErr_NewException (const char *name, PyObject *base, PyObject *dict)

Return value: New reference. This utility function creates and returns a new exception class. The name argument must be the name of the new exception, a C string of the form module.classname. The base and dict arguments are normally NULL. This creates a class object derived from Exception (accessible in C as PyExc_Exception).

The __module__ attribute of the new class is set to the first part (up to the last dot) of the *name* argument, and the class name is set to the last part (after the last dot). The *base* argument can be used to specify alternate base classes; it can either be only one class or a tuple of classes. The *dict* argument can be used to specify a dictionary of class variables and methods.

PyObject* PyErr_NewExceptionWithDoc (const char *name, const char *doc, PyObject *base, PyObject *dict)

Return value: New reference. Same as PyErr_NewException(), except that the new exception class can easily be given a docstring: If doc is non-NULL, it will be used as the docstring for the exception class.

3.2 新版功能.

5.7 Exception Objects

PyObject* PyException_GetTraceback (PyObject *ex)

Return value: New reference. Return the traceback associated with the exception as a new reference, as accessible from Python through __traceback__. If there is no traceback associated, this returns NULL.

int PyException_SetTraceback (PyObject *ex, PyObject *tb)

Set the traceback associated with the exception to tb. Use Py_None to clear it.

PyObject* PyException_GetContext (PyObject *ex)

Return value: New reference. Return the context (another exception instance during whose handling ex was raised) associated with the exception as a new reference, as accessible from Python through __context__. If there is no context associated, this returns NULL.

void PyException_SetContext (PyObject *ex, PyObject *ctx)

Set the context associated with the exception to ctx. Use NULL to clear it. There is no type check to make sure that ctx is an exception instance. This steals a reference to ctx.

PyObject* PyException_GetCause (PyObject *ex)

Return value: New reference. Return the cause (either an exception instance, or None, set by raise ... from ...) associated with the exception as a new reference, as accessible from Python through __cause__.

void PyException_SetCause (PyObject *ex, PyObject *cause)

Set the cause associated with the exception to *cause*. Use NULL to clear it. There is no type check to make sure that *cause* is either an exception instance or None. This steals a reference to *cause*.

__suppress_context__ is implicitly set to True by this function.

5.8 Unicode Exception Objects

```
The following functions are used to create and modify Unicode exceptions from C.
PyObject* PyUnicodeDecodeError Create (const
                                                      char
                                                              *encoding,
                                                                          const char
                                               Py_ssize_t length, Py_ssize_t start, Py_ssize_t end,
                                               const char *reason)
     Return value: New reference. Create a UnicodeDecodeError object with the attributes encoding, object,
     length, start, end and reason. encoding and reason are UTF-8 encoded strings.
PyObject* PyUnicodeError_Create (const char *encoding, const Py_UNICODE *object,
                                               Py_ssize_t length, Py_ssize_t start, Py_ssize_t end,
                                               const char *reason)
     Return value: New reference. Create a UnicodeEncodeError object with the attributes encoding, object,
     length, start, end and reason. encoding and reason are UTF-8 encoded strings.
PyObject* PyUnicodeTranslateError_Create (const Py_UNICODE *object, Py_ssize_t length,
                                                   Py_ssize_t start, Py_ssize_t end, const char *rea-
                                                   son)
     Return value: New reference. Create a UnicodeTranslateError object with the attributes object, length,
     start, end and reason. reason is a UTF-8 encoded string.
PyObject* PyUnicodeDecodeError_GetEncoding (PyObject *exc)
PyObject* PyUnicodeEncodeError_GetEncoding (PyObject *exc)
     Return value: New reference. Return the encoding attribute of the given exception object.
PyObject* PyUnicodeDecodeError_GetObject (PyObject *exc)
PyObject* PyUnicodeEncodeError_GetObject (PyObject *exc)
PyObject* PyUnicodeTranslateError_GetObject (PyObject *exc)
     Return value: New reference. Return the object attribute of the given exception object.
int PyUnicodeDecodeError_GetStart (PyObject *exc, Py_ssize_t *start)
int PyUnicodeEncodeError_GetStart (PyObject *exc, Py_ssize_t *start)
int PyUnicodeTranslateError_GetStart (PyObject *exc, Py_ssize_t *start)
     Get the start attribute of the given exception object and place it into *start. start must not be NULL. Return 0
     on success, -1 on failure.
int PyUnicodeDecodeError_SetStart (PyObject *exc, Py_ssize_t start)
int PyUnicodeEncodeError_SetStart (PyObject *exc, Py_ssize_t start)
int PyUnicodeTranslateError_SetStart (PyObject *exc, Py_ssize_t start)
     Set the start attribute of the given exception object to start. Return 0 on success, -1 on failure.
int PyUnicodeDecodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeEncodeError_GetEnd (PyObject *exc, Py_ssize_t *end)
int PyUnicodeTranslateError_GetEnd (PyObject *exc, Py_ssize_t *end)
     Get the end attribute of the given exception object and place it into *end. end must not be NULL. Return 0 on
     success, -1 on failure.
int PyUnicodeDecodeError SetEnd (PyObject *exc, Py ssize t end)
int PyUnicodeEncodeError_SetEnd (PyObject *exc, Py_ssize_t end)
int PyUnicodeTranslateError_SetEnd (PyObject *exc, Py_ssize_t end)
     Set the end attribute of the given exception object to end. Return 0 on success, -1 on failure.
PyObject* PyUnicodeDecodeError_GetReason (PyObject *exc)
PyObject* PyUnicodeEncodeError_GetReason (PyObject *exc)
PyObject* PyUnicodeTranslateError GetReason (PyObject *exc)
     Return value: New reference. Return the reason attribute of the given exception object.
int PyUnicodeDecodeError_SetReason (PyObject *exc, const char *reason)
```

int PyUnicodeError_SetReason (PyObject *exc, const char *reason) int PyUnicodeTranslateError_SetReason (PyObject *exc, const char *reason)

Set the reason attribute of the given exception object to reason. Return 0 on success, -1 on failure.

5.9 Recursion Control

These two functions provide a way to perform safe recursive calls at the C level, both in the core and in extension modules. They are needed if the recursive code does not necessarily invoke Python code (which tracks its recursion depth automatically).

int Py_EnterRecursiveCall (const char *where)

Marks a point where a recursive C-level call is about to be performed.

If USE_STACKCHECK is defined, this function checks if the OS stack overflowed using <code>PyOS_CheckStack()</code>. In this is the case, it sets a <code>MemoryError</code> and returns a nonzero value.

The function then checks if the recursion limit is reached. If this is the case, a RecursionError is set and a nonzero value is returned. Otherwise, zero is returned.

where should be a string such as " in instance check" to be concatenated to the RecursionError message caused by the recursion depth limit.

void Py_LeaveRecursiveCall()

Ends a Py_EnterRecursiveCall(). Must be called once for each successful invocation of Py_EnterRecursiveCall().

Properly implementing tp_repr for container types requires special recursion handling. In addition to protecting the stack, tp_repr also needs to track objects to prevent cycles. The following two functions facilitate this functionality. Effectively, these are the C equivalent to reprlib.recursive_repr().

int Py_ReprEnter (PyObject *object)

Called at the beginning of the tp_repr implementation to detect cycles.

If the object has already been processed, the function returns a positive integer. In that case the tp_repr implementation should return a string object indicating a cycle. As examples, dict objects return $\{\ldots\}$ and list objects return $[\ldots]$.

The function will return a negative integer if the recursion limit is reached. In that case the tp_repr implementation should typically return NULL.

Otherwise, the function returns zero and the tp_repr implementation can continue normally.

void Py_ReprLeave (PyObject *object)

Ends a Py_ReprEnter(). Must be called once for each invocation of Py_ReprEnter() that returns zero.

5.10 标准异常

All standard Python exceptions are available as global variables whose names are PyExc_ followed by the Python exception name. These have the type PyObject*; they are all class objects. For completeness, here are all the variables:

| C 名称 | Python 名称 | 注释 |
|------------------------------|------------------------|-----|
| PyExc_BaseException | BaseException | (1) |
| PyExc_Exception | Exception | (1) |
| PyExc_ArithmeticError | ArithmeticError | (1) |
| PyExc_AssertionError | AssertionError | |
| PyExc_AttributeError | AttributeError | |
| PyExc_BlockingIOError | BlockingIOError | |
| PyExc_BrokenPipeError | BrokenPipeError | |
| PyExc_BufferError | BufferError | |
| PyExc_ChildProcessError | ChildProcessError | |
| PyExc_ConnectionAbortedError | ConnectionAbortedError | |

下页继续

表 1 - 续上页

| C 名称 | メエリ Python 名称 | 注释 |
|------------------------------|------------------------|-----|
| PyExc_ConnectionError | ConnectionError | |
| PyExc_ConnectionRefusedError | ConnectionRefusedError | |
| PyExc_ConnectionResetError | ConnectionResetError | |
| PyExc_EOFError | EOFError | |
| PyExc_FileExistsError | FileExistsError | |
| PyExc_FileNotFoundError | FileNotFoundError | |
| PyExc_FloatingPointError | FloatingPointError | |
| PyExc_GeneratorExit | GeneratorExit | |
| PyExc_ImportError | ImportError | |
| PyExc_IndentationError | IndentationError | |
| PyExc_IndexError | IndexError | |
| PyExc_InterruptedError | InterruptedError | |
| PyExc_IsADirectoryError | IsADirectoryError | |
| PyExc_KeyError | KeyError | |
| PyExc_KeyboardInterrupt | KeyboardInterrupt | |
| PyExc_LookupError | LookupError | (1) |
| PyExc_MemoryError | MemoryError | ` ' |
| PyExc_ModuleNotFoundError | ModuleNotFoundError | |
| PyExc_NameError | NameError | |
| PyExc_NotADirectoryError | NotADirectoryError | |
| PyExc_NotImplementedError | NotImplementedError | |
| PyExc_OSError | OSError | (1) |
| PyExc_OverflowError | OverflowError | |
| PyExc_PermissionError | PermissionError | |
| PyExc_ProcessLookupError | ProcessLookupError | |
| PyExc_RecursionError | RecursionError | |
| PyExc_ReferenceError | ReferenceError | (2) |
| PyExc_RuntimeError | RuntimeError | |
| PyExc_StopAsyncIteration | StopAsyncIteration | |
| PyExc_StopIteration | StopIteration | |
| PyExc_SyntaxError | SyntaxError | |
| PyExc_SystemError | SystemError | |
| PyExc_SystemExit | SystemExit | |
| PyExc_TabError | TabError | |
| PyExc_TimeoutError | TimeoutError | |
| PyExc_TypeError | TypeError | |
| PyExc_UnboundLocalError | UnboundLocalError | |
| PyExc_UnicodeDecodeError | UnicodeDecodeError | |
| PyExc_UnicodeEncodeError | UnicodeEncodeError | |
| PyExc_UnicodeError | UnicodeError | |
| PyExc_UnicodeTranslateError | UnicodeTranslateError | |
| PyExc_ValueError | ValueError | |
| PyExc_ZeroDivisionError | ZeroDivisionError | |

3.3 新版功能: PyExc_BlockingIOError, PyExc_BrokenPipeError, PyExc_ChildProcessError, PyExc_ConnectionError, PyExc_ConnectionAbortedError, PyExc_ConnectionRefusedError, PyExc_FileExistsError, PyExc_FileNotFoundError, PyExc_InterruptedError, PyExc_IsADirectoryError, PyExc_NotADirectoryError, PyExc_ProcessLookupError and PyExc_TimeoutError介绍如下PEP 3151.

- 3.5 新版功能: PyExc_StopAsyncIteration 和 PyExc_RecursionError.
- 3.6 新版功能: PyExc_ModuleNotFoundError.

这些是兼容性别名 PyExc_OSError:

| C 名称 | 注释 |
|------------------------|-----|
| PyExc_EnvironmentError | |
| PyExc_IOError | |
| PyExc_WindowsError | (3) |

在 3.3 版更改: 这些别名曾经是单独的异常类型。

注释:

- (1) 这是其他标准异常的基类。
- (2) Only defined on Windows; protect code that uses this by testing that the preprocessor macro MS_WINDOWS is defined.

5.11 标准警告类别

All standard Python warning categories are available as global variables whose names are $PyExc_f$ followed by the Python exception name. These have the type $PyObject^*$; they are all class objects. For completeness, here are all the variables:

| C 名称 | Python 名称 | 注释 |
|---------------------------------|---------------------------|-----|
| PyExc_Warning | Warning | (1) |
| PyExc_BytesWarning | BytesWarning | |
| PyExc_DeprecationWarning | DeprecationWarning | |
| PyExc_FutureWarning | FutureWarning | |
| PyExc_ImportWarning | ImportWarning | |
| PyExc_PendingDeprecationWarning | PendingDeprecationWarning | |
| PyExc_ResourceWarning | ResourceWarning | |
| PyExc_RuntimeWarning | RuntimeWarning | |
| PyExc_SyntaxWarning | SyntaxWarning | |
| PyExc_UnicodeWarning | UnicodeWarning | |
| PyExc_UserWarning | UserWarning | |

3.2 新版功能: PyExc_ResourceWarning.

注释:

(1) 这是其他标准警告类别的基类。

5.11. 标准警告类别 33

工具

本章中的函数执行各种实用工具任务,包括帮助 C 代码提升跨平台可移植性,在 C 中使用 Python 模块,以及解析函数参数并根据 C 中的值构建 Python 中的值等等。

6.1 操作系统实用程序

PyObject* PyOS_FSPath (PyObject *path)

Return value: New reference. Return the file system representation for path. If the object is a str or bytes object, then its reference count is incremented. If the object implements the os.PathLike interface, then __fspath___() is returned as long as it is a str or bytes object. Otherwise TypeError is raised and NULL is returned.

3.6 新版功能.

int Py_FdIsInteractive (FILE *fp, const char *filename)

Return true (nonzero) if the standard I/O file fp with name filename is deemed interactive. This is the case for files for which isatty(fileno(fp)) is true. If the global flag $Py_InteractiveFlag$ is true, this function also returns true if the filename pointer is NULL or if the name is equal to one of the strings '<stdin>' or '???'.

void PyOS_BeforeFork()

Function to prepare some internal state before a process fork. This should be called before calling fork() or any similar function that clones the current process. Only available on systems where fork() is defined.

警告: The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for PyOS_BeforeFork ().

3.7 新版功能.

void PyOS_AfterFork_Parent()

Function to update some internal state after a process fork. This should be called from the parent process after calling fork() or any similar function that clones the current process, regardless of whether process cloning was successful. Only available on systems where fork() is defined.

警告: The C fork () call should only be made from the "main" thread (of the "main" interpreter). The same is true for PyOS_AfterFork_Parent().

3.7 新版功能.

void PyOS_AfterFork_Child()

Function to update internal interpreter state after a process fork. This must be called from the child process after calling fork (), or any similar function that clones the current process, if there is any chance the process will call back into the Python interpreter. Only available on systems where fork () is defined.

警告: The C fork() call should only be made from the "main" thread (of the "main" interpreter). The same is true for PyOS_AfterFork_Child().

3.7 新版功能.

参见:

os.register_at_fork() allows registering custom Python functions to be called by PyOS_BeforeFork(), PyOS_AfterFork_Parent() and PyOS_AfterFork_Child().

void PyOS_AfterFork()

Function to update some internal state after a process fork; this should be called in the new process if the Python interpreter will continue to be used. If a new executable is loaded into the new process, this function does not need to be called.

3.7 版后已移除: This function is superseded by PyOS_AfterFork_Child().

int PyOS_CheckStack()

Return true when the interpreter runs out of stack space. This is a reliable check, but is only available when USE_STACKCHECK is defined (currently on Windows using the Microsoft Visual C++ compiler). USE_STACKCHECK will be defined automatically; you should never change the definition in your own code.

${\tt PyOS_sighandler_t\ PyOS_getsig\ (int\ } i)$

Return the current signal handler for signal *i*. This is a thin wrapper around either signation() or signal(). Do not call those functions directly! PyOS_sighandler_t is a typedef alias for void (*) (int).

PyOS_sighandler_t PyOS_setsig (int i, PyOS_sighandler_t h)

Set the signal handler for signal i to be h; return the old signal handler. This is a thin wrapper around either signation() or signal(). Do not call those functions directly! PyOS_sighandler_t is a typedef alias for void (*)(int).

wchar_t* Py_DecodeLocale (const char* arg, size_t *size)

Decode a byte string from the locale encoding with the surrogateescape error handler: undecodable bytes are decoded as characters in range U+DC80..U+DCFF. If a byte sequence can be decoded as a surrogate character, escape the bytes using the surrogateescape error handler instead of decoding them.

Encoding, highest priority to lowest priority:

- UTF-8 on macOS, Android, and VxWorks;
- UTF-8 on Windows if Py_LegacyWindowsFSEncodingFlag is zero;
- UTF-8 if the Python UTF-8 mode is enabled;
- ASCII if the LC_CTYPE locale is "C", nl_langinfo(CODESET) returns the ASCII encoding (or an alias), and mbstowcs() and wcstombs() functions uses the ISO-8859-1 encoding.
- the current locale encoding.

Return a pointer to a newly allocated wide character string, use <code>PyMem_RawFree()</code> to free the memory. If size is not <code>NULL</code>, write the number of wide characters excluding the null character into <code>*size</code>

Return NULL on decoding error or memory allocation error. If size is not NULL, *size is set to $(size_t)-1$ on memory error or set to $(size_t)-2$ on decoding error.

Decoding errors should never happen, unless there is a bug in the C library.

Use the Py_EncodeLocale() function to encode the character string back to a byte string.

参见:

 $\label{localeAndSize} \begin{tabular}{ll} The $\it PyUnicode_DecodeLocaleAndSize()$ and $\it PyUnicode_DecodeLocaleAndSize()$ functions. \end{tabular}$

3.5 新版功能.

在 3.7 版更改: The function now uses the UTF-8 encoding in the UTF-8 mode.

在 3.8 版 更 改: The function now uses the UTF-8 encoding on Windows if Py_LegacyWindowsFSEncodingFlag is zero;

char* **Py_EncodeLocale** (const wchar_t *text, size_t *error_pos)

Encode a wide character string to the locale encoding with the surrogateescape error handler: surrogate characters in the range U+DC80..U+DCFF are converted to bytes 0x80..0xFF.

Encoding, highest priority to lowest priority:

- UTF-8 on macOS, Android, and VxWorks;
- UTF-8 on Windows if Py LegacyWindowsFSEncodingFlag is zero;
- UTF-8 if the Python UTF-8 mode is enabled;
- ASCII if the LC_CTYPE locale is "C", nl_langinfo(CODESET) returns the ASCII encoding (or an alias), and mbstowcs() and wcstombs() functions uses the ISO-8859-1 encoding.
- the current locale encoding.

The function uses the UTF-8 encoding in the Python UTF-8 mode.

Return a pointer to a newly allocated byte string, use <code>PyMem_Free()</code> to free the memory. Return <code>NULL</code> on encoding error or memory allocation error

If error_pos is not NULL, *error_pos is set to (size_t) -1 on success, or set to the index of the invalid character on encoding error.

Use the Py_DecodeLocale() function to decode the bytes string back to a wide character string.

参见:

The PyUnicode_EncodeFSDefault () and PyUnicode_EncodeLocale () functions.

3.5 新版功能.

在 3.7 版更改: The function now uses the UTF-8 encoding in the UTF-8 mode.

在 3.8 版 更 改: The function now uses the UTF-8 encoding on Windows if Py_LegacyWindowsFSEncodingFlag is zero;

6.2 系统功能

These are utility functions that make functionality from the sys module accessible to C code. They all work with the current interpreter thread's sys module's dict, which is contained in the internal thread state structure.

PyObject *PySys_GetObject (const char *name)

Return value: Borrowed reference. Return the object *name* from the sys module or NULL if it does not exist, without setting an exception.

int PySys_SetObject (const char *name, PyObject *v)

Set *name* in the sys module to v unless v is NULL, in which case *name* is deleted from the sys module. Returns 0 on success. -1 on error.

6.2. 系统功能 37

void PySys_ResetWarnOptions()

Reset sys.warnoptions to an empty list. This function may be called prior to Py_Initialize().

void PySys_AddWarnOption (const wchar_t *s)

Append s to sys. warnoptions. This function must be called prior to $Py_Initialize()$ in order to affect the warnings filter list.

void PySys_AddWarnOptionUnicode (PyObject *unicode)

Append unicode to sys.warnoptions.

Note: this function is not currently usable from outside the CPython implementation, as it must be called prior to the implicit import of warnings in Py_Initialize() to be effective, but can't be called until enough of the runtime has been initialized to permit the creation of Unicode objects.

void PySys_SetPath (const wchar_t *path)

Set sys.path to a list object of paths found in *path* which should be a list of paths separated with the platform's search path delimiter (: on Unix, ; on Windows).

void PySys_WriteStdout (const char *format, ...)

Write the output string described by *format* to sys.stdout. No exceptions are raised, even if truncation occurs (see below).

format should limit the total size of the formatted output string to 1000 bytes or less -- after 1000 bytes, the output string is truncated. In particular, this means that no unrestricted "%s" formats should occur; these should be limited using "%.<N>s" where <N> is a decimal number calculated so that <N> plus the maximum size of other formatted text does not exceed 1000 bytes. Also watch out for "%f", which can print hundreds of digits for very large numbers.

If a problem occurs, or sys.stdout is unset, the formatted message is written to the real (C level) stdout.

void PySys WriteStderr (const char *format, ...)

As PySys WriteStdout(), but write to sys.stderr or stderr instead.

void PySys_FormatStdout (const char *format, ...)

Function similar to PySys_WriteStdout() but format the message using $PyUnicode_FromFormatV()$ and don't truncate the message to an arbitrary length.

3.2 新版功能.

void PySys_FormatStderr (const char *format, ...)

As PySys_FormatStdout(), but write to sys.stderr or stderr instead.

3.2 新版功能.

void PySys_AddXOption (const wchar_t *s)

Parse s as a set of -X options and add them to the current options mapping as returned by $PySys_GetXOptions()$. This function may be called prior to $Py_Initialize()$.

3.2 新版功能.

PyObject *PySys_GetXOptions()

Return value: Borrowed reference. Return the current dictionary of -X options, similarly to sys. _xoptions. On error, NULL is returned and an exception is set.

3.2 新版功能.

int PySys_Audit (const char *event, const char *format, ...)

Raise an auditing event with any active hooks. Return zero for success and non-zero with an exception set on failure.

If any hooks have been added, *format* and other arguments will be used to construct a tuple to pass. Apart from N, the same format characters as used in $Py_BuildValue()$ are available. If the built value is not a tuple, it will be added into a single-element tuple. (The N format option consumes a reference, but since there is no way to know whether arguments to this function will be consumed, using it may cause reference leaks.)

Note that # format characters should always be treated as Py_ssize_t, regardless of whether PY_SSIZE_T_CLEAN was defined.

sys.audit() performs the same function from Python code.

3.8 新版功能.

在 3.8.2 版更改: Require Py_ssize_t for # format characters. Previously, an unavoidable deprecation warning was raised.

int **PySys_AddAuditHook** (Py_AuditHookFunction *hook*, void *userData)

Append the callable *hook* to the list of active auditing hooks. Return zero for success and non-zero on failure. If the runtime has been initialized, also set an error on failure. Hooks added through this API are called for all interpreters created by the runtime.

userData 指针会被传入钩子函数。因于钩子函数可能由不同的运行时调用,该指针不应直接指向 Python 状态。

This function is safe to call before $Py_Initialize()$. When called after runtime initialization, existing audit hooks are notified and may silently abort the operation by raising an error subclassed from Exception (other errors will not be silenced).

The hook function is of type int (*) (const char *event, PyObject *args, void *userData), where args is guaranteed to be a PyTupleObject. The hook function is always called with the GIL held by the Python interpreter that raised the event.

See PEP 578 for a detailed description of auditing. Functions in the runtime and standard library that raise events are listed in the audit events table. Details are in each function's documentation.

If the interpreter is initialized, this function raises a auditing event sys.addaudithook with no arguments. If any existing hooks raise an exception derived from Exception, the new hook will not be added and the exception is cleared. As a result, callers cannot assume that their hook has been added unless they control all existing hooks.

3.8 新版功能.

6.3 过程控制

void Py_FatalError (const char *message)

Print a fatal error message and kill the process. No cleanup is performed. This function should only be invoked when a condition is detected that would make it dangerous to continue using the Python interpreter; e.g., when the object administration appears to be corrupted. On Unix, the standard C library function abort () is called which will attempt to produce a core file.

void Py Exit (int status)

Exit the current process. This calls $Py_FinalizeEx()$ and then calls the standard C library function exit(status). If $Py_FinalizeEx()$ indicates an error, the exit status is set to 120.

在 3.6 版更改: Errors from finalization no longer ignored.

int Py_AtExit (void (*func)())

Register a cleanup function to be called by $Py_FinalizeEx()$. The cleanup function will be called with no arguments and should return no value. At most 32 cleanup functions can be registered. When the registration is successful, $Py_AtExit()$ returns 0; on failure, it returns -1. The cleanup function registered last is called first. Each cleanup function will be called at most once. Since Python's internal finalization will have completed before the cleanup function, no Python APIs should be called by *func*.

6.3. 过程控制 39

6.4 导入模块

PyObject* PyImport_ImportModule (const char *name)

Return value: New reference. This is a simplified interface to <code>PyImport_ImportModuleEx()</code> below, leaving the <code>globals</code> and <code>locals</code> arguments set to <code>NULL</code> and <code>level</code> set to 0. When the <code>name</code> argument contains a dot (when it specifies a submodule of a package), the <code>fromlist</code> argument is set to the list <code>['*']</code> so that the return value is the named module rather than the top-level package containing it as would otherwise be the case. (Unfortunately, this has an additional side effect when <code>name</code> in fact specifies a subpackage instead of a submodule: the submodules specified in the package's <code>__all__</code> variable are loaded.) Return a new reference to the imported module, or <code>NULL</code> with an exception set on failure. A failing import of a module doesn't leave the module in <code>sys.modules</code>.

该函数总是使用绝对路径导入。

PyObject* PyImport_ImportModuleNoBlock (const char *name)

Return value: New reference. 该函数是PyImport_ImportModule()的一个被弃用的别名。

在 3.3 版更改: This function used to fail immediately when the import lock was held by another thread. In Python 3.3 though, the locking scheme switched to per-module locks for most purposes, so this function's special behaviour isn't needed anymore.

PyObject* PyImport_ImportModuleEx (const char *name, PyObject *globals, PyObject *locals, PyObject *fromlist)

Return value: New reference. Import a module. This is best described by referring to the built-in Python function __import__().

The return value is a new reference to the imported module or top-level package, or NULL with an exception set on failure. Like for __import__(), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty *fromlist* was given.

Failing imports remove incomplete module objects, like with PyImport_ImportModule().

PyObject* PyImport_ImportModuleLevelObject (PyObject *name, PyObject *globals, PyObject *fromlist, int level)

Return value: New reference. Import a module. This is best described by referring to the built-in Python function __import__ (), as the standard __import__ () function calls this function directly.

The return value is a new reference to the imported module or top-level package, or <code>NULL</code> with an exception set on failure. Like for <code>__import__</code>(), the return value when a submodule of a package was requested is normally the top-level package, unless a non-empty <code>fromlist</code> was given.

3.3 新版功能.

PyObject* PyImport_ImportModuleLevel (const char *name, PyObject *globals, PyObject *locals, PyObject *fromlist, int level)

Return value: New reference. Similar to PyImport_ImportModuleLevelObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

在 3.3 版更改: Negative values for level are no longer accepted.

PyObject* PyImport_Import (PyObject *name)

Return value: New reference. This is a higher-level interface that calls the current "import hook function" (with an explicit level of 0, meaning absolute import). It invokes the __import__() function from the __builtins__ of the current globals. This means that the import is done using whatever import hooks are installed in the current environment.

该函数总是使用绝对路径导入。

PyObject* PyImport_ReloadModule (PyObject *m)

Return value: New reference. Reload a module. Return a new reference to the reloaded module, or NULL with an exception set on failure (the module still exists in this case).

PyObject* PyImport_AddModuleObject (PyObject *name)

Return value: Borrowed reference. Return the module object corresponding to a module name. The name argument may be of the form package.module. First check the modules dictionary if there's one there,

and if not, create a new one and insert it in the modules dictionary. Return NULL with an exception set on failure.

注解: This function does not load or import the module; if the module wasn't already loaded, you will get an empty module object. Use <code>PyImport_ImportModule()</code> or one of its variants to import a module. Package structures implied by a dotted name for *name* are not created if not already present.

3.3 新版功能.

PyObject* PyImport_AddModule (const char *name)

Return value: Borrowed reference. Similar to PyImport_AddModuleObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

PyObject* PyImport_ExecCodeModule (const char *name, PyObject *co)

Return value: New reference. Given a module name (possibly of the form package.module) and a code object read from a Python bytecode file or obtained from the built-in function compile(), load the module. Return a new reference to the module object, or NULL with an exception set if an error occurred. name is removed from sys.modules in error cases, even if name was already in sys.modules on entry to PyImport_ExecCodeModule(). Leaving incompletely initialized modules in sys.modules is dangerous, as imports of such modules have no way to know that the module object is an unknown (and probably damaged with respect to the module author's intents) state.

The module's __spec__ and __loader__ will be set, if not set already, with the appropriate values. The spec's loader will be set to the module's __loader__ (if set) and to an instance of SourceFileLoader otherwise.

The module's __file__ attribute will be set to the code object's co_filename. If applicable, cached will also be set.

This function will reload the module if it was already imported. See <code>PyImport_ReloadModule()</code> for the intended way to reload a module.

If *name* points to a dotted name of the form package.module, any package structures not already created will still not be created.

See also PyImport_ExecCodeModuleEx() and PyImport_ExecCodeModuleWithPathnames().

PyObject* PyImport_ExecCodeModuleEx (const char *name, PyObject *co, const char *pathname)

Return value: New reference. Like <code>PyImport_ExecCodeModule()</code>, but the __file__ attribute of the module object is set to <code>pathname</code> if it is non-NULL.

参见 $PyImport_ExecCodeModuleWithPathnames()。$

PyObject* PyImport_ExecCodeModuleObject (PyObject *name, PyObject *co, PyObject *pathname, PyObject *cpathname)

Return value: New reference. Like PyImport_ExecCodeModuleEx(), but the __cached__ attribute of the module object is set to *cpathname* if it is non-NULL. Of the three functions, this is the preferred one to use.

3.3 新版功能.

PyObject* PyImport_ExecCodeModuleWithPathnames (const char *name, PyObject *co, const char *pathname, const char *cpathname)

Return value: New reference. Like PyImport_ExecCodeModuleObject(), but name, pathname and cpathname are UTF-8 encoded strings. Attempts are also made to figure out what the value for pathname should be from cpathname if the former is set to NULL.

3.2 新版功能.

在 3.3 版更改: Uses imp.source_from_cache() in calculating the source path if only the bytecode path is provided.

long PyImport_GetMagicNumber()

Return the magic number for Python bytecode files (a.k.a. .pyc file). The magic number should be present in the first four bytes of the bytecode file, in little-endian byte order. Returns -1 on error.

6.4. 导入模块 41

在 3.3 版更改: 失败时返回值 -1。

const char * PyImport_GetMagicTag()

Return the magic tag string for PEP 3147 format Python bytecode file names. Keep in mind that the value at sys.implementation.cache_tag is authoritative and should be used instead of this function.

3.2 新版功能.

PyObject* PyImport_GetModuleDict()

Return value: Borrowed reference. Return the dictionary used for the module administration (a.k.a. sys.modules). Note that this is a per-interpreter variable.

PyObject* PyImport_GetModule (PyObject *name)

Return value: New reference. Return the already imported module with the given name. If the module has not been imported yet then returns NULL but does not set an error. Returns NULL and sets an error if the lookup failed.

3.7 新版功能.

PyObject* PyImport_GetImporter (PyObject *path)

Return value: New reference. Return a finder object for a sys.path/pkg.__path__ item path, possibly by fetching it from the sys.path_importer_cache dict. If it wasn't yet cached, traverse sys.path_hooks until a hook is found that can handle the path item. Return None if no hook could; this tells our caller that the path based finder could not find a finder for this path item. Cache the result in sys.path_importer_cache. Return a new reference to the finder object.

void PyImport Init()

Initialize the import mechanism. For internal use only.

void PyImport_Cleanup()

Empty the module table. For internal use only.

void _PyImport_Fini()

Finalize the import mechanism. For internal use only.

int PyImport_ImportFrozenModuleObject (PyObject *name)

Return value: New reference. Load a frozen module named name. Return 1 for success, 0 if the module is not found, and -1 with an exception set if the initialization failed. To access the imported module on a successful load, use $PyImport_ImportModule()$. (Note the misnomer --- this function would reload the module if it was already imported.)

3.3 新版功能.

在 3.4 版更改: The ___file__ attribute is no longer set on the module.

int PyImport_ImportFrozenModule (const char *name)

Similar to $PyImport_ImportFrozenModuleObject()$, but the name is a UTF-8 encoded string instead of a Unicode object.

struct frozen

This is the structure type definition for frozen module descriptors, as generated by the **freeze** utility (see Tools/freeze/ in the Python source distribution). Its definition, found in Include/import.h, is:

```
struct _frozen {
   const char *name;
   const unsigned char *code;
   int size;
};
```

const struct _frozen* PyImport_FrozenModules

This pointer is initialized to point to an array of struct _frozen records, terminated by one whose members are all NULL or zero. When a frozen module is imported, it is searched in this table. Third-party code could play tricks with this to provide a dynamically created collection of frozen modules.

int PyImport_AppendInittab (const char *name, PyObject* (*initfunc)(void))

Add a single module to the existing table of built-in modules. This is a convenience wrapper around

 $PyImport_ExtendInittab()$, returning -1 if the table could not be extended. The new module can be imported by the name *name*, and uses the function *initfunc* as the initialization function called on the first attempted import. This should be called before $Py_Initialize()$.

struct inittab

Structure describing a single entry in the list of built-in modules. Each of these structures gives the name and initialization function for a module built into the interpreter. The name is an ASCII encoded string. Programs which embed Python may use an array of these structures in conjunction with <code>PyImport_ExtendInittab()</code> to provide additional built-in modules. The structure is defined in <code>Include/import.h</code> as:

int PyImport_ExtendInittab (struct _inittab *newtab)

Add a collection of modules to the table of built-in modules. The *newtab* array must end with a sentinel entry which contains NULL for the name field; failure to provide the sentinel value can result in a memory fault. Returns 0 on success or -1 if insufficient memory could be allocated to extend the internal table. In the event of failure, no modules are added to the internal table. This should be called before <code>Py_Initialize()</code>.

6.5 Data marshalling support

These routines allow C code to work with serialized objects using the same data format as the marshal module. There are functions to write data into the serialization format, and additional functions that can be used to read the data back. Files used to store marshalled data must be opened in binary mode.

Numeric values are stored with the least significant byte first.

The module supports two versions of the data format: version 0 is the historical version, version 1 shares interned strings in the file, and upon unmarshalling. Version 2 uses a binary format for floating point numbers. Py_MARSHAL_VERSION indicates the current file format (currently 2).

```
void PyMarshal_WriteLongToFile (long value, FILE *file, int version)
```

Marshal a long integer, *value*, to *file*. This will only write the least-significant 32 bits of *value*; regardless of the size of the native long type. *version* indicates the file format.

```
void PyMarshal_WriteObjectToFile (PyObject *value, FILE *file, int version)
```

Marshal a Python object, value, to file. version indicates the file format.

```
PyObject* PyMarshal_WriteObjectToString (PyObject *value, int version)
```

Return value: New reference. Return a bytes object containing the marshalled representation of *value. version* indicates the file format.

The following functions allow marshalled values to be read back in.

```
long PyMarshal_ReadLongFromFile (FILE *file)
```

Return a C long from the data stream in a FILE* opened for reading. Only a 32-bit value can be read in using this function, regardless of the native size of long.

On error, sets the appropriate exception (EOFError) and returns -1.

int PyMarshal_ReadShortFromFile (FILE *file)

Return a C short from the data stream in a FILE* opened for reading. Only a 16-bit value can be read in using this function, regardless of the native size of short.

On error, sets the appropriate exception (EOFError) and returns -1.

PyObject* PyMarshal_ReadObjectFromFile (FILE *file)

Return value: New reference. Return a Python object from the data stream in a FILE* opened for reading.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

PyObject* PyMarshal_ReadLastObjectFromFile (FILE *file)

Return value: New reference. Return a Python object from the data stream in a FILE* opened for reading. Unlike <code>PyMarshal_ReadObjectFromFile()</code>, this function assumes that no further objects will be read from the file, allowing it to aggressively load file data into memory so that the de-serialization can operate from data in memory rather than reading a byte at a time from the file. Only use these variant if you are certain that you won't be reading anything else from the file.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

PyObject* PyMarshal_ReadObjectFromString (const char *data, Py_ssize_t len)

Return value: New reference. Return a Python object from the data stream in a byte buffer containing *len* bytes pointed to by *data*.

On error, sets the appropriate exception (EOFError, ValueError or TypeError) and returns NULL.

6.6 语句解释及变量编译

这些函数在创建你自己的函数时帮助很大。更多说明以及实例可参考说明文档中的 extending-index 小节。这些函数描述的前三个, $PyArg_ParseTuple()$, $PyArg_ParseTupleAndKeywords()$,以及 $PyArg_Parse()$,它们都使用格式化字符串来将函数期待的参数告知函数。这些函数都使用相同语法规则的格式化字符串。

6.6.1 解析参数

一个格式化字符串包含 0 或者更多的格式单元。一个格式单元用来描述一个 Python 对象;它通常是一个字符或者由括号括起来的格式单元序列。除了少数例外,一个非括号序列的格式单元通常对应这些函数的具有单一地址的参数。在接下来的描述中,双引号内的表达式是格式单元;圆括号 () 内的是对应这个格式单元的 Python 对象类型;方括号 [] 内的是传递的 C 变量 (变量集) 类型。

字符串和缓存区

这些格式允许将对象按照连续的内存块形式进行访问。你没必要提供返回的 unicode 字符或者字节区的原始数据存储。

一般的,当一个表达式设置一个指针指向一个缓冲区,这个缓冲区可以被相应的 Python 对象管理,并且这个缓冲区共享这个对象的生存周期。你不需要人为的释放任何内存空间。除了这些 es, es #, et and et #.

然而,当一个 Py_buffer 结构被赋值,其包含的缓冲区被锁住,所以调用者在随后使用这个缓冲区,即使在 $Py_BEGIN_ALLOW_THREADS$ 块中,可以避免可变数据因为调整大小或者被销毁所带来的风险。因此,**你不得不调用** $PyBuffer_Release$ () 在你结束数据的处理时 (或者在之前任何中断事件中)

除非另有说明,缓冲区是不会以空终止的。

某些格式需要只读的bytes-like object,并设置指针而不是缓冲区结构。他们通过检查对象的PyBufferProcs.bf_releasebuffer字段是否为NULL来发挥作用,该字段不允许为bytearray这样的可变对象。

注解: 所有 # 表达式的变式(s#, y#, 等等), 长度参数的类型(整型或者 Py_ssize_t) 在包含 Python. h 头文件之前由 PY_SSIZE_T_CLEAN 宏的定义控制。如果这个宏被定义,长度是一个 Py_ssize_t Python 元大小类型而不是一个 int 整型。在未来的 Python 版本中将会改变,只支持 Py_ssize_t 而放弃支持 int 整型。最好一直定义 PY_SSIZE_T_CLEAN 这个宏。

s(**str**)[**const char ***] 将一个 Unicode 对象转换成一个指向字符串的 C 指针。一个指针指向一个已经存在的字符串,这个字符串存储的是传如的字符指针变量。C 字符串是已空结束的。Python 字符串不

能包含嵌入的无效的代码点;如果由,一个 ValueError 异常会被引发。Unicode 对象被转化成 'utf-8'编码的 C 字符串。如果转换失败,一个 UnicodeError 异常被引发。

注解: 这个表达式不接受bytes-like objects。如果你想接受文件系统路径并将它们转化成 C 字符串,建议使用 O& 表达式配合PyUnicode_FSConverter() 作为 转化函数。

在 3.5 版更改: 以前, 当 Python 字符串中遇到了嵌入的 null 代码点会引发 TypeError。

- **s*** (**str or** *bytes-like object*) [**Py_buffer**] 这个表达式既接受 Unicode 对象也接受类字节类型对象。它为由调用者提供的*Py_buffer* 结构赋值。这里结果的 C 字符串可能包含嵌入的 NUL 字节。Unicode 对象通过 'utf-8' 编码转化成 C 字符串。
- **s#(str,只读bytes-like object)** [const char*, int or Py_ssize_t] 像 s*,除了它不接受易变的对象。结果存储在两个 C 变量中,第一个是指向 C 字符串的指针,第二个是它的长度。字符串可能包含嵌入的 null 字节。Unicode 对象都被通过 'utf-8' 编码转化成 C 字符串。
- **z** (**str or None**) [**const char ***] 与 s 类似,但 **Python** 对象也可能为 None,在这种情况下,C 指针设置为 NULL。
- **z* (str,** *bytes-like object* **or None)** [**Py_buffer**] 与 s* 类似,但 Python 对象也可能为 None,在这种情况下, *Py_buffer* 结构的 buf 成员设置为 NULL。
- **z#(str, 只读***bytes-like object* 或 None) [const char *, int 或 Py_ssize_t] 与 s# 类似,但 Python 对象也可能为 None,在这种情况下,C 指针设置为 NULL。
- y (read-only bytes-like object) [const char *] 这个表达式将一个类字节类型对象转化成一个指向字符串的 C 指针;它不接受 Unicode 对象。字节缓存区必须不包含嵌入的 null 字节;如果包含了 null 字节,会引发一个 ValueError 异常。
 - 在 3.5 版更改: 以前, 当字节缓冲区中遇到了嵌入的 null 字节会引发 TypeError。
- y* (bytes-like object) [Py_buffer] s* 的变式,不接受 Unicode 对象,只接受类字节类型变量。**这是接受二进制数据的推荐方法**。
- **y#(只读bytes-like object)** [const char *, int 或 Py_ssize_t] s# 的变式,不接受 Unicode 对象,只接受类 字节类型变量。
- S (bytes) [PyBytesObject*] 要求 Python 对象是一个 bytes 类型对象,没有尝试任何的转换。如果不是一个字节类型对象会引发 TypeError 异常。C 变量也可能声明为PyObject*类型。
- Y (bytearray) [PyByteArrayObject*] 要求 Python 对象是一个 bytearray 类型对象,没有尝试任何的转换。如果不是一个 bytearray 类型对象会引发 TypeError 异常。C 变量也可能声明为PyObject*类型。
- u (str) [const Py_UNICODE *] 将一个 Python Unicode 对象转化成指向一个以空终止的 Unicode 字符缓冲区的指针。你必须传入一个 Py_UNICODE 指针变量的地址,存储了一个指向已经存在的 Unicode 缓冲区的指针。请注意一个 Py_UNICODE 类型的字符宽度取决于编译选项 (16 位或者 32 位)。 Python字符串必须不能包含嵌入的 null 代码点;如果有,引发一个 ValueError 异常。
 - 在 3.5 版更改: 以前, 当 Python 字符串中遇到了嵌入的 null 代码点会引发 TypeError。
 - Deprecated since version 3.3, will be removed in version 4.0: 这是旧版样式Py_UNICODE API; 请迁移至PyUnicode AsWideCharString().
- u# (str) [const Py_UNICODE*, int 或 Py_ssize_t] u 的变式,存储两个 C 变量,第一个指针指向一个 Unicode 数据缓存区,第二个是它的长度。它允许 null 代码点。
 - Deprecated since version 3.3, will be removed in version 4.0: 这是旧版样式Py_UNICODE API; 请迁移至PyUnicode_AsWideCharString().
- **Z**(str或None)[const Py_UNICODE*]与 u 类似,但 Python 对象也可能为 None,在这种情况下Py_UNICODE 指针设置为 NULL。
 - Deprecated since version 3.3, will be removed in version 4.0: 这是旧版样式Py_UNICODE API; 请迁移至PyUnicode_AsWideCharString().

Z#(str或None)[const Py_UNICODE*, int 或 Py_ssize_t] 与 u# 类似,但 Python 对象也可能为 None,在这种情况下 *Py_UNICODE* 指针设置为 NULL。

Deprecated since version 3.3, will be removed in version 4.0: 这是旧版样式Py_UNICODE API; 请迁移 至PyUnicode_AsWideCharString().

- U(str)[PyObject*]要求Python对象是一个Unicode对象,没有尝试任何的转换。如果不是一个Unicode对象会引发TypeError异常。C变量也可能声明为PyObject*类型。
- w* (可读写bytes-like object) [Py_buffer] 这个表达式接受任何实现可读写缓存区接口的对象。它为调用者提供的Py_buffer 结构赋值。缓冲区可能存在嵌入的 null 字节。当缓冲区使用完后调用者需要调用PyBuffer Release()。
- **es** (**str**) [const char *encoding, char **buffer] s 的变式,它将编码后的 Unicode 字符存入字符缓冲区。它只处理没有嵌 NUL 字节的已编码数据。

此格式需要两个参数。第一个仅用作输入,并且必须是 const char*,该名称将编码的名称指向 NUL 终止字符串或"NULL",在这种情况下,使用 'utf-8'编码。如果 Python 不知道命名编码,则引发异常。第二个参数必须为 char** 它引用的指针的值将设置为包含参数文本内容的缓冲区。文本将以第一个参数指定的编码进行编码。

 $PyArg_ParseTuple()$ 会分配一个足够大小的缓冲区,将编码后的数据拷贝进这个缓冲区并且设置 *buffer 引用这个新分配的内存空间。调用者有责任在使用后调用 $PyMem_Free()$ 去释放已经分配的缓冲区。

- et (str, bytes or bytearray) [const char *encoding, char **buffer] 和 es 相同,除了不用重编码传入的字符串对象。相反,它假设传入的参数是编码后的字符串类型。
- **es# (str) [const char *encoding, char **buffer, int 或 Py_ssize_t *buffer_length]** s# 的变式,它将已编码的 Unicode 字符存入字符缓冲区。不像 es 表达式,它允许传入的数据包含 NUL 字符。

它需要三个参数。第一个仅用作输入,并且必须为 const char*,该对象指向一个编码格式名称,形式为以 NUL 结束的字符串或 NULL,在后一种情况下将使用 'utf-8'编码格式。如果编码格式名称无法被 Python 识别则会引发异常。第二个参数必须为 char**;它所引用的指针的值将被设为包含参数文本内容的缓冲区。文本将以第一个参数所指定的编码格式进行编码。第三个参数必须是指向一个整数的指针;所引用的整数将被设为输出缓冲区中的字节数。

有两种操作方式:

如果 *buffer 指向 NULL 指针,则函数将分配所需大小的缓冲区,将编码的数据复制到此缓冲区,并设置 *buffer 以引用新分配的存储。呼叫者负责调用PyMem_Free()以在使用后释放分配的缓冲区。

如果 *buffer 指向非 NULL 指针(已分配的缓冲区),则PyArg_ParseTuple() 将使用此位置作为缓冲区,并将 *buffer_length 的初始值解释为缓冲区大小。然后,它将将编码的数据复制到缓冲区,并终止它。如果缓冲区不够大,将设置一个 ValueError。

在这两个例子中,*buffer_length 被设置为编码后结尾不为 NUL 的数据的长度。

et# (str, bytes 或 bytearray) [const char *encoding, char **buffer, int 或 Py_ssize_t *buffer_length] 和 es# 相同,除了不用重编码传入的字符串对象。相反,它假设传入的参数是编码后的字符串类型。

数字

- **b** (int) [unsigned char] 将一个非负的 Python 整型转化成一个无符号的微整型,存储在一个 Cunsigned char 类型中。
- **B(int)[unsigned char]** 将一个 Python 整型转化成一个微整型并不检查溢出问题,存储在一个 Cunsigned char 类型中。
- h (int) [short int] 将一个 Python 整型转化成一个 C short int 短整型。
- H(int)[unsigned short int] 将一个 Python 整型转化成一个 C unsigned short int 无符号短整型, 并不检查溢出问题。
- i(int)[int] 将一个Python整型转化成一个Cint整型。

- I (int) [unsigned int] 将一个 Python 整型转化成一个 C unsigned int 无符号整型,并不检查溢出问题。
- 1 (int) [long int] 将一个 Python 整型转化成一个 Clong int 长整型。
- k (int) [unsigned long] 将一个 Python 整型转化成一个 C unsigned long int 无符号长整型, 并不检查溢出问题。
- L(int)[long long] 将一个 Python 整型转化成一个 Clong long 长长整型。
- K (int) [unsigned long long] 将一个 Python 整型转化成一个 C unsigned long long 无符号长长整型, 并不检查溢出问题。
- n (int) [Py_ssize_t] 将一个 Python 整型转化成一个 C Py_ssize_t Python 元大小类型。
- c (bytes 或者 bytearray 长度为 1) [char] 将一个 Python 字节类型,如一个长度为 1 的 bytes 或者 bytearray 对象,转化成一个 C char 字符类型。
 - 在 3.3 版更改: 允许 bytearray 类型的对象。
- **C**(**str长度为1**)[**int**] 将一个 Python 字符,如一个长度为1的 str 字符串对象,转化成一个 C int 整型 类型。
- **f**(**float**)[**float**] 将一个 Python 浮点数转化成一个 C float 浮点数。
- **d**(**float**)[**double**]将一个Python浮点数转化成一个C double 双精度浮点数。
- D (complex) [Py_complex] 将一个 Python 复数类型转化成一个 C Py_complex Python 复数类型。

其他对象

- O (object) [PyObject *] 将 Python 对象(不进行任何转换)存储在 C 对象指针中。因此,C 程序接收已传递的实际对象。对象的引用计数不会增加。存储的指针不是 NULL。
- O! (object) [typeobject, PyObject*] 将一个 Python 对象存入一个 C 指针。和 类似,但是需要两个 C 参数: 第一个是 Python 类型对象的地址,第二个是存储对象指针的 C 变量 (PyObject* 变量) 的地址。如果 Python 对象类型不对,会抛出 TypeError 异常。
- **O&** (**object**) [converter, anything] 通过一个 converter 函数将一个 Python 对象转换成一个 C 变量。这需要两个参数:第一个是一个函数,第二个是一个 C 变量的地址(任意类型的),转化为 void * 类型。converter 函数像这样被调用:

status = converter(object, address);

object* 是待转化的 Python 对象并且 *address 是传入PyArg_Parse*() 函数的 void* 类型参数。返回的 status 是 1 代表转换成功,0 代表转换失败。当转换失败,converter* 函数会引发一个异常并且不会修改 *address 的内容。

如果 converter 返回 Py_CLEANUP_SUPPORTED,则如果参数解析最终失败,它可能会再次调用该函数,从而使转换器有机会释放已分配的任何内存。在第二个调用中,object 参数将为 NULL;因此,该参数将为 NULL;因此,该参数将为 NULL``(如果值)为 ``NULL address 的值与原始呼叫中的值相同。

- 在 3.1 版更改: Py_CLEANUP_SUPPORTED 被添加。
- p (bool) [int] 测试传入的值是否为真 (一个布尔判断) 并且将结果转化为相对应的 C true/false 整型值。如果表达式为真置 1, 假则置 0。它接受任何合法的 Python 值。参见 truth 获取更多关于 Python 如何测试值为真的信息。
 - 3.3 新版功能.
- (items) (tuple) [matching-items] 对象必须是 Python 序列,它的长度是 items 中格式单元的数量。C 参数必须对应 items 中每一个独立的格式单元。序列中的格式单元可能有嵌套。

传递"long" 整型 (整型的值超过了平台的 LONG_MAX 限制) 是可能的,然而没有进行适当的范围检测——当接收字段太小而接收不到值时,最重要的位被静默地截断 (实际上,C 语言会在语义继承的基础上强制类型转换——期望的值可能会发生变化)。

格式化字符串中还有一些其他的字符具有特殊的涵义。这些可能并不嵌套在圆括号中。它们是:

- Ⅰ 表明在 Python 参数列表中剩下的参数都是可选的。C 变量对应的可选参数需要初始化为默认值——当 一个可选参数没有指定时,PyArg_ParseTuple() 不能访问相应的 C 变量(变量集)的内容。
- \$ PyArg_ParseTupleAndKeywords() only: 表明在 Python 参数列表中剩下的参数都是强制关键字 参数。当前,所有强制关键字参数都必须也是可选参数,所以格式化字符串中 | 必须一直在 \$ 前面。
 - 3.3 新版功能.
- :格式单元的列表结束标志;冒号后的字符串被用来作为错误消息中的函数名(PyArg_ParseTuple() 函数引发的"关联值"异常)。
- ;格式单元的列表结束标志;分号后的字符串被用来作为错误消息取代默认的错误消息。:和;相互排 斥。

注意任何由调用者提供的 Python 对象引用是 借来的引用;不要递减它们的引用计数!

传递给这些函数的附加参数必须是由格式化字符串确定的变量的地址;这些都是用来存储输入元组的值。 有一些情况,如上面的格式单元列表中所描述的,这些参数作为输入值使用;在这种情况下,它们应该 匹配指定的相应的格式单元。

为了转换成功,arg 对象必须匹配格式并且格式必须用尽。成功的话, $PyArg_Parse*()$ 函数返回 true,反之它们返回 false 并且引发一个合适的异常。当 $PyArg_Parse*()$ 函数因为某一个格式单元转化失败而失败时,对应的以及后续的格式单元地址内的变量都不会被使用。

API 函数

int PyArg_ParseTuple (PyObject *args, const char *format, ...)

解析一个函数的参数,表达式中的参数按参数位置顺序存入局部变量中。成功返回 true;失败返回 false 并且引发相应的异常。

int PyArg_VaParse (PyObject *args, const char *format, va_list vargs)

和PyArg_ParseTuple() 相同,然而它接受一个 va_list 类型的参数而不是可变数量的参数集。

int PyArg_ParseTupleAndKeywords (*PyObject *args*, *PyObject *kw*, const char *format, char *keywords[], ...)

分析将位置参数和关键字参数同时转换为局部变量的函数的参数。keywords 参数是关键字参数名称的 NULL 终止数组。空名称表示positional-only parameters。成功时返回 true; 发生故障时,它将返回 false 并引发相应的异常。

在 3.6 版更改: 添加了positional-only parameters 的支持。

int PyArg_VaParseTupleAndKeywords (*PyObject *args*, *PyObject *kw*, const char *format, char *keywords[], va_list vargs)

和PyArg_ParseTupleAndKeywords()相同,然而它接受一个va_list 类型的参数而不是可变数量的参数集。

int PyArg_ValidateKeywordArguments (PyObject *)

确保字典中的关键字参数都是字符串。这个函数只被使用于 $PyArg_ParseTupleAndKeywords()$ 不被使用的情况下,后者已经不再做这样的检查。

3.2 新版功能.

int PyArg_Parse (PyObject *args, const char *format, ...)

函数被用来析构"旧类型"函数的参数列表——这些函数使用的 METH_OLDARGS 参数解析方法已从 Python 3 中移除。这不被推荐用于新代码的参数解析,并且在标准解释器中的大多数代码已被修改,已不再用于该目的。它仍然方便于分解其他元组,然而可能因为这个目的被继续使用。

int PyArg_UnpackTuple (PyObject *args, const char *name, Py_ssize_t min, Py_ssize_t max, ...)

一个不使用格式化字符串指定参数类型的简单形式的参数检索。使用这种方法来检索参数的函数应该在函数或者方法表中声明METH_VARARGS。包含实际参数的元组应该以 args 形式被传入;它必须是一个实际的元组。元组的长度必须至少是 min 并且不超过 max; min 和 max 可能相同。额外的参数必须传递给函数,每一个参数必须是一个指向PyObject*类型变量的指针;它们将被赋值

为 args 的值;它们将包含借来的引用。不在 args 里面的可选参数不会被赋值;由调用者完成初始化。函数成功则返回 true 并且如果 args 不是元组或者包含错误数量的元素则返回 false;如果失败了会引发一个异常。

这是一个使用此函数的示例,取自_weakref帮助模块用来弱化引用的源代码:

```
static PyObject *
weakref_ref(PyObject *self, PyObject *args)
{
    PyObject *object;
    PyObject *callback = NULL;
    PyObject *result = NULL;

    if (PyArg_UnpackTuple(args, "ref", 1, 2, &object, &callback)) {
        result = PyWeakref_NewRef(object, callback);
    }
    return result;
}
```

这个例子中调用PyArg_UnpackTuple() 完全等价于调用PyArg_ParseTuple():

```
PyArg_ParseTuple(args, "0|0:ref", &object, &callback)
```

6.6.2 创建变量

*PyObject** **Py_BuildValue** (const char *format, ...)

Return value: New reference. 基于类似于PyArg_Parse*() 函数系列和一系列值的格式字符串创建新值。在出现错误时返回值或 NULL; 如果返回 NULL, 将引发异常。

 $Py_BuildValue()$ 并不一直创建一个元组。只有当它的格式化字符串包含两个或更多的格式单元才会创建一个元组。如果格式化字符串是空,它返回 None;如果它包含一个格式单元,它返回由格式单元描述的的任一对象。用圆括号包裹格式化字符串可以强制它返回一个大小为0或者1的元组。

当内存缓存区的数据以参数形式传递用来构建对象时,如 s 和 s# 格式单元,会拷贝需要的数据。调用者提供的缓冲区从来都不会被由 $Py_BuildValue()$ 创建的对象来引用。换句话说,如果你的代码调用 malloc() 并且将分配的内存空间传递给 $Py_BuildValue()$,你的代码就有责任在 $Py_BuildValue()$ 返回时调用 free()。

在下面的描述中,双引号的表达式使格式单元;圆括号()内的是格式单元将要返回的 Python 对象类型;方括号[]内的是传递的 C 变量(变量集)的类型。

字符例如空格,制表符,冒号和逗号在格式化字符串中会被忽略(但是不包括格式单元,如 s#)。这可以使很长的格式化字符串具有更好的可读性。

- **s**(**str或 None**)[**const char ***] 使用 'utf-8' 编码将空终止的 C 字符串转换为 Python str 对象。 如果 C 字符串指针为 NULL,则使用 None。
- **s# (str 或 None) [const char *, int 或 Py_ssize_t]** 使用 'utf-8' 编码将 C 字符串及其长度转换为 **Python** str 对象。如果 C 字符串指针为 NULL,则长度将被忽略,并返回 None。
- y (bytes) [const char *] 这将 C 字符串转换为 Python bytes 对象。如果 C 字符串指针为 NULL,则返回 None。
- y# (bytes) [const char *, int 或 Py_ssize_t] 这会将 C 字符串及其长度转换为一个 Python 对象。如果该 C 字符串指针为 NULL,则返回 None。
- z (str or None) [const char *] 和 s 一样。
- z# (str或None) [const char*, int或Py_ssize_t]和 s#一样。
- u (str) [const wchar_t *] 将空终止的 wchar_t 的 Unicode (UTF-16 或 UCS-4) 数据缓冲区转换为 Python Unicode 对象。如果 Unicode 缓冲区指针为 NULL,则返回 None。

- u# (str) [const wchar_t *, int 或 Py_ssize_t] 将 Unicode (UTF-16 或 UCS-4) 数据缓冲区及其 长度转换为 Python Unicode 对象。如果 Unicode 缓冲区指针为 NULL,则长度将被忽略,并返 回 None。
- U(str或None)[const char*]和s一样。
- U# (str或None) [const char*, int或Py_ssize_t]和s#一样。
- i(int)[int] 将一个Cint 整型转化成 Python 整型对象。
- b(int)[char] 将一个 C char 字符型转化成 Python 整型对象。
- h (int) [short int] 将一个 C short int 短整型转化成 Python 整型对象。
- 1(int)[long int] 将一个 Clong int 长整型转化成 Python 整型对象。
- B(int)[unsigned char] 将一个Cunsigned char 无符号字符型转化成 Python 整型对象。
- H(int)[unsigned short int] 将一个Cunsigned long 无符号短整型转化成 Python 整型对象。
- I (int) [unsigned int] 将一个 C unsigned long 无符号整型转化成 Python 整型对象。
- k (int) [unsigned long] 将一个 C unsigned long 无符号长整型转化成 Python 整型对象。
- L(int)[long long] 将一个Clong long长长整形转化成 Python 整形对象。
- K (int) [unsigned long long] 将一个 C unsigned long long 无符号长长整型转化成 Python 整型对象。
- n(int)[Py_ssize_t] 将一个CPy_ssize_t 类型转化为Python整型。
- c (bytes 长度为 1) [char] 将一个 C int 整型代表的字符转化为 Python bytes 长度为 1 的字节对象。
- C(str长度为1)[int]将一个Cint整型代表的字符转化为Python str长度为1的字符串对象。
- **d**(**float**)[**double**] 将一个 C double 双精度浮点数转化为 Python 浮点数类型数字。
- f(float)[float] 将一个 C float 单精度浮点数转化为 Python 浮点数类型数字。
- D (complex) [Py_complex *] 将一个 C Py_complex 类型的结构转化为 Python 复数类型。
- O (object) [PyObject *] 将 Python 对象传递不变(其引用计数除外,该计数由 1 递增)。如果传入的对象是 NULL 指针,则假定这是由于生成参数的调用发现错误并设置异常而引起的。因此,Py_BuildValue() 将返回 NULL,但不会引发异常。如果尚未引发异常,则设置 SystemError。
- S (object) [PyObject*] 和 0 相同。
- N (object) [PyObject *] 和○相同,然而它并不增加对象的引用计数。当通过调用参数列表中的对象构造器创建对象时很实用。
- O& (object) [converter, anything] 通过 converter 函数将 anything 转换为 Python 对象。该函数以 anything (应与 void * 兼容) 作为其参数,应返回"new" Python 对象,如果发生错误,则应返回 NULL。
- (items) (tuple) [matching-items] 将一个 C 变量序列转换成 Python 元组并保持相同的元素数量。
- [items] (list)[相关的元素] 将一个 C 变量序列转换成 Python 列表并保持相同的元素数量。
- {items} (dict) [相关的元素] 将一个 C 变量序列转换成 Python 字典。每一对连续的 C 变量对作为一个元素插入字典中,分别作为关键字和值。
- 如果格式字符串中出现错误,则设置 SystemError 异常并返回 NULL。
- PyObject* Py_VaBuildValue (const char *format, va_list vargs)
 - Return value: New reference. 和Py_BuildValue()相同,然而它接受一个 va_list 类型的参数而不是可变数量的参数集。

6.7 字符串转换与格式化

用于数字转换和格式化字符串输出的函数

int PyOS_snprintf (char *str, size_t size, const char *format, ...)

根据格式字符串 format 和额外参数, 输出不超过 size 字节到 str。请参见 Unix 手册页 snprintf(2)

int **PyOS vsnprintf** (char *str, size t size, const char *format, va list va)

根据格式字符串 format 和变量参数列表 va ,不能输出超过 size 字节到 str 。请参见 Unix 手册页 vsnprintf(2)。

PyOS_snprintf() 和*PyOS_vsnprintf()* 包装 C 标准库函数 snprintf() 和 vsnprintf()。它们的目的是保证在极端情况下的一致行为,而标准 C 的函数则不然。

包装器确保 $str^*[*size-1]$ 在返回时始终是 '\0'。它们从不写入超过 size 字节(包括结尾的 '\0')到字符串。两函数都需要满足 str != NULL, size > 0 和 format != NULL。

如果平台没有 vsnprintf() 而且缓冲区大小需要避免截断超出 size 512 字节以上, Python 会以一个Py_FatalError()来中止。

这些函数的返回值(rv)应按照以下规则被解释:

- 当 0 <= rv < size, 输出转换成功而且 rv 个字符被写入 str (不包含末尾 str*[*rv]的 '\0'字 节)
- 当 rv >= size ,输出转换被截断并且成功需要一个带有 rv + 1 字节的缓冲区。在这种情况下, str*[*size-1] 的值是 '\0'。
- 当 rv < 0 ,会发生一些不好的事情。在这种情况下,str*[*size-1] 的值也是 '\0' ,但是 str 的其 余部分未被定义。错误的确切原因取决于底层平台。

以下函数提供与语言环境无关的字符串到数字转换。

double PyOS_string_to_double (const char *s, char **endptr, PyObject *overflow_exception)

将字符串 s 转换为 double 类型,失败时引发 Python 异常。接受的字符串的集合对应于被 Python 的 float () 构造函数接受的字符串的集合,除了 s 必须没有前导或尾随空格。转换必须独立于当前的区域。

如果 endptr 是 NULL,转换整个字符串。引发 ValueError 并且返回 -1.0 如果字符串不是浮点数的有效的表达方式。

如果 endptr 不是 NULL,尽可能多的转换字符串并将 *endptr 设置为指向第一个未转换的字符。如果字符串的初始段不是浮点数的有效的表达方式,将 *endptr 设置为指向字符串的开头,引发 ValueError 异常,并且返回 -1.0。

如果 s 表示一个太大而不能存储在一个浮点数中的值(比方说,"1e500" 在许多平台上是一个字符串)然后如果 overflow_exception 是 NULL 返回 Py_HUGE_VAL (用适当的符号)并且不设置任何异常。在其他方面,overflow_exception 必须指向一个 Python 异常对象;引发异常并返回 -1.0。在这两种情况下,设置 *endptr 指向转换值之后的第一个字符。

如果在转换期间发生任何其他错误(比如一个内存不足的错误),设置适当的 Python 异常并且返回 -1.0。

3.1 新版功能.

char* **PyOS_double_to_string** (double *val*, char *format_code*, int *precision*, int *flags*, int **ptype*) 转换 double *val* 为一个使用 *format_code*, *precision* 和 *flags* 的字符串

格式码必须是以下其中之一, 'e', 'E', 'f', 'F', 'g', 'G' 或者 'r'。对于 'r', 提供的 精度必须是 0。'r' 格式码指定了标准函数 repr() 格式。

flags 可以为零或者其他值 Py_DTSF_SIGN, Py_DTSF_ADD_DOT_0 或 Py_DTSF_ALT 或其组合:

- Py_DTSF_SIGN 表示总是在返回的字符串前附加一个符号字符,即使 val 为非负数。
- Py_DTSF_ADD_DOT_0 表示确保返回的字符串看起来不像是一个整数。

• Py_DTSF_ALT 表示应用"替代的"格式化规则。相关细节请参阅PyOS_snprintf() '#'定义文档。

如果 ptype 不为 NULL,则它指向的值将被设为 Py_DTST_FINITE, Py_DTST_INFINITE 或 Py_DTST_NAN 中的一个,分别表示 val 是一个有限数字、无限数字或非数字。

返回值是一个指向包含转换后字符串的 buffer 的指针,如果转换失败则为 NULL。调用方要负责调用 $PyMem_Free()$ 来释放返回的字符串。

3.1 新版功能.

int **PyOS_stricmp** (const char *s1, const char *s2)

字符串不区分大小写。该函数几乎与 strcmp() 的工作方式相同,只是它忽略了大小写。

int PyOS strnicmp (const char *s1, const char *s2, Py ssize t size)

字符串不区分大小写。该函数几乎与 strncmp () 的工作方式相同,只是它忽略了大小写。

6.8 反射

PyObject* PyEval GetBuiltins()

Return value: Borrowed reference. 返回当前执行帧中内置函数的字典,如果当前没有帧正在执行,则返回线程状态的解释器。

PyObject* PyEval_GetLocals()

Return value: Borrowed reference. 返回当前执行帧中局部变量的字典,如果没有当前执行的帧则返回 NULL。

PyObject* PyEval_GetGlobals()

Return value: Borrowed reference. 返回当前执行帧中全局变量的字典,如果没有当前执行的帧则返回 NULL。

PyFrameObject* PyEval_GetFrame()

Return value: Borrowed reference. 返回当前线程状态的帧,如果没有当前执行的帧则返回 NULL。

int PyFrame_GetLineNumber (PyFrameObject *frame)

返回 frame 当前正在执行的行号。

const char* PyEval_GetFuncName (PyObject *func)

如果 func 是函数、类或实例对象,则返回它的名称,否则返回 func 的类型的名称。

const char* PyEval_GetFuncDesc (PyObject *func)

根据 func 的类型返回描述字符串。返回值包括函数和方法的"()"," constructor"," instance" 和" object"。与PyEval_GetFuncName()的结果连接,结果将是 func 的描述。

6.9 编解码器注册与支持功能

int PyCodec_Register (PyObject *search_function)

注册一个新的编解码器搜索函数。

作为副作用,其尝试加载 encodings 包,如果尚未完成,请确保它始终位于搜索函数列表的第一位。

int PyCodec KnownEncoding (const char *encoding)

根据注册的给定 encoding 的编解码器是否已存在而返回 1 或 0。此函数总能成功。

PyObject* PyCodec_Encode (PyObject *object, const char *encoding, const char *errors)

Return value: New reference. 泛型编解码器基本编码 API。

object is passed through the encoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

PyObject* PyCodec_Decode (PyObject *object, const char *encoding, const char *errors)
Return value: New reference. 泛型编解码器基本解码 API。

object is passed through the decoder function found for the given *encoding* using the error handling method defined by *errors*. *errors* may be NULL to use the default method defined for the codec. Raises a LookupError if no encoder can be found.

6.9.1 Codec 查找 API

In the following functions, the *encoding* string is looked up converted to all lower-case characters, which makes encodings looked up through this mechanism effectively case-insensitive. If no codec is found, a KeyError is set and NULL returned.

PyObject* PyCodec_Encoder (const char *encoding)

Return value: New reference. Get an encoder function for the given encoding.

PyObject* PyCodec_Decoder (const char *encoding)

Return value: New reference. Get a decoder function for the given encoding.

- PyObject* PyCodec_IncrementalEncoder (const char *encoding, const char *errors)

 Return value: New reference. Get an IncrementalEncoder object for the given encoding.
- PyObject* PyCodec_IncrementalDecoder (const char *encoding, const char *errors)

 Return value: New reference. Get an IncrementalDecoder object for the given encoding.
- PyObject* PyCodec_StreamReader (const char *encoding, PyObject *stream, const char *errors)

 Return value: New reference. Get a StreamReader factory function for the given encoding.
- PyObject* PyCodec_StreamWriter (const char *encoding, PyObject *stream, const char *errors)

 Return value: New reference. 为给定的 encoding 获取一个 StreamWriter 工厂函数。

6.9.2 用于 Unicode 编码错误处理程序的注册表 API

int PyCodec_RegisterError (const char *name, PyObject *error)

Register the error handling callback function *error* under the given *name*. This callback function will be called by a codec when it encounters unencodable characters/undecodable bytes and *name* is specified as the error parameter in the call to the encode/decode function.

The callback gets a single argument, an instance of UnicodeEncodeError, UnicodeDecodeError or UnicodeTranslateError that holds information about the problematic sequence of characters or bytes and their offset in the original string (see *Unicode Exception Objects* for functions to extract this information). The callback must either raise the given exception, or return a two-item tuple containing the replacement for the problematic sequence, and an integer giving the offset in the original string at which encoding/decoding should be resumed.

成功则返回"0",失败则返回"-1"

PyObject* PyCodec_LookupError (const char *name)

Return value: New reference. Lookup the error handling callback function registered under *name.* As a special case NULL can be passed, in which case the error handling callback for "strict" will be returned.

PyObject* PyCodec_StrictErrors (PyObject *exc)

Return value: Always NULL. Raise exc as an exception.

PyObject* PyCodec_IgnoreErrors (PyObject *exc)

Return value: New reference. Ignore the unicode error, skipping the faulty input.

PyObject* PyCodec_ReplaceErrors (PyObject *exc)

Return value: New reference. Replace the unicode encode error with ? or U+FFFD.

PyObject* PyCodec_XMLCharRefReplaceErrors (PyObject *exc)

Return value: New reference. Replace the unicode encode error with XML character references.

```
PyObject* PyCodec_BackslashReplaceErrors (PyObject *exc)
```

Return value: New reference. Replace the unicode encode error with backslash escapes (\x, \u and \U).

PyObject* PyCodec_NameReplaceErrors (PyObject *exc)

Return value: New reference. Replace the unicode encode error with \N{...} escapes.

3.5 新版功能.

抽象对象层

本章中的函数与 Python 对象交互,无论其类型,或具有广泛类的对象类型(例如,所有数值类型,或所有序列类型)。当使用对象类型并不适用时,他们会产生一个 Python 异常。

这些函数是不可能用于未正确初始化的对象的,如一个列表对象被 $PyList_New()$ 创建,但其中的项目没有被设置为一些非 "NULL"的值。

7.1 对象协议

PyObject* Py_NotImplemented

The NotImplemented singleton, used to signal that an operation is not implemented for the given type combination.

Py RETURN NOTIMPLEMENTED

Properly handle returning $Py_NotImplemented$ from within a C function (that is, increment the reference count of NotImplemented and return it).

int PyObject Print (PyObject *o, FILE *fp, int flags)

Print an object o, on file fp. Returns -1 on error. The flags argument is used to enable certain printing options. The only option currently supported is Py_PRINT_RAW; if given, the str() of the object is written instead of the repr().

int PyObject_HasAttr(PyObject *o, PyObject *attr_name)

Returns 1 if o has the attribute $attr_name$, and 0 otherwise. This is equivalent to the Python expression hasattr(o, attr_name). This function always succeeds.

Note that exceptions which occur while calling __getattr__() and __getattribute__() methods will get suppressed. To get error reporting use PyObject_GetAttr() instead.

int PyObject_HasAttrString (PyObject *o, const char *attr_name)

Returns 1 if o has the attribute $attr_name$, and 0 otherwise. This is equivalent to the Python expression hasattr(o, attr_name). This function always succeeds.

Note that exceptions which occur while calling $__getattr__()$ and $__getattribute__()$ methods and creating a temporary string object will get suppressed. To get error reporting use $PyObject_GetAttrString()$ instead.

PyObject* PyObject_GetAttr (PyObject *o, PyObject *attr_name)

Return value: New reference. Retrieve an attribute named *attr_name* from object *o*. Returns the attribute value on success, or NULL on failure. This is the equivalent of the Python expression o .attr_name.

PyObject* PyObject_GetAttrString (PyObject *o, const char *attr_name)

Return value: New reference. Retrieve an attribute named *attr_name* from object *o*. Returns the attribute value on success, or NULL on failure. This is the equivalent of the Python expression o .attr_name.

PyObject* PyObject GenericGetAttr (PyObject *o, PyObject *name)

Return value: New reference. Generic attribute getter function that is meant to be put into a type object's tp_getattro slot. It looks for a descriptor in the dictionary of classes in the object's MRO as well as an attribute in the object's __dict__ (if present). As outlined in descriptors, data descriptors take preference over instance attributes, while non-data descriptors don't. Otherwise, an AttributeError is raised.

int PyObject_SetAttr (PyObject *o, PyObject *attr_name, PyObject *v)

Set the value of the attribute named $attr_name$, for object o, to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o .attr_name = v.

If v is NULL, the attribute is deleted, however this feature is deprecated in favour of using $PyObject_DelAttr()$.

int PyObject_SetAttrString (PyObject *o, const char *attr_name, PyObject *v)

Set the value of the attribute named $attr_name$, for object o, to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o .attr_name = v.

If v is NULL, the attribute is deleted, however this feature is deprecated in favour of using $PyObject_DelAttrString()$.

int PyObject_GenericSetAttr(PyObject *o, PyObject *name, PyObject *value)

Generic attribute setter and deleter function that is meant to be put into a type object's $tp_setattro$ slot. It looks for a data descriptor in the dictionary of classes in the object's MRO, and if found it takes preference over setting or deleting the attribute in the instance dictionary. Otherwise, the attribute is set or deleted in the object's $__dict_$ (if present). On success, 0 is returned, otherwise an AttributeError is raised and -1 is returned.

int PyObject_DelAttr (PyObject *o, PyObject *attr_name)

Delete attribute named $attr_name$, for object o. Returns -1 on failure. This is the equivalent of the Python statement del o.attr_name.

int PyObject_DelAttrString (PyObject *o, const char *attr_name)

Delete attribute named $attr_name$, for object o. Returns -1 on failure. This is the equivalent of the Python statement del o.attr_name.

PyObject* PyObject_GenericGetDict (PyObject *o, void *context)

Return value: New reference. A generic implementation for the getter of a __dict__ descriptor. It creates the dictionary if necessary.

3.3 新版功能.

int PyObject_GenericSetDict (PyObject *o, void *context)

A generic implementation for the setter of a ___dict__ descriptor. This implementation does not allow the dictionary to be deleted.

3.3 新版功能.

PyObject* PyObject_RichCompare (PyObject *o1, PyObject *o2, int opid)

Return value: New reference. Compare the values of o1 and o2 using the operation specified by opid, which must be one of Py_LT, Py_LE, Py_EQ, Py_NE, Py_GT, or Py_GE, corresponding to <, <=, ==, !=, >, or >= respectively. This is the equivalent of the Python expression o1 op o2, where op is the operator corresponding to opid. Returns the value of the comparison on success, or NULL on failure.

int PyObject_RichCompareBool (PyObject *o1, PyObject *o2, int opid)

Compare the values of o1 and o2 using the operation specified by opid, which must be one of Py_LT, Py_LE, Py_EQ, Py_NE, Py_GT, or Py_GE, corresponding to <, <=, ==, !=, >, or >= respectively. Returns -1 on error, 0 if the result is false, 1 otherwise. This is the equivalent of the Python expression o1 op o2, where op is the operator corresponding to opid.

注解: If ol and o2 are the same object, PyObject_RichCompareBool() will always return 1 for Py_EQ and 0 for Py_NE.

PyObject* PyObject_Repr (PyObject *o)

Return value: New reference. Compute a string representation of object o. Returns the string representation on success, NULL on failure. This is the equivalent of the Python expression repr(o). Called by the repr() built-in function.

在 3.4 版更改: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

PyObject* PyObject ASCII (PyObject *o)

Return value: New reference. As $PyObject_Repr()$, compute a string representation of object o, but escape the non-ASCII characters in the string returned by $PyObject_Repr()$ with \x , \u or \u escapes. This generates a string similar to that returned by $PyObject_Repr()$ in Python 2. Called by the ascii() built-in function.

PyObject* PyObject_Str (PyObject *o)

Return value: New reference. Compute a string representation of object o. Returns the string representation on success, NULL on failure. This is the equivalent of the Python expression str(o). Called by the str() built-in function and, therefore, by the print() function.

在 3.4 版更改: This function now includes a debug assertion to help ensure that it does not silently discard an active exception.

PyObject* PyObject_Bytes (PyObject *o)

Return value: New reference. Compute a bytes representation of object o. NULL is returned on failure and a bytes object on success. This is equivalent to the Python expression bytes (o), when o is not an integer. Unlike bytes (o), a TypeError is raised when o is an integer instead of a zero-initialized bytes object.

int PyObject_IsSubclass (PyObject *derived, PyObject *cls)

Return 1 if the class *derived* is identical to or derived from the class cls, otherwise return 0. In case of an error, return -1.

If *cls* is a tuple, the check will be done against every entry in *cls*. The result will be 1 when at least one of the checks returns 1, otherwise it will be 0.

If *cls* has a __subclasscheck__() method, it will be called to determine the subclass status as described in **PEP 3119**. Otherwise, *derived* is a subclass of *cls* if it is a direct or indirect subclass, i.e. contained in cls.__mro__.

Normally only class objects, i.e. instances of type or a derived class, are considered classes. However, objects can override this by having a __bases__ attribute (which must be a tuple of base classes).

int PyObject_IsInstance (PyObject *inst, PyObject *cls)

Return 1 if *inst* is an instance of the class *cls* or a subclass of *cls*, or 0 if not. On error, returns -1 and sets an exception.

If cls is a tuple, the check will be done against every entry in cls. The result will be 1 when at least one of the checks returns 1, otherwise it will be 0.

If *cls* has a __instancecheck__() method, it will be called to determine the subclass status as described in PEP 3119. Otherwise, *inst* is an instance of *cls* if its class is a subclass of *cls*.

An instance *inst* can override what is considered its class by having a ___class__ attribute.

An object *cls* can override if it is considered a class, and what its base classes are, by having a ___bases__ attribute (which must be a tuple of base classes).

int PyCallable_Check (PyObject *o)

Determine if the object o is callable. Return 1 if the object is callable and 0 otherwise. This function always succeeds.

7.1. 对象协议 57

PyObject* PyObject_Call (PyObject *callable, PyObject *args, PyObject *kwargs)

Return value: New reference. Call a callable Python object *callable*, with arguments given by the tuple *args*, and named arguments given by the dictionary *kwargs*.

args must not be NULL, use an empty tuple if no arguments are needed. If no named arguments are needed, kwargs can be NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (*args, **kwargs).

PyObject* PyObject_CallObject (PyObject *callable, PyObject *args)

Return value: New reference. Call a callable Python object *callable*, with arguments given by the tuple *args*. If no arguments are needed, then *args* can be NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (*args).

PyObject* PyObject_CallFunction (PyObject *callable, const char *format, ...)

Return value: New reference. Call a callable Python object callable, with a variable number of C arguments. The C arguments are described using a Py_BuildValue() style format string. The format can be NULL, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (*args).

Note that if you only pass PyObject * args, PyObject_CallFunctionObjArgs() is a faster alternative.

在 3.4 版更改: The type of format was changed from char *.

PyObject * PyObject CallMethod (PyObject *obj, const char *name, const char *format, ...)

Return value: New reference. Call the method named *name* of object *obj* with a variable number of C arguments. The C arguments are described by a *Py_BuildValue()* format string that should produce a tuple.

The format can be NULL, indicating that no arguments are provided.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: obj.name(arg1, arg2, ...).

Note that if you only pass PyObject * args, $PyObject_CallMethodObjArgs()$ is a faster alternative.

在 3.4 版更改: The types of name and format were changed from char *.

PyObject* PyObject_CallFunctionObjArgs (PyObject *callable, ..., NULL)

Return value: New reference. Call a callable Python object *callable*, with a variable number of *PyObject** arguments. The arguments are provided as a variable number of parameters followed by NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

This is the equivalent of the Python expression: callable (arg1, arg2, ...).

PyObject * PyObject CallMethodObjArgs (PyObject *obj, PyObject *name, ..., NULL)

Return value: New reference. Calls a method of the Python object obj, where the name of the method is given as a Python string object in name. It is called with a variable number of PyObject* arguments. The arguments are provided as a variable number of parameters followed by NULL.

Return the result of the call on success, or raise an exception and return NULL on failure.

```
PyObject* _PyObject_Vectorcall (PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kwnames)
```

Call a callable Python object callable, using vectorcall if possible.

args is a C array with the positional arguments.

nargsf is the number of positional arguments plus optionally the flag PY_VECTORCALL_ARGUMENTS_OFFSET (see below). To get actual number of arguments, use PyVectorcall_NARGS(nargsf).

kwnames can be either NULL (no keyword arguments) or a tuple of keyword names. In the latter case, the values of the keyword arguments are stored in args after the positional arguments. The number of keyword arguments does not influence nargsf.

kwnames must contain only objects of type str (not a subclass), and all keys must be unique.

Return the result of the call on success, or raise an exception and return NULL on failure.

This uses the vectorcall protocol if the callable supports it; otherwise, the arguments are converted to use tp_call .

注解: This function is provisional and expected to become public in Python 3.9, with a different name and, possibly, changed semantics. If you use the function, plan for updating your code for Python 3.9.

3.8 新版功能.

PY_VECTORCALL_ARGUMENTS_OFFSET

If set in a vectorcall nargsf argument, the callee is allowed to temporarily change args[-1]. In other words, args points to argument 1 (not 0) in the allocated vector. The callee must restore the value of args[-1] before returning.

Whenever they can do so cheaply (without additional allocation), callers are encouraged to use PY_VECTORCALL_ARGUMENTS_OFFSET. Doing so will allow callables such as bound methods to make their onward calls (which include a prepended *self* argument) cheaply.

3.8 新版功能.

Py_ssize_t PyVectorcall_NARGS (size_t nargsf)

Given a vectorcall *nargsf* argument, return the actual number of arguments. Currently equivalent to nargsf & ~PY_VECTORCALL_ARGUMENTS_OFFSET.

3.8 新版功能.

PyObject* _PyObject_FastCallDict (PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kwdict)

Same as _PyObject_Vectorcali() except that the keyword arguments are passed as a dictionary in *kwdict*. This may be NULL if there are no keyword arguments.

For callables supporting <code>vectorcall</code>, the arguments are internally converted to the vectorcall convention. Therefore, this function adds some overhead compared to <code>_PyObject_Vectorcall()</code>. It should only be used if the caller already has a dictionary ready to use.

注解: This function is provisional and expected to become public in Python 3.9, with a different name and, possibly, changed semantics. If you use the function, plan for updating your code for Python 3.9.

3.8 新版功能.

Py_hash_t PyObject_Hash (PyObject *o)

Compute and return the hash value of an object o. On failure, return -1. This is the equivalent of the Python expression hash (o).

在 3.2 版更改: The return type is now Py_hash_t. This is a signed integer the same size as Py_ssize_t.

Py hash t PyObject HashNotImplemented (PyObject *o)

Set a TypeError indicating that type (o) is not hashable and return -1. This function receives special treatment when stored in a tp_hash slot, allowing a type to explicitly indicate to the interpreter that it is not hashable.

7.1. 对象协议 59

int PyObject_IsTrue (PyObject *o)

Returns 1 if the object o is considered to be true, and 0 otherwise. This is equivalent to the Python expression not not o. On failure, return -1.

int PyObject Not (PyObject *o)

Returns 0 if the object o is considered to be true, and 1 otherwise. This is equivalent to the Python expression not o. On failure, return -1.

PyObject* PyObject_Type (PyObject *o)

Return value: New reference. When o is non-NULL, returns a type object corresponding to the object type of object o. On failure, raises SystemError and returns NULL. This is equivalent to the Python expression type (o). This function increments the reference count of the return value. There's really no reason to use this function instead of the common expression $o->ob_type$, which returns a pointer of type PyTypeObject*, except when the incremented reference count is needed.

int PyObject_TypeCheck (PyObject *o, PyTypeObject *type)

Return true if the object o is of type type or a subtype of type. Both parameters must be non-NULL.

Py_ssize_t PyObject_Size (PyObject *o)

Py_ssize_t PyObject_Length (PyObject *o)

Return the length of object o. If the object o provides either the sequence and mapping protocols, the sequence length is returned. On error, -1 is returned. This is the equivalent to the Python expression len(o).

Py_ssize_t PyObject_LengthHint (PyObject *o, Py_ssize_t default)

Return an estimated length for the object o. First try to return its actual length, then an estimate using __length_hint__(), and finally return the default value. On error return -1. This is the equivalent to the Python expression operator.length_hint(o, default).

3.4 新版功能.

PyObject* PyObject GetItem (PyObject *o, PyObject *key)

Return value: New reference. Return element of o corresponding to the object key or NULL on failure. This is the equivalent of the Python expression o[key].

int PyObject_SetItem (PyObject *o, PyObject *key, PyObject *v)

Map the object key to the value v. Raise an exception and return -1 on failure; return 0 on success. This is the equivalent of the Python statement o[key] = v. This function does not steal a reference to v.

int PyObject_DelItem (PyObject *o, PyObject *key)

Remove the mapping for the object *key* from the object o. Return -1 on failure. This is equivalent to the Python statement del o[key].

PyObject* PyObject_Dir (PyObject *o)

Return value: New reference. This is equivalent to the Python expression dir(0), returning a (possibly empty) list of strings appropriate for the object argument, or <code>NULL</code> if there was an error. If the argument is <code>NULL</code>, this is like the Python dir(), returning the names of the current locals; in this case, if no execution frame is active then <code>NULL</code> is returned but $PyErr_Occurred()$ will return false.

PyObject* PyObject GetIter (PyObject *o)

Return value: New reference. This is equivalent to the Python expression iter(0). It returns a new iterator for the object argument, or the object itself if the object is already an iterator. Raises TypeError and returns NULL if the object cannot be iterated.

7.2 数字协议

int PyNumber_Check (PyObject *o)

如果对象 o 提供数字的协议, 返回真 1, 否则返回假。这个函数不会调用失败。

在 3.8 版更改: 如果 o 是一个索引整数则返回 1。

PyObject* PyNumber_Add (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of adding o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 + o2.

PyObject* PyNumber_Subtract (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of subtracting o2 from o1, or NULL on failure. This is the equivalent of the Python expression o1 - o2.

PyObject* PyNumber_Multiply (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of multiplying o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 * o2.

PyObject* PyNumber_MatrixMultiply (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. This is the equivalent of the Python expression o1 @ o2.

3.5 新版功能.

PyObject* PyNumber_FloorDivide (PyObject *o1, PyObject *o2)

Return value: New reference. Return the floor of *o1* divided by *o2*, or NULL on failure. This is equivalent to the "classic" division of integers.

PyObject* PyNumber_TrueDivide (PyObject *o1, PyObject *o2)

Return value: New reference. Return a reasonable approximation for the mathematical value of o1 divided by o2, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers.

PyObject* PyNumber_Remainder (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the remainder of dividing o1 by o2, or NULL on failure. This is the equivalent of the Python expression o1 % o2.

PyObject* PyNumber_Divmod (PyObject *o1, PyObject *o2)

Return value: New reference. See the built-in function divmod(). Returns NULL on failure. This is the equivalent of the Python expression divmod(o1, o2).

PyObject* PyNumber_Power (PyObject *o1, PyObject *o2, PyObject *o3)

Return value: New reference. See the built-in function pow(). Returns NULL on failure. This is the equivalent of the Python expression pow(o1, o2, o3), where o3 is optional. If o3 is to be ignored, pass Py_None in its place (passing NULL for o3 would cause an illegal memory access).

PyObject* PyNumber Negative (PyObject *o)

Return value: New reference. Returns the negation of o on success, or NULL on failure. This is the equivalent of the Python expression $-\circ$.

PyObject* PyNumber_Positive (PyObject *o)

Return value: New reference. Returns o on success, or NULL on failure. This is the equivalent of the Python expression $+ \circ$.

PyObject* PyNumber_Absolute (PyObject *o)

Return value: New reference. Returns the absolute value of o, or NULL on failure. This is the equivalent of the Python expression abs (o).

PyObject* PyNumber_Invert (PyObject *o)

Return value: New reference. Returns the bitwise negation of o on success, or NULL on failure. This is the equivalent of the Python expression $\sim \circ$.

7.2. 数字协议 61

PyObject* PyNumber_Lshift (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of left shifting o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 << o2.

PyObject* PyNumber_Rshift (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of right shifting o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 >> o2.

PyObject* PyNumber_And (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the "bitwise and" of o1 and o2 on success and NULL on failure. This is the equivalent of the Python expression o1 & o2.

PyObject* PyNumber_Xor (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the "bitwise exclusive or" of o1 by o2 on success, or NULL on failure. This is the equivalent of the Python expression o1 oo 2.

PyObject* PyNumber_Or (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the "bitwise or" of o1 and o2 on success, or NULL on failure. This is the equivalent of the Python expression $o1 \mid o2$.

PyObject* PyNumber_InPlaceAdd (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of adding o1 and o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 + = o2.

PyObject* PyNumber_InPlaceSubtract (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of subtracting o2 from o1, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 -= o2.

PyObject* PyNumber_InPlaceMultiply (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of multiplying o1 and o2, or NULL on failure. The operation is done in-place when o1 supports it. This is the equivalent of the Python statement o1 *= o2.

PyObject* PyNumber_InPlaceMatrixMultiply (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of matrix multiplication on o1 and o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 @= o2.

3.5 新版功能.

PyObject* PyNumber_InPlaceFloorDivide (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the mathematical floor of dividing o1 by o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 //= o2.

PyObject* PyNumber_InPlaceTrueDivide (PyObject *o1, PyObject *o2)

Return value: New reference. Return a reasonable approximation for the mathematical value of o1 divided by o2, or NULL on failure. The return value is "approximate" because binary floating point numbers are approximate; it is not possible to represent all real numbers in base two. This function can return a floating point value when passed two integers. The operation is done *in-place* when o1 supports it.

PyObject* PyNumber_InPlaceRemainder (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the remainder of dividing o1 by o2, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 % = o2.

PyObject* PyNumber InPlacePower (PyObject *o1, PyObject *o2, PyObject *o3)

Return value: New reference. See the built-in function pow(). Returns NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 **= o2 when o3 is Py_None , or an in-place variant of pow(o1, o2, o3) otherwise. If o3 is to be ignored, pass Py_None in its place (passing NULL for o3 would cause an illegal memory access).

PyObject* PyNumber_InPlaceLshift (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of left shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 <<= o2.

PyObject* PyNumber_InPlaceRshift (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the result of right shifting o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 >>= o2.

PyObject* PyNumber_InPlaceAnd (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the "bitwise and" of o1 and o2 on success and NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 &= o2.

PyObject* PyNumber InPlaceXor (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the "bitwise exclusive or" of o1 by o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement $o1 ^- o2$.

PyObject* PyNumber_InPlaceOr (PyObject *o1, PyObject *o2)

Return value: New reference. Returns the "bitwise or" of o1 and o2 on success, or NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python statement o1 = o2.

PyObject* PyNumber_Long (PyObject *o)

Return value: New reference. Returns the o converted to an integer object on success, or NULL on failure. This is the equivalent of the Python expression int (0).

PyObject* PyNumber_Float (PyObject *o)

Return value: New reference. Returns the o converted to a float object on success, or NULL on failure. This is the equivalent of the Python expression float (o).

PyObject* PyNumber_Index (PyObject *o)

Return value: New reference. Returns the o converted to a Python int on success or NULL with a TypeError exception raised on failure.

PyObject* PyNumber_ToBase (PyObject *n, int base)

Return value: New reference. 返回整数 n 转换成以 base 为基数的字符串后的结果。这个 base 参数必须是 2, 8, 10 或者 16。对于基数 2, 8, 或 16,返回的字符串将分别加上基数标识 '0b', '0o', or '0x'。如果 n 不是 Python 中的整数 int 类型,就先通过 $PyNumber_Index()$ 将它转换成整数类型。

Py_ssize_t PyNumber_AsSsize_t (PyObject *o, PyObject *exc)

如果o是一个整数类型的解释型,返回o转换成一个 Py_size_t 值项后的结果。如果调用失败,返回-1并引发异常。

If o can be converted to a Python int but the attempt to convert to a Py_ssize_t value would raise an OverflowError, then the exc argument is the type of exception that will be raised (usually IndexError or OverflowError). If exc is NULL, then the exception is cleared and the value is clipped to PY_SSIZE_T_MIN for a negative integer or PY_SSIZE_T_MAX for a positive integer.

int PyIndex_Check (PyObject *o)

如果 o 是一个索引整数(存有 nb_index 位置并有 tp_as_number 填入其中)则返回 1,否则返回 0。这个函数不会调用失败。

7.3 序列协议

int PySequence_Check (PyObject *o)

如果对象提供序列协议,函数返回 1,否则返回 0。请注意它将为具有 __getitem__() 方法的 Python 类返回 1,除非它们是 dict 的子类,因为在一般情况下无法确定它所支持键类型。此函数 总是会成功执行。

Py_ssize_t PySequence_Size (PyObject *o)

Py_ssize_t PySequence_Length (PyObject *o)

到哪里积分返回序列 o 中对象的数量,失败时返回 -1。这相当于 Python 表达式 1en(o)。

PyObject* PySequence_Concat (PyObject *o1, PyObject *o2)

Return value: New reference. Return the concatenation of o1 and o2 on success, and NULL on failure. This is the equivalent of the Python expression o1 + o2.

PyObject* PySequence_Repeat (PyObject *o, Py_ssize_t count)

Return value: New reference. Return the result of repeating sequence object *o count* times, or NULL on failure. This is the equivalent of the Python expression o * count.

7.3. 序列协议 63

PyObject* PySequence_InPlaceConcat (PyObject *o1, PyObject *o2)

Return value: New reference. Return the concatenation of o1 and o2 on success, and NULL on failure. The operation is done *in-place* when o1 supports it. This is the equivalent of the Python expression o1 += o2.

PyObject* PySequence InPlaceRepeat (PyObject *o, Py ssize t count)

Return value: New reference. Return the result of repeating sequence object o *count* times, or NULL on failure. The operation is done *in-place* when o supports it. This is the equivalent of the Python expression o *= count.

PyObject* PySequence_GetItem (PyObject *o, Py_ssize_t i)

Return value: New reference. Return the *i*th element of o, or NULL on failure. This is the equivalent of the Python expression o[i].

PyObject* PySequence_GetSlice (PyObject *o, Py_ssize_t i1, Py_ssize_t i2)

Return value: New reference. Return the slice of sequence object o between i1 and i2, or NULL on failure. This is the equivalent of the Python expression o[i1:i2].

int PySequence_SetItem (PyObject *o, Py_ssize_t i, PyObject *v)

将对象 v 赋值给 o 的第 i 号元素。失败时会引发异常并返回 -1;成功时返回 0。这相当于 Python 语句 o [i] = v。此函数 不会改变对 v 的引用。

If v is NULL, the element is deleted, however this feature is deprecated in favour of using $PySequence_DelItem()$.

int PySequence_DelItem (PyObject *o, Py_ssize_t i)

删除对象 o 的第 i 号元素。失败时返回 -1。这相当于 Python 语句 del \circ [i]。

int PySequence_SetSlice (PyObject *o, Py_ssize_t i1, Py_ssize_t i2, PyObject *v)

将序列对象 ν 赋值给序列对象 o 的从 il 到 i2 切片。这相当于 Python 语句 o [i1:i2] = v.

int PySequence_DelSlice (PyObject *o, Py_ssize_t i1, Py_ssize_t i2)

删除序列对象 o 的从 i1 到 i2 的切片。失败时返回 -1。这相当于 Python 语句 del o[i1:i2]。

Py_ssize_t PySequence_Count (PyObject *o, PyObject *value)

返回 value 在 o 中出现的次数,即返回使得 o [key] == value 的键的数量。失败时返回 -1。这相当于 Python 表达式 o.count (value)。

int PySequence_Contains (PyObject *o, PyObject *value)

确定 o 是否包含 value。如果 o 中的某一项等于 value,则返回 1,否则返回 0。出错时,返回 -1。这相当于 Python 表达式 value in o。

Py_ssize_t PySequence_Index (PyObject *o, PyObject *value)

返回第一个索引 *i*, 其中 o [i] == value. 出错时, 返回 "-1". 相当于 Python 的 "o.index(value)"表达式.

PyObject* PySequence_List (PyObject *o)

Return value: New reference. Return a list object with the same contents as the sequence or iterable o, or NULL on failure. The returned list is guaranteed to be new. This is equivalent to the Python expression list (0).

PyObject* PySequence Tuple (PyObject *o)

Return value: New reference. Return a tuple object with the same contents as the sequence or iterable o, or NULL on failure. If o is a tuple, a new reference will be returned, otherwise a tuple will be constructed with the appropriate contents. This is equivalent to the Python expression tuple (0).

PyObject* PySequence_Fast (PyObject *o, const char *m)

Return value: New reference. Return the sequence or iterable o as an object usable by the other PySequence_Fast* family of functions. If the object is not a sequence or iterable, raises TypeError with m as the message text. Returns NULL on failure.

PySequence_Fast* 函数之所以这样命名,是因为它们会假定 o 是一个PyTupleObject 或PyListObject 并直接访问 o 的数据字段。

作为 CPython 的实现细节,如果 o 已经是一个序列或列表,它将被直接返回。

Py_ssize_t PySequence_Fast_GET_SIZE (PyObject *o)

Returns the length of o, assuming that o was returned by PySequence_Fast () and that o is not NULL. The

size can also be gotten by calling $PySequence_Size()$ on o, but $PySequence_Fast_GET_SIZE()$ is faster because it can assume o is a list or tuple.

PyObject* PySequence_Fast_GET_ITEM (PyObject *o, Py_ssize_t i)

Return value: Borrowed reference. Return the *i*th element of o, assuming that o was returned by $PySequence_Fast()$, o is not NULL, and that i is within bounds.

PyObject** PySequence_Fast_ITEMS (PyObject *o)

Return the underlying array of PyObject pointers. Assumes that *o* was returned by *PySequence_Fast()* and *o* is not NULL.

请注意,如果列表调整大小,重新分配可能会重新定位 items 数组. 因此,仅在序列无法更改的上下文中使用基础数组指针.

PyObject* PySequence_ITEM (PyObject *o, Py_ssize_t i)

Return value: New reference. Return the ith element of o or NULL on failure. Faster form of $PySequence_GetItem()$ but without checking that $PySequence_Check()$ on o is true and without adjustment for negative indices.

7.4 映射协议

参见PyObject_GetItem()、PyObject_SetItem()与PyObject_DelItem()。

int PyMapping_Check (PyObject *o)

如果对象提供映射协议或支持切片则返回 1, 否则返回 0。请注意它将为具有 __getitem__() 方法的 Python 类返回 1, 因为在一般情况下无法确定它所支持的键类型。此函数总是会成功执行。

Py_ssize_t PyMapping_Size (PyObject *o)

Py_ssize_t PyMapping_Length (PyObject *o)

成功时返回对象 o 中键的数量,失败时返回 -1。这相当于 Python 表达式 len(o)。

PyObject* PyMapping_GetItemString (PyObject *o, const char *key)

Return value: New reference. 返回 o 中对应于字符串 key 的元素,或者失败时返回 NULL。这相当于 Python 表达式 o [key]。另请参见 also PyObject_GetItem()。

int PyMapping_SetItemString (PyObject *o, const char *key, PyObject *v)

在对象 o 中将字符串 key 映射到值 v。失败时返回 -1。这相当于 Python 语句 o[key] = v。另请 参见 $PyObject_SetItem()$ 。此函数 不会增加对 v 的引用。

int PyMapping DelItem (PyObject *o, PyObject *key)

从对象 o 中移除对象 key 的映射。失败时返回 -1。这相当于 Python 语句 del o[key]。这是 $PyObject_DelItem()$ 的一个别名。

int PyMapping_DelItemString (PyObject *o, const char *key)

从对象 o 中移除字符串 key 的映射。失败时返回 -1。这相当于 Python 语句 del o[key]。

int PyMapping_HasKey (PyObject *o, PyObject *key)

如果映射对象具有键 key 则返回 1,否则返回 0。这相当于 Python 表达式 key in o。此函数总是会成功执行。

请注意在调用 $__getitem__()$ 方法期间发生的异常将会被屏蔽。要获取错误报告请改用 $PyObject_GetItem()$ 。

int PyMapping_HasKeyString (PyObject *o, const char *key)

如果映射对象具有键 key 则返回 1,否则返回 0。这相当于 Python 表达式 key in 0。此函数总是会成功执行。

请注意在调用 ___getitem__() 方法期间发生的异常将会被屏蔽。要获取错误报告请改用PyMapping_GetItemString()。

PyObject* PyMapping_Keys (PyObject *o)

Return value: New reference. 成功时,返回对象 o 中的键的列表。失败时,返回 NULL。

在 3.7 版更改: 在之前版本中,此函数返回一个列表或元组。

7.4. 映射协议 65

PyObject* PyMapping_Values (PyObject *o)

Return value: New reference. 成功时,返回对象 o 中的值的列表。失败时,返回 NULL。

在 3.7 版更改: 在之前版本中, 此函数返回一个列表或元组。

PyObject* PyMapping_Items (PyObject *o)

Return value: New reference. 成功时,返回对象 o 中条目的列表,其中每个条目是一个包含键值对的元组。失败时,返回 NULL 。

在 3.7 版更改: 在之前版本中, 此函数返回一个列表或元组。

7.5 迭代器协议

迭代器有两个函数。

int PyIter_Check (PyObject *o)

返回 true,如果对象 o 支持迭代器协议的话。

PyObject* PyIter_Next (PyObject *o)

Return value: New reference. 返回迭代 o 的下一个值。对象必须是一个迭代器(这应由调用者来判断)。如果没有余下的值,则返回 NULL 并且不设置异常。如果在获取条目时发生了错误,则返回 NULL 并且传递异常。

要为迭代器编写一个一个循环, C 代码应该看起来像这样

```
PyObject *iterator = PyObject_GetIter(obj);
PyObject *item;

if (iterator == NULL) {
    /* propagate error */
}

while ((item = PyIter_Next(iterator))) {
    /* do something with item */
    ...
    /* release reference when done */
    Py_DECREF(item);
}

Py_DECREF(iterator);

if (PyErr_Occurred()) {
    /* propagate error */
}
else {
    /* continue doing useful work */
}
```

7.6 缓冲协议

在 Python 中可使用一些对象来包装对底层内存数组或称 缓冲的访问。此类对象包括内置的 bytes 和 bytearray 以及一些如 array array 这样的扩展类型。第三方库也可能会为了特殊的目的而定义它们自己的类型,例如用于图像处理和数值分析等。

虽然这些类型中的每一种都有自己的语义,但它们具有由可能较大的内存缓冲区支持的共同特征。在某些情况下,希望直接访问该缓冲区而无需中间复制。

Python 以缓冲协议 的形式在 C 层级上提供这样的功能。此协议包括两个方面:

• 在生产者这一方面,该类型的协议可以导出一个"缓冲区接口",允许公开它的底层缓冲区信息。 该接口的描述信息在Buffer Object Structures —节中; • 在消费者一侧,有几种方法可用于获得指向对象的原始底层数据的指针(例如一个方法的形参)。

一些简单的对象例如 bytes 和 bytearray 会以面向字节的形式公开它们的底层缓冲区。也可能会用其他形式;例如 array.array 所公开的元素可以是多字节值。

缓冲区接口的消费者的一个例子是文件对象的 write() 方法:任何可以输出为一系列字节流的对象可以被写入文件。然而 write() 方法只需要对于传入对象的只读权限,其他的方法,如 readinto() 需要参数内容的写入权限。缓冲区接口使得对象可以选择性地允许或拒绝读写或只读缓冲区的导出。

对于缓冲接口的消费者而言,有两种方式来获取一个目的对象的缓冲:

- 使用正确的参数来调用PyObject_GetBuffer() 函数;
- 调用PyArg ParseTuple()(或其同级对象之一)并传入 y*, w* or s* 格式代码中的一个。

在这两种情况下,当不再需要缓冲区时必须调用 $PyBuffer_Release()$ 。如果此操作失败,可能会导致各种问题,例如资源泄漏。

7.6.1 缓冲区结构

缓冲区结构(或者简单地称为"buffers")对于将二进制数据从另一个对象公开给 Python 程序员非常有用。它们还可以用作零拷贝切片机制。使用它们引用内存块的能力,可以很容易地将任何数据公开给 Python 程序员。内存可以是 C 扩展中的一个大的常量数组,也可以是在传递到操作系统库之前用于操作的原始内存块,或者可以用来传递本机内存格式的结构化数据。

与 Python 解释器公开的大多部数据类型不同,缓冲区不是 PyObject 指针而是简单的 C 结构。这使得它们可以非常简单地创建和复制。当需要为缓冲区加上泛型包装器时,可以创建一个内存视图 对象。

有关如何编写并导出对象的简短说明,请参阅缓冲区对象结构。要获取缓冲区对象,请参阅PyObject GetBuffer()。

Py_buffer

void *buf

指向由缓冲区字段描述的逻辑结构开始的指针。这可以是导出程序底层物理内存块中的任何位置。例如,使用负的*strides* 值可能指向内存块的末尾。

对于contiguous, '邻接'数组, 值指向内存块的开头。

void *obj

对导出对象的新引用。该引用归使用者所有,并由PyBuffer_Release() 自动递减并设置为 NULL。该字段等于任何标准 C-API 函数的返回值。

作为一种特殊情况,对于由PyMemoryView_FromBuffer()或PyBuffer_FillInfo()包装的temporary缓冲区,此字段为NULL。通常,导出对象不得使用此方案。

Py_ssize_t len

product (shape) * itemsize。对于连续数组,这是基础内存块的长度。对于非连续数组,如果逻辑结构复制到连续表示形式,则该长度将具有该长度。

仅当缓冲区是通过保证连续性的请求获取时,才访问 ((char *)buf)[0] up to ((char *)buf)[len-1] 时才有效。在大多数情况下,此类请求将为PyBUF_SIMPLE或PyBUF_WRITABLE。

int readonly

缓冲区是否为只读的指示器。此字段由PyBUF_WRITABLE 标志控制。

Py_ssize_t itemsize

单个元素的项大小 (以字节为单位)。与 struct.calcsize() 调用非 NULL format 的值相

重要例外:如果使用者请求的缓冲区没有PyBUF_FORMAT 标志,format 将设置为 NULL,但itemsize 仍具有原始格式的值。

如果*shape* 存在,则相等的 product (shape) * itemsize == len 仍然存在,使用者可以使用*itemsize* 来导航缓冲区。

7.6. 缓冲协议 67

如果shape 是 NULL,因为结果为PyBUF_SIMPLE 或PyBUF_WRITABLE 请求,则使用者必须忽略itemsize,并假设itemsize == 1。

const char *format

在 struct 模块样式语法中 NUL 字符串, 描述单个项的内容。如果这是 NULL, 则假定为 ""B""(无符号字节)。

此字段由PyBUF_FORMAT标志控制。

int ndim

The number of dimensions the memory represents as an n-dimensional array. If it is 0, buf points to a single item representing a scalar. In this case, shape, strides and suboffsets MUST be NULL.

The macro PyBUF_MAX_NDIM limits the maximum number of dimensions to 64. Exporters MUST respect this limit, consumers of multi-dimensional buffers SHOULD be able to handle up to PyBUF_MAX_NDIM dimensions.

Py_ssize_t *shape

An array of Py_ssize_t of length *ndim* indicating the shape of the memory as an n-dimensional array. Note that shape [0] * ... * shape [ndim-1] * itemsize MUST be equal to *len*.

Shape values are restricted to shape[n] >= 0. The case shape[n] == 0 requires special attention. See *complex arrays* for further information.

The shape array is read-only for the consumer.

Py_ssize_t *strides

An array of Py_ssize_t of length *ndim* giving the number of bytes to skip to get to a new element in each dimension.

Stride values can be any integer. For regular arrays, strides are usually positive, but a consumer MUST be able to handle the case strides[n] <= 0. See *complex arrays* for further information.

The strides array is read-only for the consumer.

Py_ssize_t *suboffsets

An array of Py_ssize_t of length ndim. If suboffsets[n] >= 0, the values stored along the nth dimension are pointers and the suboffset value dictates how many bytes to add to each pointer after de-referencing. A suboffset value that is negative indicates that no de-referencing should occur (striding in a contiguous memory block).

If all suboffsets are negative (i.e. no de-referencing is needed), then this field must be NULL (the default value).

This type of array representation is used by the Python Imaging Library (PIL). See *complex arrays* for further information how to access elements of such an array.

The suboffsets array is read-only for the consumer.

void *internal

This is for use internally by the exporting object. For example, this might be re-cast as an integer by the exporter and used to store flags about whether or not the shape, strides, and suboffsets arrays must be freed when the buffer is released. The consumer MUST NOT alter this value.

7.6.2 Buffer request types

Buffers are usually obtained by sending a buffer request to an exporting object via <code>PyObject_GetBuffer()</code>. Since the complexity of the logical structure of the memory can vary drastically, the consumer uses the <code>flags</code> argument to specify the exact buffer type it can handle.

All Py_buffer fields are unambiguously defined by the request type.

request-independent fields

The following fields are not influenced by *flags* and must always be filled in with the correct values: <code>obj</code>, <code>buf</code>, <code>len</code>, <code>itemsize</code>, <code>ndim</code>.

readonly, format

PyBUF_WRITABLE

Controls the *readonly* field. If set, the exporter MUST provide a writable buffer or else report failure. Otherwise, the exporter MAY provide either a read-only or writable buffer, but the choice MUST be consistent for all consumers.

PyBUF_FORMAT

Controls the format field. If set, this field MUST be filled in correctly. Otherwise, this field MUST be NULL.

PyBUF_WRITABLE can be I'd to any of the flags in the next section. Since PyBUF_SIMPLE is defined as 0, PyBUF WRITABLE can be used as a stand-alone flag to request a simple writable buffer.

 $PyBUF_FORMAT$ can be I'd to any of the flags except $PyBUF_SIMPLE$. The latter already implies format B (unsigned bytes).

shape, strides, suboffsets

The flags that control the logical structure of the memory are listed in decreasing order of complexity. Note that each flag contains all bits of the flags below it.

| 请求 | 形状 | 步幅 | 子偏移量 |
|----------------|------|------|--------|
| PyBUF_INDIRECT | 是 | 是 | 如果需要的话 |
| PyBUF_STRIDES | 是 | 是 | NULL |
| PyBUF_ND | 是 | NULL | NULL |
| PyBUF_SIMPLE | NULL | NULL | NULL |

连续性的请求

C or Fortran *contiguity* can be explicitly requested, with and without stride information. Without stride information, the buffer must be C-contiguous.

| 请求 | 形状 | 步幅 | 子偏移量 | 邻接 |
|----------------------|----|------|------|-----|
| PyBUF_C_CONTIGUOUS | 是 | 是 | NULL | С |
| PyBUF_F_CONTIGUOUS | 是 | 是 | NULL | F |
| PyBUF_ANY_CONTIGUOUS | 是 | 是 | NULL | C或F |
| PyBUF_ND | 是 | NULL | NULL | С |

7.6. 缓冲协议 69

复合请求

所有可能的请求都由上一节中某些标志的组合完全定义。为方便起见,缓冲区协议提供常用的组合作为 单个标志。

In the following table U stands for undefined contiguity. The consumer would have to call $PyBuffer_IsContiguous$ () to determine contiguity.

| 请求 | 形状 | 步幅 | 子偏移量 | 邻接 | 只读 | 格式 |
|------------------|----|------|--------|----|-----|------|
| PyBUF_FULL | 是 | 是 | 如果需要的话 | U | 0 | 是 |
| PyBUF_FULL_RO | 是 | 是 | 如果需要的话 | U | 1或0 | 是 |
| PyBUF_RECORDS | 是 | 是 | NULL | U | 0 | 是 |
| PyBUF_RECORDS_RO | 是 | 是 | NULL | U | 1或0 | 是 |
| PyBUF_STRIDED | 是 | 是 | NULL | U | 0 | NULL |
| PyBUF_STRIDED_RO | 是 | 是 | NULL | U | 1或0 | NULL |
| PyBUF_CONTIG | 是 | NULL | NULL | С | 0 | NULL |
| PyBUF_CONTIG_RO | 是 | NULL | NULL | С | 1或0 | NULL |

7.6.3 复杂数组

NumPy-style: shape and strides

The logical structure of NumPy-style arrays is defined by itemsize, ndim, shape and strides.

If ndim == 0, the memory location pointed to by buf is interpreted as a scalar of size itemsize. In that case, both shape and strides are NULL.

If *strides* is NULL, the array is interpreted as a standard n-dimensional C-array. Otherwise, the consumer must access an n-dimensional array as follows:

```
ptr = (char *)buf + indices[0] * strides[0] + ... + indices[n-1] * strides[n-1];
item = *((typeof(item) *)ptr);
```

As noted above, buf can point to any location within the actual memory block. An exporter can check the validity of a buffer with this function:

```
def verify_structure(memlen, itemsize, ndim, shape, strides, offset):
    """Verify that the parameters represent a valid array within
        the bounds of the allocated memory:
            char *mem: start of the physical memory block
            memlen: length of the physical memory block
            offset: (char *)buf - mem
    """
    if offset % itemsize:
        return False
    if offset < 0 or offset+itemsize > memlen:
```

(下页继续)

(续上页)

PIL-style: shape, strides and suboffsets

In addition to the regular items, PIL-style arrays can contain pointers that must be followed in order to get to the next element in a dimension. For example, the regular three-dimensional C-array char v[2][2][3] can also be viewed as an array of 2 pointers to 2 two-dimensional arrays: char (*v[2])[2][3]. In suboffsets representation, those two pointers can be embedded at the start of buf, pointing to two char x[2][3] arrays that can be located anywhere in memory.

Here is a function that returns a pointer to the element in an N-D array pointed to by an N-dimensional index when there are both non-NULL strides and suboffsets:

7.6.4 Buffer-related functions

```
int PyObject_CheckBuffer (PyObject *obj)
```

Return 1 if *obj* supports the buffer interface otherwise 0. When 1 is returned, it doesn't guarantee that *PyObject_GetBuffer()* will succeed. This function always succeeds.

```
int PyObject_GetBuffer (PyObject *exporter, Py_buffer *view, int flags)
```

Send a request to *exporter* to fill in *view* as specified by *flags*. If the exporter cannot provide a buffer of the exact type, it MUST raise PyExc_BufferError, set view->obj to NULL and return -1.

On success, fill in *view*, set view->obj to a new reference to *exporter* and return 0. In the case of chained buffer providers that redirect requests to a single object, view->obj MAY refer to this object instead of *exporter* (See *Buffer Object Structures*).

Successful calls to $PyObject_GetBuffer()$ must be paired with calls to $PyBuffer_Release()$, similar to malloc() and free(). Thus, after the consumer is done with the buffer, $PyBuffer_Release()$ must be called exactly once.

7.6. 缓冲协议 71

void PyBuffer_Release (Py_buffer *view)

Release the buffer *view* and decrement the reference count for view->obj. This function MUST be called when the buffer is no longer being used, otherwise reference leaks may occur.

It is an error to call this function on a buffer that was not obtained via PyObject_GetBuffer().

Py_ssize_t PyBuffer_SizeFromFormat (const char *)

Return the implied *itemsize* from *format*. This function is not yet implemented.

int PyBuffer_IsContiguous (*Py_buffer *view*, char *order*)

Return 1 if the memory defined by the *view* is C-style (*order* is 'C') or Fortran-style (*order* is 'F') *contiguous* or either one (*order* is 'A'). Return 0 otherwise. This function always succeeds.

void* PyBuffer_GetPointer (Py_buffer *view, Py_ssize_t *indices)

Get the memory area pointed to by the *indices* inside the given *view*. *indices* must point to an array of view->ndim indices.

int PyBuffer_FromContiguous (Py_buffer *view, void *buf, Py_ssize_t len, char fort)

Copy contiguous *len* bytes from *buf* to *view*. *fort* can be 'C' or 'F' (for C-style or Fortran-style ordering). 0 is returned on success, -1 on error.

int PyBuffer_ToContiguous (void *buf, Py_buffer *src, Py_ssize_t len, char order)

Copy *len* bytes from *src* to its contiguous representation in *buf*. *order* can be 'C' or 'F' or 'A' (for C-style or Fortran-style ordering or either one). 0 is returned on success, -1 on error.

This function fails if len != src -> len.

void PyBuffer_FillContiguousStrides (int ndims, Py_ssize_t *shape, Py_ssize_t *strides, int itemsize, char order)

Fill the *strides* array with byte-strides of a *contiguous* (C-style if *order* is 'C' or Fortran-style if *order* is 'F') array of the given shape with the given number of bytes per element.

int PyBuffer_FillInfo (*Py_buffer *view*, *PyObject *exporter*, void *buf, Py_ssize_t len, int readonly, int flags)

Handle buffer requests for an exporter that wants to expose *buf* of size *len* with writability set according to *readonly*. *buf* is interpreted as a sequence of unsigned bytes.

The *flags* argument indicates the request type. This function always fills in *view* as specified by flags, unless *buf* has been designated as read-only and *PyBUF_WRITABLE* is set in *flags*.

On success, set view->obj to a new reference to *exporter* and return 0. Otherwise, raise PyExc_BufferError, set view->obj to NULL and return -1;

如果此函数用作getbufferproc 的一部分,则 exporter 必须设置为导出对象,并且必须在未修改的情况下传递 flags。否则,exporter 必须是 NULL。

7.7 旧缓冲协议

3.0 版后已移除.

这些函数是 Python 2 中"旧缓冲协议"API 的组成部分。在 Python 3 中,此协议已不复存在,但这些函数仍然被公开以便移植 2.x 的代码。它们被用作新缓冲协议 的兼容性包装器,但它们并不会在缓冲被导出时向你提供对所获资源的生命周期控制。

因此,推荐你调用PyObject_GetBuffer()(或者配合PyArg_ParseTuple()函数族使用 y* 或 w* 格式码)来获取一个对象的缓冲视图,并在缓冲视图可被释放时调用PyBuffer_Release()。

int PyObject_AsCharBuffer (PyObject *obj, const char **buffer, Py_ssize_t *buffer_len)

返回一个指向可用作基于字符的输入的只读内存地址的指针。obj 参数必须支持单段字符缓冲接口。成功时返回 0,将 buffer 设为内存地址并将 buffer_len 设为缓冲区长度。出错时返回 -1 并设置一个 TypeError。

int PyObject_AsReadBuffer (PyObject *obj, const void **buffer, Py_ssize_t *buffer_len)

返回一个指向包含任意数据的只读内存地址的指针。obj 参数必须支持单段可读缓冲接口。成功

时返回 0,将 buffer 设为内存地址并将 $buffer_len$ 设为缓冲区长度。出错时返回 -1 并设置一个 TypeError。

int PyObject_CheckReadBuffer (PyObject *o)

如果 o 支持单段可读缓冲接口则返回 1。否则返回 0。此函数总是会成功执行。

请注意此函数会尝试获取并释放一个缓冲区,并且在调用对应函数期间发生的异常会被屏蔽。要获取错误报告则应改用PyObject_GetBuffer()。

int PyObject_AsWriteBuffer (PyObject *obj, void **buffer, Py_ssize_t *buffer_len)

返回一个指向可写内存地址的指针。obj 必须支持单段字符缓冲接口。成功时返回 0,将 buffer 设为内存地址并将 buffer_len 设为缓冲区长度。出错时返回 -1 并设置一个 TypeError。

7.7. 旧缓冲协议 73

具体的对象层

本章中的函数特定于某些 Python 对象类型。将错误类型的对象传递给它们并不是一个好主意;如果您从 Python 程序接收到一个对象,但不确定它是否具有正确的类型,则必须首先执行类型检查;例如,要检查对象是否为字典,请使用 $PyDict_Check()$ 。本章的结构类似于 Python 对象类型的"家族树"。

警告: 虽然本章所描述的函数会仔细检查传入对象的类型, 但是其中许多函数不会检查传入的对象是否为 NULL。允许传入 NULL 可能导致内存访问冲突和解释器的立即终止。

8.1 基本对象

本节描述 Python 类型对象和单一实例对象 象 None。

8.1.1 Type 对象

PyTypeObject

对象的 C 结构用于描述 built-in 类型。

PyObject* PyType_Type

这是属于 type 对象的 type object,它在 Python 层面和 type 是相同的对象。

int PyType_Check (PyObject *o)

如果对象o是一个类型对象,包括继承于标准类型对象的类型实例,返回真。在其它所有情况下返回假。

int PyType_CheckExact (PyObject *o)

如果对象 o 是一个类型对象, 但不是标准类型对象的子类型时, 返回真。在其它所有情况下返回假。

unsigned int PyType_ClearCache()

Clear the internal lookup cache. Return the current version tag.

unsigned long PyType_GetFlags (PyTypeObject* type)

Return the tp_flags member of type. This function is primarily meant for use with $Py_LIMITED_API$; the individual flag bits are guaranteed to be stable across Python releases, but access to tp_flags itself is not part of the limited API.

3.2 新版功能.

在 3.4 版更改: The return type is now unsigned long rather than long.

void PyType_Modified (PyTypeObject *type)

Invalidate the internal lookup cache for the type and all of its subtypes. This function must be called after any manual modification of the attributes or base classes of the type.

int PyType_HasFeature (PyTypeObject *o, int feature)

Return true if the type object o sets the feature feature. Type features are denoted by single bit flags.

int PyType_IS_GC (PyTypeObject *o)

Return true if the type object includes support for the cycle detector; this tests the type flag $Py_TPFLAGS_HAVE_GC$.

int PyType_IsSubtype (PyTypeObject *a, PyTypeObject *b)

Return true if *a* is a subtype of *b*.

This function only checks for actual subtypes, which means that __subclasscheck__() is not called on b. Call PyObject_IsSubclass() to do the same check that issubclass() would do.

PyObject* PyType_GenericAlloc (PyTypeObject *type, Py_ssize_t nitems)

Return value: New reference. Generic handler for the tp_alloc slot of a type object. Use Python's default memory allocation mechanism to allocate a new instance and initialize all its contents to NULL.

PyObject* PyType_GenericNew (PyTypeObject *type, PyObject *args, PyObject *kwds)

Return value: New reference. Generic handler for the tp_new slot of a type object. Create a new instance using the type's tp_alloc slot.

int PyType_Ready (PyTypeObject *type)

Finalize a type object. This should be called on all type objects to finish their initialization. This function is responsible for adding inherited slots from a type's base class. Return 0 on success, or return -1 and sets an exception on error.

void* PyType_GetSlot (PyTypeObject *type, int slot)

Return the function pointer stored in the given slot. If the result is NULL, this indicates that either the slot is NULL, or that the function was called with invalid parameters. Callers will typically cast the result pointer into the appropriate function type.

See PyType_Slot.slot for possible values of the *slot* argument.

An exception is raised if *type* is not a heap type.

3.4 新版功能.

Creating Heap-Allocated Types

The following functions and structs are used to create *heap types*.

PyObject* PyType_FromSpecWithBases (PyType_Spec *spec, PyObject *bases)

Return value: New reference. Creates and returns a heap type object from the spec (Py_TPFLAGS_HEAPTYPE).

If bases is a tuple, the created heap type contains all types contained in it as base types.

If bases is NULL, the Py_tp_base slot is used instead. If that also is NULL, the new type derives from object.

This function calls PyType_Ready () on the new type.

3.3 新版功能.

PyObject* PyType_FromSpec (PyType_Spec *spec)

Return value: New reference. Equivalent to PyType_FromSpecWithBases(spec, NULL).

PyType_Spec

Structure defining a type's behavior.

const char* PyType_Spec.name

Name of the type, used to set PyTypeObject.tp_name.

int PyType_Spec.basicsize

int PyType_Spec.itemsize

Size of the instance in bytes, used to set $PyTypeObject.tp_basicsize$ and $PyTypeObject.tp_itemsize$.

int PyType_Spec.flags

Type flags, used to set PyTypeObject.tp_flags.

If the $Py_TPFLAGS_HEAPTYPE$ flag is not set, $PyType_FromSpecWithBases()$ sets it automatically.

PyType_Slot *PyType_Spec.slots

Array of $PyType_Slot$ structures. Terminated by the special slot value {0, NULL}.

PyType_Slot

Structure defining optional functionality of a type, containing a slot ID and a value pointer.

int PyType_Slot.slot

A slot ID.

Slot IDs are named like the field names of the structures <code>PyTypeObject</code>, <code>PyNumberMethods</code>, <code>PySequenceMethods</code>, <code>PyMappingMethods</code> and <code>PyAsyncMethods</code> with an added <code>Py_prefix</code>. For example, use:

- Py_tp_dealloc to set PyTypeObject.tp_dealloc
- Py_nb_add to set PyNumberMethods.nb_add
- Py_sq_length to set PySequenceMethods.sq_length

The following fields cannot be set using PyType_Spec and PyType_Slot:

- tp_dict
- tp_mro
- tp_cache
- tp_subclasses
- tp_weaklist
- tp_print
- tp_weaklistoffset
- tp_dictoffset
- bf_getbuffer
- bf_releasebuffer

Setting Py_tp_bases may be problematic on some platforms. To avoid issues, use the *bases* argument of $PyType_FromSpecWithBases$ () instead.

void *PyType_Slot.pfunc

The desired value of the slot. In most cases, this is a pointer to a function.

May not be NULL.

8.1. 基本对象 77

8.1.2 None 对象

请注意, None 的 PyTypeObject 不会直接在 Python / C API 中公开。由于 None 是单例,测试对象标识 (在 C 中使用 ==) 就足够了。由于同样的原因,没有 PyNone_Check () 函数。

PyObject* Py_None

Python None 对象,表示缺乏值。这个对象没有方法。它需要像引用计数一样处理任何其他对象。

Py_RETURN_NONE

正确处理来自 C 函数内的Py_None 返回(也就是说,增加 None 的引用计数并返回它。)

8.2 数值对象

8.2.1 整数型对象

所有整数都使用以任意大小的长整数对象表示。

On error, most PyLong_As* APIs return (return type) -1 which cannot be distinguished from a number. Use PyErr_Occurred() to disambiguate.

PyLongObject

This subtype of PyObject represents a Python integer object.

PyTypeObject PyLong_Type

This instance of PyTypeObject represents the Python integer type. This is the same object as int in the Python layer.

int PyLong_Check (PyObject *p)

Return true if its argument is a PyLongObject or a subtype of PyLongObject.

int PyLong_CheckExact (PyObject *p)

Return true if its argument is a PyLongObject, but not a subtype of PyLongObject.

PyObject* PyLong_FromLong (long v)

Return value: New reference. Return a new PyLongObject object from v, or NULL on failure.

The current implementation keeps an array of integer objects for all integers between -5 and 256, when you create an int in that range you actually just get back a reference to the existing object. So it should be possible to change the value of 1. I suspect the behaviour of Python in this case is undefined. :-)

PyObject* PyLong_FromUnsignedLong (unsigned long v)

Return value: New reference. Return a new PyLongObject object from a C unsigned long, or NULL on failure.

PyObject* PyLong_FromSsize_t (Py_ssize_t v)

Return value: New reference. Return a new PyLongObject object from a C Py_ssize_t, or NULL on failure.

PyObject* PyLong_FromSize_t (size_t v)

Return value: New reference. Return a new PyLongObject object from a C size_t, or NULL on failure.

*PyObject** **PyLong_FromLongLong** (long long *v*)

Return value: New reference. Return a new PyLongObject object from a C long long, or NULL on failure

*PyObject** **PyLong_FromUnsignedLongLong** (unsigned long long *v*)

Return value: New reference. Return a new PyLongObject object from a C unsigned long long, or NULL on failure.

PyObject* PyLong_FromDouble (double v)

Return value: New reference. Return a new PyLongObject object from the integer part of v, or NULL on failure.

PyObject* PyLong_FromString (const char *str, char **pend, int base)

Return value: New reference. Return a new PyLongObject based on the string value in str, which is interpreted according to the radix in base. If pend is non-NULL, *pend will point to the first character in str which follows the representation of the number. If base is 0, str is interpreted using the integers definition; in this case, leading zeros in a non-zero decimal number raises a ValueError. If base is not 0, it must be between 2 and 36, inclusive. Leading spaces and single underscores after a base specifier and between digits are ignored. If there are no digits, ValueError will be raised.

PyObject* PyLong_FromUnicode (Py_UNICODE *u, Py_ssize_t length, int base)

Return value: New reference. Convert a sequence of Unicode digits to a Python integer value. The Unicode string is first encoded to a byte string using PyUnicode_EncodeDecimal() and then converted using PyLong_FromString().

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyLong_FromUnicodeObject()*.

PyObject* PyLong_FromUnicodeObject (PyObject *u, int base)

Return value: New reference. Convert a sequence of Unicode digits in the string u to a Python integer value. The Unicode string is first encoded to a byte string using PyUnicode_EncodeDecimal() and then converted using PyLong_FromString().

3.3 新版功能.

PyObject* PyLong_FromVoidPtr (void *p)

Return value: New reference. Create a Python integer from the pointer p. The pointer value can be retrieved from the resulting value using $PyLong_AsVoidPtr()$.

long PyLong_AsLong (PyObject *obj)

Return a C long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its index () or int () method (if present) to convert it to a *PyLongObject*.

Raise OverflowError if the value of *obj* is out of range for a long.

Returns -1 on error. Use PyErr_Occurred() to disambiguate.

在 3.8 版更改: 如果可用将使用 __index__()。

3.8 版后已移除: Using __int__() is deprecated.

long PyLong_AsLongAndOverflow (*PyObject *obj*, int *overflow)

Return a C long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its __index__() or __int__() method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is greater than LONG_MAX or less than LONG_MIN, set **overflow* to 1 or -1, respectively, and return -1; otherwise, set **overflow* to 0. If any other exception occurs set **overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr_Occurred() to disambiguate.

在 3.8 版更改: 如果可用将使用 __index__()。

3.8 版后已移除: Using __int__() is deprecated.

$long long PyLong_AsLongLong (PyObject *obj)$

Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its __index__() or __int__() method (if present) to convert it to a *PyLongObject*.

Raise OverflowError if the value of *obj* is out of range for a long long.

Returns -1 on error. Use PyErr_Occurred () to disambiguate.

在 3.8 版更改: 如果可用将使用 __index__()。

3.8 版后已移除: Using __int__() is deprecated.

long long PyLong_AsLongLongAndOverflow (PyObject *obj, int *overflow)

Return a C long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its __index__() or __int__() method (if present) to convert it to a *PyLongObject*.

8.2. 数值对象 79

If the value of *obj* is greater than PY_LLONG_MAX or less than PY_LLONG_MIN, set **overflow* to 1 or -1, respectively, and return -1; otherwise, set **overflow* to 0. If any other exception occurs set **overflow* to 0 and return -1 as usual.

Returns -1 on error. Use PyErr_Occurred () to disambiguate.

3.2 新版功能.

在 3.8 版更改: 如果可用将使用 ___index___()。

3.8 版后已移除: Using __int__() is deprecated.

Py_ssize_t PyLong_AsSsize_t (PyObject *pylong)

Return a C Py_ssize_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a Py_ssize_t.

Returns -1 on error. Use PyErr_Occurred () to disambiguate.

unsigned long PyLong_AsUnsignedLong (PyObject *pylong)

Return a C unsigned long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for a unsigned long.

Returns (unsigned long) -1 on error. Use PyErr_Occurred() to disambiguate.

size_t PyLong_AsSize_t (PyObject *pylong)

Return a C size_t representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of *pylong* is out of range for a size_t.

Returns (size_t) -1 on error. Use PyErr_Occurred() to disambiguate.

unsigned long long PyLong_AsUnsignedLongLong (PyObject *pylong)

Return a C unsigned long long representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for an unsigned long long.

Returns (unsigned long long) -1 on error. Use PyErr_Occurred() to disambiguate.

在 3.1 版更改: A negative pylong now raises OverflowError, not TypeError.

unsigned long PyLong_AsUnsignedLongMask (PyObject *obj)

Return a C unsigned long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its __index__() or __int__() method (if present) to convert it to a *PyLongObject*.

If the value of obj is out of range for an unsigned long, return the reduction of that value modulo ULONG_MAX + 1.

Returns (unsigned long) -1 on error. Use PyErr_Occurred() to disambiguate.

在 3.8 版更改: 如果可用将使用 ___index___()。

3.8 版后已移除: Using ___int___() is deprecated.

unsigned long long PyLong_AsUnsignedLongLongMask (PyObject *obj)

Return a C unsigned long long representation of *obj*. If *obj* is not an instance of *PyLongObject*, first call its __index__() or __int__() method (if present) to convert it to a *PyLongObject*.

If the value of *obj* is out of range for an unsigned long long, return the reduction of that value modulo PY_ULLONG_MAX + 1.

Returns (unsigned long long) -1 on error. Use PyErr_Occurred() to disambiguate.

在 3.8 版更改: 如果可用将使用 ___index___()。

3.8 版后已移除: Using __int__() is deprecated.

double PyLong_AsDouble (PyObject *pylong)

Return a C double representation of pylong. pylong must be an instance of PyLongObject.

Raise OverflowError if the value of pylong is out of range for a double.

Returns -1.0 on error. Use PyErr_Occurred () to disambiguate.

void* PyLong_AsVoidPtr (PyObject *pylong)

Convert a Python integer *pylong* to a C void pointer. If *pylong* cannot be converted, an OverflowError will be raised. This is only assured to produce a usable void pointer for values created with <code>PyLong_FromVoidPtr()</code>.

Returns NULL on error. Use PyErr_Occurred () to disambiguate.

8.2.2 布尔对象

Python 中的布尔值是作为整数的子类实现的。只有 Py_False 和 Py_True 两个布尔值。因此,正常的创建和删除功能不适用于布尔值。但是,下列宏可用。

int PyBool_Check (PyObject *o)

如果 o 的类型为 PyBool_Type,则返回 true。

PyObject* Py False

Python 的 False 对象没有任何方法,它需要和其他对象一样遵循引用计数。

PyObject* Py_True

Python 的 True 对象没有任何方法,它需要和其他对象一样遵循引用计数。

Py RETURN FALSE

从函数返回 Py_False 时,需要增加它的引用计数。

Py_RETURN_TRUE

从函数返回 Py_True 时,需要增加它的引用计数。

*PyObject** **PyBool FromLong** (long *v*)

Return value: New reference. 根据 v 的实际值, 返回一个 Py_True 或者 Py_False 的新引用。

8.2.3 浮点数对象

PyFloatObject

这个 C 类型PyObject 的子类型代表一个 Python 浮点数对象。

PyTypeObject PyFloat_Type

这是个属于 C 类型PyTypeObject 的代表 Python 浮点类型的实例。在 Python 层面的类型 float 是同一个对象。

int PyFloat_Check (PyObject *p)

当他的参数是一个 C 类型PyFloatObject 或者是 C 类型PyFloatObject 的子类型时,返回真。

int PyFloat_CheckExact (PyObject *p)

当他的参数是一个 C 类型PyFloatObject 但不是 C 类型PyFloatObject 的子类型时,返回真。

PyObject* PyFloat_FromString (PyObject *str)

Return value: New reference. 根据字符串 str 的值创建一个PyFloatObject,失败时返回 NULL。

PyObject* PyFloat_FromDouble (double v)

Return value: New reference. 根据 v 创建一个PyFloatObject 对象,失败时返回 NULL。

double PyFloat_AsDouble (PyObject *pyfloat)

返回一个 C double 代表 pyfloat 的内容。如果 pyfloat 不是一个 Python 浮点数对象但是具有 __float__() 方法,此方法将首先被调用,将 pyfloat 转换成一个数点数。如果 __float__() 未定义则将回退至 __index__()。如果失败,此方法将返回 -1.0,因此开发者应当调用 $PyErr_Occurred()$ 来检查错误。

在 3.8 版更改: 如果可用将使用 __index__()。

double PyFloat_AS_DOUBLE (PyObject *pyfloat)

返回一个 pyfloat 内容的 C double 表示, 但没有错误检查。

8.2. 数值对象 81

PyObject* PyFloat_GetInfo (void)

Return value: New reference. 返回一个 structseq 实例,其中包含有关 float 的精度、最小值和最大值的信息。它是头文件 float.h 的一个简单包装。

double PyFloat GetMax()

返回最大可表示的有限浮点数 DBL_MAX 为 C double。

double PyFloat_GetMin()

返回最小可表示归一化正浮点数 DBL_MIN 为 C double。

int PyFloat_ClearFreeList()

清空浮点数释放列表。返回无法释放的项目数。

8.2.4 复数对象

从 C API 看, Python 的复数对象由两个不同的部分实现: 一个是在 Python 程序使用的 Python 对象, 另外的是一个代表真正复数值的 C 结构体。API 提供了函数共同操作两者。

表示复数的 C 结构体

需要注意的是接受这些结构体的作为参数并当做结果返回的函数,都是传递"值"而不是引用指针。此规则适用于整个 API。

Py_complex

这是一个对应 Python 复数对象的值部分的 C 结构体。绝大部分处理复数对象的函数都用这类型的结构体作为输入或者输出值,它可近似地定义为:

```
typedef struct {
   double real;
   double imag;
} Py_complex;
```

 Py_complex _Py_c_sum (Py_complex left, Py_complex right)

 返回两个复数的和,用 C 类型Py_complex 表示。

 Py_complex _Py_c_diff (Py_complex left, Py_complex right)

 返回两个复数的差,用C类型Py_complex表示。

Py_complex _Py_c_neg (Py_complex complex)

返回复数 complex 的负值,用 C 类型Py_complex 表示。

Py_complex _Py_c_prod (Py_complex left, Py_complex right)

返回两个复数的乘积,用 C 类型Py_complex 表示。
Py_complex _**Py_c** _**quot** (Py_complex dividend, Py_complex divisor)

返回两个复数的商,用 C 类型 $P_{Y_complex}$ 表示。

如果 divisor 为空,这个方法返回零并设置 errno 为 EDOM。

Py_complex _Py_c_pow (Py_complex num, Py_complex exp) 返回 num 的 exp 次幂,用 C 类型Py_complex 表示。

如果 num 为空且 exp 不是正实数,这个方法返回零并设置 errno 为 EDOM。

表示复数的 Python 对象

PyComplexObject

这个 C 类型PyObject 的子类型代表一个 Python 复数对象。

PyTypeObject PyComplex_Type

这是个属于 C 类型PyTypeObject 的代表 Python 复数类型的实例。和 Python 层面的类 complex 是同一个对象。

int PyComplex_Check (PyObject *p)

如果它的参数是一个 C 类型PyComplexObject 或者是 C 类型PyComplexObject 的子类型,返回真。

int PyComplex_CheckExact (PyObject *p)

如果它的参数是一个 C 类型PyComplexObject 但不是 C 类型PyComplexObject 的子类型,返回真。

PyObject* PyComplex_FromCComplex (Py_complex v)

Return value: New reference. 根据 C 类型Py_complex 的值生成一个新的 Python 复数对象。

PyObject* PyComplex_FromDoubles (double real, double imag)

Return value: New reference. 根据 real 和 imag 返回一个新的 C 类型PyComplexObject 对象。

$\label{eq:complex_RealAsDouble} \ (\textit{PyObject *op})$

以 C 类型 double 返回 op 的实部。

double PyComplex_ImagAsDouble (PyObject *op)

以C类型 double 返回 op 的虚部。

Py_complex PyComplex_AsCComplex (PyObject *op)

返回复数 op 的 C 类型Py_complex 值。

如果 op 不是一个 Python 复数对象,但是具有 __complex__() 方法,此方法将首先被调用,将 op 转换为一个 Python 复数对象。如果 __complex__() 未定义则将回退至 __float__(),如果 __float__() 未定义则将回退至 __index__()。如果失败,此方法将返回 -1.0 作为实数值。

在 3.8 版更改: 如果可用将使用 ___index___()。

8.3 序列对象

序列对象的一般操作在前一章中讨论过;本节介绍 Python 语言固有的特定类型的序列对象。

8.3.1 字节对象

当期望带一个字节串形参但却带一个非字节串形参被调用时,这些函数会引发 TypeError。

PyBytesObject

这种PyObject 的子类型表示一个 Python 字节对象。

PyTypeObject PyBytes_Type

PyTypeObject 的实例代表一个 Python 字节类型,在 Python 层面它与 bytes 是相同的对象。

int PyBytes_Check (PyObject *o)

如果对象 o 是字节对象或字节类型的子类型的实例,则返回 true。

int PyBytes CheckExact (PyObject *o)

如果对象 o 是字节对象,但不是字节类型子类型的实例,则返回 true。

PyObject* PyBytes FromString (const char *v)

Return value: New reference. Return a new bytes object with a copy of the string v as value on success, and NULL on failure. The parameter v must not be NULL; it will not be checked.

PyObject* PyBytes_FromStringAndSize (const char *v, Py_ssize_t len)

Return value: New reference. Return a new bytes object with a copy of the string v as value and length len on success, and NULL on failure. If v is NULL, the contents of the bytes object are uninitialized.

PyObject* PyBytes FromFormat (const char *format, ...)

Return value: New reference. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python bytes object and return a bytes object with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format string. The following format characters are allowed:

| 格式字符 | 类型 | 注释 |
|------|-------------|------------------------------------------------------------------------|
| 용용 | 不适用 | 文字%字符。 |
| 응C | int | 一个字节,被表示为一个 C 语言的整型 |
| %d | int | 相当于 printf("%d").1 |
| %u | 无符号整型 | 相当于 printf("%u").1 |
| %ld | 长整型 | 相当于 printf("%ld").1 |
| %lu | 无符号长整型 | 相当于 printf("%lu").1 |
| %zd | Py_ssize_t | 相当于 printf("%zd").1 |
| %zu | size_t | 相当于 printf("%zu").1 |
| 응i | int | 相当于 printf ("%i").1 |
| %X | int | 相当于 printf("%x").1 |
| % S | const char* | A null-terminated C character array. |
| %p | const void* | The hex representation of a C pointer. Mostly equivalent to |
| | | printf("%p") except that it is guaranteed to start with the literal 0x |
| | | regardless of what the platform's printf yields. |

无法识别的格式字符会导致将格式字符串的其余所有内容原样复制到结果对象,并丢弃所有多余 的参数。

PyObject* PyBytes_FromFormatV (const char *format, va_list vargs)

Return value: New reference. 与PyBytes_FromFormat() 完全相同,除了它需要两个参数。

PyObject* PyBytes_FromObject (PyObject *o)

Return value: New reference. 返回字节表示实现缓冲区协议的对象 *o*。

Py_ssize_t PyBytes_Size (PyObject *o)

返回字节对象 *o* 中字节的长度。

Py_ssize_t PyBytes_GET_SIZE (PyObject *o)

Macro form of PyBytes_Size() but without error checking.

char* PyBytes_AsString (PyObject *o)

Return a pointer to the contents of o. The pointer refers to the internal buffer of o, which consists of len(o) + 1 bytes. The last byte in the buffer is always null, regardless of whether there are any other null bytes. The data must not be modified in any way, unless the object was just created using PyBytes_FromStringAndSize(NULL, size). It must not be deallocated. If o is not a bytes object at all, $PyBytes_AsString()$ returns NULL and raises TypeError.

char* PyBytes_AS_STRING (PyObject *string)

Macro form of PyBytes_AsString() but without error checking.

int PyBytes_AsStringAndSize (PyObject *obj, char **buffer, Py_ssize_t *length)

Return the null-terminated contents of the object obj through the output variables buffer and length.

If *length* is NULL, the bytes object may not contain embedded null bytes; if it does, the function returns -1 and a ValueError is raised.

The buffer refers to an internal buffer of *obj*, which includes an additional null byte at the end (not counted in *length*). The data must not be modified in any way, unless the object was just created using PyBytes_FromStringAndSize(NULL, size). It must not be deallocated. If *obj* is not a bytes object at all, *PyBytes_AsStringAndSize()* returns -1 and raises TypeError.

¹ 对于整数说明符 (d, u, ld, lu, zd, zu, i, x): 当给出精度时, 0 转换标志是有效的。

在 3.5 版更改: Previously, TypeError was raised when embedded null bytes were encountered in the bytes object.

void PyBytes_Concat (PyObject **bytes, PyObject *newpart)

Create a new bytes object in *bytes containing the contents of newpart appended to bytes; the caller will own the new reference. The reference to the old value of bytes will be stolen. If the new object cannot be created, the old reference to bytes will still be discarded and the value of *bytes will be set to NULL; the appropriate exception will be set.

void PyBytes_ConcatAndDel (PyObject **bytes, PyObject *newpart)

Create a new bytes object in *bytes containing the contents of newpart appended to bytes. This version decrements the reference count of newpart.

int _PyBytes_Resize (PyObject **bytes, Py_ssize_t newsize)

A way to resize a bytes object even though it is "immutable". Only use this to build up a brand new bytes object; don't use this if the bytes may already be known in other parts of the code. It is an error to call this function if the refcount on the input bytes object is not one. Pass the address of an existing bytes object as an Ivalue (it may be written into), and the new size desired. On success, *bytes holds the resized bytes object and 0 is returned; the address in *bytes may differ from its input value. If the reallocation fails, the original bytes object at *bytes is deallocated, *bytes is set to NULL, MemoryError is set, and -1 is returned.

8.3.2 字节数组对象

PyByteArrayObject

这个PyObject 的子类型表示一个 Python 字节数组对象。

PyTypeObject PyByteArray_Type

Python bytearray 类型表示为PyTypeObject 的实例;这与 Python 层面的 bytearray 是相同的对象。

类型检查宏

int PyByteArray_Check (PyObject *o)

当对象 o 是一个字节数组对象而且是一个字节数组类型的子类型实例时,返回真。

int PyByteArray_CheckExact (PyObject *o)

当对象 o 是一个字节数组对象, 但不是一个字节数组类型的子类型实例时, 返回真。

直接 API 函数

PyObject* PyByteArray_FromObject (PyObject *o)

Return value: New reference. 根据任何实现了缓冲区协议 的对象 o, 返回一个新的字节数组对象。

PyObject* PyByteArray_FromStringAndSize (const char *string, Py_ssize_t len)

Return value: New reference. 根据 string 及其长度 len 创建一个新的 bytearray 对象。当失败时返回 NULL。

PyObject* PyByteArray_Concat (PyObject *a, PyObject *b)

Return value: New reference. 连接字节数组 a 和 b 并返回一个带有结果的新的字节数组。

Py_ssize_t PyByteArray_Size (PyObject *bytearray)

在检查 NULL 指针后返回 bytearray 的大小。

char* PyByteArray_AsString (PyObject *bytearray)

在检查 NULL 指针后返回将 bytearray 返回为一个字符数组。返回的数组总是会附加一个额外的空字节。

int PyByteArray_Resize (PyObject *bytearray, Py_ssize_t len)

将 bytearray 的内部缓冲区的大小调整为 len。

宏

这些宏减低安全性以换取性能,它们不检查指针。

```
char* PyByteArray_AS_STRING (PyObject *bytearray)
C函数PyByteArray_AsString()的宏版本。
```

Py_ssize_t PyByteArray_GET_SIZE (PyObject *bytearray)
C 函数PyByteArray Size()的宏版本。

8.3.3 Unicode Objects and Codecs

Unicode 对象

Since the implementation of **PEP 393** in Python 3.3, Unicode objects internally use a variety of representations, in order to allow handling the complete range of Unicode characters while staying memory efficient. There are special cases for strings where all code points are below 128, 256, or 65536; otherwise, code points must be below 1114112 (which is the full Unicode range).

 $Py_UNICODE*$ and UTF-8 representations are created on demand and cached in the Unicode object. The $Py_UNICODE*$ representation is deprecated and inefficient; it should be avoided in performance- or memory-sensitive situations.

Due to the transition between the old APIs and the new APIs, Unicode objects can internally be in two states depending on how they were created:

- "canonical" Unicode objects are all objects created by a non-deprecated Unicode API. They use the most efficient representation allowed by the implementation.
- "legacy" Unicode objects have been created through one of the deprecated APIs (typically <code>PyUnicode_FromUnicode())</code> and only bear the <code>Py_UNICODE*</code> representation; you will have to call <code>PyUnicode_READY()</code> on them before calling any other API.

Unicode 类型

These are the basic Unicode object types used for the Unicode implementation in Python:

Py_UCS4

Py_UCS2

Py_UCS1

These types are typedefs for unsigned integer types wide enough to contain characters of 32 bits, 16 bits and 8 bits, respectively. When dealing with single Unicode characters, use Py_UCS4 .

3.3 新版功能.

Py_UNICODE

This is a typedef of wchar_t, which is a 16-bit type or 32-bit type depending on the platform.

在 3.3 版更改: In previous versions, this was a 16-bit type or a 32-bit type depending on whether you selected a "narrow" or "wide" Unicode version of Python at build time.

PyASCIIObject

PyCompactUnicodeObject

PyUnicodeObject

These subtypes of *PyObject* represent a Python Unicode object. In almost all cases, they shouldn't be used directly, since all API functions that deal with Unicode objects take and return *PyObject* pointers.

3.3 新版功能.

PyTypeObject PyUnicode_Type

This instance of PyTypeObject represents the Python Unicode type. It is exposed to Python code as str.

The following APIs are really C macros and can be used to do fast checks and to access internal read-only data of Unicode objects:

```
int PyUnicode_Check (PyObject *o)
```

Return true if the object o is a Unicode object or an instance of a Unicode subtype.

int PyUnicode_CheckExact (PyObject *o)

Return true if the object o is a Unicode object, but not an instance of a subtype.

```
int PyUnicode_READY (PyObject *o)
```

Ensure the string object o is in the "canonical" representation. This is required before using any of the access macros described below.

Returns 0 on success and -1 with an exception set on failure, which in particular happens if memory allocation fails.

3.3 新版功能.

Py_ssize_t PyUnicode_GET_LENGTH (PyObject *o)

Return the length of the Unicode string, in code points. o has to be a Unicode object in the "canonical" representation (not checked).

3.3 新版功能.

```
Py_UCS1* PyUnicode_1BYTE_DATA (PyObject *o)
Py_UCS2* PyUnicode_2BYTE_DATA (PyObject *o)
Py_UCS4* PyUnicode_4BYTE_DATA (PyObject *o)
```

Return a pointer to the canonical representation cast to UCS1, UCS2 or UCS4 integer types for direct character access. No checks are performed if the canonical representation has the correct character size; use <code>PyUnicode_KIND()</code> to select the right macro. Make sure <code>PyUnicode_READY()</code> has been called before accessing this.

3.3 新版功能.

```
PyUnicode_WCHAR_KIND
PyUnicode_1BYTE_KIND
PyUnicode_2BYTE_KIND
PyUnicode_4BYTE_KIND
```

Return values of the PyUnicode_KIND() macro.

3.3 新版功能.

int PyUnicode_KIND (PyObject *o)

Return one of the PyUnicode kind constants (see above) that indicate how many bytes per character this Unicode object uses to store its data. *o* has to be a Unicode object in the "canonical" representation (not checked).

3.3 新版功能.

```
void* PyUnicode_DATA (PyObject *o)
```

Return a void pointer to the raw Unicode buffer. o has to be a Unicode object in the "canonical" representation (not checked).

3.3 新版功能.

void PyUnicode_WRITE (int kind, void *data, Py_ssize_t index, Py_UCS4 value)

Write into a canonical representation *data* (as obtained with <code>PyUnicode_DATA()</code>). This macro does not do any sanity checks and is intended for usage in loops. The caller should cache the *kind* value and *data* pointer as obtained from other macro calls. *index* is the index in the string (starts at 0) and *value* is the new code point value which should be written to that location.

3.3 新版功能.

Py_UCS4 PyUnicode_READ (int kind, void *data, Py_ssize_t index)

Read a code point from a canonical representation *data* (as obtained with *PyUnicode_DATA()*). No checks or ready calls are performed.

3.3 新版功能.

Py_UCS4 PyUnicode_READ_CHAR (PyObject *o, Py_ssize_t index)

Read a character from a Unicode object o, which must be in the "canonical" representation. This is less efficient than $PyUnicode_READ$ () if you do multiple consecutive reads.

3.3 新版功能.

PyUnicode_MAX_CHAR_VALUE (PyObject *o)

Return the maximum code point that is suitable for creating another string based on o, which must be in the "canonical" representation. This is always an approximation but more efficient than iterating over the string.

3.3 新版功能.

int PyUnicode_ClearFreeList()

清空释放列表。返回所释放的条目数。

Py_ssize_t PyUnicode_GET_SIZE (PyObject *o)

Return the size of the deprecated $PY_UNICODE$ representation, in code units (this includes surrogate pairs as 2 units). o has to be a Unicode object (not checked).

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Unicode API, please migrate to using PyUnicode_GET_LENGTH().

Py_ssize_t PyUnicode_GET_DATA_SIZE (PyObject *o)

Return the size of the deprecated $Py_UNICODE$ representation in bytes. o has to be a Unicode object (not checked).

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Unicode API, please migrate to using <code>PyUnicode_GET_LENGTH()</code>.

Py_UNICODE* PyUnicode_AS_UNICODE (PyObject *o)

const char* PyUnicode_AS_DATA (PyObject *o)

Return a pointer to a $Py_UNICODE$ representation of the object. The returned buffer is always terminated with an extra null code point. It may also contain embedded null code points, which would cause the string to be truncated when used in most C functions. The AS_DATA form casts the pointer to const_char *. The o argument has to be a Unicode object (not checked).

在 3.3 版更改: This macro is now inefficient -- because in many cases the <code>Py_UNICODE</code> representation does not exist and needs to be created -- and can fail (return <code>NULL</code> with an exception set). Try to port the code to use the new <code>PyUnicode_nBYTE_DATA()</code> macros or use <code>PyUnicode_WRITE()</code> or <code>PyUnicode_READ()</code>.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Unicode API, please migrate to using the PyUnicode_nBYTE_DATA() family of macros.

Unicode 字符属性

Unicode provides many different character properties. The most often needed ones are available through these macros which are mapped to C functions depending on the Python configuration.

int Py_UNICODE_ISSPACE (Py_UNICODE ch)

Return 1 or 0 depending on whether ch is a whitespace character.

int Py_UNICODE_ISLOWER (Py_UNICODE ch)

Return 1 or 0 depending on whether *ch* is a lowercase character.

int Py UNICODE ISUPPER (Py UNICODE ch)

Return 1 or 0 depending on whether ch is an uppercase character.

int Py_UNICODE_ISTITLE (Py_UNICODE ch)

Return 1 or 0 depending on whether ch is a titlecase character.

int Py_UNICODE_ISLINEBREAK (Py_UNICODE ch)

Return 1 or 0 depending on whether *ch* is a linebreak character.

int Py UNICODE ISDECIMAL (Py UNICODE ch)

Return 1 or 0 depending on whether ch is a decimal character.

int Py_UNICODE_ISDIGIT (Py_UNICODE ch)

Return 1 or 0 depending on whether ch is a digit character.

int Py_UNICODE_ISNUMERIC (Py_UNICODE ch)

Return 1 or 0 depending on whether ch is a numeric character.

int Py_UNICODE_ISALPHA (Py_UNICODE ch)

Return 1 or 0 depending on whether *ch* is an alphabetic character.

int Py_UNICODE_ISALNUM (Py_UNICODE ch)

Return 1 or 0 depending on whether ch is an alphanumeric character.

int Py_UNICODE_ISPRINTABLE (Py_UNICODE ch)

Return 1 or 0 depending on whether ch is a printable character. Nonprintable characters are those characters defined in the Unicode character database as "Other" or "Separator", excepting the ASCII space (0x20) which is considered printable. (Note that printable characters in this context are those which should not be escaped when repr() is invoked on a string. It has no bearing on the handling of strings written to sys.stdout or sys.stdout.)

These APIs can be used for fast direct character conversions:

Py_UNICODE Py_UNICODE_TOLOWER (Py_UNICODE ch)

Return the character ch converted to lower case.

3.3 版后已移除: This function uses simple case mappings.

Py_UNICODE Py_UNICODE_TOUPPER (Py_UNICODE ch)

Return the character *ch* converted to upper case.

3.3 版后已移除: This function uses simple case mappings.

Py_UNICODE Py_UNICODE_TOTITLE (Py_UNICODE ch)

Return the character *ch* converted to title case.

3.3 版后已移除: This function uses simple case mappings.

int Py_UNICODE_TODECIMAL (Py_UNICODE ch)

Return the character ch converted to a decimal positive integer. Return -1 if this is not possible. This macro does not raise exceptions.

int Py_UNICODE_TODIGIT (Py_UNICODE ch)

Return the character ch converted to a single digit integer. Return -1 if this is not possible. This macro does not raise exceptions.

double Py_UNICODE_TONUMERIC (Py_UNICODE ch)

Return the character ch converted to a double. Return -1.0 if this is not possible. This macro does not raise exceptions.

These APIs can be used to work with surrogates:

Py UNICODE IS SURROGATE (ch)

Check if ch is a surrogate (0xD800 <= ch <= 0xDFFF).

Py_UNICODE_IS_HIGH_SURROGATE (ch)

Check if ch is a high surrogate (0xD800 <= ch <= 0xDBFF).

Py_UNICODE_IS_LOW_SURROGATE (ch)

Check if ch is a low surrogate (0xDC00 <= ch <= 0xDFFF).

Py_UNICODE_JOIN_SURROGATES (high, low)

Join two surrogate characters and return a single Py_UCS4 value. *high* and *low* are respectively the leading and trailing surrogates in a surrogate pair.

Creating and accessing Unicode strings

To create Unicode objects and access their basic sequence properties, use these APIs:

PyObject* PyUnicode_New (Py_ssize_t size, Py_UCS4 maxchar)

Return value: New reference. Create a new Unicode object. *maxchar* should be the true maximum code point to be placed in the string. As an approximation, it can be rounded up to the nearest value in the sequence 127, 255, 65535, 1114111.

This is the recommended way to allocate a new Unicode object. Objects created using this function are not resizable.

3.3 新版功能.

PyObject* PyUnicode_FromKindAndData (int kind, const void *buffer, Py_ssize_t size)

Return value: New reference. Create a new Unicode object with the given kind (possible values are PyUnicode_1BYTE_KIND etc., as returned by PyUnicode_KIND()). The buffer must point to an array of size units of 1, 2 or 4 bytes per character, as given by the kind.

3.3 新版功能.

PyObject* PyUnicode_FromStringAndSize (const char *u, Py_ssize_t size)

Return value: New reference. Create a Unicode object from the char buffer *u*. The bytes will be interpreted as being UTF-8 encoded. The buffer is copied into the new object. If the buffer is not NULL, the return value might be a shared object, i.e. modification of the data is not allowed.

If u is NULL, this function behaves like $PyUnicode_FromUnicode$ () with the buffer set to NULL. This usage is deprecated in favor of $PyUnicode_New$ ().

PyObject *PyUnicode_FromString (const char *u)

Return value: New reference. Create a Unicode object from a UTF-8 encoded null-terminated char buffer u.

PyObject* PyUnicode_FromFormat (const char *format, ...)

Return value: New reference. Take a C printf()-style format string and a variable number of arguments, calculate the size of the resulting Python Unicode string and return a string with the values formatted into it. The variable arguments must be C types and must correspond exactly to the format characters in the format ASCII-encoded string. The following format characters are allowed:

| 格式字符 | 类型 | 注释 |
|------|------------------------|-------------------------------------------------------------------|
| 응응 | 不适用 | 文字%字符。 |
| %C | 整型 | 单个字符,表示为 C 语言的整型。 |
| %d | 整型 | 相当于 printf("%d"). |
| %u | 无符号整型 | 相当于 printf("%u"). ¹ |
| %ld | 长整型 | 相当于 printf("%ld").1 |
| %li | 长整型 | 相当于 printf("%li").1 |
| %lu | 无符号长整型 | 相当于 printf("%lu").1 |
| %lld | long long | 相当于 printf("%lld"). ¹ |
| %lli | long long | 相当于 printf("%lli"). ¹ |
| %llu | 无符号 long long | 相当于 printf("%llu"). ^l |
| %zd | Py_ssize_t | 相当于 printf("%zd").1 |
| %zi | Py_ssize_t | 相当于 printf("%zi").1 |
| %zu | size_t | 相当于 printf("%zu").1 |
| %i | 整型 | 相当于 printf("%i").1 |
| %X | 整型 | 相当于 printf("%x").1 |
| %S | const char* | A null-terminated C character array. |
| %p | const void* | The hex representation of a C pointer. Mostly equivalent to |
| | | printf("%p") except that it is guaranteed to start with the |
| | | literal 0x regardless of what the platform's printf yields. |
| %A | PyObject* | ascii() 调用的结果。 |
| 용U | PyObject* | A Unicode object. |
| 용V | PyObject*, const char* | A Unicode object (which may be NULL) and a null-terminated C |
| | | character array as a second parameter (which will be used, if the |
| | | first parameter is NULL). |
| %S | PyObject* | The result of calling PyObject_Str(). |
| %R | PyObject* | The result of calling PyObject_Repr(). |

An unrecognized format character causes all the rest of the format string to be copied as-is to the result string, and any extra arguments discarded.

注解: The width formatter unit is number of characters rather than bytes. The precision formatter unit is number of bytes for "%s" and "%V" (if the PyObject* argument is NULL), and a number of characters for "%A", "%U", "%S", "%R" and "%V" (if the PyObject* argument is not NULL).

在 3.2 版更改: Support for "%lld" and "%llu" added.

在 3.3 版更改: Support for "%li", "%lli" and "%zi" added.

在 3.4 版更改: Support width and precision formatter for "%s", "%A", "%U", "%V", "%S", "%R" added.

PyObject* PyUnicode_FromFormatV (const char *format, va_list vargs)

Return value: New reference. Identical to PyUnicode_FromFormat() except that it takes exactly two arguments.

PyObject* PyUnicode_FromEncodedObject (PyObject *obj, const char *encoding, const char *errors)

Return value: New reference. Decode an encoded object obj to a Unicode object.

bytes, bytearray and other *bytes-like objects* are decoded according to the given *encoding* and using the error handling defined by *errors*. Both can be NULL to have the interface use the default values (see *Built-in Codecs* for details).

All other objects, including Unicode objects, cause a TypeError to be set.

The API returns NULL if there was an error. The caller is responsible for decrefing the returned objects.

Py_ssize_t PyUnicode_GetLength (PyObject *unicode)

Return the length of the Unicode object, in code points.

¹ For integer specifiers (d, u, ld, li, lu, lld, lli, llu, zd, zi, zu, i, x): the 0-conversion flag has effect even when a precision is given.

3.3 新版功能.

Py_ssize_t PyUnicode_CopyCharacters (*PyObject* *to, Py_ssize_t to_start, PyObject *from, Py_ssize_t from_start, Py_ssize_t how_many)

Copy characters from one Unicode object into another. This function performs character conversion when necessary and falls back to memcpy() if possible. Returns -1 and sets an exception on error, otherwise returns the number of copied characters.

3.3 新版功能.

Py_ssize_t PyUnicode_Fill (PyObject *unicode, Py_ssize_t start, Py_ssize_t length, Py_UCS4 fill_char) Fill a string with a character: write fill_char into unicode[start:start+length].

Fail if *fill char* is bigger than the string maximum character, or if the string has more than 1 reference.

Return the number of written character, or return -1 and raise an exception on error.

3.3 新版功能.

int PyUnicode_WriteChar (PyObject *unicode, Py_ssize_t index, Py_UCS4 character)

Write a character to a string. The string must have been created through <code>PyUnicode_New()</code>. Since Unicode strings are supposed to be immutable, the string must not be shared, or have been hashed yet.

This function checks that *unicode* is a Unicode object, that the index is not out of bounds, and that the object can be modified safely (i.e. that it its reference count is one).

3.3 新版功能.

Py_UCS4 PyUnicode_ReadChar (PyObject *unicode, Py_ssize_t index)

Read a character from a string. This function checks that *unicode* is a Unicode object and the index is not out of bounds, in contrast to the macro version <code>PyUnicode_READ_CHAR()</code>.

3.3 新版功能.

PyObject* PyUnicode_Substring (PyObject *str, Py_ssize_t start, Py_ssize_t end)

Return value: New reference. Return a substring of *str*, from character index *start* (included) to character index *end* (excluded). Negative indices are not supported.

3.3 新版功能.

Py UCS4* PyUnicode AsUCS4 (PyObject *u, Py UCS4 *buffer, Py ssize t buflen, int copy null)

Copy the string u into a UCS4 buffer, including a null character, if $copy_null$ is set. Returns NULL and sets an exception on error (in particular, a SystemError if buflen is smaller than the length of u). buffer is returned on success.

3.3 新版功能.

Py_UCS4* PyUnicode_AsUCS4Copy (PyObject *u)

Copy the string u into a new UCS4 buffer that is allocated using $PyMem_Malloc()$. If this fails, NULL is returned with a MemoryError set. The returned buffer always has an extra null code point appended.

3.3 新版功能.

Deprecated Py_UNICODE APIs

Deprecated since version 3.3, will be removed in version 4.0.

These API functions are deprecated with the implementation of **PEP 393**. Extension modules can continue using them, as they will not be removed in Python 3.x, but need to be aware that their use can now cause performance and memory hits.

PyObject* PyUnicode_FromUnicode (const Py_UNICODE *u, Py_ssize_t size)

Return value: New reference. Create a Unicode object from the Py_UNICODE buffer u of the given size. u may be NULL which causes the contents to be undefined. It is the user's responsibility to fill in the needed data. The buffer is copied into the new object.

If the buffer is not NULL, the return value might be a shared object. Therefore, modification of the resulting Unicode object is only allowed when u is NULL.

If the buffer is NULL, *PyUnicode_READY()* must be called once the string content has been filled before using any of the access macros such as *PyUnicode_KIND()*.

Please migrate to using PyUnicode_FromKindAndData(), PyUnicode_FromWideChar() or PyUnicode New().

Py_UNICODE* PyUnicode_AsUnicode (PyObject *unicode)

Return a read-only pointer to the Unicode object's internal $Py_UNICODE$ buffer, or NULL on error. This will create the $Py_UNICODE*$ representation of the object if it is not yet available. The buffer is always terminated with an extra null code point. Note that the resulting $Py_UNICODE$ string may also contain embedded null code points, which would cause the string to be truncated when used in most C functions.

Please migrate to using PyUnicode_AsUCS4(), PyUnicode_AsWideChar(), PyUnicode_ReadChar() or similar new APIs.

PyObject* PyUnicode_TransformDecimalToASCII (Py_UNICODE *s, Py_ssize_t size)

Return value: New reference. Create a Unicode object by replacing all decimal digits in *Py_UNICODE* buffer of the given *size* by ASCII digits 0--9 according to their decimal value. Return NULL if an exception occurs.

Py_UNICODE* PyUnicode_AsUnicodeAndSize (PyObject *unicode, Py_ssize_t *size)

Like $PyUnicode_AsUnicode()$, but also saves the $Py_UNICODE()$ array length (excluding the extra null terminator) in *size*. Note that the resulting $Py_UNICODE*$ string may contain embedded null code points, which would cause the string to be truncated when used in most C functions.

3.3 新版功能.

Py_UNICODE* PyUnicode_AsUnicodeCopy (PyObject *unicode)

Create a copy of a Unicode string ending with a null code point. Return NULL and raise a MemoryError exception on memory allocation failure, otherwise return a new allocated buffer (use $PyMem_Free()$) to free the buffer). Note that the resulting $Py_UNICODE*$ string may contain embedded null code points, which would cause the string to be truncated when used in most C functions.

3.2 新版功能.

Please migrate to using PyUnicode_AsUCS4Copy() or similar new APIs.

Py_ssize_t PyUnicode_GetSize (PyObject *unicode)

Return the size of the deprecated *Py_UNICODE* representation, in code units (this includes surrogate pairs as 2 units).

Please migrate to using PyUnicode_GetLength().

PyObject* PyUnicode_FromObject (PyObject *obj)

Return value: New reference. Copy an instance of a Unicode subtype to a new true Unicode object if necessary. If *obj* is already a true Unicode object (not a subtype), return the reference with incremented refcount.

Objects other than Unicode or its subtypes will cause a TypeError.

Locale Encoding

The current locale encoding can be used to decode text from the operating system.

PyObject* PyUnicode_DecodeLocaleAndSize (const char *str, Py_ssize_t len, const char *errors)

Return value: New reference. Decode a string from UTF-8 on Android and VxWorks, or from the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogatescape" (PEP 383). The decoder uses "strict" error handler if errors is NULL. str must end with a null character but cannot contain embedded null characters.

Use <code>PyUnicode_DecodeFSDefaultAndSize()</code> to decode a string from <code>Py_FileSystemDefaultEncoding()</code> the locale encoding read at Python startup).

This function ignores the Python UTF-8 mode.

参见:

The Py_DecodeLocale() function.

3.3 新版功能.

在 3.7 版更改: The function now also uses the current locale encoding for the surrogateescape error handler, except on Android. Previously, <code>Py_DecodeLocale()</code> was used for the surrogateescape, and the current locale encoding was used for strict.

PyObject* PyUnicode_DecodeLocale (const char *str, const char *errors)

Return value: New reference. Similar to $PyUnicode_DecodeLocaleAndSize()$, but compute the string length using strlen().

3.3 新版功能.

PyObject* PyUnicode_EncodeLocale (PyObject *unicode, const char *errors)

Return value: New reference. Encode a Unicode object to UTF-8 on Android and VxWorks, or to the current locale encoding on other platforms. The supported error handlers are "strict" and "surrogateescape" (PEP 383). The encoder uses "strict" error handler if errors is NULL. Return a bytes object. unicode cannot contain embedded null characters.

Use PyUnicode_EncodeFSDefault() to encode a string to Py_FileSystemDefaultEncoding (the locale encoding read at Python startup).

This function ignores the Python UTF-8 mode.

参见:

The Py_EncodeLocale() function.

3.3 新版功能.

在 3.7 版更改: The function now also uses the current locale encoding for the <code>surrogateescape</code> error handler, except on Android. Previously, <code>Py_EncodeLocale()</code> was used for the <code>surrogateescape</code>, and the current locale encoding was used for <code>strict</code>.

File System Encoding

To encode and decode file names and other environment strings, Py_FileSystemDefaultEncoding should be used as the encoding, and Py_FileSystemDefaultEncodeErrors should be used as the error handler (PEP 383 and PEP 529). To encode file names to bytes during argument parsing, the "O&" converter should be used, passing PyUnicode FSConverter() as the conversion function:

int PyUnicode_FSConverter (*PyObject* obj*, void* *result*)

ParseTuple converter: encode str objects -- obtained directly or through the os.PathLike interface -- to bytes using PyUnicode_EncodeFSDefault(); bytes objects are output as-is. result must be a PyBytesObject* which must be released when it is no longer used.

3.1 新版功能.

在 3.6 版更改: 接受一个类路径对象。

To decode file names to str during argument parsing, the "O&" converter should be used, passing PyUnicode_FSDecoder() as the conversion function:

int PyUnicode_FSDecoder (PyObject* obj, void* result)

ParseTuple converter: decode bytes objects -- obtained either directly or indirectly through the os. PathLike interface -- to str using <code>PyUnicode_DecodeFSDefaultAndSize()</code>; str objects are output as-is. <code>result</code> must be a <code>PyUnicodeObject*</code> which must be released when it is no longer used.

3.2 新版功能.

在 3.6 版更改:接受一个类路径对象。

PyObject* PyUnicode_DecodeFSDefaultAndSize (const char *s, Py_ssize_t size)

Return value: New reference. Decode a string using Py_FileSystemDefaultEncoding and the Py_FileSystemDefaultEncodeErrors error handler.

If Py_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Py_FileSystemDefaultEncoding is initialized at startup from the locale encoding and cannot be modified later. If you need to decode a string from the current locale encoding, use PyUnicode_DecodeLocaleAndSize().

参见:

The Py_DecodeLocale() function.

在 3.6 版更改: Use Py_FileSystemDefaultEncodeErrors error handler.

PyObject* PyUnicode_DecodeFSDefault (const char *s)

Return value: New reference. Decode a null-terminated string using Py_FileSystemDefaultEncoding and the Py_FileSystemDefaultEncodeErrors error handler.

If Py_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Use PyUnicode_DecodeFSDefaultAndSize() if you know the string length.

在 3.6 版更改: Use Py_FileSystemDefaultEncodeErrors error handler.

PyObject* PyUnicode_EncodeFSDefault (PyObject *unicode)

Return value: New reference. Encode a Unicode object to Py_FileSystemDefaultEncoding with the Py_FileSystemDefaultEncodeErrors error handler, and return bytes. Note that the resulting bytes object may contain null bytes.

If Py_FileSystemDefaultEncoding is not set, fall back to the locale encoding.

Py_FileSystemDefaultEncoding is initialized at startup from the locale encoding and cannot be modified later. If you need to encode a string to the current locale encoding, use $PyUnicode_EncodeLocale()$.

参见:

The $Py_EncodeLocale()$ function.

3.2 新版功能.

在 3.6 版更改: Use Py_FileSystemDefaultEncodeErrors error handler.

wchar_t Support

wchar_t support for platforms which support it:

PyObject* PyUnicode_FromWideChar (const wchar_t *w, Py_ssize_t size)

Return value: New reference. Create a Unicode object from the wchar_t buffer w of the given *size*. Passing -1 as the *size* indicates that the function must itself compute the length, using wcslen. Return NULL on failure.

Py_ssize_t PyUnicode_AsWideChar (PyObject *unicode, wchar_t *w, Py_ssize_t size)

Copy the Unicode object contents into the wchar_t buffer w. At most size wchar_t characters are copied (excluding a possibly trailing null termination character). Return the number of wchar_t characters copied or -1 in case of an error. Note that the resulting wchar_t* string may or may not be null-terminated. It is the responsibility of the caller to make sure that the wchar_t* string is null-terminated in case this is required by the application. Also, note that the wchar_t* string might contain null characters, which would cause the string to be truncated when used with most C functions.

wchar_t* PyUnicode_AsWideCharString (PyObject *unicode, Py_ssize_t *size)

Convert the Unicode object to a wide character string. The output string always ends with a null character. If *size* is not NULL, write the number of wide characters (excluding the trailing null termination character) into *size. Note that the resulting wchar_t string might contain null characters, which would cause the string to be truncated when used with most C functions. If size is NULL and the wchar_t* string contains null characters a ValueError is raised.

Returns a buffer allocated by PyMem_Alloc() (use PyMem_Free() to free it) on success. On error, returns NULL and *size is undefined. Raises a MemoryError if memory allocation is failed.

3.2 新版功能.

在 3.7 版更改: Raises a ValueError if size is NULL and the wchar_t* string contains null characters.

Built-in Codecs

Python provides a set of built-in codecs which are written in C for speed. All of these codecs are directly usable via the following functions.

Many of the following APIs take two arguments encoding and errors, and they have the same semantics as the ones of the built-in str() string object constructor.

Setting encoding to NULL causes the default encoding to be used which is ASCII. The file system calls should use <code>PyUnicode_FSConverter()</code> for encoding file names. This uses the variable <code>Py_FileSystemDefaultEncoding</code> internally. This variable should be treated as read-only: on some systems, it will be a pointer to a static string, on others, it will change at run-time (such as when the application invokes setlocale).

Error handling is set by errors which may also be set to NULL meaning to use the default handling defined for the codec. Default error handling for all built-in codecs is "strict" (ValueError is raised).

The codecs all use a similar interface. Only deviation from the following generic ones are documented for simplicity.

Generic Codecs

These are the generic codec APIs:

PyObject* PyUnicode_Decode (const char *s, Py_ssize_t size, const char *encoding, const char *errors)

Return value: New reference. Create a Unicode object by decoding size bytes of the encoded string s. encoding and errors have the same meaning as the parameters of the same name in the str() built-in function. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_AsEncodedString (PyObject *unicode, const char *encoding, const char *errors)

Return value: New reference. Encode a Unicode object and return the result as Python bytes object. encoding and errors have the same meaning as the parameters of the same name in the Unicode encode () method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_Encode (const Py_UNICODE *s, Py_ssize_t size, const char *encoding, const char *errors)

Return value: New reference. Encode the $Py_UNICODE$ buffer s of the given size and return a Python bytes object. encoding and errors have the same meaning as the parameters of the same name in the Unicode encode () method. The codec to be used is looked up using the Python codec registry. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_AsEncodedString()*.

UTF-8 Codecs

These are the UTF-8 codec APIs:

PyObject* PyUnicode_DecodeUTF8 (const char *s, Py_ssize_t size, const char *errors)

Return value: New reference. Create a Unicode object by decoding *size* bytes of the UTF-8 encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_DecodeUTF8Stateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)

Return value: New reference. If consumed is NULL, behave like PyUnicode_DecodeUTF8(). If consumed is not NULL, trailing incomplete UTF-8 byte sequences will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in consumed.

PyObject* PyUnicode_AsUTF8String (PyObject *unicode)

Return value: New reference. Encode a Unicode object using UTF-8 and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

```
const char* PyUnicode_AsUTF8AndSize (PyObject *unicode, Py_ssize_t *size)
```

Return a pointer to the UTF-8 encoding of the Unicode object, and store the size of the encoded representation (in bytes) in *size*. The *size* argument can be NULL; in this case no size will be stored. The returned buffer always has an extra null byte appended (not included in *size*), regardless of whether there are any other null code points.

In the case of an error, NULL is returned with an exception set and no size is stored.

This caches the UTF-8 representation of the string in the Unicode object, and subsequent calls will return a pointer to the same buffer. The caller is not responsible for deallocating the buffer.

3.3 新版功能.

在 3.7 版更改: The return type is now const char * rather of char *.

const char* PyUnicode_AsUTF8 (PyObject *unicode)

As PyUnicode_AsUTF8AndSize(), but does not store the size.

3.3 新版功能.

在 3.7 版更改: The return type is now const char * rather of char *.

PyObject* PyUnicode_EncodeUTF8 (const Py_UNICODE *s, Py_ssize_t size, const char *errors)

Return value: New reference. Encode the $Py_UNICODE$ buffer s of the given size using UTF-8 and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py_UNICODE API; please migrate to using PyUnicode_AsUTF8String(), PyUnicode_AsUTF8AndSize() or PyUnicode_AsEncodedString().

UTF-32 Codecs

These are the UTF-32 codec APIs:

PyObject* PyUnicode_DecodeUTF32 (const char *s, Py_ssize_t size, const char *errors, int *byteorder)

Return value: New reference. Decode size bytes from a UTF-32 encoded buffer string and return the corresponding Unicode object. errors (if non-NULL) defines the error handling. It defaults to "strict".

If byteorder is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If *byteorder is zero, and the first four bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *byteorder is -1 or 1, any byte order mark is copied to the output.

After completion, *byteorder is set to the current byte order at the end of input data.

If *byteorder* is NULL, the codec starts in native order mode.

Return NULL if an exception was raised by the codec.

```
PyObject* PyUnicode_DecodeUTF32Stateful (const char *s, Py_ssize_t size, const char *errors, int *byteorder, Py_ssize_t *consumed)
```

Return value: New reference. If consumed is NULL, behave like <code>PyUnicode_DecodeUTF32()</code>. If consumed is not <code>NULL</code>, <code>PyUnicode_DecodeUTF32Stateful()</code> will not treat trailing incomplete UTF-32 byte sequences (such as a number of bytes not divisible by four) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in <code>consumed</code>.

```
PyObject* PyUnicode_AsUTF32String (PyObject *unicode)
```

Return value: New reference. Return a Python byte string using the UTF-32 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return NULL if an exception was raised by the codec.

```
PyObject* PyUnicode_EncodeUTF32 (const Py_UNICODE *s, Py_ssize_t size, const char *errors, int by-teorder)
```

Return value: New reference. Return a Python bytes object holding the UTF-32 encoded value of the Unicode data in s. Output is written according to the following byte order:

```
byteorder == -1: little endian
byteorder == 0: native byte order (writes a BOM mark)
byteorder == 1: big endian
```

If byteorder is 0, the output string will always start with the Unicode BOM mark (U+FEFF). In the other two modes, no BOM mark is prepended.

If Py_UNICODE_WIDE is not defined, surrogate pairs will be output as a single code point.

Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_AsUTF32String()* or *PyUnicode_AsEncodedString()*.

UTF-16 Codecs

These are the UTF-16 codec APIs:

PyObject* PyUnicode_DecodeUTF16 (const char *s, Py_ssize_t size, const char *errors, int *byteorder)

Return value: New reference. Decode size bytes from a UTF-16 encoded buffer string and return the corresponding Unicode object. errors (if non-NULL) defines the error handling. It defaults to "strict".

If *byteorder* is non-NULL, the decoder starts decoding using the given byte order:

```
*byteorder == -1: little endian

*byteorder == 0: native order

*byteorder == 1: big endian
```

If *byteorder is zero, and the first two bytes of the input data are a byte order mark (BOM), the decoder switches to this byte order and the BOM is not copied into the resulting Unicode string. If *byteorder is -1 or 1, any byte order mark is copied to the output (where it will result in either a \ufeff or a \ufeffe character).

After completion, *byteorder is set to the current byte order at the end of input data.

If byteorder is NULL, the codec starts in native order mode.

Return \mathtt{NULL} if an exception was raised by the codec.

```
PyObject* PyUnicode_DecodeUTF16Stateful (const char *s, Py_ssize_t size, const char *errors, int *byteorder, Py_ssize_t *consumed)
```

Return value: New reference. If consumed is NULL, behave like PyUnicode_DecodeUTF16(). If consumed is not NULL, PyUnicode_DecodeUTF16Stateful() will not treat trailing incomplete UTF-16

byte sequences (such as an odd number of bytes or a split surrogate pair) as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in *consumed*.

PyObject* PyUnicode_AsUTF16String (PyObject *unicode)

Return value: New reference. Return a Python byte string using the UTF-16 encoding in native byte order. The string always starts with a BOM mark. Error handling is "strict". Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_EncodeUTF16 (const Py_UNICODE *s, Py_ssize_t size, const char *errors, int by-teorder)

Return value: New reference. Return a Python bytes object holding the UTF-16 encoded value of the Unicode data in *s.* Output is written according to the following byte order:

```
byteorder == -1: little endian
byteorder == 0: native byte order (writes a BOM mark)
byteorder == 1: big endian
```

If byteorder is 0, the output string will always start with the Unicode BOM mark (U+FEFF). In the other two modes, no BOM mark is prepended.

If Py_UNICODE_WIDE is defined, a single $Py_UNICODE$ value may get represented as a surrogate pair. If it is not defined, each $Py_UNICODE$ values is interpreted as a UCS-2 character.

Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_AsUTF16String()* or *PyUnicode_AsEncodedString()*.

UTF-7 Codecs

These are the UTF-7 codec APIs:

```
PyObject* PyUnicode_DecodeUTF7 (const char *s, Py_ssize_t size, const char *errors)
```

Return value: New reference. Create a Unicode object by decoding *size* bytes of the UTF-7 encoded string *s*. Return NULL if an exception was raised by the codec.

```
PyObject* PyUnicode_DecodeUTF7Stateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)
```

Return value: New reference. If consumed is NULL, behave like <code>PyUnicode_DecodeUTF7()</code>. If consumed is not NULL, trailing incomplete UTF-7 base-64 sections will not be treated as an error. Those bytes will not be decoded and the number of bytes that have been decoded will be stored in <code>consumed</code>.

```
PyObject* PyUnicode_EncodeUTF7 (const Py_UNICODE *s, Py_ssize_t size, int base64SetO, int base64WhiteSpace, const char *errors)
```

Return value: New reference. Encode the *Py_UNICODE* buffer of the given size using UTF-7 and return a Python bytes object. Return NULL if an exception was raised by the codec.

If *base64SetO* is nonzero, "Set O" (punctuation that has no otherwise special meaning) will be encoded in base-64. If *base64WhiteSpace* is nonzero, whitespace will be encoded in base-64. Both are set to zero for the Python "utf-7" codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_AsEncodedString()*.

Unicode-Escape Codecs

These are the "Unicode Escape" codec APIs:

PyObject* PyUnicode_DecodeUnicodeEscape (const char *s, Py_ssize_t size, const char *errors)

Return value: New reference. Create a Unicode object by decoding size bytes of the Unicode-Escape encoded string s. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_AsUnicodeEscapeString (PyObject *unicode)

Return value: New reference. Encode a Unicode object using Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_EncodeUnicodeEscape (const Py_UNICODE *s, Py_ssize_t size)

Return value: New reference. Encode the *Py_UNICODE* buffer of the given *size* using Unicode-Escape and return a bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_AsUnicodeEscapeString()*.

Raw-Unicode-Escape Codecs

These are the "Raw Unicode Escape" codec APIs:

PyObject* PyUnicode_DecodeRawUnicodeEscape (const char *s, Py_ssize_t size, const char *er-

Return value: New reference. Create a Unicode object by decoding *size* bytes of the Raw-Unicode-Escape encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_AsRawUnicodeEscapeString (PyObject *unicode)

Return value: New reference. Encode a Unicode object using Raw-Unicode-Escape and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_EncodeRawUnicodeEscape (const Py_UNICODE *s, Py_ssize_t size)

Return value: New reference. Encode the *Py_UNICODE* buffer of the given *size* using Raw-Unicode-Escape and return a bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py_UNICODE API; please migrate to using PyUnicode_AsRawUnicodeEscapeString() or PyUnicode_AsEncodedString().

Latin-1 Codecs

These are the Latin-1 codec APIs: Latin-1 corresponds to the first 256 Unicode ordinals and only these are accepted by the codecs during encoding.

PyObject* PyUnicode DecodeLatin1 (const char *s, Py ssize t size, const char *errors)

Return value: New reference. Create a Unicode object by decoding *size* bytes of the Latin-1 encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_AsLatin1String (PyObject *unicode)

Return value: New reference. Encode a Unicode object using Latin-1 and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_EncodeLatin1 (const Py_UNICODE *s, Py_ssize_t size, const char *errors)

Return value: New reference. Encode the *Py_UNICODE* buffer of the given *size* using Latin-1 and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_AsLatin1String()* or *PyUnicode_AsEncodedString()*.

ASCII Codecs

These are the ASCII codec APIs. Only 7-bit ASCII data is accepted. All other codes generate errors.

PyObject* PyUnicode_DecodeASCII (const char *s, Py_ssize_t size, const char *errors)

Return value: New reference. Create a Unicode object by decoding *size* bytes of the ASCII encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_AsASCIIString (PyObject *unicode)

Return value: New reference. Encode a Unicode object using ASCII and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_EncodeASCII (const Py_UNICODE *s, Py_ssize_t size, const char *errors)

Return value: New reference. Encode the *Py_UNICODE* buffer of the given *size* using ASCII and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_AsASCIIString()* or *PyUnicode_AsEncodedString()*.

Character Map Codecs

This codec is special in that it can be used to implement many different codecs (and this is in fact what was done to obtain most of the standard codecs included in the <code>encodings</code> package). The codec uses mapping to encode and decode characters. The mapping objects provided must support the <code>__getitem__()</code> mapping interface; dictionaries and sequences work well.

These are the mapping codec APIs:

PyObject* PyUnicode_DecodeCharmap (const char *data, Py_ssize_t size, PyObject *mapping, const char *errors)

Return value: New reference. Create a Unicode object by decoding *size* bytes of the encoded string *s* using the given *mapping* object. Return NULL if an exception was raised by the codec.

If mapping is NULL, Latin-1 decoding will be applied. Else mapping must map bytes ordinals (integers in the range from 0 to 255) to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None. Unmapped data bytes -- ones which cause a LookupError, as well as ones which get mapped to None, 0xFFFE or '\ufffe', are treated as undefined mappings and cause an error.

PyObject* PyUnicode_AsCharmapString (PyObject *unicode, PyObject *mapping)

Return value: New reference. Encode a Unicode object using the given *mapping* object and return the result as a bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

The *mapping* object must map Unicode ordinal integers to bytes objects, integers in the range from 0 to 255 or None. Unmapped character ordinals (ones which cause a LookupError) as well as mapped to None are treated as "undefined mapping" and cause an error.

PyObject* PyUnicode_EncodeCharmap (const Py_UNICODE *s, Py_ssize_t size, PyObject *mapping, const char *errors)

const char *errors')

Return value: New reference. Encode the $Py_UNICODE$ buffer of the given size using the given mapping object and return the result as a bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode AsCharmapString()* or *PyUnicode AsEncodedString()*.

The following codec API is special in that maps Unicode to Unicode.

PyObject* PyUnicode_Translate (PyObject *unicode, PyObject *mapping, const char *errors)

Return value: New reference. Translate a Unicode object using the given *mapping* object and return the resulting Unicode object. Return NULL if an exception was raised by the codec.

The *mapping* object must map Unicode ordinal integers to Unicode strings, integers (which are then interpreted as Unicode ordinals) or None (causing deletion of the character). Unmapped character ordinals (ones which cause a LookupError) are left untouched and are copied as-is.

PyObject* PyUnicode_TranslateCharmap (const Py_UNICODE *s, Py_ssize_t size, PyObject *map-ping, const char *errors)

Return value: New reference. Translate a $Py_UNICODE$ buffer of the given size by applying a character mapping table to it and return the resulting Unicode object. Return NULL when an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style *Py_UNICODE* API; please migrate to using *PyUnicode_Translate()*. or *generic codec based API*

MBCS codecs for Windows

These are the MBCS codec APIs. They are currently only available on Windows and use the Win32 MBCS converters to implement the conversions. Note that MBCS (or DBCS) is a class of encodings, not just one. The target encoding is defined by the user settings on the machine running the codec.

PyObject* PyUnicode_DecodeMBCS (const char *s, Py_ssize_t size, const char *errors)

Return value: New reference. Create a Unicode object by decoding *size* bytes of the MBCS encoded string *s*. Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_DecodeMBCSStateful (const char *s, Py_ssize_t size, const char *errors, Py_ssize_t *consumed)

Return value: New reference. If consumed is NULL, behave like <code>PyUnicode_DecodeMBCS()</code>. If consumed is not <code>NULL</code>, <code>PyUnicode_DecodeMBCSStateful()</code> will not decode trailing lead byte and the number of bytes that have been decoded will be stored in <code>consumed</code>.

PyObject* PyUnicode_AsMBCSString (PyObject *unicode)

Return value: New reference. Encode a Unicode object using MBCS and return the result as Python bytes object. Error handling is "strict". Return NULL if an exception was raised by the codec.

PyObject* PyUnicode_EncodeCodePage (int code_page, PyObject *unicode, const char *errors)

Return value: New reference. Encode the Unicode object using the specified code page and return a Python bytes object. Return NULL if an exception was raised by the codec. Use CP_ACP code page to get the MBCS encoder.

3.3 新版功能.

PyObject* PyUnicode_EncodeMBCS (const Py_UNICODE *s, Py_ssize_t size, const char *errors)

Return value: New reference. Encode the *Py_UNICODE* buffer of the given *size* using MBCS and return a Python bytes object. Return NULL if an exception was raised by the codec.

Deprecated since version 3.3, will be removed in version 4.0: Part of the old-style Py_UNICODE API; please migrate to using PyUnicode_AsMBCSString(), PyUnicode_EncodeCodePage() or PyUnicode_AsEncodedString().

Methods & Slots

Methods and Slot Functions

The following APIs are capable of handling Unicode objects and strings on input (we refer to them as strings in the descriptions) and return Unicode objects or integers as appropriate.

They all return NULL or −1 if an exception occurs.

PyObject* PyUnicode_Concat (PyObject *left, PyObject *right)

Return value: New reference. Concat two strings giving a new Unicode string.

PyObject* PyUnicode_Split (PyObject *s, PyObject *sep, Py_ssize_t maxsplit)

Return value: New reference. Split a string giving a list of Unicode strings. If *sep* is NULL, splitting will be done at all whitespace substrings. Otherwise, splits occur at the given separator. At most *maxsplit* splits will be done. If negative, no limit is set. Separators are not included in the resulting list.

PyObject* PyUnicode_Splitlines (PyObject *s, int keepend)

Return value: New reference. Split a Unicode string at line breaks, returning a list of Unicode strings. CRLF is considered to be one line break. If *keepend* is 0, the Line break characters are not included in the resulting strings.

PyObject* PyUnicode_Translate (PyObject *str, PyObject *table, const char *errors)

Translate a string by applying a character mapping table to it and return the resulting Unicode object.

The mapping table must map Unicode ordinal integers to Unicode ordinal integers or None (causing deletion of the character).

Mapping tables need only provide the __getitem__() interface; dictionaries and sequences work well. Unmapped character ordinals (ones which cause a LookupError) are left untouched and are copied as-is.

errors has the usual meaning for codecs. It may be NULL which indicates to use the default error handling.

PyObject* PyUnicode_Join (PyObject *separator, PyObject *seq)

Return value: New reference. Join a sequence of strings using the given separator and return the resulting Unicode string.

Py_ssize_t PyUnicode_Tailmatch (PyObject *str, PyObject *substr, Py_ssize_t start, Py_ssize_t end, int direction)

Return 1 if *substr* matches str[start:end] at the given tail end (*direction* == -1 means to do a prefix match, *direction* == 1 a suffix match), 0 otherwise. Return -1 if an error occurred.

Py_ssize_t PyUnicode_Find (PyObject *str, PyObject *substr, Py_ssize_t start, Py_ssize_t end, int direction)

Return the first position of *substr* in str[start:end] using the given *direction* (*direction* == 1 means to do a forward search, *direction* == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

Py_ssize_t PyUnicode_FindChar (PyObject *str, Py_UCS4 ch, Py_ssize_t start, Py_ssize_t end, int direction)

Return the first position of the character ch in str[start:end] using the given direction (direction == 1 means to do a forward search, direction == -1 a backward search). The return value is the index of the first match; a value of -1 indicates that no match was found, and -2 indicates that an error occurred and an exception has been set.

3.3 新版功能.

在 3.7 版更改: start and end are now adjusted to behave like str[start:end].

Py_ssize_t PyUnicode_Count (PyObject *str, PyObject *substr, Py_ssize_t start, Py_ssize_t end)

Return the number of non-overlapping occurrences of *substr* in str[start:end]. Return -1 if an error occurred.

PyObject* PyUnicode_Replace (PyObject *str, PyObject *substr, PyObject *replstr, Py_ssize_t max-count)

Return value: New reference. Replace at most maxcount occurrences of substr in str with replstr and return the resulting Unicode object. maxcount == -1 means replace all occurrences.

int PyUnicode_Compare (PyObject *left, PyObject *right)

Compare two strings and return -1, 0, 1 for less than, equal, and greater than, respectively.

This function returns -1 upon failure, so one should call PyErr_Occurred() to check for errors.

int PyUnicode_CompareWithASCIIString (PyObject *uni, const char *string)

Compare a Unicode object, uni, with string and return -1, 0, 1 for less than, equal, and greater than, respectively. It is best to pass only ASCII-encoded strings, but the function interprets the input string as ISO-8859-1 if it contains non-ASCII characters.

This function does not raise exceptions.

PyObject* PyUnicode_RichCompare (PyObject *left, PyObject *right, int op)

Return value: New reference. Rich compare two Unicode strings and return one of the following:

• NULL in case an exception was raised

8.3. 序列对象 103

- Py_True or Py_False for successful comparisons
- Py_NotImplemented in case the type combination is unknown

Possible values for op are Py_GT, Py_GE, Py_EQ, Py_NE, Py_LT, and Py_LE.

PyObject* PyUnicode_Format (PyObject *format, PyObject *args)

Return value: New reference. Return a new string object from format and args; this is analogous to format % args.

int PyUnicode_Contains (PyObject *container, PyObject *element)

Check whether *element* is contained in *container* and return true or false accordingly.

element has to coerce to a one element Unicode string. -1 is returned if there was an error.

void PyUnicode_InternInPlace (PyObject **string)

Intern the argument *string in place. The argument must be the address of a pointer variable pointing to a Python Unicode string object. If there is an existing interned string that is the same as *string, it sets *string to it (decrementing the reference count of the old string object and incrementing the reference count of the interned string object), otherwise it leaves *string alone and interns it (incrementing its reference count). (Clarification: even though there is a lot of talk about reference counts, think of this function as reference-count-neutral; you own the object after the call if and only if you owned it before the call.)

PyObject* PyUnicode_InternFromString (const char *v)

Return value: New reference. A combination of PyUnicode_FromString() and PyUnicode_InternInPlace(), returning either a new Unicode string object that has been interned, or a new ("owned") reference to an earlier interned string object with the same value.

8.3.4 元组对象

PyTupleObject

这个PyObject 的子类型代表一个 Python 的元组对象。

PyTypeObject PyTuple_Type

PyTypeObject 的实例代表一个 Python 元组类型,这与 Python 层面的 tuple 是相同的对象。

int PyTuple_Check (PyObject *p)

如果p是一个元组对象或者元组类型的子类型的实例,则返回真值。

int PyTuple_CheckExact (PyObject *p)

如果p是一个元组对象,而不是一个元组子类型的实例,则返回真值。

PyObject* PyTuple_New (Py_ssize_t len)

Return value: New reference. Return a new tuple object of size len, or NULL on failure.

PyObject* PyTuple_Pack (Py_ssize_t n, ...)

Return value: New reference. Return a new tuple object of size n, or NULL on failure. The tuple values are initialized to the subsequent n C arguments pointing to Python objects. PyTuple_Pack(2, a, b) is equivalent to Py_BuildValue("(00)", a, b).

Py_ssize_t PyTuple_Size (PyObject *p)

Take a pointer to a tuple object, and return the size of that tuple.

Py_ssize_t PyTuple_GET_SIZE (PyObject *p)

Return the size of the tuple p, which must be non-NULL and point to a tuple; no error checking is performed.

PyObject* PyTuple_GetItem (PyObject *p, Py_ssize_t pos)

Return value: Borrowed reference. Return the object at position *pos* in the tuple pointed to by *p*. If *pos* is out of bounds, return NULL and set an IndexError exception.

PyObject* PyTuple_GET_ITEM (PyObject *p, Py_ssize_t pos)

Return value: Borrowed reference. Like PyTuple_GetItem(), but does no checking of its arguments.

PyObject* PyTuple_GetSlice (PyObject *p, Py_ssize_t low, Py_ssize_t high)

Return value: New reference. Return the slice of the tuple pointed to by p between low and high, or NULL on

failure. This is the equivalent of the Python expression p[low:high]. Indexing from the end of the list is not supported.

int PyTuple_SetItem (PyObject *p, Py_ssize_t pos, PyObject *o)

Insert a reference to object o at position pos of the tuple pointed to by p. Return 0 on success. If pos is out of bounds, return -1 and set an IndexError exception.

注解: This function "steals" a reference to o and discards a reference to an item already in the tuple at the affected position.

void **PyTuple SET ITEM** (*PyObject* *p, Py ssize t pos, *PyObject* *o)

Like PyTuple_SetItem(), but does no error checking, and should *only* be used to fill in brand new tuples.

注解: This macro "steals" a reference to o, and, unlike <code>PyTuple_SetItem()</code>, does not discard a reference to any item that is being replaced; any reference in the tuple at position pos will be leaked.

int **_PyTuple_Resize** (*PyObject* **p, Py_ssize_t newsize)

Can be used to resize a tuple. *newsize* will be the new length of the tuple. Because tuples are *supposed* to be immutable, this should only be used if there is only one reference to the object. Do *not* use this if the tuple may already be known to some other part of the code. The tuple will always grow or shrink at the end. Think of this as destroying the old tuple and creating a new one, only more efficiently. Returns 0 on success. Client code should never assume that the resulting value of *p will be the same as before calling this function. If the object referenced by *p is replaced, the original *p is destroyed. On failure, returns -1 and sets *p to NULL, and raises MemoryError or SystemError.

int PyTuple_ClearFreeList()

清空释放列表。返回所释放的条目数。

8.3.5 Struct Sequence Objects

Struct sequence objects are the C equivalent of namedtuple () objects, i.e. a sequence whose items can also be accessed through attributes. To create a struct sequence, you first have to create a specific struct sequence type.

PyTypeObject* PyStructSequence_NewType (PyStructSequence_Desc *desc)

Return value: New reference. Create a new struct sequence type from the data in desc, described below. Instances of the resulting type can be created with PyStructSequence_New().

void PyStructSequence_InitType (PyTypeObject *type, PyStructSequence_Desc *desc)

Initializes a struct sequence type type from desc in place.

int PyStructSequence_InitType2 (PyTypeObject *type, PyStructSequence_Desc *desc)

The same as PyStructSequence_InitType, but returns 0 on success and -1 on failure.

3.4 新版功能.

PyStructSequence_Desc

包含要创建的结构序列类型的元信息。

| 域 | C 类型 | 意义 |
|------------------|----------------------|---------------------------------------------------------|
| name | const char * | 结构序列类型的名称 |
| doc | const char * | pointer to docstring for the type or NULL to omit |
| fields | PyStructSequence_Fie | pointer to NULL-terminated array with field names of |
| | * | the new type |
| n_in_sequen¢eint | | number of fields visible to the Python side (if used as |
| | | tuple) |

PyStructSequence_Field

Describes a field of a struct sequence. As a struct sequence is modeled as a tuple, all fields are typed as

8.3. 序列对象 105

*PyObject**. The index in the fields array of the *PyStructSequence_Desc* determines which field of the struct sequence is described.

| 域 | C 类型 | 意义 | |
|------|--------|--------------------------------------------------------------------|--|
| name | const | name for the field or NULL to end the list of named fields, set to | |
| | char * | PyStructSequence_UnnamedField to leave unnamed | |
| doc | const | field docstring or NULL to omit | |
| | char * | | |

char* PyStructSequence_UnnamedField

Special value for a field name to leave it unnamed.

PyObject* PyStructSequence_New (PyTypeObject *type)

Return value: New reference. Creates an instance of type, which must have been created with PyStructSequence_NewType().

PyObject* PyStructSequence_GetItem (PyObject *p, Py_ssize_t pos)

Return value: Borrowed reference. Return the object at position *pos* in the struct sequence pointed to by *p*. No bounds checking is performed.

PyObject* PyStructSequence_GET_ITEM (PyObject *p, Py_ssize_t pos)

Return value: Borrowed reference. Macro equivalent of PyStructSequence_GetItem().

void PyStructSequence_SetItem (PyObject *p, Py_ssize_t pos, PyObject *o)

Sets the field at index pos of the struct sequence p to value o. Like $PyTuple_SET_ITEM()$, this should only be used to fill in brand new instances.

注解: This function "steals" a reference to o.

void PyStructSequence_SET_ITEM (PyObject *p, Py_ssize_t *pos, PyObject *o)

Macro equivalent of PyStructSequence_SetItem().

注解: This function "steals" a reference to o.

8.3.6 列表对象

PyListObject

这个 C 类型PyObject 的子类型代表一个 Python 列表对象。

PyTypeObject PyList_Type

这是个属于PyTypeObject 的代表 Python 列表类型的实例。在 Python 层面和类型 list 是同一个对象。

int PyList_Check (PyObject *p)

如果 p 是一个列表对象或者是一个列表类型的子类型实例时,返回真。

int PyList_CheckExact (PyObject *p)

 $\exists p$ 是一个列表对象,但是不是列表类型的子类型实例时,返回真。

PyObject* PyList_New (Py_ssize_t len)

Return value: New reference. 成功时返回一个长度为 len 的新列表,失败时返回 NULL。

注解: 当 len 大于零时,被返回的列表对象项目被设成 NULL。因此你不能用类似 C 函数 $PySequence_SetItem()$ 的抽象 API 或者用 C 函数 $PyList_SetItem()$ 将所有项目设置成真实对象前对 Python 代码公开这个对象。

Py_ssize_t PyList_Size (PyObject *list)

返回 list 中列表对象的长度;这等于在列表对象调用 len(list)。

Py_ssize_t PyList_GET_SIZE (PyObject *list)

宏版本的 C 函数PyList Size(),没有错误检测。

PyObject* PyList_GetItem (PyObject *list, Py_ssize_t index)

Return value: Borrowed reference. 返回 list 所指向列表中 index 位置上的对象。位置值必须为非负数;不支持从列表末尾进行索引。如果 index 超出边界 (<0 or >=len(list)),则返回 NULL 并设置 IndexError 异常。

PyObject* PyList_GET_ITEM (PyObject *list, Py_ssize_t i)

Return value: Borrowed reference. 宏版本的 C 函数PyList GetItem(),没有错误检测。

int PyList_SetItem (PyObject *list, Py_ssize_t index, PyObject *item)

将列表中索引为 index 的项设为 item。成功时返回 0。如果 index 超出范围则返回 -1 并设定 IndexError 异常。

注解: 此函数会"偷走"一个对 item 的引用并丢弃一个对列表中受影响位置上的已有条目的引用。

void PyList_SET_ITEM (PyObject *list, Py_ssize_t i, PyObject *o)

不带错误检测的宏版本 $PyList_SetItem()$ 。这通常只被用于新列表中之前没有内容的位置进行填充。

注解: 该宏会"偷走"一个对 item 的引用,但与 $PyList_SetItem()$ 不同的是它 不会丢弃对任何 被替换条目的引用;在 list 的 i 位置上的任何引用都将被泄露。

int PyList Insert (PyObject *list, Py ssize t index, PyObject *item)

将条目 item 插入到列表 list 索引号 index 之前的位置。如果成功将返回 0;如果不成功则返回 -1 并设置一个异常。相当于 list.insert (index, item)。

int PyList_Append (PyObject *list, PyObject *item)

将对象 item 添加到列表 list 的末尾。如果成功将返回 0;如果不成功则返回 -1 并设置一个异常。相当于 list.append(item)。

PyObject* PyList_GetSlice (PyObject *list, Py_ssize_t low, Py_ssize_t high)

Return value: New reference. 返回一个对象列表,包含 list 当中位于 low 和 high 之间的对象。如果不成功则返回 NULL 并设置异常。相当于 list [low: high]。不支持从列表末尾进行索引。

int PyList_SetSlice (PyObject *list, Py_ssize_t low, Py_ssize_t high, PyObject *itemlist)

将 list 当中 low 与 high 之间的切片设为 itemlist 的内容。相当于 list [low:high] = itemlist。 itemlist 可以为 NULL,表示赋值为一个空列表(删除切片)。成功时返回 0,失败时返回 -1。这里不支持从列表末尾进行索引。

int PyList Sort (PyObject *list)

对 list 中的条目进行原地排序。成功时返回 0,失败时返回 -1。这等价于 list.sort()。

int PyList_Reverse (PyObject *list)

对 list 中的条目进行原地反转。成功时返回 0,失败时返回 -1。这等价于 list.reverse()。

PyObject* PyList_AsTuple (PyObject *list)

Return value: New reference. 返回一个新的元组对象,其中包含 list 的内容;等价于 tuple (list)。

int PyList_ClearFreeList()

清空释放列表。返回所释放的条目数。

3.3 新版功能.

8.3. 序列对象 107

8.4 容器对象

8.4.1 字典对象

PyDictObject

这个PyObject 的子类型代表一个 Python 字典对象。

PyTypeObject PyDict_Type

Python 字典类型表示为PyTypeObject 的实例。这与 Python 层面的 dict 是相同的对象。

int PyDict_Check (PyObject *p)

如果 p 是字典对象或者字典类型的子类型的实例,则返回真。

int PyDict_CheckExact (PyObject *p)

如果 p 是字典对象但不是字典类型的子类型的实例,则返回真。

PyObject* PyDict_New()

Return value: New reference. 返回一个新的空字典,失败时返回 NULL。

PyObject* PyDictProxy_New (PyObject *mapping)

Return value: New reference. 返回 types.MappingProxyType 对象,用于强制执行只读行为的映射。这通常用于创建视图以防止修改非动态类类型的字典。

void PyDict_Clear (PyObject *p)

清空现有字典的所有键值对。

int PyDict_Contains (PyObject *p, PyObject *key)

确定 key 是否包含在字典 p 中。如果 key 匹配上 p 的某一项,则返回 1 ,否则返回 0 。返回 -1 表示出错。这等同于 Python 表达式 key in p 。

PyObject* PyDict Copy (PyObject *p)

Return value: New reference. 返回与 p 包含相同键值对的新字典。

int PyDict_SetItem (PyObject *p, PyObject *key, PyObject *val)

使用 key 作为键将 val 插入字典 p。 key 必须为hashable;如果不是,则将引发 TypeError。成功时返回 0,失败时返回 -1。此函数 不会附带对 val 的引用。

int PyDict_SetItemString (PyObject *p, const char *key, PyObject *val)

使用 key 作为键将 val 插入到字典 p。key 应当为 const char*。键对象是使用 PyUnicode_FromString(key) 创建的。成功时返回 0,失败时返回 -1。此函数 不会附带对 val 的引用。

int PyDict_DelItem (PyObject *p, PyObject *key)

使用键 key 删除字典 p 中的条目。key 必须是可哈希的;如果不是,则抛出 TypeError 异常。成功时返回 0 ,失败时返回 -1 。

int PyDict_DelItemString (PyObject *p, const char *key)

删除字典 p 中的条目,其中包含由字符串 key 指定的键。成功时返回"0,失败时返回"-1"。

PyObject* PyDict GetItem (PyObject *p, PyObject *key)

Return value: Borrowed reference. 从字典 p 中返回以 key 为键的对象。如果键名 key 不存在但 没有设置一个异常则返回 NULL。

需要注意的是,调用 __hash__() 和 __eq__() 方法产生的异常不会被抛出。改用PyDict_GetItemWithError()获得错误报告。

PyObject* PyDict_GetItemWithError (PyObject *p, PyObject *key)

Return value: Borrowed reference. PyDict_GetItem() 的变种,它不会屏蔽异常。当异常发生时将返回 NULL 并且设置一个异常。如果键不存在则返回 NULL 并且不会设置一个异常。

PyObject* PyDict_GetItemString (PyObject *p, const char *key)

Return value: Borrowed reference. 这与PyDict_GetItem() 一样,但是 key 需要指定一个 const char*, 而不是PyObject*。

需要注意的是,调用 __hash__() 、__eq__() 方法和创建一个临时的字符串对象时产生的异常不会被抛出。改用PyDict_GetItemWithError() 获得错误报告。

PyObject* PyDict_SetDefault (PyObject *p, PyObject *key, PyObject *defaultobj)

Return value: Borrowed reference. 这跟 Python 层面的 dict.setdefault() 一样。如果键 key 存在,它返回在字典 p 里面对应的值。如果键不存在,它会和值 defaultobj 一起插入并返回 defaultobj。这个函数只计算 key 的哈希函数一次,而不是在查找和插入时分别计算它。

3.4 新版功能.

PyObject* PyDict_Items (PyObject *p)

Return value: New reference. 返回一个包含字典中所有键值项的PyListObject。

PyObject* PyDict_Keys (PyObject *p)

Return value: New reference. 返回一个包含字典中所有键 (keys) 的PyListObject。

PyObject* PyDict_Values (PyObject *p)

Return value: New reference. 返回一个包含字典中所有值 (values) 的PyListObject。

Py_ssize_t PyDict_Size (PyObject *p)

返回字典中项目数,等价于对字典p使用 len (p)。

int PyDict_Next (PyObject *p, Py_ssize_t *ppos, PyObject **pkey, PyObject **pvalue)

迭代字典 p 中的所有键值对。在第一次调用此函数开始迭代之前,由 ppos 所引用的 Py_ssize_t 必须初始化为 0; 该函数将为字典中的每个键值对返回真值,一旦所有键值对报告完毕则返回假值。形参 pkey 和 pvalue 应当指向PyObject* 变量,它们将分别使用每个键和值来填充,或者也可以为 NULL。通过它们返回的任何引用都是暂借的。ppos 在迭代期间不应被更改。它的值表示内部字典结构中的偏移量,并且由于结构是稀疏的,因此偏移量并不连续。

例如:

```
PyObject *key, *value;
Py_ssize_t pos = 0;
while (PyDict_Next(self->dict, &pos, &key, &value)) {
    /* do something interesting with the values... */
    ...
}
```

字典p不应该在遍历期间发生改变。在遍历字典时,改变键中的值是安全的,但仅限于键的集合不发生改变。例如:

```
PyObject *key, *value;
Py_ssize_t pos = 0;

while (PyDict_Next(self->dict, &pos, &key, &value)) {
    long i = PyLong_AsLong(value);
    if (i == -1 && PyErr_Occurred()) {
        return -1;
    }
    PyObject *o = PyLong_FromLong(i + 1);
    if (o == NULL)
        return -1;
    if (PyDict_SetItem(self->dict, key, o) < 0) {
        Py_DECREF(o);
        return -1;
    }
    Py_DECREF(o);
}</pre>
```

int PyDict_Merge (PyObject *a, PyObject *b, int override)

对映射对象 b 进行迭代,将键值对添加到字典 a。b 可以是一个字典,或任何支持 $PyMapping_Keys$ () 和 $PyObject_GetItem$ () 的对象。如果 override 为真值,则如果在 b 中找到相同的键则 a 中已存在的相应键值对将被替换,否则如果在 a 中没有相同的键则只是添加键值对。当成功时返回 0 或者当引发异常时返回 -1。

int PyDict Update (PyObject *a, PyObject *b)

这与 C 中的 PyDict_Merge (a, b, 1) 一样, 也类似于 Python 中的 a.update (b), 差别在

8.4. 容器对象 109

于 $PyDict_Update()$ 在第二个参数没有"keys" 属性时不会回退到迭代键值对的序列。当成功时返回 0 或者当引发异常时返回 -1。

int PyDict_MergeFromSeq2 (PyObject *a, PyObject *seq2, int override)

将 seq2 中的键值对更新或合并到字典 a。seq2 必须为产生长度为 2 的用作键值对的元素的可迭代对象。当存在重复的键时,如果 override 真值则最后出现的键胜出。当成功时返回 0 或者当引发异常时返回 -1。等价的 Python 代码(返回值除外):

```
def PyDict_MergeFromSeq2(a, seq2, override):
    for key, value in seq2:
        if override or key not in a:
        a[key] = value
```

int PyDict_ClearFreeList()

清空释放列表。返回所释放的条目数。

3.3 新版功能.

8.4.2 集合对象

This section details the public API for set and frozenset objects. Any functionality not listed below is best accessed using the either the abstract object protocol (including $PyObject_CallMethod()$, $PyObject_RichCompareBool()$, $PyObject_Hash()$, $PyObject_Repr()$, $PyObject_IsTrue()$, $PyObject_Print()$, and $PyObject_GetIter()$) or the abstract number protocol (including $PyNumber_And()$, $PyNumber_Subtract()$, $PyNumber_Nor()$, $PyNumber_InPlaceAnd()$, $PyNumber_InPlaceSubtract()$, $PyNumber_InPlaceOr()$, and $PyNumber_InPlaceNor()$).

PySetObject

This subtype of <code>PyObject</code> is used to hold the internal data for both <code>set</code> and <code>frozenset</code> objects. It is like a <code>PyDictObject</code> in that it is a fixed size for small sets (much like tuple storage) and will point to a separate, variable sized block of memory for medium and large sized sets (much like list storage). None of the fields of this structure should be considered public and are subject to change. All access should be done through the documented API rather than by manipulating the values in the structure.

PyTypeObject PySet_Type

This is an instance of PyTypeObject representing the Python set type.

PyTypeObject PyFrozenSet_Type

This is an instance of PyTypeObject representing the Python frozenset type.

The following type check macros work on pointers to any Python object. Likewise, the constructor functions work with any iterable Python object.

```
int PySet_Check (PyObject *p)
```

Return true if p is a set object or an instance of a subtype.

```
int PyFrozenSet_Check (PyObject *p)
```

Return true if p is a frozenset object or an instance of a subtype.

```
int PyAnySet_Check (PyObject *p)
```

Return true if p is a set object, a frozenset object, or an instance of a subtype.

int PyAnySet_CheckExact (PyObject *p)

Return true if *p* is a set object or a frozenset object but not an instance of a subtype.

int PyFrozenSet CheckExact (PyObject *p)

Return true if *p* is a frozenset object but not an instance of a subtype.

```
PyObject* PySet_New (PyObject *iterable)
```

Return value: New reference. Return a new set containing objects returned by the iterable. The iterable may be NULL to create a new empty set. Return the new set on success or NULL on failure. Raise TypeError if iterable is not actually iterable. The constructor is also useful for copying a set (c=set (s)).

PyObject* PyFrozenSet_New (PyObject *iterable)

Return value: New reference. Return a new frozenset containing objects returned by the iterable. The iterable may be NULL to create a new empty frozenset. Return the new set on success or NULL on failure. Raise TypeError if iterable is not actually iterable.

The following functions and macros are available for instances of set or frozenset or instances of their subtypes.

Py_ssize_t PySet_Size (PyObject *anyset)

Return the length of a set or frozenset object. Equivalent to len(anyset). Raises a PyExc_SystemError if anyset is not a set, frozenset, or an instance of a subtype.

Py_ssize_t PySet_GET_SIZE (PyObject *anyset)

Macro form of PySet Size() without error checking.

int PySet_Contains (PyObject *anyset, PyObject *key)

Return 1 if found, 0 if not found, and -1 if an error is encountered. Unlike the Python __contains__() method, this function does not automatically convert unhashable sets into temporary frozensets. Raise a TypeError if the *key* is unhashable. Raise PyExc_SystemError if *anyset* is not a set, frozenset, or an instance of a subtype.

int PySet_Add (PyObject *set, PyObject *key)

Add key to a set instance. Also works with frozenset instances (like PyTuple_SetItem() it can be used to fill-in the values of brand new frozensets before they are exposed to other code). Return 0 on success or -1 on failure. Raise a TypeError if the key is unhashable. Raise a MemoryError if there is no room to grow. Raise a SystemError if set is not an instance of set or its subtype.

The following functions are available for instances of set or its subtypes but not for instances of frozenset or its subtypes.

int PySet Discard (PyObject *set, PyObject *key)

Return 1 if found and removed, 0 if not found (no action taken), and -1 if an error is encountered. Does not raise KeyError for missing keys. Raise a TypeError if the *key* is unhashable. Unlike the Python discard() method, this function does not automatically convert unhashable sets into temporary frozensets. Raise PyExc_SystemError if *set* is not an instance of set or its subtype.

PyObject* PySet_Pop (PyObject *set)

Return value: New reference. Return a new reference to an arbitrary object in the set, and removes the object from the set. Return NULL on failure. Raise KeyError if the set is empty. Raise a SystemError if set is not an instance of set or its subtype.

int PySet_Clear (PyObject *set)

清空现有字典的所有键值对。

int PySet_ClearFreeList()

清空释放列表。返回所释放的条目数。

3.3 新版功能.

8.5 函数对象

8.5.1 函数对象

有一些特定于 Python 函数的函数。

PyFunctionObject

用于函数的C结构体。

PyTypeObject PyFunction_Type

这是一个PyTypeObject 实例并表示 Python 函数类型。它作为 types.FunctionType 向 Python 程序员公开。

8.5. 函数对象 111

int PyFunction_Check (PyObject *o)

如果 o 是函数对象 (类型为PyFunction_Type) 则返回真值。形参必须不为 NULL。

PyObject* PyFunction_New (PyObject *code, PyObject *globals)

Return value: New reference. 返回与代码对象 code 关联的新函数对象。globals 必须是一个字典,该函数可以访问全局变量。

从代码对象中提取函数的文档字符串和名称。__module__ 会从 globals 中提取。参数 defaults, annotations 和 closure 设为 NULL。__qualname__ 设为与函数名称相同的值。

PyObject* PyFunction_NewWithQualName (PyObject *code, PyObject *globals, PyObject *qualname)

Return value: New reference. 类似PyFunction_New(), 但还允许设置函数对象的 __qualname__ 属性。qualname 应当是 unicode 对象或 NULL; 如果是 NULL 则 __qualname__ 属性设为与其 __name__ 属性相同的值。

3.3 新版功能.

PyObject* PyFunction_GetCode (PyObject *op)

Return value: Borrowed reference. 返回与函数对象 op 关联的代码对象。

PyObject* PyFunction_GetGlobals (PyObject *op)

Return value: Borrowed reference. 返回与函数对象 *op* 相关联的全局字典。

PyObject* PyFunction_GetModule (PyObject *op)

Return value: Borrowed reference. 返回函数对象 op 的 __module__ 属性,通常为一个包含了模块名称的字符串,但可以通过 Python 代码设为返回其他任意对象。

PyObject* PyFunction_GetDefaults (PyObject *op)

Return value: Borrowed reference. 返回函数对象 op 的参数默认值。这可以是一个参数元组或 NULL。

int PyFunction_SetDefaults (PyObject *op, PyObject *defaults)

为函数对象 op 设置参数默认值。defaults 必须为 Py_None 或一个元组。

失败时引发 SystemError 异常并返回 -1。

PyObject* PyFunction_GetClosure (PyObject *op)

Return value: Borrowed reference. 返回关联到函数对象 op 的闭包。这可以是 NULL 或 cell 对象的元组。

int PyFunction_SetClosure (PyObject *op, PyObject *closure)

设置关联到函数对象 op 的闭包。closure 必须为 Py_None 或 cell 对象的元组。

失败时引发 SystemError 异常并返回 -1。

PyObject *PyFunction_GetAnnotations (PyObject *op)

Return value: Borrowed reference. 返回函数对象 op 的标注。这可以是一个可变字典或 NULL。

int PyFunction_SetAnnotations (PyObject *op, PyObject *annotations)

设置函数对象 op 的标注。annotations 必须为一个字典或 Py_None。

失败时引发 SystemError 异常并返回 -1。

8.5.2 实例方法对象

An instance method is a wrapper for a *PyCFunction* and the new way to bind a *PyCFunction* to a class object. It replaces the former call <code>PyMethod_New(func, NULL, class)</code>.

PyTypeObject PyInstanceMethod_Type

This instance of PyTypeObject represents the Python instance method type. It is not exposed to Python programs.

int PyInstanceMethod_Check (PyObject *o)

Return true if o is an instance method object (has type $PyInstanceMethod_Type$). The parameter must not be NULL.

PyObject* PyInstanceMethod_New (PyObject *func)

Return value: New reference. Return a new instance method object, with *func* being any callable object *func* is the function that will be called when the instance method is called.

PyObject* PyInstanceMethod_Function (PyObject *im)

Return value: Borrowed reference. Return the function object associated with the instance method im.

PyObject* PyInstanceMethod_GET_FUNCTION (PyObject *im)

Return value: Borrowed reference. Macro version of *PyInstanceMethod_Function()* which avoids error checking.

8.5.3 方法对象

Methods are bound function objects. Methods are always bound to an instance of a user-defined class. Unbound methods (methods bound to a class object) are no longer available.

PyTypeObject PyMethod_Type

This instance of *PyTypeObject* represents the Python method type. This is exposed to Python programs as types. MethodType.

int PyMethod_Check (PyObject *o)

Return true if o is a method object (has type $PyMethod_Type$). The parameter must not be NULL.

PyObject* PyMethod_New (PyObject *func, PyObject *self)

Return value: New reference. Return a new method object, with func being any callable object and self the instance the method should be bound. func is the function that will be called when the method is called. self must not be NULL.

PyObject* PyMethod_Function (PyObject *meth)

Return value: Borrowed reference. Return the function object associated with the method meth.

PyObject* PyMethod_GET_FUNCTION (PyObject *meth)

Return value: Borrowed reference. Macro version of PyMethod_Function () which avoids error checking.

PyObject* PyMethod Self (PyObject *meth)

Return value: Borrowed reference. Return the instance associated with the method meth.

PyObject* PyMethod_GET_SELF (PyObject *meth)

Return value: Borrowed reference. Macro version of PyMethod Self() which avoids error checking.

int PyMethod_ClearFreeList()

清空释放列表。返回所释放的条目数。

8.5.4 Cell 对象

"Cell"对象用于实现由多个作用域引用的变量。对于每个这样的变量,一个"Cell"对象为了存储该值而被创建;引用该值的每个堆栈框架的局部变量包含同样使用该变量的对外部作用域的"Cell"引用。访问该值时,将使用"Cell"中包含的值而不是单元格对象本身。这种对"Cell"对象的非关联化的引用需要支持生成的字节码;访问时不会自动非关联化这些内容。"Cell"对象在其他地方可能不太有用。

PyCellObject

用于 Cell 对象的 C 结构体。

PyTypeObject PyCell_Type

与 Cell 对象对应的类型对 象。

$int \ \textbf{PyCell_Check} \ (ob)$

如果 ob 是一个 cell 对象则返回真值; ob 必须不为 NULL。

PyObject* PyCell_New (PyObject *ob)

Return value: New reference. 创建并返回一个包含值 ob 的新 cell 对象。形参可以为 NULL。

PyObject* PyCell_Get (PyObject *cell)

Return value: New reference. 返回 cell 对象 cell 的内容。

PyObject* PyCell_GET (PyObject *cell)

Return value: Borrowed reference. 返回 cell 对象 cell 的内容,但是不检测 cell 是否非 NULL 并且为一个 cell 对象。

8.5. 函数对象 113

int PyCell_Set (PyObject *cell, PyObject *value)

将 cell 对象 cell 的内容设为 value。这将释放任何对 cell 对象当前内容的引用。value 可以为 NULL。cell 必须为非 NULL;如果它不是一个 cell 对象则将返回 -1。如果设置成功则将返回 0。

void PyCell_SET (PyObject *cell, PyObject *value)

将 cell 对象 cell 的值设为 value。不会调整引用计数,并且不会进行检测以保证安全;cell 必须为非 NULL 并且为一个 cell 对象。

8.5.5 代码对象

代码对象是 CPython 实现的低级细节。每个代表一块尚未绑定到函数中的可执行代码。

PyCodeObject

用于描述代码对象的对象的 C 结构。此类型字段可随时更改。

PyTypeObject PyCode_Type

这是一个PyTypeObject 实例, 其表示 Python 的 code 类型。

int PyCode Check (PyObject *co)

如果 co 是一个 code 对象则返回 true。

int PyCode_GetNumFree (PyCodeObject *co)

返回 co 中的自由变量数。

PyCodeObject* PyCode_New (int argcount, int kwonlyargcount, int nlocals, int stacksize, int flags, PyObject *code, PyObject *consts, PyObject *names, PyObject *varnames, PyObject *freevars, PyObject *filename, PyObject *name, int firstlineno, PyObject *lnotab)

Return value: New reference. 返回一个新的代码对象。如果你需要一个虚拟代码对象来创建一个代码帧,请使用PyCode_NewEmpty()。调用PyCode_New()直接可以绑定到准确的 Python 版本,因为字节码的定义经常变化。

PyCodeObject* PyCode_NewWithPosOnlyArgs (int argcount, int posonlyargcount, int kwonlyargcount, int nlocals, int stacksize, int flags, PyObject *code, PyObject *consts, PyObject *names, PyObject *varnames, PyObject *freevars, PyObject *cellvars, PyObject *filename, PyObject *name, int firstlineno, PyObject *lnotab)

Return value: New reference. 类似于PyCode_New(), 但带有一个额外的"posonlyargcount" 用于仅限位置参数。

3.8 新版功能.

 PyCodeObject* PyCode_NewEmpty (const char *filename, const char *funcname, int firstlineno)

 Return value: New reference.
 返回具有指定文件名、函数名和第一行号的新空代码对象。对于 exec()

 或 eval() 生成的代码对象是非法的。

8.6 其他对象

8.6.1 文件对象

这些 API 是内置文件对象的 Python 2 C API 的最小仿真,它过去依赖于 C 标准库的缓冲 I/O (FILE*) 支持。在 Python 3 中,文件和流使用新的 $i \circ$ 模块,该模块在操作系统的低级无缓冲 I/O 上定义了几个层。下面描述的函数是针对这些新 API 的便捷 C 包装器,主要用于解释器中的内部错误报告;建议第三方代码访问 $i \circ$ API。

PyFile_FromFd (int fd, const char *name, const char *mode, int buffering, const char *encoding, const char *encoding, const char *rewline, int closefd)

Return value: New reference. 根据已打开文件 fd 的文件描述符创建一个 Python 文件对象。参数 name, encoding, errors 和 newline 可以为 NULL 表示使用默认值; buffering 可以为 -1 表示使用默认值。name

会被忽略仅保留用于向下兼容。失败时返回 NULL。有关参数的更全面描述,请参阅 io.open()函数的文档。

警告: 由于 Python 流具有自己的缓冲层,因此将它们与 OS 级文件描述符混合会产生各种问题 (例如数据的意外排序)。

在 3.2 版更改: 忽略 name 属性。

int PyObject_AsFileDescriptor (PyObject *p)

将与p关联的文件描述器返回为 int。如果对象是整数,则返回其值。如果没有,则调用对象的 fileno() 方法(如果存在);该方法必须返回一个整数,该整数作为文件描述器值返回。设置异常并在失败时返回-1。

PyObject* PyFile_GetLine (PyObject *p, int n)

Return value: New reference. 等价于 p.readline([n]), 这个函数从对象 p 中读取一行。p 可以是文件对象或具有 readline() 方法的任何对象。如果 n 是 0,则无论该行的长度如何,都会读取一行。如果 n 大于 "0",则从文件中读取不超过 n 个字节;可以返回行的一部分。在这两种情况下,如果立即到达文件末尾,则返回空字符串。但是,如果 n 小于 0,则无论长度如何都会读取一行,但是如果立即到达文件末尾,则引发 EOFError。

int PyFile_SetOpenCodeHook (Py_OpenCodeHookFunction handler)

重载 io.open_code()的正常行为,将其形参通过所提供的处理程序来传递。

处理程序是一个类型为 PyObject *(*)(PyObject *path, void *userData)的函数, 其中 path 确保为 PyUnicodeObject。

userData 指针会被传入钩子函数。因于钩子函数可能由不同的运行时调用,该指针不应直接指向 Python 状态。

鉴于这个钩子专门在导入期间使用的,请避免在新模块执行期间进行导入操作,除非已知它们为冻结状态或者是在 sys.modules 中可用。

一旦钩子被设定,它就不能被移除或替换,之后对PyFile_SetOpenCodeHook()的调用也将失败,如果解释器已经被初始化,函数将返回-1并设置一个异常。

此函数可以安全地在Py_Initialize()之前调用。

3.8 新版功能.

int PyFile_WriteObject (PyObject *obj, PyObject *p, int flags)

将对象 obj 写入文件对象 p 。 flags 唯一支持的标志是 Py_PRINT_RAW; 如果给定,则写入对象的 str() 而不是 repr() 。成功时返回 0,失败时返回 -1 。将设置适当的例外。

int PyFile_WriteString (const char *s, PyObject *p)

将字符串 s 写入文件对象 p。成功返回 0 失败返回 -1;将设定相应的异常。

8.6.2 模块对象

PyTypeObject PyModule_Type

This instance of PyTypeObject represents the Python module type. This is exposed to Python programs as types. ModuleType.

int PyModule_Check (PyObject *p)

Return true if p is a module object, or a subtype of a module object.

int PyModule_CheckExact (PyObject *p)

Return true if p is a module object, but not a subtype of $PyModule_Type$.

PyObject* PyModule_NewObject (PyObject *name)

Return value: New reference. Return a new module object with the __name__ attribute set to name. The module's __name__, __doc__, __package__, and __loader__ attributes are filled in (all but __name__ are set to None); the caller is responsible for providing a __file attribute.

3.3 新版功能.

在 3.4 版更改: __package__ and __loader__ are set to None.

PyObject* PyModule_New (const char *name)

Return value: New reference. Similar to PyModule_NewObject(), but the name is a UTF-8 encoded string instead of a Unicode object.

PyObject* PyModule_GetDict (PyObject *module)

Return value: Borrowed reference. Return the dictionary object that implements module's namespace; this object is the same as the __dict__ attribute of the module object. If module is not a module object (or a subtype of a module object), SystemError is raised and NULL is returned.

It is recommended extensions use other PyModule_* () and PyObject_* () functions rather than directly manipulate a module's __dict__.

PyObject* PyModule_GetNameObject (PyObject *module)

Return value: New reference. Return *module*'s __name__ value. If the module does not provide one, or if it is not a string, SystemError is raised and NULL is returned.

3.3 新版功能.

const char* PyModule_GetName (PyObject *module)

Similar to PyModule_GetNameObject() but return the name encoded to 'utf-8'.

void* PyModule_GetState (PyObject *module)

Return the "state" of the module, that is, a pointer to the block of memory allocated at module creation time, or NULL. See PyModuleDef.m size.

PyModuleDef* PyModule_GetDef (PyObject *module)

Return a pointer to the *PyModuleDef* struct from which the module was created, or NULL if the module wasn't created from a definition.

PyObject* PyModule_GetFilenameObject (PyObject *module)

Return value: New reference. Return the name of the file from which module was loaded using module's ___file__ attribute. If this is not defined, or if it is not a unicode string, raise SystemError and return NULL; otherwise return a reference to a Unicode object.

3.2 新版功能.

const char* PyModule_GetFilename (PyObject *module)

Similar to PyModule_GetFilenameObject() but return the filename encoded to 'utf-8'.

3.2 版后已移除: PyModule_GetFilename() raises UnicodeEncodeError on unencodable filenames, use PyModule_GetFilenameObject() instead.

Initializing C modules

Modules objects are usually created from extension modules (shared libraries which export an initialization function), or compiled-in modules (where the initialization function is added using <code>PyImport_AppendInittab()</code>). See building or extending-with-embedding for details.

The initialization function can either pass a module definition instance to <code>PyModule_Create()</code>, and return the resulting module object, or request "multi-phase initialization" by returning the definition struct itself.

PyModuleDef

The module definition struct, which holds all information needed to create a module object. There is usually only one statically initialized variable of this type for each module.

PyModuleDef Base m base

Always initialize this member to PyModuleDef_HEAD_INIT.

const char *m_name

Name for the new module.

const char *m_doc

Docstring for the module; usually a docstring variable created with PyDoc_STRVAR() is used.

Py_ssize_t m_size

Module state may be kept in a per-module memory area that can be retrieved with $PyModule_GetState()$, rather than in static globals. This makes modules safe for use in multiple sub-interpreters.

This memory area is allocated based on m_size on module creation, and freed when the module object is deallocated, after the m free function has been called, if present.

Setting m_size to -1 means that the module does not support sub-interpreters, because it has global state.

Setting it to a non-negative value means that the module can be re-initialized and specifies the additional amount of memory it requires for its state. Non-negative m_size is required for multi-phase initialization.

See PEP 3121 for more details.

PyMethodDef* m_methods

A pointer to a table of module-level functions, described by <code>PyMethodDef</code> values. Can be <code>NULL</code> if no functions are present.

PyModuleDef_Slot* m_slots

An array of slot definitions for multi-phase initialization, terminated by a $\{0, \text{NULL}\}\$ entry. When using single-phase initialization, m_slots must be NULL.

在 3.5 版更改: Prior to version 3.5, this member was always set to NULL, and was defined as:

inquiry m_reload

traverseproc m_traverse

A traversal function to call during GC traversal of the module object, or NULL if not needed. This function may be called before module state is allocated ($PyModule_GetState()$) may return NULL), and before the Py_mod_exec function is executed.

inquiry m_clear

A clear function to call during GC clearing of the module object, or NULL if not needed. This function may be called before module state is allocated ($PyModule_GetState()$) may return NULL), and before the Py_mod_exec function is executed.

freefunc m_free

A function to call during deallocation of the module object, or NULL if not needed. This function may be called before module state is allocated (PyModule_GetState() may return NULL), and before the Py_mod_exec function is executed.

Single-phase initialization

The module initialization function may create and return the module object directly. This is referred to as "single-phase initialization", and uses one of the following two module creation functions:

PyObject* PyModule_Create (PyModuleDef *def)

Return value: New reference. Create a new module object, given the definition in *def*. This behaves like *PyModule_Create2()* with *module_api_version* set to PYTHON_API_VERSION.

PyObject* PyModule_Create2 (PyModuleDef *def, int module_api_version)

Return value: New reference. Create a new module object, given the definition in def, assuming the API version module_api_version. If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

注解: Most uses of this function should be using <code>PyModule_Create()</code> instead; only use this if you are sure you need it.

Before it is returned from in the initialization function, the resulting module object is typically populated using functions like <code>PyModule_AddObject()</code>.

Multi-phase initialization

An alternate way to specify extensions is to request "multi-phase initialization". Extension modules created this way behave more like Python modules: the initialization is split between the *creation phase*, when the module object is created, and the *execution phase*, when it is populated. The distinction is similar to the __new__() and __init__() methods of classes.

Unlike modules created using single-phase initialization, these modules are not singletons: if the *sys.modules* entry is removed and the module is re-imported, a new module object is created, and the old module is subject to normal garbage collection -- as with Python modules. By default, multiple modules created from the same definition should be independent: changes to one should not affect the others. This means that all state should be specific to the module object (using e.g. using <code>PyModule_GetState()</code>), or its contents (such as the module's __dict__ or individual classes created with <code>PyType_FromSpec()</code>).

All modules created using multi-phase initialization are expected to support *sub-interpreters*. Making sure multiple modules are independent is typically enough to achieve this.

To request multi-phase initialization, the initialization function (PyInit_modulename) returns a PyModuleDef instance with non-empty m_slots . Before it is returned, the PyModuleDef instance must be initialized with the following function:

```
PyObject* PyModuleDef_Init (PyModuleDef *def)
```

Return value: Borrowed reference. Ensures a module definition is a properly initialized Python object that correctly reports its type and reference count.

Returns def cast to PyObject*, or NULL if an error occurred.

3.5 新版功能.

The *m_slots* member of the module definition must point to an array of PyModuleDef_Slot structures:

PyModuleDef_Slot

```
int slot
```

A slot ID, chosen from the available values explained below.

void* value

Value of the slot, whose meaning depends on the slot ID.

3.5 新版功能.

The m_slots array must be terminated by a slot with id 0.

The available slot types are:

Py_mod_create

Specifies a function that is called to create the module object itself. The *value* pointer of this slot must point to a function of the signature:

```
PyObject* create_module (PyObject *spec, PyModuleDef *def)
```

The function receives a ModuleSpec instance, as defined in PEP 451, and the module definition. It should return a new module object, or set an error and return NULL.

This function should be kept minimal. In particular, it should not call arbitrary Python code, as trying to import the same module again may result in an infinite loop.

Multiple Py_mod_create slots may not be specified in one module definition.

If Py_{mod_create} is not specified, the import machinery will create a normal module object using $Py_{module_New()}$. The name is taken from spec, not the definition, to allow extension modules to dynamically adjust to their place in the module hierarchy and be imported under different names through symlinks, all while sharing a single module definition.

There is no requirement for the returned object to be an instance of <code>PyModule_Type</code>. Any type can be used, as long as it supports setting and getting import-related attributes. However, only <code>PyModule_Type</code> instances may be returned if the <code>PyModuleDef</code> has non-<code>NULL m_traverse</code>, <code>m_clear</code>, <code>m_free</code>; non-zero <code>m_size</code>; or slots other than <code>Py_mod_create</code>.

Py_mod_exec

Specifies a function that is called to *execute* the module. This is equivalent to executing the code of a Python module: typically, this function adds classes and constants to the module. The signature of the function is:

```
int exec_module (PyObject* module)
```

If multiple Py_mod_exec slots are specified, they are processed in the order they appear in the m_slots array. See **PEP 489** for more details on multi-phase initialization.

Low-level module creation functions

The following functions are called under the hood when using multi-phase initialization. They can be used directly, for example when creating module objects dynamically. Note that both PyModule_FromDefAndSpec and PyModule_ExecDef must be called to fully initialize a module.

PyObject * PyModule_FromDefAndSpec (PyModuleDef *def, PyObject *spec)

Return value: New reference. Create a new module object, given the definition in module and the ModuleSpec spec. This behaves like PyModule_FromDefAndSpec2() with module_api_version set to PYTHON API VERSION.

3.5 新版功能.

PyObject * PyModule_FromDefAndSpec2 (PyModuleDef *def, PyObject *spec, int module api version)

Return value: New reference. Create a new module object, given the definition in module and the ModuleSpec spec, assuming the API version module_api_version. If that version does not match the version of the running interpreter, a RuntimeWarning is emitted.

注解: Most uses of this function should be using <code>PyModule_FromDefAndSpec()</code> instead; only use this if you are sure you need it.

3.5 新版功能.

int PyModule_ExecDef (PyObject *module, PyModuleDef *def)

Process any execution slots (Py_mod_exec) given in def.

3.5 新版功能.

int PyModule_SetDocString (PyObject *module, const char *docstring)

Set the docstring for *module* to *docstring*. This function is called automatically when creating a module from PyModuleDef, using either PyModule_Create or PyModule_FromDefAndSpec.

3.5 新版功能.

int PyModule_AddFunctions (PyObject *module, PyMethodDef *functions)

Add the functions from the NULL terminated *functions* array to *module*. Refer to the *PyMethodDef* documentation for details on individual entries (due to the lack of a shared module namespace, module level "functions" implemented in C typically receive the module as their first parameter, making them similar to instance methods on Python classes). This function is called automatically when creating a module from PyModuleDef, using either PyModule_Create or PyModule_FromDefAndSpec.

3.5 新版功能.

Support functions

The module initialization function (if using single phase initialization) or a function called from a module execution slot (if using multi-phase initialization), can use the following functions to help initialize the module state:

```
int PyModule_AddObject (PyObject *module, const char *name, PyObject *value)
```

Add an object to *module* as *name*. This is a convenience function which can be used from the module's initialization function. This steals a reference to *value* on success. Return -1 on error, 0 on success.

注解: Unlike other functions that steal references, PyModule_AddObject() only decrements the reference count of *value* on success.

This means that its return value must be checked, and calling code must $Py_DECREF()$ value manually on error. Example usage:

```
Py_INCREF(spam);
if (PyModule_AddObject(module, "spam", spam) < 0) {
    Py_DECREF(module);
    Py_DECREF(spam);
    return NULL;
}</pre>
```

int PyModule_AddIntConstant (PyObject *module, const char *name, long value)

Add an integer constant to *module* as *name*. This convenience function can be used from the module's initialization function. Return -1 on error, 0 on success.

```
int PyModule_AddStringConstant (PyObject *module, const char *name, const char *value)
```

Add a string constant to *module* as *name*. This convenience function can be used from the module's initialization function. The string *value* must be NULL-terminated. Return -1 on error, 0 on success.

```
int PyModule_AddIntMacro (PyObject *module, macro)
```

Add an int constant to *module*. The name and the value are taken from *macro*. For example $PyModule_AddIntMacro(module, AF_INET)$ adds the int constant AF_INET with the value of AF_INET to *module*. Return -1 on error, 0 on success.

```
int PyModule_AddStringMacro (PyObject *module, macro)
```

Add a string constant to *module*.

Module lookup

Single-phase initialization creates singleton modules that can be looked up in the context of the current interpreter. This allows the module object to be retrieved later with only a reference to the module definition.

These functions will not work on modules created using multi-phase initialization, since multiple such modules can be created from a single definition.

```
PyObject* PyState_FindModule (PyModuleDef *def)
```

Return value: Borrowed reference. Returns the module object that was created from def for the current interpreter. This method requires that the module object has been attached to the interpreter state with $PyState_AddModule()$ beforehand. In case the corresponding module object is not found or has not been attached to the interpreter state yet, it returns NULL.

```
int PyState_AddModule (PyObject *module, PyModuleDef *def)
```

Attaches the module object passed to the function to the interpreter state. This allows the module object to be accessible via <code>PyState_FindModule()</code>.

Only effective on modules created using single-phase initialization.

Python calls PyState_AddModule automatically after importing a module, so it is unnecessary (but harmless) to call it from module initialization code. An explicit call is needed only if the module's own init code subsequently calls PyState_FindModule. The function is mainly intended for implementing alternative

import mechanisms (either by calling it directly, or by referring to its implementation for details of the required state updates).

Return 0 on success or -1 on failure.

3.3 新版功能.

int PyState_RemoveModule (PyModuleDef *def)

Removes the module object created from def from the interpreter state. Return 0 on success or -1 on failure.

3.3 新版功能.

8.6.3 迭代器对象

Python 提供了两个通用迭代器对象。第一个是序列迭代器,它使用支持 __getitem__() 方法的任意序列。第二个使用可调用对象和一个 sentinel 值,为序列中的每个项调用可调用对象,并在返回 sentinel 值时结束迭代。

PyTypeObject PySeqIter_Type

PySeqIter_New() 返回迭代器对象的类型对象和内置序列类型内置函数 iter() 的单参数形式。

int PySeqIter_Check (op)

如果 op 的类型为PySeqIter_Type 则返回 true。

PyObject* PySeqIter New (PyObject *seq)

Return value: New reference. 返回一个与常规序列对象一起使用的迭代器 seq。当序列订阅操作引发 IndexError 时,迭代结束。

PyTypeObject PyCallIter_Type

由函数PyCallIter_New()和iter()内置函数的双参数形式返回的迭代器对象类型对象。

int PyCallIter_Check (op)

如果 op 的类型为PyCallIter_Type 则返回 true。

PyObject* PyCallIter_New (PyObject *callable, PyObject *sentinel)

Return value: New reference. 返回一个新的迭代器。第一个参数 callable 可以是任何可以在没有参数的情况下调用的 Python 可调用对象;每次调用都应该返回迭代中的下一个项目。当 callable 返回等于 sentinel 的值时,迭代将终止。

8.6.4 描述符对象

"描述符"是描述对象的某些属性的对象。它们存在于类型对象的字典中。

PyTypeObject PyProperty_Type

内建描述符类型的类型对象。

PyObject* PyDescr_NewGetSet (PyTypeObject *type, struct PyGetSetDef *getset)

Return value: New reference.

PyObject* PyDescr_NewMember (PyTypeObject *type, struct PyMemberDef *meth)

Return value: New reference.

PyObject* PyDescr_NewMethod (PyTypeObject *type, struct PyMethodDef *meth)

Return value: New reference.

$\textit{PyObject*} \ \textbf{PyDescr_NewWrapper} \ (\textit{PyTypeObject*type}, \text{struct wrapperbase *} \textit{wrapper}, \text{void *} \textit{wrapped})$

Return value: New reference.

PyObject* PyDescr_NewClassMethod (PyTypeObject *type, PyMethodDef *method)

Return value: New reference.

int PyDescr_IsData (PyObject *descr)

如果描述符对象 *descr* 描述数据属性,则返回 true;如果描述方法,则返回 false。*descr* 必须是描述符对象;没有错误检查。

```
PyObject* PyWrapper_New (PyObject *, PyObject *)
```

Return value: New reference.

8.6.5 切片对象

```
PyTypeObject PySlice_Type
```

The type object for slice objects. This is the same as slice in the Python layer.

```
int PySlice_Check (PyObject *ob)
```

Return true if *ob* is a slice object; *ob* must not be NULL.

```
PyObject* PySlice_New (PyObject *start, PyObject *stop, PyObject *step)
```

Return value: New reference. Return a new slice object with the given values. The start, stop, and step parameters are used as the values of the slice object attributes of the same names. Any of the values may be NULL, in which case the None will be used for the corresponding attribute. Return NULL if the new object could not be allocated.

```
int PySlice_GetIndices (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)
```

Retrieve the start, stop and step indices from the slice object *slice*, assuming a sequence of length *length*. Treats indices greater than *length* as errors.

Returns 0 on success and -1 on error with no exception set (unless one of the indices was not None and failed to be converted to an integer, in which case -1 is returned with an exception set).

You probably do not want to use this function.

在 3.2 版更改: The parameter type for the *slice* parameter was PySliceObject* before.

```
int PySlice_GetIndicesEx (PyObject *slice, Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step, Py_ssize_t *slicelength)
```

Usable replacement for PySlice_GetIndices(). Retrieve the start, stop, and step indices from the slice object *slice* assuming a sequence of length *length*, and store the length of the slice in *slicelength*. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Returns 0 on success and -1 on error with exception set.

注解: This function is considered not safe for resizable sequences. Its invocation should be replaced by a combination of <code>PySlice_Unpack()</code> and <code>PySlice_AdjustIndices()</code> where

is replaced by

```
if (PySlice_Unpack(slice, &start, &stop, &step) < 0) {
    // return error
}
slicelength = PySlice_AdjustIndices(length, &start, &stop, step);</pre>
```

在 3.2 版更改: The parameter type for the slice parameter was PySliceObject* before.

在 3.6.1 版更改: If Py_LIMITED_API is not set or set to the value between 0×03050400 and 0×03060000 (not including) or 0×03060100 or higher PySlice_GetIndicesEx() is implemented as a macro using PySlice_Unpack() and PySlice_AdjustIndices(). Arguments start, stop and step are evaluated more than once.

3.6.1 版后已移除: If Py_LIMITED_API is set to the value less than 0x03050400 or between 0x03060000 and 0x03060100 (not including) PySlice_GetIndicesEx() is a deprecated function.

int PySlice_Unpack (PyObject *slice, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t *step)

Extract the start, stop and step data members from a slice object as C integers. Silently reduce values larger than PY_SSIZE_T_MAX to PY_SSIZE_T_MAX, silently boost the start and stop values less than PY_SSIZE_T_MIN to PY_SSIZE_T_MIN, and silently boost the step values less than PY_SSIZE_T_MAX to -PY_SSIZE_T_MAX.

Return -1 on error, 0 on success.

3.6.1 新版功能.

Py_ssize_t PySlice_AdjustIndices (Py_ssize_t length, Py_ssize_t *start, Py_ssize_t *stop, Py_ssize_t step)

Adjust start/end slice indices assuming a sequence of the specified length. Out of bounds indices are clipped in a manner consistent with the handling of normal slices.

Return the length of the slice. Always successful. Doesn't call Python code.

3.6.1 新版功能.

8.6.6 Ellipsis Object

PyObject *Py_Ellipsis

The Python Ellipsis object. This object has no methods. It needs to be treated just like any other object with respect to reference counts. Like <code>Py_None</code> it is a singleton object.

8.6.7 MemoryView 对象

一个 memoryview 对象 C 级别的缓冲区接口 暴露为一个可以像任何其他对象一样传递的 Python 对象。

PyObject *PyMemoryView_FromObject (PyObject *obj)

Return value: New reference. 从提供缓冲区接口的对象创建 memoryview 对象。如果 obj 支持可写缓冲区导出,则 memoryview 对象将可以被读/写,否则它可能是只读的,也可以是导出器自行决定的读/写。

PyObject *PyMemoryView_FromMemory (char *mem, Py_ssize_t size, int flags)

Return value: New reference. 使用 mem 作为底层缓冲区创建一个 memoryview 对象。flags 可以是 PyBUF_READ 或者 PyBUF_WRITE 之一.

3.3 新版功能.

PyObject *PyMemoryView_FromBuffer (Py_buffer *view)

Return value: New reference. 创建一个包含给定缓冲区结构 view 的 memoryview 对象。对于简单的字节缓冲区,PyMemoryView_FromMemory() 是首选函数。

PyObject *PyMemoryView GetContiquous (PyObject *obj, int buffertype, char order)

Return value: New reference. 从定义缓冲区接口的对象创建一个 memoryview 对象contiguous 内存块(在'C' 或'F'ortran order 中)。如果内存是连续的,则 memoryview 对象指向原始内存。否则,复制并且 memoryview 指向新的 bytes 对象。

int PyMemoryView_Check (PyObject *obj)

如果对象 *obj* 是 memoryview 对象,则返回 true 。目前不允许创建 memoryview 的子类。

Py_buffer *PyMemoryView_GET_BUFFER (PyObject *mview)

返回指向 memoryview 的导出缓冲区私有副本的指针。*mview 必须*是一个 memoryview 实例;这个宏不检查它的类型,你必须自己检查,否则你将面临崩溃风险。

Py_buffer *PyMemoryView_GET_BASE (PyObject *mview)

返回 memoryview 所基于的导出对象的指针,或者如果 memoryview 已由函数PyMemoryView_FromMemory()或PyMemoryView_FromBuffer()创建则返回 NULL。
mview 必须是一个 memoryview 实例。

8.6.8 弱引用对象

Python 支持"弱引用"作为一类对象。具体来说,有两种直接实现弱引用的对象。第一种就是简单的引用对象,第二种尽可能地作用为一个原对象的代理。

int PyWeakref_Check (ob)

如果 "ob" 是一个引用或者一个代理对象,则返回一个 true。

int PyWeakref_CheckRef (ob)

如果 "ob" 是一个引用,则返回 true。

int PyWeakref_CheckProxy (ob)

如果"ob"是一个代理对象,则返回 true。

PyObject* PyWeakref_NewRef (PyObject *ob, PyObject *callback)

Return value: New reference. 返回对象 ob 的一个弱引用对象。该函数总是会返回一个新的引用,但不保证创建一个新的对象;它有可能返回一个现有的引用对象。第二个形参 callback 为一个可调用对象,它会在 ob 被作为垃圾回收时接收通知;它应该接受一个单独形参,即弱引用对象本身。callback 也可以为 None 或 NULL。如果 ob 不是一个弱引用对象,或者如果 callback 不是可调用对象,None 或 NULL,该函数将返回 NULL 并且引发 TypeError。

PyObject* PyWeakref_NewProxy (PyObject *ob, PyObject *callback)

Return value: New reference. 返回对象 ob 的一个弱引用代理对象。该函数将总是返回一个新的引用,但不保证创建一个新的对象;它有可能返回一个现有的代理对象。第二个形参 callback 为一个可调用对象,它会在 ob 被作为垃圾回收时接收通知;它应该接受一个单独形参,即弱引用对象本身。callback 也可以为 None 或 NULL。如果 ob 不是一个弱引用对象,或者如果 callback 不是可调用对象,None 或 NULL,该函数将返回 NULL 并且引发 TypeError。

PyObject* PyWeakref_GetObject (PyObject *ref)

Return value: Borrowed reference. 返回弱引用对象 ref 的被引用对象。如果被引用对象不再存在,则返回 Py_None。

注解: 该函数返回被引用对象的一个**借来的引用**。这意味着除非你很清楚在你使用期间这个对象不可能被销毁,否则你应该始终对该对象调用Py_INCREF()。

PyObject* PyWeakref_GET_OBJECT (PyObject *ref)

Return value: Borrowed reference. 类似PyWeakref_GetObject(), 但实现为一个不做类型检查的宏。

8.6.9 胶囊

有关使用这些对象的更多信息请参阅 using-capsules。

3.1 新版功能.

PyCapsule

这个PyObject 的子类型代表着一个任意值,当需要通过 Python 代码将任意值(以 void* 指针的形式)从 C 扩展模块传递给其他 C 代码时非常有用。它通常用于将指向一个模块中定义的 C 语言函数指针传递给其他模块,以便可以从那里调用它们。这允许通过正常的模块导入机制访问动态加载的模块中的 C API。

PyCapsule_Destructor

这种类型的一个析构器返回一个胶囊, 定义如下:

typedef void (*PyCapsule_Destructor) (PyObject *);

参阅PyCapsule_New() 来获取 PyCapsule_Destructor 返回值的语义。

int PyCapsule CheckExact (PyObject *p)

如果参数是一个PyCapsule 则返回 True

PyObject* PyCapsule New (void *pointer, const char *name, PyCapsule Destructor destructor)

Return value: New reference. Create a *PyCapsule* encapsulating the *pointer*. The *pointer* argument may not be NULL.

On failure, set an exception and return NULL.

The *name* string may either be NULL or a pointer to a valid C string. If non-NULL, this string must outlive the capsule. (Though it is permitted to free it inside the *destructor*.)

If the destructor argument is not NULL, it will be called with the capsule as its argument when it is destroyed.

If this capsule will be stored as an attribute of a module, the *name* should be specified as modulename. attributename. This will enable other modules to import the capsule using <code>PyCapsule_Import()</code>.

void* PyCapsule GetPointer (PyObject *capsule, const char *name)

Retrieve the *pointer* stored in the capsule. On failure, set an exception and return NULL.

The *name* parameter must compare exactly to the name stored in the capsule. If the name stored in the capsule is NULL, the *name* passed in must also be NULL. Python uses the C function strcmp() to compare capsule names.

PyCapsule_Destructor PyCapsule_GetDestructor (PyObject *capsule)

Return the current destructor stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL destructor. This makes a NULL return code somewhat ambiguous; use <code>PyCapsule_IsValid()</code> or <code>PyErr_Occurred()</code> to disambiguate.

void* PyCapsule GetContext (PyObject *capsule)

Return the current context stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL context. This makes a NULL return code somewhat ambiguous; use PyCapsule IsValid() or PyErr Occurred() to disambiguate.

const char* PyCapsule_GetName (PyObject *capsule)

Return the current name stored in the capsule. On failure, set an exception and return NULL.

It is legal for a capsule to have a NULL name. This makes a NULL return code somewhat ambiguous; use <code>PyCapsule_IsValid()</code> or <code>PyErr_Occurred()</code> to disambiguate.

void* PyCapsule_Import (const char *name, int no_block)

Import a pointer to a C object from a capsule attribute in a module. The *name* parameter should specify the full name to the attribute, as in module.attribute. The *name* stored in the capsule must match this string exactly. If *no_block* is true, import the module without blocking (using <code>PyImport_ImportModuleNoBlock())</code>. If <code>no_block</code> is false, import the module conventionally (using <code>PyImport_ImportModule())</code>.

Return the capsule's internal *pointer* on success. On failure, set an exception and return NULL.

int PyCapsule_IsValid (*PyObject *capsule*, const char *name)

Determines whether or not *capsule* is a valid capsule. A valid capsule is non-NULL, passes $PyCapsule_CheckExact()$, has a non-NULL pointer stored in it, and its internal name matches the *name* parameter. (See $PyCapsule_GetPointer()$) for information on how capsule names are compared.)

In other words, if $PyCapsule_IsValid()$ returns a true value, calls to any of the accessors (any function starting with $PyCapsule_Get()$) are guaranteed to succeed.

Return a nonzero value if the object is valid and matches the name passed in. Return 0 otherwise. This function will not fail.

int PyCapsule_SetContext (PyObject *capsule, void *context)

Set the context pointer inside *capsule* to *context*.

Return 0 on success. Return nonzero and set an exception on failure.

int PyCapsule_SetDestructor (PyObject *capsule, PyCapsule_Destructor destructor)

Set the destructor inside *capsule* to *destructor*.

Return 0 on success. Return nonzero and set an exception on failure.

int PyCapsule_SetName (*PyObject *capsule*, const char *name)

Set the name inside *capsule* to *name*. If non-NULL, the name must outlive the capsule. If the previous *name* stored in the capsule was not NULL, no attempt is made to free it.

Return 0 on success. Return nonzero and set an exception on failure.

int PyCapsule_SetPointer (PyObject *capsule, void *pointer)

Set the void pointer inside *capsule* to *pointer*. The pointer may not be NULL.

Return 0 on success. Return nonzero and set an exception on failure.

8.6.10 生成器对象

生成器对象是 Python 用来实现生成器迭代器的对象。它们通常通过迭代产生值的函数来创建,而不是显式调用 PyGen_New()或 PyGen_NewWithQualName()。

PyGenObject

用于生成器对象的C结构体。

PyTypeObject PyGen_Type

与生成器对象对应的类型对 象。

int PyGen_Check (PyObject *ob)

如果 ob 是一个生成器对象则返回真值; ob 必须不为 NULL。

int PyGen_CheckExact (PyObject *ob)

如果 ob 的类型为PyGen_Type 则返回真值; ob 必须不为 NULL。

PyObject* PyGen_New (PyFrameObject *frame)

Return value: New reference. 基于 frame 对象创建并返回一个新的生成器对象。此函数会取走一个对 frame 的引用。参数必须不为 NULL。

PyObject* PyGen_NewWithQualName (PyFrameObject *frame, PyObject *name, PyObject *qualname)

Return value: New reference. 基于 frame 对象创建并返回一个新的生成器对象,其中 ___name __ 和 ___qualname __ 设为 name 和 qualname。此函数会取走一个对 frame 的引用。frame 参数必须不为 NULL。

8.6.11 协程对象

3.5 新版功能.

协程对象是使用 async 关键字声明的函数返回的。

PyCoroObject

用于协程对象的C结构体。

PyTypeObject PyCoro_Type

与协程对象对应的类型对 象。

int PyCoro_CheckExact (PyObject *ob)

如果 ob 的类型是PyCoro_Type 则返回真值; ob 必须不为 NULL。

PyObject* PyCoro_New (PyFrameObject *frame, PyObject *name, PyObject *qualname)

Return value: New reference. 基于 frame 对象创建并返回一个新的协程对象,其中 ___name__ 和 __qualname__ 设为 name 和 qualname。此函数会取得一个对 frame 的引用。frame 参数必须不为 NULL。

8.6.12 上下文变量对象

注解: 在 3.7.1 版更改: 在 Python 3.7.1 中,所有上下文变量 C API 的签名被 **更改**为使用PyObject 指针而不是PyContext, PyContextVar 以及PyContextToken,例如:

```
// in 3.7.0:
PyContext *PyContext_New(void);

// in 3.7.1+:
PyObject *PyContext_New(void);
```

详情请参阅:issue: '34762'。

3.7 新版功能.

This section details the public C API for the contextvars module.

PyContext

The C structure used to represent a contextvars.Context object.

PyContextVar

The C structure used to represent a contextvars. ContextVar object.

PyContextToken

The C structure used to represent a contextvars. Token object.

PyTypeObject PyContext_Type

The type object representing the *context* type.

PyTypeObject PyContextVar_Type

The type object representing the *context variable* type.

PyTypeObject PyContextToken_Type

The type object representing the *context variable token* type.

类型检查宏:

int PyContext_CheckExact (PyObject *o)

Return true if o is of type PyContext Type. o must not be NULL. This function always succeeds.

int PyContextVar_CheckExact (PyObject *o)

Return true if o is of type PyContextVar Type. o must not be NULL. This function always succeeds.

int PyContextToken_CheckExact (PyObject *o)

Return true if o is of type $PyContextToken_Type$. o must not be NULL. This function always succeeds.

Context object management functions:

PyObject *PyContext_New (void)

Return value: New reference. Create a new empty context object. Returns NULL if an error has occurred.

PyObject *PyContext_Copy (PyObject *ctx)

Return value: New reference. Create a shallow copy of the passed *ctx* context object. Returns NULL if an error has occurred.

PyObject *PyContext_CopyCurrent (void)

Return value: New reference. Create a shallow copy of the current thread context. Returns NULL if an error has occurred

int PyContext_Enter (PyObject *ctx)

Set ctx as the current context for the current thread. Returns 0 on success, and -1 on error.

int PyContext_Exit (PyObject *ctx)

Deactivate the *ctx* context and restore the previous context as the current context for the current thread. Returns 0 on success, and -1 on error.

int PyContext_ClearFreeList()

Clear the context variable free list. Return the total number of freed items. This function always succeeds.

Context variable functions:

PyObject *PyContextVar_New (const char *name, PyObject *def)

Return value: New reference. 创建一个新的'' ContextVar'' 对象。形参 *name* 用于自我检查和调试目的。可选形参 *def* 为上下文变量指定默认值。如果发生错误,这个函数返回''' NULL'''。

int PyContextVar_Get (PyObject *var, PyObject *default_value, PyObject **value)

获取上下文变量的值。如果在查找过程中发生错误,返回''-1'',如果没有发生错误,无论是否找到值,都返回''0'',

如果找到上下文变量,value 将是指向它的指针。如果上下文变量 没有找到,value 将指向:

- default_value, 如果非 "NULL";
- var 的默认值,如果不是 NULL;
- NULL

如果找到该值,函数将创建对它的新引用。

PyObject *PyContextVar_Set (PyObject *var, PyObject *value)

Return value: New reference. 在当前上下文中将 var 的值设为 value。返回指向PyObject 对象的指针,如果发生错误则返回 NULL。

int PyContextVar_Reset (PyObject *var, PyObject *token)

将上下文变量 var 的状态重置为它在返回 token 的 $PyContextVar_Set()$ 被调用之前的状态。此函数成功时返回 0,出错时返回 -1。

8.6.13 DateTime 对象

datetime 模块提供了各种日期和时间对象。在使用任何这些函数之前,必须在你的源码中包含头文件 datetime.h (请注意此文件并未包含在 Python.h 中),并且宏 PyDateTime_IMPORT 必须被发起调用,通常是作为模块初始化函数的一部分。这个宏会将指向特定 C 结构的指针放入一个静态变量 PyDateTimeAPI 中,它会由下面的宏来使用。

宏访问 UTC 单例:

PyObject* PyDateTime_TimeZone_UTC

返回表示 UTC 的时区单例,与 datetime.timezone.utc 为同一对象。

3.7 新版功能.

类型检查宏:

int PyDate_Check (PyObject *ob)

如果 ob 为 PyDateTime_DateType 类型或 PyDateTime_DateType 的某个子类型则返回真值。ob 不能为 NULL。

int PyDate_CheckExact (PyObject *ob)

如果 ob 为 PyDateTime_DateType 类型则返回真值。ob 不能为 NULL。

int PyDateTime_Check (PyObject *ob)

如果 ob 为 PyDateTime_DateTimeType 类型或 PyDateTime_DateTimeType 的某个子类型则返回真值。ob 不能为 NULL。

int PyDateTime_CheckExact (PyObject *ob)

如果 ob 为 PyDateTime_DateTimeType 类型则返回真值。ob 不能为 NULL。

int PyTime_Check (PyObject *ob)

如果 ob 的类型是 PyDateTime_TimeType 或是 PyDateTime_TimeType 的子类型则返回真值。ob 必须不为 NULL。

int PyTime_CheckExact (PyObject *ob)

如果 ob 的类型是 PyDateTime TimeType 则返回真值。ob 必须不为 NULL。

int PyDelta_Check (PyObject *ob)

如果 ob 为 PyDateTime_DeltaType 类型或 PyDateTime_DeltaType 的某个子类型则返回真值。ob 不能为 NULL。

int PyDelta_CheckExact (PyObject *ob)

如果 ob 为 PyDateTime_DeltaType 类型则返回真值。ob 不能为 NULL。

int PyTZInfo_Check (PyObject *ob)

如果 ob 为 PyDateTime_TZInfoType 类型或 PyDateTime_TZInfoType 的某个子类型则返回真值。ob 不能为 NULL。

int PyTZInfo_CheckExact (PyObject *ob)

如果 ob 的类型是 PyDateTime_TZInfoType 则返回真值。ob 不能为 NULL。

用于创建对象的宏:

PyObject* PyDate_FromDate (int year, int month, int day)

Return value: New reference. 返回指定年、月、日的 datetime.date 对象。

PyObject* PyDateTime_FromDateAndTime (int year, int month, int day, int hour, int minute, int second, int usecond)

Return value: New reference. Return a datetime.datetime object with the specified year, month, day, hour, minute, second and microsecond.

PyObject* PyDateTime_FromDateAndTimeAndFold (int year, int month, int day, int hour, int minute,

int second, int usecond, int fold)

Return value: New reference. Return a datetime.datetime object with the specified year, month, day, hour, minute, second, microsecond and fold.

3.6 新版功能.

PyObject* PyTime FromTime (int hour, int minute, int second, int usecond)

Return value: New reference. Return a datetime.time object with the specified hour, minute, second and microsecond.

PyObject* PyTime_FromTimeAndFold (int hour, int minute, int second, int usecond, int fold)

Return value: New reference. Return a datetime.time object with the specified hour, minute, second, microsecond and fold.

3.6 新版功能.

PyObject* PyDelta_FromDSU (int days, int seconds, int useconds)

Return value: New reference. Return a datetime.timedelta object representing the given number of days, seconds and microseconds. Normalization is performed so that the resulting number of microseconds and seconds lie in the ranges documented for datetime.timedelta objects.

PyObject* PyTimeZone_FromOffset (PyDateTime_DeltaType* offset)

Return value: New reference. Return a datetime.timezone object with an unnamed fixed offset represented by the offset argument.

3.7 新版功能.

PyObject* PyTimeZone_FromOffsetAndName (PyDateTime_DeltaType* offset, PyUnicode* name)

Return value: New reference. Return a datetime.timezone object with a fixed offset represented by the *offset* argument and with tzname *name*.

3.7 新版功能.

Macros to extract fields from date objects. The argument must be an instance of PyDateTime_Date, including subclasses (such as PyDateTime_DateTime). The argument must not be NULL, and the type is not checked:

int PyDateTime GET YEAR (PyDateTime Date *o)

Return the year, as a positive int.

int PyDateTime_GET_MONTH (PyDateTime_Date *o)

返回月,从0到12的整数。

int PyDateTime_GET_DAY (PyDateTime_Date *o)

返回日期,从0到31的整数。

Macros to extract fields from datetime objects. The argument must be an instance of PyDateTime_DateTime, including subclasses. The argument must not be NULL, and the type is not checked:

int PyDateTime_DATE_GET_HOUR (PyDateTime_DateTime *o)

返回小时,从0到23的整数。

int PyDateTime_DATE_GET_MINUTE (PyDateTime_DateTime *o)

返回分钟,从0到59的整数。

int PyDateTime_DATE_GET_SECOND (PyDateTime_DateTime *o)

返回秒,从0到59的整数。

int PyDateTime_DATE_GET_MICROSECOND (PyDateTime_DateTime *o)

返回微秒,从0到99999的整数。

Macros to extract fields from time objects. The argument must be an instance of PyDateTime_Time, including subclasses. The argument must not be NULL, and the type is not checked:

int PyDateTime_TIME_GET_HOUR (PyDateTime_Time *o)

返回小时,从0到23的整数。

int PyDateTime_TIME_GET_MINUTE (PyDateTime_Time *o)

返回分钟,从0到59的整数。

int PyDateTime_TIME_GET_SECOND (PyDateTime_Time *o)

返回秒,从0到59的整数。

int $PyDateTime_TIME_GET_MICROSECOND$ (PyDateTime_Time *o)

返回微秒,从0到99999的整数。

Macros to extract fields from time delta objects. The argument must be an instance of PyDateTime_Delta, including subclasses. The argument must not be NULL, and the type is not checked:

int PyDateTime_DELTA_GET_DAYS (PyDateTime_Delta *o)

返回天数,从-999999999到999999999的整数。

3.3 新版功能.

int PyDateTime_DELTA_GET_SECONDS (PyDateTime_Delta *o)

返回秒数,从0到86399的整数。

3.3 新版功能.

int PyDateTime_DELTA_GET_MICROSECONDS (PyDateTime_Delta *o)

返回微秒数,从0到99999的整数。

3.3 新版功能.

Macros for the convenience of modules implementing the DB API:

PyObject* PyDateTime_FromTimestamp (PyObject *args)

Return value: New reference. Create and return a new datetime.datetime object given an argument tuple suitable for passing to datetime.datetime.fromtimestamp().

PyObject* PyDate_FromTimestamp (PyObject *args)

Return value: New reference. Create and return a new datetime.date object given an argument tuple suitable for passing to datetime.date.fromtimestamp().

CHAPTER 9

Initialization, Finalization, and Threads

请参阅Python 初始化配置。

9.1 在 Python 初始化之前

In an application embedding Python, the $Py_Initialize()$ function must be called before using any other Python/C API functions; with the exception of a few functions and the *global configuration variables*.

在初始化 Python 之前,可以安全地调用以下函数:

- 配置函数:
 - PyImport_AppendInittab()
 - PyImport_ExtendInittab()
 - PyInitFrozenExtensions()
 - PyMem_SetAllocator()
 - PyMem_SetupDebugHooks()
 - PyObject_SetArenaAllocator()
 - Py_SetPath()
 - Py_SetProgramName()
 - Py_SetPythonHome()
 - Py_SetStandardStreamEncoding()
 - PySys_AddWarnOption()
 - PySys_AddXOption()
 - PySys_ResetWarnOptions()
- 信息函数:
 - Py_IsInitialized()
 - PyMem_GetAllocator()
 - PyObject_GetArenaAllocator()

- Py_GetBuildInfo()
- Py_GetCompiler()
- Py_GetCopyright()
- Py_GetPlatform()
- Py GetVersion()
- 工具
 - Py_DecodeLocale()
- 内存分配器:
 - PyMem_RawMalloc()
 - PyMem_RawRealloc()
 - PyMem_RawCalloc()
 - PyMem_RawFree()

注解: 以下函数不应该在Py_Initialize(): Py_EncodeLocale(), Py_GetPath(), Py_GetPrefix(), Py_GetExecPrefix(), Py_GetProgramFullPath(), Py_GetPythonHome(), Py_GetProgramName()和PyEval_InitThreads()前调用。

9.2 全局配置变量

Python has variables for the global configuration to control different features and options. By default, these flags are controlled by command line options.

When a flag is set by an option, the value of the flag is the number of times that the option was set. For example, -b sets $Py_BytesWarningFlag$ to 1 and -bb sets $Py_BytesWarningFlag$ to 2.

Py_BytesWarningFlag

Issue a warning when comparing bytes or bytearray with str or bytes with int. Issue an error if greater or equal to 2.

由-b选项设置。

Py DebugFlag

Turn on parser debugging output (for expert only, depending on compilation options).

Set by the -d option and the PYTHONDEBUG environment variable.

Py_DontWriteBytecodeFlag

If set to non-zero, Python won't try to write .pyc files on the import of source modules.

Set by the -B option and the PYTHONDONTWRITEBYTECODE environment variable.

Py_FrozenFlag

Suppress error messages when calculating the module search path in Py_GetPath().

Private flag used by $_\texttt{freeze_importlib}$ and frozenmain programs.

Py_HashRandomizationFlag

Set to 1 if the PYTHONHASHSEED environment variable is set to a non-empty string.

If the flag is non-zero, read the PYTHONHASHSEED environment variable to initialize the secret hash seed.

Py IgnoreEnvironmentFlag

忽略所有 PYTHON* 环境变量,例如可能已设置的 PYTHONPATH 和 PYTHONHOME。

由-E和-I选项设置。

Py_InspectFlag

When a script is passed as first argument or the -c option is used, enter interactive mode after executing the script or the command, even when sys.stdin does not appear to be a terminal.

Set by the -i option and the PYTHONINSPECT environment variable.

Py InteractiveFlag

由-i选项设置。

Py_IsolatedFlag

Run Python in isolated mode. In isolated mode sys.path contains neither the script's directory nor the user's site-packages directory.

由-I选项设置。

3.4 新版功能.

Py_LegacyWindowsFSEncodingFlag

If the flag is non-zero, use the mbcs encoding instead of the UTF-8 encoding for the filesystem encoding.

Set to 1 if the PYTHONLEGACYWINDOWSFSENCODING environment variable is set to a non-empty string.

有关更多详细信息,请参阅 PEP 529。

可用性: Windows。

Py_LegacyWindowsStdioFlag

If the flag is non-zero, use io.FileIO instead of WindowsConsoleIO for sys standard streams.

Set to 1 if the PYTHONLEGACYWINDOWSSTDIO environment variable is set to a non-empty string.

有关更多详细信息,请参阅 PEP 528。

可用性: Windows。

Py_NoSiteFlag

禁用 site 的导入及其所附带的基于站点对 sys.path 的操作。如果 site 会在稍后被显式地导入也会禁用这些操作(如果你希望触发它们则应调用 site.main())。

由-S 洗项设置。

Py_NoUserSiteDirectory

不要将 用户 site-packages 目录添加到 sys.path。

Set by the -s and -I options, and the PYTHONNOUSERSITE environment variable.

Py_OptimizeFlag

Set by the -O option and the PYTHONOPTIMIZE environment variable.

Py_QuietFlag

即使在交互模式下也不显示版权和版本信息。

由-q 选项设置。

3.2 新版功能.

Py_UnbufferedStdioFlag

Force the stdout and stderr streams to be unbuffered.

Set by the -u option and the PYTHONUNBUFFERED environment variable.

Py_VerboseFlag

Print a message each time a module is initialized, showing the place (filename or built-in module) from which it is loaded. If greater or equal to 2, print a message for each file that is checked for when searching for a module. Also provides information on module cleanup at exit.

Set by the $\neg v$ option and the PYTHONVERBOSE environment variable.

9.2. 全局配置变量 133

9.3 Initializing and finalizing the interpreter

void Py_Initialize()

Initialize the Python interpreter. In an application embedding Python, this should be called before using any other Python/C API functions; see *Before Python Initialization* for the few exceptions.

This initializes the table of loaded modules (sys.modules), and creates the fundamental modules builtins, __main__ and sys. It also initializes the module search path (sys.path). It does not set sys.argv; use $PySys_SetArgvEx()$ for that. This is a no-op when called for a second time (without calling $Py_FinalizeEx()$ first). There is no return value; it is a fatal error if the initialization fails.

注解: On Windows, changes the console mode from O_TEXT to O_BINARY, which will also affect non-Python uses of the console using the C Runtime.

void Py_InitializeEx (int initsigs)

This function works like Py_Initialize() if *initsigs* is 1. If *initsigs* is 0, it skips initialization registration of signal handlers, which might be useful when Python is embedded.

int Py_IsInitialized()

Return true (nonzero) when the Python interpreter has been initialized, false (zero) if not. After Py FinalizeEx() is called, this returns false until Py Initialize() is called again.

int Py_FinalizeEx()

Undo all initializations made by $Py_Initialize()$ and subsequent use of Python/C API functions, and destroy all sub-interpreters (see $Py_NewInterpreter()$ below) that were created and not yet destroyed since the last call to $Py_Initialize()$. Ideally, this frees all memory allocated by the Python interpreter. This is a no-op when called for a second time (without calling $Py_Initialize()$ again first). Normally the return value is 0. If there were errors during finalization (flushing buffered data), -1 is returned.

This function is provided for a number of reasons. An embedding application might want to restart Python without having to restart the application itself. An application that has loaded the Python interpreter from a dynamically loadable library (or DLL) might want to free all memory allocated by Python before unloading the DLL. During a hunt for memory leaks in an application a developer might want to free all memory allocated by Python before exiting from the application.

Bugs and caveats: The destruction of modules and objects in modules is done in random order; this may cause destructors (__del__() methods) to fail when they depend on other objects (even functions) or modules. Dynamically loaded extension modules loaded by Python are not unloaded. Small amounts of memory allocated by the Python interpreter may not be freed (if you find a leak, please report it). Memory tied up in circular references between objects is not freed. Some memory allocated by extension modules may not be freed. Some extensions may not work properly if their initialization routine is called more than once; this can happen if an application calls Py_Initialize() and Py_FinalizeEx() more than once.

Raises an auditing event cpython._PySys_ClearAuditHooks with no arguments.

3.6 新版功能.

void Py_Finalize()

This is a backwards-compatible version of Py_FinalizeEx() that disregards the return value.

9.4 Process-wide parameters

int Py_SetStandardStreamEncoding (const char *encoding, const char *errors)

This function should be called before $Py_Initialize()$, if it is called at all. It specifies which encoding and error handling to use with standard IO, with the same meanings as in str.encode().

It overrides PYTHONIOENCODING values, and allows embedding code to control IO encoding when the environment variable does not work.

encoding and/or *errors* may be NULL to use PYTHONIOENCODING and/or default values (depending on other settings).

Note that sys.stderr always uses the "backslashreplace" error handler, regardless of this (or any other) setting.

If $Py_FinalizeEx()$ is called, this function will need to be called again in order to affect subsequent calls to $Py_Initialize()$.

Returns 0 if successful, a nonzero value on error (e.g. calling after the interpreter has already been initialized). 3.4 新版功能.

void Py_SetProgramName (const wchar_t *name)

This function should be called before $Py_Initialize()$ is called for the first time, if it is called at all. It tells the interpreter the value of the argv[0] argument to the main() function of the program (converted to wide characters). This is used by $Py_GetPath()$ and some other functions below to find the Python runtime libraries relative to the interpreter executable. The default value is 'python'. The argument should point to a zero-terminated wide character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

wchar* Py_GetProgramName ()

Return the program name set with $Py_SetProgramName()$, or the default. The returned string points into static storage; the caller should not modify its value.

wchar t* Py GetPrefix()

Return the *prefix* for installed platform-independent files. This is derived through a number of complicated rules from the program name set with <code>Py_SetProgramName()</code> and some environment variables; for example, if the program name is '/usr/local/bin/python', the prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the <code>prefix</code> variable in the top-level <code>Makefile</code> and the <code>--prefix</code> argument to the <code>configure</code> script at build time. The value is available to Python code as <code>sys.prefix</code>. It is only useful on Unix. See also the next function.

wchar t* Py GetExecPrefix()

Return the *exec_prefix* for installed platform-*dependent* files. This is derived through a number of complicated rules from the program name set with <code>Py_SetProgramName()</code> and some environment variables; for example, if the program name is '/usr/local/bin/python', the exec-prefix is '/usr/local'. The returned string points into static storage; the caller should not modify its value. This corresponds to the <code>exec_prefix</code> variable in the top-level <code>Makefile</code> and the <code>--exec-prefix</code> argument to the <code>configure</code> script at build time. The value is available to Python code as <code>sys.exec_prefix</code>. It is only useful on Unix.

Background: The exec-prefix differs from the prefix when platform dependent files (such as executables and shared libraries) are installed in a different directory tree. In a typical installation, platform dependent files may be installed in the /usr/local/plat subtree while platform independent may be installed in /usr/local

Generally speaking, a platform is a combination of hardware and software families, e.g. Sparc machines running the Solaris 2.x operating system are considered the same platform, but Intel machines running Solaris 2.x are another platform, and Intel machines running Linux are yet another platform. Different major revisions of the same operating system generally also form different platforms. Non-Unix operating systems are a different

story; the installation strategies on those systems are so different that the prefix and exec-prefix are meaningless, and set to the empty string. Note that compiled Python bytecode files are platform independent (but not independent from the Python version by which they were compiled!).

System administrators will know how to configure the **mount** or **automount** programs to share /usr/local between platforms while having /usr/local/plat be a different filesystem for each platform.

wchar t* Py GetProgramFullPath()

Return the full program name of the Python executable; this is computed as a side-effect of deriving the default module search path from the program name (set by $Py_SetProgramName()$ above). The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.executable.

wchar_t* Py_GetPath()

Return the default module search path; this is computed from the program name (set by $Py_SetProgramName()$ above) and some environment variables. The returned string consists of a series of directory names separated by a platform dependent delimiter character. The delimiter character is ':' on Unix and Mac OS X, ';' on Windows. The returned string points into static storage; the caller should not modify its value. The list sys.path is initialized with this value on interpreter startup; it can be (and usually is) modified later to change the search path for loading modules.

void Py SetPath (const wchar t *)

Set the default module search path. If this function is called before $Py_Initialize()$, then $Py_GetPath()$ won't attempt to compute a default search path but uses the one provided instead. This is useful if Python is embedded by an application that has full knowledge of the location of all modules. The path components should be separated by the platform dependent delimiter character, which is ':' on Unix and Mac OS X, ';' on Windows.

This also causes sys.executable to be set to the program full path (see $Py_GetProgramFullPath()$) and for sys.prefix and sys.exec_prefix to be empty. It is up to the caller to modify these if required after calling $Py_Initialize()$.

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

The path argument is copied internally, so the caller may free it after the call completes.

在 3.8 版更改: The program full path is now used for sys.executable, instead of the program name.

const char* Py_GetVersion()

Return the version of this Python interpreter. This is a string that looks something like

```
"3.0a5+ (py3k:63103M, May 12 2008, 00:53:55) \n[GCC 4.2.3]"
```

The first word (up to the first space character) is the current Python version; the first three characters are the major and minor version separated by a period. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.version.

const char* Py_GetPlatform()

Return the platform identifier for the current platform. On Unix, this is formed from the "official" name of the operating system, converted to lower case, followed by the major revision number; e.g., for Solaris 2.x, which is also known as SunOS 5.x, the value is 'sunos5'. On Mac OS X, it is 'darwin'. On Windows, it is 'win'. The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.platform.

const char* Py_GetCopyright()

Return the official copyright string for the current Python version, for example

```
'Copyright 1991-1995 Stichting Mathematisch Centrum, Amsterdam'
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as sys.copyright.

const char* Py_GetCompiler()

Return an indication of the compiler used to build the current Python version, in square brackets, for example:

```
"[GCC 2.7.2.2]"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

const char* Py_GetBuildInfo()

Return information about the sequence number and build date and time of the current Python interpreter instance, for example

```
"#67, Aug 1 1997, 22:34:28"
```

The returned string points into static storage; the caller should not modify its value. The value is available to Python code as part of the variable sys.version.

void PySys_SetArgvEx (int argc, wchar_t **argv, int updatepath)

Set sys.argv based on *argc* and *argv*. These parameters are similar to those passed to the program's main() function with the difference that the first entry should refer to the script file to be executed rather than the executable hosting the Python interpreter. If there isn't a script that will be run, the first entry in *argv* can be an empty string. If this function fails to initialize sys.argv, a fatal condition is signalled using $Py_FatalError()$.

If *updatepath* is zero, this is all the function does. If *updatepath* is non-zero, the function also modifies sys. path according to the following algorithm:

- If the name of an existing script is passed in argv[0], the absolute path of the directory where the script is located is prepended to sys.path.
- Otherwise (that is, if *argc* is 0 or argv[0] doesn't point to an existing file name), an empty string is prepended to sys.path, which is the same as prepending the current working directory (".").

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

注解: It is recommended that applications embedding the Python interpreter for purposes other than executing a single script pass 0 as *updatepath*, and update sys.path themselves if desired. See CVE-2008-5983.

On versions before 3.1.3, you can achieve the same effect by manually popping the first sys.path element after having called $PySys_SetArgv()$, for example using:

```
PyRun_SimpleString("import sys; sys.path.pop(0)\n");
```

3.1.3 新版功能.

void PySys_SetArgv (int argc, wchar_t **argv)

This function works like $PySys_SetArgvEx$ () with updatepath set to 1 unless the **python** interpreter was started with the -I.

Use Py_DecodeLocale () to decode a bytes string to get a wchar_* string.

在 3.4 版更改: The updatepath value depends on -I.

void Py_SetPythonHome (const wchar_t *home)

Set the default "home" directory, that is, the location of the standard Python libraries. See PYTHONHOME for the meaning of the argument string.

The argument should point to a zero-terminated character string in static storage whose contents will not change for the duration of the program's execution. No code in the Python interpreter will change the contents of this storage.

Use Py_DecodeLocale() to decode a bytes string to get a wchar_* string.

w_char* Py_GetPythonHome()

Return the default "home", that is, the value set by a previous call to Py_SetPythonHome(), or the value of the PYTHONHOME environment variable if it is set.

9.5 Thread State and the Global Interpreter Lock

The Python interpreter is not fully thread-safe. In order to support multi-threaded Python programs, there's a global lock, called the *global interpreter lock* or *GIL*, that must be held by the current thread before it can safely access Python objects. Without the lock, even the simplest operations could cause problems in a multi-threaded program: for example, when two threads simultaneously increment the reference count of the same object, the reference count could end up being incremented only once instead of twice.

Therefore, the rule exists that only the thread that has acquired the *GIL* may operate on Python objects or call Python/C API functions. In order to emulate concurrency of execution, the interpreter regularly tries to switch threads (see sys.setswitchinterval()). The lock is also released around potentially blocking I/O operations like reading or writing a file, so that other Python threads can run in the meantime.

The Python interpreter keeps some thread-specific bookkeeping information inside a data structure called PyThreadState. There's also one global variable pointing to the current PyThreadState: it can be retrieved using $PyThreadState_Get()$.

9.5.1 Releasing the GIL from extension code

Most extension code manipulating the GIL has the following simple structure:

```
Save the thread state in a local variable.
Release the global interpreter lock.
... Do some blocking I/O operation ...
Reacquire the global interpreter lock.
Restore the thread state from the local variable.
```

This is so common that a pair of macros exists to simplify it:

```
Py_BEGIN_ALLOW_THREADS
... Do some blocking I/O operation ...
Py_END_ALLOW_THREADS
```

The Py_BEGIN_ALLOW_THREADS macro opens a new block and declares a hidden local variable; the Py_END_ALLOW_THREADS macro closes the block.

The block above expands to the following code:

```
PyThreadState *_save;

_save = PyEval_SaveThread();
... Do some blocking I/O operation ...
PyEval_RestoreThread(_save);
```

Here is how these functions work: the global interpreter lock is used to protect the pointer to the current thread state. When releasing the lock and saving the thread state, the current thread state pointer must be retrieved before the lock is released (since another thread could immediately acquire the lock and store its own thread state in the global variable). Conversely, when acquiring the lock and restoring the thread state, the lock must be acquired before storing the thread state pointer.

注解: Calling system I/O functions is the most common use case for releasing the GIL, but it can also be useful before calling long-running computations which don't need access to Python objects, such as compression or cryptographic functions operating over memory buffers. For example, the standard zlib and hashlib modules release the GIL when compressing or hashing data.

9.5.2 非 Python 创建的线程

When threads are created using the dedicated Python APIs (such as the threading module), a thread state is automatically associated to them and the code showed above is therefore correct. However, when threads are created from C (for example by a third-party library with its own thread management), they don't hold the GIL, nor is there a thread state structure for them.

If you need to call Python code from these threads (often this will be part of a callback API provided by the aforementioned third-party library), you must first register these threads with the interpreter by creating a thread state data structure, then acquiring the GIL, and finally storing their thread state pointer, before you can start using the Python/C API. When you are done, you should reset the thread state pointer, release the GIL, and finally free the thread state data structure.

The <code>PyGILState_Ensure()</code> and <code>PyGILState_Release()</code> functions do all of the above automatically. The typical idiom for calling into Python from a C thread is:

```
PyGILState_STATE gstate;
gstate = PyGILState_Ensure();

/* Perform Python actions here. */
result = CallSomeFunction();
/* evaluate result or handle exception */

/* Release the thread. No Python API allowed beyond this point. */
PyGILState_Release(gstate);
```

Note that the PyGILState_*() functions assume there is only one global interpreter (created automatically by $Py_Initialize()$). Python supports the creation of additional interpreters (using $Py_NewInterpreter()$), but mixing multiple interpreters and the PyGILState_*() API is unsupported.

9.5.3 Cautions about fork()

Another important thing to note about threads is their behaviour in the face of the $C \; fork \; ()$ call. On most systems with $fork \; ()$, after a process forks only the thread that issued the fork will exist. This has a concrete impact both on how locks must be handled and on all stored state in CPython's runtime.

The fact that only the "current" thread remains means any locks held by other threads will never be released. Python solves this for os.fork() by acquiring the locks it uses internally before the fork, and releasing them afterwards. In addition, it resets any lock-objects in the child. When extending or embedding Python, there is no way to inform Python of additional (non-Python) locks that need to be acquired before or reset after a fork. OS facilities such as pthread_atfork() would need to be used to accomplish the same thing. Additionally, when extending or embedding Python, calling fork() directly rather than through os.fork() (and returning to or calling into Python) may result in a deadlock by one of Python's internal locks being held by a thread that is defunct after the fork, PyOS AfterFork Child() tries to reset the necessary locks, but is not always able to.

The fact that all other threads go away also means that CPython's runtime state there must be cleaned up properly, which os.fork() does. This means finalizing all other <code>PyThreadState</code> objects belonging to the current interpreter and all other <code>PyInterpreterState</code> objects. Due to this and the special nature of the "main" interpreter, fork() should only be called in that interpreter's "main" thread, where the CPython global runtime was originally initialized. The only exception is if <code>exec()</code> will be called immediately after.

9.5.4 高阶 API

These are the most commonly used types and functions when writing C extension code, or when embedding the Python interpreter:

PyInterpreterState

This data structure represents the state shared by a number of cooperating threads. Threads belonging to the same interpreter share their module administration and a few other internal items. There are no public members in this structure.

Threads belonging to different interpreters initially share nothing, except process state like available memory, open file descriptors and such. The global interpreter lock is also shared by all threads, regardless of to which interpreter they belong.

PyThreadState

This data structure represents the state of a single thread. The only public data member is *PyInterpreterState* *interp, which points to this thread's interpreter state.

void PyEval_InitThreads()

Initialize and acquire the global interpreter lock. It should be called in the main thread before creating a second thread or engaging in any other thread operations such as $PyEval_ReleaseThread(tstate)$. It is not needed before calling $PyEval_SaveThread()$ or $PyEval_RestoreThread()$.

This is a no-op when called for a second time.

在 3.7 版更改: This function is now called by <code>Py_Initialize()</code>, so you don't have to call it yourself anymore.

在 3.2 版更改: This function cannot be called before Py_Initialize() anymore.

int PyEval_ThreadsInitialized()

Returns a non-zero value if PyEval_InitThreads () has been called. This function can be called without holding the GIL, and therefore can be used to avoid calls to the locking API when running single-threaded.

在 3.7 版更改: The GIL is now initialized by Py_Initialize().

PyThreadState* PyEval_SaveThread()

Release the global interpreter lock (if it has been created) and reset the thread state to NULL, returning the previous thread state (which is not NULL). If the lock has been created, the current thread must have acquired it.

void PyEval_RestoreThread (PyThreadState *tstate)

Acquire the global interpreter lock (if it has been created) and set the thread state to *tstate*, which must not be NULL. If the lock has been created, the current thread must not have acquired it, otherwise deadlock ensues.

注解: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>_Py_IsFinalizing()</code> or <code>sys.is_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

PyThreadState* PyThreadState_Get()

Return the current thread state. The global interpreter lock must be held. When the current thread state is NULL, this issues a fatal error (so that the caller needn't check for NULL).

PyThreadState* PyThreadState_Swap (PyThreadState *tstate)

Swap the current thread state with the thread state given by the argument *tstate*, which may be NULL. The global interpreter lock must be held and is not released.

The following functions use thread-local storage, and are not compatible with sub-interpreters:

PyGILState_STATE PyGILState_Ensure()

Ensure that the current thread is ready to call the Python C API regardless of the current state of Python, or of the global interpreter lock. This may be called as many times as desired by a thread as long as each call is matched with a call to <code>PyGILState_Release()</code>. In general, other thread-related APIs

may be used between <code>PyGILState_Ensure()</code> and <code>PyGILState_Release()</code> calls as long as the thread state is restored to its previous state before the Release(). For example, normal usage of the <code>Py_BEGIN_ALLOW_THREADS</code> and <code>Py_END_ALLOW_THREADS</code> macros is acceptable.

The return value is an opaque "handle" to the thread state when <code>PyGILState_Ensure()</code> was called, and must be passed to <code>PyGILState_Release()</code> to ensure Python is left in the same state. Even though recursive calls are allowed, these handles <code>cannot</code> be shared - each unique call to <code>PyGILState_Ensure()</code> must save the handle for its call to <code>PyGILState_Release()</code>.

When the function returns, the current thread will hold the GIL and be able to call arbitrary Python code. Failure is a fatal error.

注解: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>_Py_IsFinalizing()</code> or <code>sys.is_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

void PyGILState_Release (PyGILState_STATE)

Release any resources previously acquired. After this call, Python's state will be the same as it was prior to the corresponding <code>PyGILState_Ensure()</code> call (but generally this state will be unknown to the caller, hence the use of the GILState API).

Every call to $PyGILState_Ensure()$ must be matched by a call to $PyGILState_Release()$ on the same thread.

PyThreadState* PyGILState_GetThisThreadState()

Get the current thread state for this thread. May return <code>NULL</code> if no GILState API has been used on the current thread. Note that the main thread always has such a thread-state, even if no auto-thread-state call has been made on the main thread. This is mainly a helper/diagnostic function.

int PyGILState_Check()

Return 1 if the current thread is holding the GIL and 0 otherwise. This function can be called from any thread at any time. Only if it has had its Python thread state initialized and currently is holding the GIL will it return 1. This is mainly a helper/diagnostic function. It can be useful for example in callback contexts or memory allocation functions when knowing that the GIL is locked can allow the caller to perform sensitive actions or otherwise behave differently.

3.4 新版功能.

The following macros are normally used without a trailing semicolon; look for example usage in the Python source distribution.

Py_BEGIN_ALLOW_THREADS

This macro expands to { PyThreadState *_save; _save = PyEval_SaveThread();. Note that it contains an opening brace; it must be matched with a following $Py_END_ALLOW_THREADS$ macro. See above for further discussion of this macro.

Py_END_ALLOW_THREADS

This macro expands to PyEval_RestoreThread (_save); }. Note that it contains a closing brace; it must be matched with an earlier $Py_BEGIN_ALLOW_THREADS$ macro. See above for further discussion of this macro.

Py BLOCK THREADS

This macro expands to PyEval_RestoreThread(_save);: it is equivalent to Py_END_ALLOW_THREADS without the closing brace.

Py_UNBLOCK_THREADS

This macro expands to _save = PyEval_SaveThread();: it is equivalent to Py_BEGIN_ALLOW_THREADS without the opening brace and variable declaration.

9.5.5 Low-level API

All of the following functions must be called after Py_Initialize().

在 3.7 版更改: Py_Initialize () now initializes the GIL.

PyInterpreterState* PyInterpreterState_New ()

Create a new interpreter state object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

Raises an auditing event cpython.PyInterpreterState New with no arguments.

void PyInterpreterState Clear (PyInterpreterState *interp)

Reset all information in an interpreter state object. The global interpreter lock must be held.

Raises an auditing event cpython.PyInterpreterState_Clear with no arguments.

void PyInterpreterState_Delete (PyInterpreterState *interp)

Destroy an interpreter state object. The global interpreter lock need not be held. The interpreter state must have been reset with a previous call to <code>PyInterpreterState_Clear()</code>.

PyThreadState* PyThreadState_New (PyInterpreterState *interp)

Create a new thread state object belonging to the given interpreter object. The global interpreter lock need not be held, but may be held if it is necessary to serialize calls to this function.

void PyThreadState_Clear (PyThreadState *tstate)

Reset all information in a thread state object. The global interpreter lock must be held.

void PyThreadState_Delete (PyThreadState *tstate)

Destroy a thread state object. The global interpreter lock need not be held. The thread state must have been reset with a previous call to PyThreadState Clear().

PY_INT64_T PyInterpreterState_GetID (PyInterpreterState *interp)

Return the interpreter's unique ID. If there was any error in doing so then -1 is returned and an error is set.

3.7 新版功能.

PyObject* PyInterpreterState_GetDict (PyInterpreterState *interp)

Return a dictionary in which interpreter-specific data may be stored. If this function returns NULL then no exception has been raised and the caller should assume no interpreter-specific dict is available.

This is not a replacement for $PyModule_GetState()$, which extensions should use to store interpreter-specific state information.

3.8 新版功能.

PyObject* PyThreadState_GetDict()

Return value: Borrowed reference. Return a dictionary in which extensions can store thread-specific state information. Each extension should use a unique key to use to store state in the dictionary. It is okay to call this function when no current thread state is available. If this function returns NULL, no exception has been raised and the caller should assume no current thread state is available.

int PyThreadState_SetAsyncExc (unsigned long id, PyObject *exc)

Asynchronously raise an exception in a thread. The *id* argument is the thread id of the target thread; *exc* is the exception object to be raised. This function does not steal any references to *exc*. To prevent naive misuse, you must write your own C extension to call this. Must be called with the GIL held. Returns the number of thread states modified; this is normally one, but will be zero if the thread id isn't found. If *exc* is NULL, the pending exception (if any) for the thread is cleared. This raises no exceptions.

在 3.7 版更改: The type of the id parameter changed from long to unsigned long.

void PyEval_AcquireThread (PyThreadState *tstate)

Acquire the global interpreter lock and set the current thread state to *tstate*, which should not be NULL. The lock must have been created earlier. If this thread already has the lock, deadlock ensues.

注解: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use _Py_IsFinalizing() or sys.is_finalizing() to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

在 3.8 版 更 改: Updated to be consistent with <code>PyEval_RestoreThread()</code>, <code>Py_END_ALLOW_THREADS()</code>, and <code>PyGILState_Ensure()</code>, and terminate the current thread if called while the interpreter is finalizing.

PyEval_RestoreThread() is a higher-level function which is always available (even when threads have not been initialized).

void PyEval_ReleaseThread (PyThreadState *tstate)

Reset the current thread state to <code>NULL</code> and release the global interpreter lock. The lock must have been created earlier and must be held by the current thread. The *tstate* argument, which must not be <code>NULL</code>, is only used to check that it represents the current thread state --- if it isn't, a fatal error is reported.

PyEval_SaveThread() is a higher-level function which is always available (even when threads have not been initialized).

void PyEval_AcquireLock()

Acquire the global interpreter lock. The lock must have been created earlier. If this thread already has the lock, a deadlock ensues.

3.2 版 后 已 移 除: This function does not update the current thread state. Please use PyEval_RestoreThread() or PyEval_AcquireThread() instead.

注解: Calling this function from a thread when the runtime is finalizing will terminate the thread, even if the thread was not created by Python. You can use <code>_Py_IsFinalizing()</code> or <code>sys.is_finalizing()</code> to check if the interpreter is in process of being finalized before calling this function to avoid unwanted termination.

在 3.8 版 更 改: Updated to be consistent with <code>PyEval_RestoreThread()</code>, <code>Py_END_ALLOW_THREADS()</code>, and <code>PyGILState_Ensure()</code>, and terminate the current thread if called while the interpreter is finalizing.

void PyEval_ReleaseLock()

Release the global interpreter lock. The lock must have been created earlier.

3.2 版 后 已 移 除: This function does not update the current thread state. Please use PyEval_SaveThread() or PyEval_ReleaseThread() instead.

9.6 Sub-interpreter support

While in most uses, you will only embed a single Python interpreter, there are cases where you need to create several independent interpreters in the same process and perhaps even in the same thread. Sub-interpreters allow you to do that

The "main" interpreter is the first one created when the runtime initializes. It is usually the only Python interpreter in a process. Unlike sub-interpreters, the main interpreter has unique process-global responsibilities like signal handling. It is also responsible for execution during runtime initialization and is usually the active interpreter during runtime finalization. The <code>PyInterpreterState_Main()</code> function returns a pointer to its state.

You can switch between sub-interpreters using the <code>PyThreadState_Swap()</code> function. You can create and destroy them using the following functions:

PyThreadState* Py_NewInterpreter()

Create a new sub-interpreter. This is an (almost) totally separate environment for the execution of Python code. In particular, the new interpreter has separate, independent versions of all imported modules, including

the fundamental modules <code>builtins</code>, __main__ and <code>sys</code>. The table of loaded modules (<code>sys.modules</code>) and the module search path (<code>sys.path</code>) are also separate. The new environment has no <code>sys.argv</code> variable. It has new standard I/O stream file objects <code>sys.stdin</code>, <code>sys.stdout</code> and <code>sys.stderr</code> (however these refer to the same underlying file descriptors).

The return value points to the first thread state created in the new sub-interpreter. This thread state is made in the current thread state. Note that no actual thread is created; see the discussion of thread states below. If creation of the new interpreter is unsuccessful, NULL is returned; no exception is set since the exception state is stored in the current thread state and there may not be a current thread state. (Like all other Python/C API functions, the global interpreter lock must be held before calling this function and is still held when it returns; however, unlike most other Python/C API functions, there needn't be a current thread state on entry.)

Extension modules are shared between (sub-)interpreters as follows:

- For modules using multi-phase initialization, e.g. <code>PyModule_FromDefAndSpec()</code>, a separate module object is created and initialized for each interpreter. Only C-level static and global variables are shared between these module objects.
- For modules using single-phase initialization, e.g. <code>PyModule_Create()</code>, the first time a particular extension is imported, it is initialized normally, and a (shallow) copy of its module's dictionary is squirreled away. When the same extension is imported by another (sub-)interpreter, a new module is initialized and filled with the contents of this copy; the extension's <code>init</code> function is not called. Objects in the module's dictionary thus end up shared across (sub-)interpreters, which might cause unwanted behavior (see <code>Bugs and caveats below</code>).

Note that this is different from what happens when an extension is imported after the interpreter has been completely re-initialized by calling $Py_FinalizeEx()$ and $Py_Initialize()$; in that case, the extension's initmodule function is called again. As with multi-phase initialization, this means that only C-level static and global variables are shared between these modules.

void Py EndInterpreter (PyThreadState *tstate)

Destroy the (sub-)interpreter represented by the given thread state. The given thread state must be the current thread state. See the discussion of thread states below. When the call returns, the current thread state is NULL. All thread states associated with this interpreter are destroyed. (The global interpreter lock must be held before calling this function and is still held when it returns.) $Py_FinalizeEx()$ will destroy all sub-interpreters that haven't been explicitly destroyed at that point.

9.6.1 错误和警告

Because sub-interpreters (and the main interpreter) are part of the same process, the insulation between them isn't perfect --- for example, using low-level file operations like os.close() they can (accidentally or maliciously) affect each other's open files. Because of the way extensions are shared between (sub-)interpreters, some extensions may not work properly; this is especially likely when using single-phase initialization or (static) global variables. It is possible to insert objects created in one sub-interpreter into a namespace of another (sub-)interpreter; this should be avoided if possible.

Special care should be taken to avoid sharing user-defined functions, methods, instances or classes between sub-interpreters, since import operations executed by such objects may affect the wrong (sub-)interpreter's dictionary of loaded modules. It is equally important to avoid sharing objects from which the above are reachable.

Also note that combining this functionality with PyGILState_*() APIs is delicate, because these APIs assume a bijection between Python thread states and OS-level threads, an assumption broken by the presence of sub-interpreters. It is highly recommended that you don't switch sub-interpreters between a pair of matching <code>PyGILState_Ensure()</code> and <code>PyGILState_Release()</code> calls. Furthermore, extensions (such as <code>ctypes</code>) using these APIs to allow calling of Python code from non-Python created threads will probably be broken when using sub-interpreters.

9.7 异步通知

A mechanism is provided to make asynchronous notifications to the main interpreter thread. These notifications take the form of a function pointer and a void pointer argument.

int Py_AddPendingCall (int (*func)(void *), void *arg)

Schedule a function to be called from the main interpreter thread. On success, 0 is returned and *func* is queued for being called in the main thread. On failure, -1 is returned without setting any exception.

When successfully queued, *func* will be *eventually* called from the main interpreter thread with the argument *arg*. It will be called asynchronously with respect to normally running Python code, but with both these conditions met:

- on a *bytecode* boundary;
- with the main thread holding the *global interpreter lock* (func can therefore use the full C API).

func must return 0 on success, or -1 on failure with an exception set. func won't be interrupted to perform another asynchronous notification recursively, but it can still be interrupted to switch threads if the global interpreter lock is released.

This function doesn't need a current thread state to run, and it doesn't need the global interpreter lock.

警告: This is a low-level function, only useful for very special cases. There is no guarantee that *func* will be called as quick as possible. If the main thread is busy executing a system call, *func* won't be called before the system call returns. This function is generally **not** suitable for calling Python code from arbitrary C threads. Instead, use the *PyGILState API*.

3.1 新版功能.

9.8 分析和跟踪

The Python interpreter provides some low-level support for attaching profiling and execution tracing facilities. These are used for profiling, debugging, and coverage analysis tools.

This C interface allows the profiling or tracing code to avoid the overhead of calling through Python-level callable objects, making a direct C function call instead. The essential attributes of the facility have not changed; the interface allows trace functions to be installed per-thread, and the basic events reported to the trace function are the same as had been reported to the Python-level trace functions in previous versions.

int (*Py_tracefunc) (PyObject *obj, PyFrameObject *frame, int what, PyObject *arg)

The type of the trace function registered using <code>PyEval_SetProfile()</code> and <code>PyEval_SetTrace()</code>. The first parameter is the object passed to the registration function as <code>obj</code>, <code>frame</code> is the frame object to which the event pertains, <code>what</code> is one of the constants <code>PyTrace_CALL</code>, <code>PyTrace_EXCEPTION</code>, <code>PyTrace_LINE</code>, <code>PyTrace_RETURN</code>, <code>PyTrace_C_CALL</code>, <code>PyTrace_CEXCEPTION</code>, <code>PyTrace_C_RETURN</code>, or <code>PyTrace_OPCODE</code>, and <code>arg</code> depends on the value of <code>what</code>:

| what 的值 | arg 的含义 |
|---------------------|------------------------------------------------------------------------|
| PyTrace_CALL | 总是Py_None. |
| PyTrace_EXCEPTION | sys.exc_info() 返回的异常信息。 |
| PyTrace_LINE | 总是Py_None. |
| PyTrace_RETURN | Value being returned to the caller, or NULL if caused by an exception. |
| PyTrace_C_CALL | 正在调用函数对象。 |
| PyTrace_C_EXCEPTION | 正在调用函数对象。 |
| PyTrace_C_RETURN | 正在调用函数对象。 |
| PyTrace_OPCODE | 总是Py_None. |

9.7. 异步通知 145

int PyTrace_CALL

The value of the *what* parameter to a *Py_tracefunc* function when a new call to a function or method is being reported, or a new entry into a generator. Note that the creation of the iterator for a generator function is not reported as there is no control transfer to the Python bytecode in the corresponding frame.

int PyTrace_EXCEPTION

The value of the *what* parameter to a *Py_tracefunc* function when an exception has been raised. The callback function is called with this value for *what* when after any bytecode is processed after which the exception becomes set within the frame being executed. The effect of this is that as exception propagation causes the Python stack to unwind, the callback is called upon return to each frame as the exception propagates. Only trace functions receives these events; they are not needed by the profiler.

int PyTrace_LINE

The value passed as the *what* parameter to a $Py_tracefunc$ function (but not a profiling function) when a line-number event is being reported. It may be disabled for a frame by setting f_trace_lines to θ on that frame.

int PyTrace_RETURN

The value for the *what* parameter to Py_tracefunc functions when a call is about to return.

int PyTrace_C_CALL

The value for the *what* parameter to *Py_tracefunc* functions when a C function is about to be called.

int PyTrace_C_EXCEPTION

The value for the *what* parameter to *Py_tracefunc* functions when a C function has raised an exception.

int PyTrace_C_RETURN

The value for the *what* parameter to Py_tracefunc functions when a C function has returned.

int PyTrace_OPCODE

The value for the *what* parameter to $Py_tracefunc$ functions (but not profiling functions) when a new opcode is about to be executed. This event is not emitted by default: it must be explicitly requested by setting $f_trace_opcodes$ to I on the frame.

void PyEval_SetProfile (Py_tracefunc func, PyObject *obj)

Set the profiler function to *func*. The *obj* parameter is passed to the function as its first parameter, and may be any Python object, or NULL. If the profile function needs to maintain state, using a different value for *obj* for each thread provides a convenient and thread-safe place to store it. The profile function is called for all monitored events except PyTrace_LINE PyTrace_OPCODE and PyTrace_EXCEPTION.

void PyEval_SetTrace (Py_tracefunc func, PyObject *obj)

Set the tracing function to *func*. This is similar to *PyEval_SetProfile()*, except the tracing function does receive line-number events and per-opcode events, but does not receive any event related to C function objects being called. Any trace function registered using *PyEval_SetTrace()* will not receive PyTrace_C_CALL, PyTrace_C_EXCEPTION or PyTrace_C_RETURN as a value for the *what* parameter.

9.9 高级调试器支持

These functions are only intended to be used by advanced debugging tools.

PyInterpreterState* PyInterpreterState_Head()

Return the interpreter state object at the head of the list of all such objects.

PyInterpreterState* PyInterpreterState_Main()

Return the main interpreter state object.

PyInterpreterState* PyInterpreterState_Next (PyInterpreterState *interp)

Return the next interpreter state object after *interp* from the list of all such objects.

PyThreadState * PyInterpreterState_ThreadHead (PyInterpreterState *interp)

Return the pointer to the first *PyThreadState* object in the list of threads associated with the interpreter *interp*.

PyThreadState* PyThreadState_Next (PyThreadState *tstate)

Return the next thread state object after *tstate* from the list of all such objects belonging to the same <code>PyInterpreterState</code> object.

9.10 Thread Local Storage Support

The Python interpreter provides low-level support for thread-local storage (TLS) which wraps the underlying native TLS implementation to support the Python-level thread local storage API (threading.local). The CPython C level APIs are similar to those offered by pthreads and Windows: use a thread key and functions to associate a void* value per thread.

The GIL does not need to be held when calling these functions; they supply their own locking.

Note that Python.h does not include the declaration of the TLS APIs, you need to include pythread.h to use thread-local storage.

注解: None of these API functions handle memory management on behalf of the void* values. You need to allocate and deallocate them yourself. If the void* values happen to be PyObject*, these functions don't do refcount operations on them either.

9.10.1 Thread Specific Storage (TSS) API

TSS API is introduced to supersede the use of the existing TLS API within the CPython interpreter. This API uses a new type Py_tss_t instead of int to represent thread keys.

3.7 新版功能.

参见:

"A New C-API for Thread-Local Storage in CPython" (PEP 539)

Py_tss_t

This data structure represents the state of a thread key, the definition of which may depend on the underlying TLS implementation, and it has an internal field representing the key's initialization state. There are no public members in this structure.

When Py_LIMITED_API is not defined, static allocation of this type by Py_tss_NEEDS_INIT is allowed.

Py_tss_NEEDS_INIT

This macro expands to the initializer for Py_tss_t variables. Note that this macro won't be defined with $Py_LIMITED_API$.

Dynamic Allocation

Dynamic allocation of the Py_tss_t , required in extension modules built with $Py_LIMITED_API$, where static allocation of this type is not possible due to its implementation being opaque at build time.

Py_tss_t* PyThread_tss_alloc()

Return a value which is the same state as a value initialized with $Py_tss_NEEDS_INIT$, or NULL in the case of dynamic allocation failure.

void PyThread_tss_free (Py_tss_t *key)

Free the given key allocated by $PyThread_tss_alloc()$, after first calling $PyThread_tss_delete()$ to ensure any associated thread locals have been unassigned. This is a no-op if the key argument is NULL.

注解: A freed key becomes a dangling pointer, you should reset the key to NULL.

方法

The parameter key of these functions must not be NULL. Moreover, the behaviors of $PyThread_tss_set()$ and $PyThread_tss_get()$ are undefined if the given Py_tss_t has not been initialized by $PyThread_tss_create()$.

```
int PyThread_tss_is_created (Py_tss_t *key)
```

Return a non-zero value if the given Py_tss_t has been initialized by PyThread_tss_create().

```
int PyThread_tss_create (Py_tss_t *key)
```

Return a zero value on successful initialization of a TSS key. The behavior is undefined if the value pointed to by the *key* argument is not initialized by $Py_tss_NEEDS_INIT$. This function can be called repeatedly on the same key -- calling it on an already initialized key is a no-op and immediately returns success.

```
void PyThread_tss_delete (Py_tss_t *key)
```

Destroy a TSS key to forget the values associated with the key across all threads, and change the key's initialization state to uninitialized. A destroyed key is able to be initialized again by <code>PyThread_tss_create()</code>. This function can be called repeatedly on the same key -- calling it on an already destroyed key is a no-op.

```
int PyThread_tss_set (Py_tss_t *key, void *value)
```

Return a zero value to indicate successfully associating a void* value with a TSS key in the current thread. Each thread has a distinct mapping of the key to a void* value.

```
void* PyThread_tss_get (Py_tss_t *key)
```

Return the void* value associated with a TSS key in the current thread. This returns NULL if no value is associated with the key in the current thread.

9.10.2 Thread Local Storage (TLS) API

3.7 版后已移除: This API is superseded by Thread Specific Storage (TSS) API.

注解: This version of the API does not support platforms where the native TLS key is defined in a way that cannot be safely cast to int. On such platforms, <code>PyThread_create_key()</code> will return immediately with a failure status, and the other TLS functions will all be no-ops on such platforms.

由于上面提到的兼容性问题,不应在新代码中使用此版本的 API。

```
int PyThread_create_key ()
void PyThread_delete_key (int key)
int PyThread_set_key_value (int key, void *value)
void* PyThread_get_key_value (int key)
void PyThread_delete_key_value (int key)
void PyThread_ReInitTLS()
```

CHAPTER 10

Python 初始化配置

3.8 新版功能.

结构

- PyConfig
- PyPreConfig
- PyStatus
- PyWideStringList

函数

- PyConfig_Clear()
- PyConfig_InitIsolatedConfig()
- PyConfig_InitPythonConfig()
- PyConfig_Read()
- PyConfig_SetArgv()
- PyConfig_SetBytesArgv()
- PyConfig_SetBytesString()
- PyConfig_SetString()
- PyConfig_SetWideStringList()
- PyPreConfig_InitIsolatedConfig()
- PyPreConfig_InitPythonConfig()
- PyStatus_Error()
- PyStatus_Exception()
- PyStatus_Exit()
- PyStatus_IsError()
- PyStatus_IsExit()
- PyStatus_NoMemory()

- PyStatus_Ok()
- PyWideStringList_Append()
- PyWideStringList_Insert()
- Py_ExitStatusException()
- Py_InitializeFromConfig()
- Py_PreInitialize()
- Py_PreInitializeFromArgs()
- Py_PreInitializeFromBytesArgs()
- Py_RunMain()

The preconfiguration (PyPreConfig type) is stored in _PyRuntime.preconfig and the configuration (PyConfig type) is stored in PyInterpreterState.config.

See also Initialization, Finalization, and Threads.

参见:

PEP 587 "Python 初始化配置".

10.1 PyWideStringList

```
PyWideStringList
```

List of wchar_t * strings.

If *length* is non-zero, *items* must be non-NULL and all strings must be non-NULL.

方法

PyStatus PyWideStringList_Append (PyWideStringList *list, const wchar_t *item)

Append item to list.

Python must be preinitialized to call this function.

```
PyStatus PyWideStringList_Insert (PyWideStringList *list, Py_ssize_t index, const wchar t *item)
```

Insert item into list at index.

If *index* is greater than or equal to *list* length, append *item* to *list*.

index must be greater than or equal to 0.

Python must be preinitialized to call this function.

Structure fields:

```
Py_ssize_t length
List 长度。
```

wchar_t** items

列表项目。

10.2 PyStatus

PyStatus

Structure to store an initialization function status: success, error or exit.

For an error, it can store the C function name which created the error.

Structure fields:

```
int exitcode
```

Exit code. Argument passed to exit().

```
const char *err_msg
错误信息
```

const char *func

Name of the function which created an error, can be NULL.

Functions to create a status:

```
PyStatus PyStatus_Ok (void) 完成。
```

PyStatus_Error (const char *err_msg)

Initialization error with a message.

```
PyStatus PyStatus_NoMemory (void)
```

Memory allocation failure (out of memory).

```
PyStatus PyStatus_Exit (int exitcode)
```

Exit Python with the specified exit code.

Functions to handle a status:

```
int PyStatus_Exception (PyStatus status)
```

Is the status an error or an exit? If true, the exception must be handled; by calling <code>Py_ExitStatusException()</code> for example.

```
int PyStatus_IsError (PyStatus status)
```

结果错误吗?

```
int PyStatus_IsExit (PyStatus status)
```

结果是否退出?

void Py_ExitStatusException (PyStatus status)

Call exit (exitcode) if *status* is an exit. Print the error message and exit with a non-zero exit code if *status* is an error. Must only be called if PyStatus_Exception(status) is non-zero.

注解: Internally, Python uses macros which set PyStatus.func, whereas functions to create a status set func to NULL.

示例:

```
PyStatus alloc(void **ptr, size_t size)
{
    *ptr = PyMem_RawMalloc(size);
    if (*ptr == NULL) {
        return PyStatus_NoMemory();
    }
    return PyStatus_Ok();
}
int main(int argc, char **argv)
{
```

(下页继续)

10.2. PyStatus 151

(续上页)

```
void *ptr;
PyStatus status = alloc(&ptr, 16);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}
PyMem_Free(ptr);
return 0;
}
```

10.3 PyPreConfig

PyPreConfig

Structure used to preinitialize Python:

- Set the Python memory allocator
- Configure the LC_CTYPE locale
- Set the UTF-8 mode

Function to initialize a preconfiguration:

```
void \ {\tt PyPreConfig\_InitIsolatedConfig} \ ( \textit{PyPreConfig} \ *preconfig) \\
```

Initialize the preconfiguration with *Python Configuration*.

void PyPreConfig_InitPythonConfig (PyPreConfig *preconfig)

Initialize the preconfiguration with Isolated Configuration.

Structure fields:

int allocator

Name of the memory allocator:

- PYMEM_ALLOCATOR_NOT_SET (0): don't change memory allocators (use defaults)
- PYMEM_ALLOCATOR_DEFAULT (1): default memory allocators
- PYMEM ALLOCATOR DEBUG (2): default memory allocators with debug hooks
- PYMEM_ALLOCATOR_MALLOC(3): force usage of malloc()
- PYMEM_ALLOCATOR_MALLOC_DEBUG (4): force usage of malloc() with debug hooks
- PYMEM_ALLOCATOR_PYMALLOC (5): Python pymalloc memory allocator
- PYMEM_ALLOCATOR_PYMALLOC_DEBUG (6): Python pymalloc memory allocator with debug hooks

 $\label{locator_pymalloc} {\tt PYMEM_ALLOCATOR_PYMALLOC_DEBUG} \ are \ not \ supported if Python is configured using --without-pymalloc$

See Memory Management.

int configure_locale

Set the LC_CTYPE locale to the user preferred locale? If equals to 0, set <code>coerce_c_locale</code> and <code>coerce_c_locale_warn</code> to 0.

int coerce_c_locale

If equals to 2, coerce the C locale; if equals to 1, read the LC_CTYPE locale to decide if it should be coerced.

int coerce_c_locale_warn

If non-zero, emit a warning if the C locale is coerced.

int dev mode

参见PyConfig.dev_mode.

int isolated

```
参见PyConfig.isolated.
```

int legacy_windows_fs_encoding (Windows only)

If non-zero, disable UTF-8 Mode, set the Python filesystem encoding to mbcs, set the filesystem error handler to replace.

Only available on Windows. #ifdef MS_WINDOWS macro can be used for Windows specific code.

int parse_argv

If non-zero, $Py_PreInitializeFromArgs()$ and $Py_PreInitializeFromBytesArgs()$ parse their argv argument the same way the regular Python parses command line arguments: see Command Line Arguments.

int use_environment

```
参见PyConfig.use_environment.
```

int utf8_mode

If non-zero, enable the UTF-8 mode.

10.4 Preinitialization with PyPreConfig

Functions to preinitialize Python:

```
PyStatus Py_PreInitialize (const PyPreConfig *preconfig)
```

Preinitialize Python from *preconfig* preconfiguration.

```
PyStatus Py_PreInitializeFromBytesArgs (const PyPreConfig *preconfig, int argc, char * const *argv)
```

Preinitialize Python from *preconfig* preconfiguration and command line arguments (bytes strings).

PyStatus Py_PreInitializeFromArgs (const PyPreConfig *preconfig, int argc, wchar_t * const * argv)
Preinitialize Python from preconfig preconfiguration and command line arguments (wide strings).

The caller is responsible to handle exceptions (error or exit) using $PyStatus_Exception()$ and $Py_ExitStatusException()$.

For *Python Configuration* (*PyPreConfig_InitPythonConfig()*), if Python is initialized with command line arguments, the command line arguments must also be passed to preinitialize Python, since they have an effect on the pre-configuration like encodings. For example, the -X utf8 command line option enables the UTF-8 Mode.

PyMem_SetAllocator() can be called after Py_PreInitialize() and before Py_InitializeFromConfig() to install a custom memory allocator. It can be called before Py_PreInitialize() if PyPreConfig.allocator is set to PYMEM_ALLOCATOR_NOT_SET.

Python memory allocation functions like $PyMem_RawMalloc()$ must not be used before Python preinitialization, whereas calling directly malloc() and free() is always safe. $Py_DecodeLocale()$ must not be called before the preinitialization.

Example using the preinitialization to enable the UTF-8 Mode:

```
PyStatus status;
PyPreConfig preconfig;
PyPreConfig_InitPythonConfig(&preconfig);

preconfig.utf8_mode = 1;

status = Py_PreInitialize(&preconfig);
if (PyStatus_Exception(status)) {
    Py_ExitStatusException(status);
}

/* at this point, Python will speak UTF-8 */
```

(下页继续)

(续上页)

```
Py_Initialize();
/* ... use Python API here ... */
Py_Finalize();
```

10.5 PyConfig

PyConfig

Structure containing most parameters to configure Python.

Structure methods:

```
void PyConfig_InitPythonConfig (PyConfig *config)
```

Initialize configuration with *Python Configuration*.

```
void PyConfig_InitIsolatedConfig (PyConfig *config)
```

Initialize configuration with Isolated Configuration.

PyStatus PyConfig_SetString (PyConfig *config, wchar_t * const *config_str, const wchar_t *str)

Copy the wide character string str into *config_str.

Preinitialize Python if needed.

PyStatus PyConfig_SetBytesString (PyConfig *config, wchar_t * const *config_str, const char *str)

Decode str using Py_DecodeLocale() and set the result into *config_str.

Preinitialize Python if needed.

PyStatus PyConfig_SetArgv (PyConfig *config, int argc, wchar_t * const *argv)

Set command line arguments from wide character strings.

Preinitialize Python if needed.

PyStatus PyConfig_SetBytesArgv (PyConfig *config, int argc, char * const *argv)

Set command line arguments: decode bytes using Py_DecodeLocale().

Preinitialize Python if needed.

PyStatus PyConfig_SetWideStringList (PyConfig *config, PyWideStringList *list, Py_ssize_t length, wchar_t **items)

Set the list of wide strings list to length and items.

Preinitialize Python if needed.

PyStatus PyConfig_Read (PyConfig *config)

Read all Python configuration.

Fields which are already initialized are left unchanged.

Preinitialize Python if needed.

```
void PyConfig_Clear (PyConfig *config)
```

Release configuration memory.

Most PyConfig methods preinitialize Python if needed. In that case, the Python preinitialization configuration in based on the PyConfig. If configuration fields which are in common with PyPreConfig are tuned, they must be set before calling a PyConfig method:

- dev_mode
- isolated
- parse_argv
- use_environment

Moreover, if PyConfig_SetArgv() or PyConfig_SetBytesArgv() is used, this method must be called first, before other methods, since the preinitialization configuration depends on command line arguments (if parse_argv is non-zero).

The caller of these methods is responsible to handle exceptions (error or exit) using PyStatus_Exception() and Py_ExitStatusException().

Structure fields:

PyWideStringList argv

Command line arguments, sys.argv. See *parse_argv* to parse *argv* the same way the regular Python parses Python command line arguments. If *argv* is empty, an empty string is added to ensure that sys.argv always exists and is never empty.

wchar_t* base_exec_prefix

sys.base_exec_prefix.

wchar_t* base_executable

sys._base_executable: __PYVENV_LAUNCHER__ environment variable value, or copy of PyConfig.executable.

wchar_t* base_prefix

sys.base_prefix.

int buffered_stdio

If equals to 0, enable unbuffered mode, making the stdout and stderr streams unbuffered.

stdin is always opened in buffered mode.

int bytes_warning

If equals to 1, issue a warning when comparing bytes or bytearray with str, or comparing bytes with int. If equal or greater to 2, raise a BytesWarning exception.

wchar_t* check_hash_pycs_mode

Control the validation behavior of hash-based .pyc files (see PEP 552): --check-hash-based-pycs command line option value.

Valid values: always, never and default.

默认值为: default.

int configure_c_stdio

If non-zero, configure C standard streams (stdio, stdout, stdout). For example, set their mode to O_BINARY on Windows.

int dev mode

Development mode: see -X dev.

int dump_refs

If non-zero, dump all objects which are still alive at exit.

Require a debug build of Python (Py_REF_DEBUG macro must be defined).

wchar_t* exec_prefix

sys.exec_prefix.

wchar_t* executable

sys.executable.

int faulthandler

If non-zero, call faulthandler.enable() at startup.

wchar_t* filesystem_encoding

Filesystem encoding, sys.getfilesystemencoding().

wchar_t* filesystem_errors

Filesystem encoding errors, sys.getfilesystemencodeerrors().

unsigned long hash_seed

10.5. PyConfig 155

int use_hash_seed

Randomized hash function seed.

If use_hash_seed is zero, a seed is chosen randomly at Pythonstartup, and hash_seed is ignored.

wchar t* home

Python home directory.

Initialized from PYTHONHOME environment variable value by default.

int import_time

If non-zero, profile import time.

int inspect

Enter interactive mode after executing a script or a command.

int install_signal_handlers

Install signal handlers?

int interactive

交互模式

int isolated

If greater than 0, enable isolated mode:

- sys.path contains neither the script's directory (computed from argv[0] or the current directory) nor the user's site-packages directory.
- Python REPL doesn't import readline nor enable default readline configuration on interactive prompts.
- Set use_environment and user_site_directory to 0.

int legacy_windows_stdio

If non-zero, use io.FileIO instead of io.WindowsConsoleIO for sys.stdin, sys.stdout and sys.stderr.

Only available on Windows. #ifdef MS_WINDOWS macro can be used for Windows specific code.

int malloc_stats

If non-zero, dump statistics on Python pymalloc memory allocator at exit.

The option is ignored if Python is built using --without-pymalloc.

wchar_t* pythonpath_env

Module search paths as a string separated by DELIM (os.path.pathsep).

Initialized from PYTHONPATH environment variable value by default.

PyWideStringList module_search_paths

int module_search_paths_set

sys.path. If module_search_paths_set is equal to 0, the module_search_paths is overridden by the function calculating the *Path Configuration*.

int optimization_level

Compilation optimization level:

- 0: Peephole optimizer (and __debug__ is set to True)
- 1: Remove assertions, set __debug__ to False
- 2: Strip docstrings

int parse_argv

If non-zero, parse *argv* the same way the regular Python command line arguments, and strip Python arguments from *argv*: see Command Line Arguments.

int parser_debug

If non-zero, turn on parser debugging output (for expert only, depending on compilation options).

int pathconfig_warnings

If equal to 0, suppress warnings when calculating the *Path Configuration* (Unix only, Windows does not log any warning). Otherwise, warnings are written into stderr.

wchar_t* prefix

sys.prefix.

wchar_t* program_name

Program name. Used to initialize executable, and in early error messages.

wchar_t* pycache_prefix

sys.pycache_prefix: .pyc cache prefix.

If NULL, sys.pycache_prefix is set to None.

int quiet

Quiet mode. For example, don't display the copyright and version messages in interactive mode.

wchar_t* run_command

python3 -c COMMAND argument. Used by Py_RunMain().

wchar_t* run_filename

python3 FILENAME argument. Used by Py_RunMain().

wchar_t* run_module

python3 -m MODULE argument. Used by Py_RunMain().

int show_alloc_count

Show allocation counts at exit?

Set to 1 by -X showalloccount command line option.

Need a special Python build with COUNT_ALLOCS macro defined.

int show_ref_count

Show total reference count at exit?

Set to 1 by -X showrefcount command line option.

Need a debug build of Python (Py_REF_DEBUG macro must be defined).

int site_import

Import the site module at startup?

int skip_source_first_line

Skip the first line of the source?

wchar_t* stdio_encoding

wchar_t* stdio_errors

Encoding and encoding errors of sys.stdin, sys.stdout and sys.stderr.

int tracemalloc

If non-zero, call tracemalloc.start() at startup.

int use_environment

If greater than 0, use environment variables.

int user_site_directory

If non-zero, add user site directory to sys.path.

int verbose

If non-zero, enable verbose mode.

PyWideStringList warnoptions

sys.warnoptions: options of the warnings module to build warnings filters: lowest to highest priority.

10.5. PyConfig 157

The warnings module adds sys.warnoptions in the reverse order: the last *PyConfig.* warnoptions item becomes the first item of warnings.filters which is checked first (highest priority).

int write_bytecode

If non-zero, write .pyc files.

sys.dont_write_bytecode is initialized to the inverted value of write_bytecode.

```
PyWideStringList xoptions sys._xoptions.
```

If parse_argv is non-zero, argv arguments are parsed the same way the regular Python parses command line arguments, and Python arguments are stripped from argv: see Command Line Arguments.

The xoptions options are parsed to set other options: see -X option.

10.6 Initialization with PyConfig

Function to initialize Python:

```
PyStatus Py_InitializeFromConfig (const PyConfig *config)
Initialize Python from config configuration.
```

The caller is responsible to handle exceptions (error or exit) using PyStatus_Exception() and Py_ExitStatusException().

If PyImport_FrozenModules, PyImport_AppendInittab() or PyImport_ExtendInittab() are used, they must be set or called after Python preinitialization and before the Python initialization.

Example setting the program name:

```
void init_python(void)
    PyStatus status;
    PyConfig config;
    PyConfig_InitPythonConfig(&config);
    /* Set the program name. Implicitly preinitialize Python. */
    status = PyConfig_SetString(&config, &config.program_name,
                                 L"/path/to/my_program");
    if (PyStatus_Exception(status)) {
        goto fail;
    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto fail;
    PyConfig_Clear(&config);
    return;
fail:
    PyConfig_Clear(&config);
    Py_ExitStatusException(status);
```

More complete example modifying the default configuration, read the configuration, and then override some parameters:

```
PyStatus init_python(const char *program_name)
{
    PyStatus status;
    PyConfig config;
   PyConfig_InitPythonConfig(&config);
    /* Set the program name before reading the configuration
       (decode byte string from the locale encoding).
       Implicitly preinitialize Python. */
    status = PyConfig_SetBytesString(&config, &config.program_name,
                                  program_name);
    if (PyStatus_Exception(status)) {
        goto done;
    /* Read all configuration at once */
    status = PyConfig_Read(&config);
    if (PyStatus_Exception(status)) {
       goto done;
    /* Append our custom search path to sys.path */
    status = PyWideStringList_Append(&config.module_search_paths,
                                     L"/path/to/more/modules");
    if (PyStatus_Exception(status)) {
       goto done;
    /* Override executable computed by PyConfig_Read() */
    status = PyConfig_SetString(&config, &config.executable,
                                L"/path/to/my_executable");
    if (PyStatus_Exception(status)) {
       goto done;
    status = Py_InitializeFromConfig(&config);
done:
   PyConfig_Clear(&config);
    return status;
```

10.7 Isolated Configuration

 $\label{eq:pypreConfig} \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() and PyConfig_InitIsolatedConfig() functions create a configuration to isolate Python from the system. For example, to embed Python into an application. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration to isolate Python from the system. For example, to embed Python into an application. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration to isolate Python from the system. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration to isolate Python from the system. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration to isolate Python from the system. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration to isolate Python from the system. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration for the system. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration for the system. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration for the system. \\ \begin{subarray}{ll} PyPreConfig_InitIsolatedConfig() functions create a configuration for the system for th$

This configuration ignores global configuration variables, environments variables, command line arguments (PyConfig.argv is not parsed) and user site directory. The C standard streams (ex: stdout) and the LC_CTYPE locale are left unchanged. Signal handlers are not installed.

Configuration files are still used with this configuration. Set the *Path Configuration* ("output fields") to ignore these configuration files and avoid the function computing the default path configuration.

10.8 Python Configuration

PyPreConfig_InitPythonConfig() and PyConfig_InitPythonConfig() functions create a configuration to build a customized Python which behaves as the regular Python.

Environments variables and command line arguments are used to configure Python, whereas global configuration variables are ignored.

This function enables C locale coercion (PEP 538) and UTF-8 Mode (PEP 540) depending on the LC_CTYPE locale. PYTHONUTF 8 and PYTHONCOERCECLOCALE environment variables.

Example of customized Python always running in isolated mode:

```
int main(int argc, char **argv)
    PyStatus status;
    PyConfig config;
    PyConfig_InitPythonConfig(&config);
   config.isolated = 1;
    /* Decode command line arguments.
       Implicitly preinitialize Python (in isolated mode). */
    status = PyConfig_SetBytesArgv(&config, argc, argv);
    if (PyStatus_Exception(status)) {
        goto fail;
    status = Py_InitializeFromConfig(&config);
    if (PyStatus_Exception(status)) {
        goto fail;
    PyConfig_Clear(&config);
    return Py_RunMain();
fail:
    PyConfig_Clear(&config);
    if (PyStatus_IsExit(status)) {
        return status.exitcode;
    /* Display the error message and exit the process with
      non-zero exit code */
   Py_ExitStatusException(status);
```

10.9 路径配置

PyConfig contains multiple fields for the path configuration:

- 路径配置输入:
 - PyConfig.home
 - PyConfig.pathconfig_warnings
 - PyConfig.program_name
 - PyConfig.pythonpath_env
 - current working directory: to get absolute paths
 - PATH environment variable to get the program full path (from PyConfig.program_name)

- PYVENV_LAUNCHER__ environment variable
- (Windows only) Application paths in the registry under "SoftwarePythonPythonCoreX.YPythonPath" of HKEY_CURRENT_USER and HKEY_LOCAL_MACHINE (where X.Y is the Python version).
- Path configuration output fields:
 - PyConfig.base_exec_prefix
 - PyConfig.base_executable
 - PyConfig.base_prefix
 - PyConfig.exec_prefix
 - PyConfig.executable
 - PyConfig.module_search_paths_set, PyConfig.module_search_paths
 - PyConfig.prefix

If at least one "output field" is not set, Python calculates the path configuration to fill unset fields. If <code>module_search_paths_set</code> is equal to 0, <code>module_search_paths</code> is overridden and <code>module_search_paths_set</code> is set to 1.

It is possible to completely ignore the function calculating the default path configuration by setting explicitly all path configuration output fields listed above. A string is considered as set even if it is non-empty. module_search_paths is considered as set if module_search_paths_set is set to 1. In this case, path configuration input fields are ignored as well.

Set pathconfig_warnings to 0 to suppress warnings when calculating the path configuration (Unix only, Windows does not log any warning).

If base_prefix or base_exec_prefix fields are not set, they inherit their value from prefix and exec_prefix respectively.

Py_RunMain() and Py_Main() modify sys.path:

- If run_filename is set and is a directory which contains a __main__.py script, prepend run_filename to sys.path.
- If isolated is zero:
 - If run_module is set, prepend the current directory to sys.path. Do nothing if the current directory cannot be read.
 - If run_filename is set, prepend the directory of the filename to sys.path.
 - Otherwise, prepend an empty string to sys.path.

If <code>site_import</code> is non-zero, <code>sys.path</code> can be modified by the <code>site</code> module. If <code>user_site_directory</code> is non-zero and the user's site-package directory exists, the <code>site</code> module appends the user's site-package directory to <code>sys.path</code>.

The following configuration files are used by the path configuration:

- pyvenv.cfg
- python._pth (仅 Windows)
- pybuilddir.txt(仅Unix)

The __PYVENV_LAUNCHER__ environment variable is used to set PyConfig.base_executable

10.9. 路径配置 161

10.10 Py_RunMain()

int Py_RunMain (void)

Execute the command (PyConfig.run_command), the script (PyConfig.run_filename) or the module (PyConfig.run_module) specified on the command line or in the configuration.

By default and when if -i option is used, run the REPL.

Finally, finalizes Python and returns an exit status that can be passed to the exit () function.

See *Python Configuration* for an example of customized Python always running in isolated mode using *Py_RunMain()*.

10.11 Multi-Phase Initialization Private Provisional API

This section is a private provisional API introducing multi-phase initialization, the core feature of the PEP 432:

- "Core" initialization phase, "bare minimum Python":
 - Builtin types;
 - Builtin exceptions;
 - Builtin and frozen modules;
 - The sys module is only partially initialized (ex: sys.path doesn't exist yet).
- "Main" initialization phase, Python is fully initialized:
 - Install and configure importlib;
 - Apply the *Path Configuration*;
 - Install signal handlers;
 - Finish sys module initialization (ex: create sys.stdout and sys.path);
 - Enable optional features like faulthandler and tracemalloc;
 - Import the site module;
 - 等等.

Private provisional API:

• PyConfig._init_main: if set to 0, Py_InitializeFromConfig() stops at the "Core" initialization phase.

PyStatus _Py_InitializeMain (void)

Move to the "Main" initialization phase, finish the Python initialization.

No module is imported during the "Core" phase and the importlib module is not configured: the *Path Configuration* is only applied during the "Main" phase. It may allow to customize Python in Python to override or tune the *Path Configuration*, maybe install a custom sys.meta_path importer or an import hook, etc.

It may become possible to calculatin the *Path Configuration* in Python, after the Core phase and before the Main phase, which is one of the **PEP 432** motivation.

The "Core" phase is not properly defined: what should be and what should not be available at this phase is not specified yet. The API is marked as private and provisional: the API can be modified or even be removed anytime until a proper public API is designed.

Example running Python code between "Core" and "Main" initialization phases:

```
void init_python(void)
   PyStatus status;
   PyConfig config;
   PyConfig_InitPythonConfig(&config);
   config._init_main = 0;
   /* ... customize 'config' configuration ... */
   status = Py_InitializeFromConfig(&config);
   PyConfig_Clear(&config);
   if (PyStatus_Exception(status)) {
       Py_ExitStatusException(status);
   /* Use sys.stderr because sys.stdout is only created
      by _Py_InitializeMain() */
   int res = PyRun_SimpleString(
        "import sys; "
       "print('Run Python code before _Py_InitializeMain', "
              "file=sys.stderr)");
   if (res < 0) {
       exit(1);
   /* ... put more configuration code here ... */
   status = _Py_InitializeMain();
   if (PyStatus_Exception(status)) {
       Py_ExitStatusException(status);
```

CHAPTER 11

内存管理

11.1 概述

Memory management in Python involves a private heap containing all Python objects and data structures. The management of this private heap is ensured internally by the *Python memory manager*. The Python memory manager has different components which deal with various dynamic storage management aspects, like sharing, segmentation, preallocation or caching.

At the lowest level, a raw memory allocator ensures that there is enough room in the private heap for storing all Python-related data by interacting with the memory manager of the operating system. On top of the raw memory allocator, several object-specific allocators operate on the same heap and implement distinct memory management policies adapted to the peculiarities of every object type. For example, integer objects are managed differently within the heap than strings, tuples or dictionaries because integers imply different storage requirements and speed/space tradeoffs. The Python memory manager thus delegates some of the work to the object-specific allocators, but ensures that the latter operate within the bounds of the private heap.

It is important to understand that the management of the Python heap is performed by the interpreter itself and that the user has no control over it, even if they regularly manipulate object pointers to memory blocks inside that heap. The allocation of heap space for Python objects and other internal buffers is performed on demand by the Python memory manager through the Python/C API functions listed in this document.

To avoid memory corruption, extension writers should never try to operate on Python objects with the functions exported by the C library: malloc(), calloc(), realloc() and free(). This will result in mixed calls between the C allocator and the Python memory manager with fatal consequences, because they implement different algorithms and operate on different heaps. However, one may safely allocate and release memory blocks with the C library allocator for individual purposes, as shown in the following example:

```
PyObject *res;
char *buf = (char *) malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
...Do some I/O operation involving buf...
res = PyBytes_FromString(buf);
free(buf); /* malloc'ed */
return res;
```

In this example, the memory request for the I/O buffer is handled by the C library allocator. The Python memory manager is involved only in the allocation of the bytes object returned as a result.

In most situations, however, it is recommended to allocate memory from the Python heap specifically because the latter is under control of the Python memory manager. For example, this is required when the interpreter is extended with new object types written in C. Another reason for using the Python heap is the desire to *inform* the Python memory manager about the memory needs of the extension module. Even when the requested memory is used exclusively for internal, highly-specific purposes, delegating all memory requests to the Python memory manager causes the interpreter to have a more accurate image of its memory footprint as a whole. Consequently, under certain circumstances, the Python memory manager may or may not trigger appropriate actions, like garbage collection, memory compaction or other preventive procedures. Note that by using the C library allocator as shown in the previous example, the allocated memory for the I/O buffer escapes completely the Python memory manager.

参见:

The PYTHONMALLOC environment variable can be used to configure the memory allocators used by Python.

The PYTHONMALLOCSTATS environment variable can be used to print statistics of the *pymalloc memory allocator* every time a new pymalloc object arena is created, and on shutdown.

11.2 原始内存接口

以下函数集封装了系统分配器。这些函数是线程安全的,不需要持有GIL。

default raw memory allocator 使用这些函数: malloc()、calloc()、realloc() 和 free(); 申请零字 节时则调用 malloc(1) `` (或 ``calloc(1, 1))

3.4 新版功能.

void* PyMem_RawMalloc (size_t n)

Allocates n bytes and returns a pointer of type void* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem_RawMalloc(1) had been called instead. The memory will not have been initialized in any way.

void* PyMem_RawCalloc (size_t nelem, size_t elsize)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type void* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyMem_RawCalloc(1, 1) had been called instead.

3.5 新版功能.

$void* PyMem_RawRealloc (void *p, size_t n)$

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem_RawMalloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to $PyMem_RawMalloc()$, $PyMem_RawRealloc()$ or $PyMem_RawCalloc()$.

If the request fails, $PyMem_RawRealloc()$ returns NULL and p remains a valid pointer to the previous memory area.

void PyMem_RawFree (void *p)

Frees the memory block pointed to by p, which must have been returned by a previous call to $PyMem_RawMalloc()$, $PyMem_RawRealloc()$ or $PyMem_RawCalloc()$. Otherwise, or if $PyMem_RawFree(p)$ has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

11.3 内存接口

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The default memory allocator uses the pymalloc memory allocator.

警告: The GIL must be held when using these functions.

在 3.6 版更改: The default allocator is now pymalloc instead of system malloc().

void* PyMem_Malloc (size_t n)

Allocates n bytes and returns a pointer of type void* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyMem_Malloc(1) had been called instead. The memory will not have been initialized in any way.

void* PyMem_Calloc (size_t nelem, size_t elsize)

Allocates nelem elements each whose size in bytes is elsize and returns a pointer of type void* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyMem_Calloc(1, 1) had been called instead.

3.5 新版功能.

void* PyMem_Realloc (void *p, size_t n)

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyMem_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to $PyMem_Malloc()$, $PyMem_Realloc()$ or $PyMem_Calloc()$.

If the request fails, $PyMem_Realloc()$ returns NULL and p remains a valid pointer to the previous memory area.

void $PyMem_Free (void *p)$

Frees the memory block pointed to by p, which must have been returned by a previous call to $PyMem_Malloc()$, $PyMem_Realloc()$ or $PyMem_Calloc()$. Otherwise, or if $PyMem_Free(p)$ has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

The following type-oriented macros are provided for convenience. Note that TYPE refers to any C type.

TYPE* **PyMem_New** (TYPE, size_t *n*)

Same as <code>PyMem_Malloc()</code>, but allocates (n * sizeof(TYPE)) bytes of memory. Returns a pointer cast to <code>TYPE*</code>. The memory will not have been initialized in any way.

TYPE* PyMem_Resize (void *p, TYPE, size_t n)

Same as $PyMem_Realloc()$, but the memory block is resized to (n * sizeof(TYPE)) bytes. Returns a pointer cast to TYPE*. On return, p will be a pointer to the new memory area, or NULL in the event of failure.

This is a C preprocessor macro; p is always reassigned. Save the original value of p to avoid losing memory when handling errors.

```
void PyMem_Del (void *p)
与PyMem_Free()相同
```

In addition, the following macro sets are provided for calling the Python memory allocator directly, without involving the C API functions listed above. However, note that their use does not preserve binary compatibility across Python versions and is therefore deprecated in extension modules.

11.3. 内存接口 167

- PyMem_MALLOC(size)
- PyMem_NEW(type, size)
- PyMem_REALLOC(ptr, size)
- PyMem_RESIZE(ptr, type, size)
- PyMem FREE (ptr)
- PyMem_DEL(ptr)

11.4 对象分配器

The following function sets, modeled after the ANSI C standard, but specifying behavior when requesting zero bytes, are available for allocating and releasing memory from the Python heap.

The default object allocator uses the pymalloc memory allocator.

警告: The GIL must be held when using these functions.

void* PyObject_Malloc (size_t n)

Allocates n bytes and returns a pointer of type void* to the allocated memory, or NULL if the request fails.

Requesting zero bytes returns a distinct non-NULL pointer if possible, as if PyObject_Malloc(1) had been called instead. The memory will not have been initialized in any way.

void* PyObject_Calloc (size_t nelem, size_t elsize)

Allocates *nelem* elements each whose size in bytes is *elsize* and returns a pointer of type void* to the allocated memory, or NULL if the request fails. The memory is initialized to zeros.

Requesting zero elements or elements of size zero bytes returns a distinct non-NULL pointer if possible, as if PyObject_Calloc(1, 1) had been called instead.

3.5 新版功能.

void* PyObject_Realloc (void*p, $size_t n$)

Resizes the memory block pointed to by p to n bytes. The contents will be unchanged to the minimum of the old and the new sizes.

If p is NULL, the call is equivalent to PyObject_Malloc(n); else if n is equal to zero, the memory block is resized but is not freed, and the returned pointer is non-NULL.

Unless p is NULL, it must have been returned by a previous call to $PyObject_Malloc()$, $PyObject_Realloc()$ or $PyObject_Calloc()$.

If the request fails, $PyObject_Realloc()$ returns NULL and p remains a valid pointer to the previous memory area.

void PyObject_Free (void *p)

Frees the memory block pointed to by p, which must have been returned by a previous call to $PyObject_Malloc()$, $PyObject_Realloc()$ or $PyObject_Calloc()$. Otherwise, or if $PyObject_Free(p)$ has been called before, undefined behavior occurs.

If p is NULL, no operation is performed.

11.5 默认内存分配器

默认内存分配器:

| 配置 | 名称 | PyMem_RawMalle | odPyMem_Malloc | PyOb- |
|----------------------------|----------------|----------------|----------------|--------------|
| | | | | ject_Malloc |
| 发布版本 | "pymalloc" | malloc | pymalloc | pymalloc |
| 调试构建 | "pymalloc_debu | gMmalloc+debug | pymalloc + | pymalloc + |
| | | | debug | debug |
| Release build, without py- | "malloc" | malloc | malloc | malloc |
| malloc | | | | |
| Debug build, without py- | "malloc_debug" | malloc + debug | malloc + de- | malloc + de- |
| malloc | | | bug | bug |

说明:

- Name: value for PYTHONMALLOC environment variable
- malloc: system allocators from the standard C library, C functions: malloc(), calloc(), realloc() and free()
- pymalloc: pymalloc memory allocator
- "+ debug": with debug hooks installed by PyMem_SetupDebugHooks()

11.6 Customize Memory Allocators

3.4 新版功能.

PyMemAllocatorEx

Structure used to describe a memory block allocator. The structure has four fields:

| 域 | 含义 |
|-------------------------------------------------------|---------------------------------------|
| void *ctx | user context passed as first argument |
| <pre>void* malloc(void *ctx, size_t size)</pre> | allocate a memory block |
| <pre>void* calloc(void *ctx, size_t nelem,</pre> | allocate a memory block initialized |
| size_t elsize) | with zeros |
| <pre>void* realloc(void *ctx, void *ptr, size_t</pre> | allocate or resize a memory block |
| new_size) | |
| <pre>void free(void *ctx, void *ptr)</pre> | 释放一个内存块 |

在 3.5 版更改: The PyMemAllocator structure was renamed to PyMemAllocatorEx and a new calloc field was added.

PyMemAllocatorDomain

Enum used to identify an allocator domain. Domains:

PYMEM_DOMAIN_RAW

函数

- PyMem_RawMalloc()
- PyMem_RawRealloc()
- PyMem_RawCalloc()
- PyMem_RawFree()

PYMEM_DOMAIN_MEM

函数

11.5. 默认内存分配器 169

- PyMem_Malloc(),
- PyMem_Realloc()
- PyMem_Calloc()
- PyMem_Free()

PYMEM_DOMAIN_OBJ

函数

- PyObject_Malloc()
- PyObject_Realloc()
- PyObject_Calloc()
- PyObject_Free()

void **PyMem_GetAllocator** (*PyMemAllocatorDomain domain*, *PyMemAllocatorEx *allocator*) Get the memory block allocator of the specified domain.

void **PyMem_SetAllocator** (*PyMemAllocatorDomain domain*, *PyMemAllocatorEx *allocator*) Set the memory block allocator of the specified domain.

The new allocator must return a distinct non-NULL pointer when requesting zero bytes.

For the PYMEM_DOMAIN_RAW domain, the allocator must be thread-safe: the GIL is not held when the allocator is called.

If the new allocator is not a hook (does not call the previous allocator), the <code>PyMem_SetupDebugHooks()</code> function must be called to reinstall the debug hooks on top on the new allocator.

void PyMem_SetupDebugHooks (void)

Setup hooks to detect bugs in the Python memory allocator functions.

Newly allocated memory is filled with the byte $0 \times CD$ (CLEANBYTE), freed memory is filled with the byte $0 \times DD$ (DEADBYTE). Memory blocks are surrounded by "forbidden bytes" (FORBIDDENBYTE: byte $0 \times FD$).

Runtime checks:

- Detect API violations, ex: PyObject_Free() called on a buffer allocated by PyMem_Malloc()
- Detect write before the start of the buffer (buffer underflow)
- Detect write after the end of the buffer (buffer overflow)
- Check that the *GIL* is held when allocator functions of *PYMEM_DOMAIN_OBJ* (ex: *PyObject_Malloc()*) and *PYMEM_DOMAIN_MEM* (ex: *PyMem_Malloc()*) domains are called

On error, the debug hooks use the tracemalloc module to get the traceback where a memory block was allocated. The traceback is only displayed if tracemalloc is tracing Python memory allocations and the memory block was traced.

These hooks are *installed by default* if Python is compiled in debug mode. The PYTHONMALLOC environment variable can be used to install debug hooks on a Python compiled in release mode.

在 3.6 版更改: This function now also works on Python compiled in release mode. On error, the debug hooks now use tracemalloc to get the traceback where a memory block was allocated. The debug hooks now also check if the GIL is held when functions of <code>PYMEM_DOMAIN_OBJ</code> and <code>PYMEM_DOMAIN_MEM</code> domains are called.

在 3.8 版更改: Byte patterns 0xCB (CLEANBYTE), 0xDB (DEADBYTE) and 0xFB (FORBIDDENBYTE) have been replaced with 0xCD, 0xDD and 0xFD to use the same values than Windows CRT debug malloc() and free().

11.7 The pymalloc allocator

Python has a *pymalloc* allocator optimized for small objects (smaller or equal to 512 bytes) with a short lifetime. It uses memory mappings called "arenas" with a fixed size of 256 KiB. It falls back to <code>PyMem_RawMalloc()</code> and <code>PyMem_RawRealloc()</code> for allocations larger than 512 bytes.

pymalloc is the default allocator of the PYMEM_DOMAIN_MEM (ex: PyMem_Malloc()) and PYMEM_DOMAIN_OBJ (ex: PyObject_Malloc()) domains.

The arena allocator uses the following functions:

- VirtualAlloc() and VirtualFree() on Windows,
- mmap() and munmap() if available,
- malloc() and free() otherwise.

11.7.1 Customize pymalloc Arena Allocator

3.4 新版功能.

PyObjectArenaAllocator

Structure used to describe an arena allocator. The structure has three fields:

| 域 | 含义 | |
|---------------------------------------------------|---------------------------------------|--|
| void *ctx | user context passed as first argument | |
| <pre>void* alloc(void *ctx, size_t size)</pre> | allocate an arena of size bytes | |
| <pre>void free(void *ctx, size_t size, void</pre> | free an arena | |
| *ptr) | | |

PyObject_GetArenaAllocator (PyObjectArenaAllocator *allocator)

Get the arena allocator.

PyObject_SetArenaAllocator (PyObjectArenaAllocator *allocator)

Set the arena allocator.

11.8 tracemalloc C API

3.7 新版功能.

int PyTraceMalloc_Track (unsigned int domain, uintptr_t ptr, size_t size)

Track an allocated memory block in the tracemalloc module.

Return 0 on success, return -1 on error (failed to allocate memory to store the trace). Return -2 if tracemalloc is disabled.

If memory block is already tracked, update the existing trace.

int PyTraceMalloc_Untrack (unsigned int domain, uintptr_t ptr)

Untrack an allocated memory block in the tracemalloc module. Do nothing if the block was not tracked.

Return -2 if tracemalloc is disabled, otherwise return 0.

11.9 示例

Here is the example from section 概述, rewritten so that the I/O buffer is allocated from the Python heap by using the first function set:

```
PyObject *res;
char *buf = (char *) PyMem_Malloc(BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Free(buf); /* allocated with PyMem_Malloc */
return res;
```

The same code using the type-oriented function set:

```
PyObject *res;
char *buf = PyMem_New(char, BUFSIZ); /* for I/O */

if (buf == NULL)
    return PyErr_NoMemory();
/* ...Do some I/O operation involving buf... */
res = PyBytes_FromString(buf);
PyMem_Del(buf); /* allocated with PyMem_New */
return res;
```

Note that in the two examples above, the buffer is always manipulated via functions belonging to the same set. Indeed, it is required to use the same memory API family for a given memory block, so that the risk of mixing different allocators is reduced to a minimum. The following code sequence contains two errors, one of which is labeled as *fatal* because it mixes two different allocators operating on different heaps.

```
char *buf1 = PyMem_New(char, BUFSIZ);
char *buf2 = (char *) malloc(BUFSIZ);
char *buf3 = (char *) PyMem_Malloc(BUFSIZ);
...
PyMem_Del(buf3); /* Wrong -- should be PyMem_Free() */
free(buf2); /* Right -- allocated via malloc() */
free(buf1); /* Fatal -- should be PyMem_Del() */
```

In addition to the functions aimed at handling raw memory blocks from the Python heap, objects in Python are allocated and released with PyObject_New(), PyObject_NewVar() and PyObject_Del().

These will be explained in the next chapter on defining and implementing new object types in C.

对象实现支持

本章描述了定义新对象类型时所使用的函数、类型和宏。

12.1 在堆中分配对象

PyObject* _PyObject_New (PyTypeObject *type)

Return value: New reference.

PyVarObject* _PyObject_NewVar (PyTypeObject *type, Py_ssize_t size)

Return value: New reference.

PyObject* PyObject Init (PyObject *op, PyTypeObject *type)

Return value: Borrowed reference. 为新分配的对象 op 初始化它的类型和引用。返回初始化后的对象。如果 type 声明这个对象参与循环垃圾检测,那么这个对象会被添加进垃圾检测的对象集中。这个对象的其他字段不会被影响。

PyVarObject* PyObject_InitVar (PyVarObject *op, PyTypeObject *type, Py_ssize_t size)

Return value: Borrowed reference. 它的功能和PyObject_Init()一样,并且初始化变量大小的对象的长度。

TYPE* PyObject_New (TYPE, PyTypeObject *type)

Return value: New reference. 使用 C 结构类型 TYPE 和 Python 类型对象 type 分配一个新的 Python 对象。未在该 Python 对象头中定义的字段不会被初始化;对象的引用计数将为一。内存分配大小由 type 对象的 tp_basicsize 字段来确定。

TYPE* PyObject_NewVar (TYPE, PyTypeObject *type, Py_ssize_t size)

Return value: New reference. 使用 C 的数据结构类型 TYPE 和 Python 的类型对象 type 分配一个新的 Python 对象。Python 对象头文件中没有定义的字段不会被初始化。被分配的内存空间预留了 TYPE 结构加 type 对象中 tp_i temsize 字段提供的 size 字段的值。这对于实现类似元组这种能够在构造期决定自己大小的对象是很实用的。将字段的数组嵌入到相同的内存分配中可以减少内存分配的次数,这提高了内存分配的效率。

void PyObject_Del (void *op)

释放由 $PyObject_New()$ 或者 $PyObject_NewVar()$ 分配内存的对象。这通常由对象的 type 字段定义的 $tp_dealloc$ 处理函数来调用。调用这个函数以后 op 对象中的字段都不可以被访问,因为原分配的内存空间已不再是一个有效的 Python 对象。

PyObject _Py_NoneStruct

像 None 一样的 **Python** 对象。这个对象仅可以使用 P_{Y} None 宏访问,这个宏取得指向这个对象的指针。

参见:

PyModule_Create()分配内存和创建扩展模块。

12.2 Common Object Structures

There are a large number of structures which are used in the definition of object types for Python. This section describes these structures and how they are used.

All Python objects ultimately share a small number of fields at the beginning of the object's representation in memory. These are represented by the *PyObject* and *PyVarObject* types, which are defined, in turn, by the expansions of some macros also used, whether directly or indirectly, in the definition of all other Python objects.

PyObject

All object types are extensions of this type. This is a type which contains the information Python needs to treat a pointer to an object as an object. In a normal "release" build, it contains only the object's reference count and a pointer to the corresponding type object. Nothing is actually declared to be a PyObject, but every pointer to a Python object can be cast to a PyObject*. Access to the members must be done by using the macros Py_REFCNT and Py_TYPE .

PyVarObject

This is an extension of PyObject that adds the ob_size field. This is only used for objects that have some notion of *length*. This type does not often appear in the Python/C API. Access to the members must be done by using the macros Py_REFCNT , Py_TYPE , and Py_SIZE .

PyObject_HEAD

This is a macro used when declaring new types which represent objects without a varying length. The PyObject HEAD macro expands to:

```
PyObject ob_base;
```

See documentation of PyObject above.

PyObject_VAR_HEAD

This is a macro used when declaring new types which represent objects with a length that varies from instance to instance. The PyObject_VAR_HEAD macro expands to:

```
PyVarObject ob_base;
```

See documentation of PyVarObject above.

Py_TYPE (o)

This macro is used to access the ob_type member of a Python object. It expands to:

```
(((PyObject*)(o))->ob_type)
```

Py_REFCNT (o)

This macro is used to access the ob_refent member of a Python object. It expands to:

```
(((PyObject*)(o))->ob_refcnt)
```

Py_SIZE (o)

This macro is used to access the ob_size member of a Python object. It expands to:

```
(((PyVarObject*)(o))->ob_size)
```

PyObject_HEAD_INIT (type)

This is a macro which expands to initialization values for a new PyObject type. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type,
```

PyVarObject_HEAD_INIT (type, size)

This is a macro which expands to initialization values for a new PyVarObject type, including the ob_size field. This macro expands to:

```
_PyObject_EXTRA_INIT
1, type, size,
```

PyCFunction

Type of the functions used to implement most Python callables in C. Functions of this type take two PyObject* parameters and return one such value. If the return value is NULL, an exception shall have been set. If not NULL, the return value is interpreted as the return value of the function as exposed in Python. The function must return a new reference.

PyCFunctionWithKeywords

Type of the functions used to implement Python callables in C with signature <code>METH_VARARGS</code> | <code>METH_KEYWORDS</code>.

_PyCFunctionFast

Type of the functions used to implement Python callables in C with signature METH_FASTCALL.

_PyCFunctionFastWithKeywords

Type of the functions used to implement Python callables in C with signature <code>METH_FASTCALL | METH_KEYWORDS</code>.

PyMethodDef

Structure used to describe a method of an extension type. This structure has four fields:

| 域 | C 类型 | 意义 |
|----------|--------------|---------------------------------------------------------|
| ml_name | const char * | name of the method |
| ml_meth | PyCFunction | pointer to the C implementation |
| ml_flags | int | flag bits indicating how the call should be constructed |
| ml_doc | const char * | points to the contents of the docstring |

The ml_meth is a C function pointer. The functions may be of different types, but they always return PyObject*. If the function is not of the PyCFunction, the compiler will require a cast in the method table. Even though PyCFunction defines the first parameter as PyObject*, it is common that the method implementation uses the specific C type of the self object.

The ml_flags field is a bitfield which can include the following flags. The individual flags indicate either a calling convention or a binding convention.

There are four basic calling conventions for positional arguments and two of them can be combined with METH_KEYWORDS to support also keyword arguments. So there are a total of 6 calling conventions:

METH_VARARGS

This is the typical calling convention, where the methods have the type PyCFunction. The function expects two PyObject* values. The first one is the self object for methods; for module functions, it is the module object. The second parameter (often called args) is a tuple object representing all arguments. This parameter is typically processed using $PyArg_ParseTuple()$ or $PyArg_UnpackTuple()$.

METH_VARARGS | METH_KEYWORDS

Methods with these flags must be of type PyCFunctionWithKeywords. The function expects three parameters: self, args, kwargs where kwargs is a dictionary of all the keyword arguments or possibly NULL if there are no keyword arguments. The parameters are typically processed using $PyArg_ParseTupleAndKeywords()$.

METH_FASTCALL

Fast calling convention supporting only positional arguments. The methods have the type

_PyCFunctionFast. The first parameter is *self*, the second parameter is a C array of PyObject* values indicating the arguments and the third parameter is the number of arguments (the length of the array).

This is not part of the *limited API*.

3.7 新版功能.

METH_FASTCALL | METH_KEYWORDS

Extension of METH_FASTCALL supporting also keyword arguments, with methods of type _PyCFunctionFastWithKeywords. Keyword arguments are passed the same way as in the vectorcall protocol: there is an additional fourth PyObject* parameter which is a tuple representing the names of the keyword arguments or possibly NULL if there are no keywords. The values of the keyword arguments are stored in the args array, after the positional arguments.

This is not part of the *limited API*.

3.7 新版功能.

METH_NOARGS

Methods without parameters don't need to check whether arguments are given if they are listed with the METH_NOARGS flag. They need to be of type PyCFunction. The first parameter is typically named self and will hold a reference to the module or object instance. In all cases the second parameter will be NULL.

METH_O

Methods with a single object argument can be listed with the $METH_O$ flag, instead of invoking $PyArg_ParseTuple()$ with a "O" argument. They have the type PyCFunction, with the self parameter, and a PyObject* parameter representing the single argument.

These two constants are not used to indicate the calling convention but the binding when use with methods of classes. These may not be used for functions defined for modules. At most one of these flags may be set for any given method.

METH CLASS

The method will be passed the type object as the first parameter rather than an instance of the type. This is used to create *class methods*, similar to what is created when using the classmethod() built-in function.

METH_STATIC

The method will be passed NULL as the first parameter rather than an instance of the type. This is used to create *static methods*, similar to what is created when using the staticmethod() built-in function.

One other constant controls whether a method is loaded in place of another definition with the same method name.

METH_COEXIST

The method will be loaded in place of existing definitions. Without *METH_COEXIST*, the default is to skip repeated definitions. Since slot wrappers are loaded before the method table, the existence of a *sq_contains* slot, for example, would generate a wrapped method named ___contains___() and preclude the loading of a corresponding PyCFunction with the same name. With the flag defined, the PyCFunction will be loaded in place of the wrapper object and will co-exist with the slot. This is helpful because calls to PyCFunctions are optimized more than wrapper object calls.

PyMemberDef

Structure which describes an attribute of a type which corresponds to a C struct member. Its fields are:

| 域 | C 类型 | 意义 |
|--------|--------------|----------------------------------------------------------------------------|
| name | const char * | name of the member |
| type | int | the type of the member in the C struct |
| offset | Py_ssize_t | the offset in bytes that the member is located on the type's object struct |
| flags | int | flag bits indicating if the field should be read-only or writable |
| doc | const char * | points to the contents of the docstring |

type can be one of many T_{macros} corresponding to various C types. When the member is accessed in Python, it will be converted to the equivalent Python type.

| Macro name | C 数据类型 |
|-------------|----------------|
| T_SHORT | short |
| T_INT | int |
| T_LONG | 长整型 |
| T_FLOAT | float |
| T_DOUBLE | double |
| T_STRING | const char * |
| T_OBJECT | PyObject * |
| T_OBJECT_EX | PyObject * |
| T_CHAR | char |
| T_BYTE | char |
| T_UBYTE | unsigned char |
| T_UINT | 无符号整型 |
| T_USHORT | unsigned short |
| T_ULONG | 无符号长整型 |
| T_BOOL | char |
| T_LONGLONG | long long |
| T_ULONGLONG | 无符号 long long |
| T_PYSSIZET | Py_ssize_t |

 T_OBJECT and T_OBJECT_EX differ in that T_OBJECT returns None if the member is NULL and T_OBJECT_EX raises an AttributeError. Try to use T_OBJECT_EX over T_OBJECT because T_OBJECT_EX handles use of the del statement on that attribute more correctly than T_OBJECT .

flags can be 0 for write and read access or READONLY for read-only access. Using <code>T_STRING</code> for type implies <code>READONLY</code>. <code>T_STRING</code> data is interpreted as UTF-8. Only <code>T_OBJECT</code> and <code>T_OBJECT_EX</code> members can be deleted. (They are set to <code>NULL</code>).

PyGetSetDef

Structure to define property-like access for a type. See also description of the $PyTypeObject.tp_getset$ slot.

| 域 | C 类型 | 意义 |
|------|--------------|------------------------------------------------------------------------------------------|
| name | const char * | attribute name |
| get | getter | C Function to get the attribute |
| set | setter | optional C function to set or delete the attribute, if omitted the attribute is readonly |
| doc | const char * | optional docstring |
| clo- | void * | optional function pointer, providing additional data for getter and setter |
| sure | | |

The get function takes one PyObject* parameter (the instance) and a function pointer (the associated closure):

```
typedef PyObject *(*getter)(PyObject *, void *);
```

It should return a new reference on success or NULL with a set exception on failure.

set functions take two PyObject* parameters (the instance and the value to be set) and a function pointer (the associated closure):

```
typedef int (*setter)(PyObject *, PyObject *, void *);
```

In case the attribute should be deleted the second parameter is NULL. Should return 0 on success or -1 with a set exception on failure.

12.3 Type 对象

Perhaps one of the most important structures of the Python object system is the structure that defines a new type: the PyTypeObject structure. Type objects can be handled using any of the $PyObject_*$ () or $PyType_*$ () functions, but do not offer much that's interesting to most Python applications. These objects are fundamental to how objects behave, so they are very important to the interpreter itself and to any extension module that implements new types.

Type objects are fairly large compared to most of the standard types. The reason for the size is that each type object stores a large number of values, mostly C function pointers, each of which implements a small part of the type's functionality. The fields of the type object are examined in detail in this section. The fields will be described in the order in which they occur in the structure.

In addition to the following quick reference, the M section provides at-a-glance insight into the meaning and use of PyTypeObject.

12.3.1 快速参考

"tp 槽"

| PyTypeObject 槽 ¹ | Туре | 特殊方法/属性 | | | ≣ | |
|-----------------------------|--------------------|----------------------|----|-----|----------|----|
| | | | С |) T | D | Т |
| <r> tp_name</r> | const char * | name | X | X | | |
| tp_basicsize | Py_ssize_t | | X | X | | X |
| tp_itemsize | Py_ssize_t | | | X | | X |
| tp_dealloc | destructor | | X | X | | X |
| tp_vectorcall_offset | Py_ssize_t | | | | | ? |
| (tp_getattr) | getattrfunc | getattribute,getattr | | | | G |
| (tp_setattr) | setattrfunc | setattr,delattr | | | | G |
| tp_as_async | PyAsyncMethods* | sub-slots | | | | % |
| tp_repr | reprfunc | repr | X | X | | X |
| tp_as_number | PyNumberMethods* | sub-slots | | | | % |
| tp_as_sequence | PySequenceMethods* | sub-slots | | | | % |
| tp_as_mapping | PyMappingMethods* | sub-slots | | | | % |
| tp_hash | hashfunc | hash | X | | | G |
| tp_call | ternaryfunc | call | | X | | X |
| tp_str | reprfunc | str | X | | | X |
| tp_getattro | getattrofunc | getattribute,getattr | X | X | | G |
| tp_setattro | setattrofunc | setattr,delattr | X | X | | G |
| tp_as_buffer | PyBufferProcs* | | | | | % |
| tp_flags | 无符号长整型 | | X | X | | ? |
| tp_doc | const char * | doc | X | X | | |
| tp_traverse | traverseproc | | | X | | G |
| tp_clear | inquiry | | | X | | G |
| tp_richcompare | richcmpfunc | lt,le,eq,ne, | X | | | G |
| tp_weaklistoffset | Py_ssize_t | gt,ge | | X | | ? |
| tp_iter | getiterfunc | iter | | | | · |
| tp_iternext | iternextfunc | next | | | | -X |
| tp_methods | PyMethodDef[] | | X | X | | |
| tp_members | PyMemberDef[] | | 1 | X | | |
| tp_getset | PyGetSetDef[] | | X | | | |
| tp_base | PyTypeObject* | base | 23 | | X | |

下页继续

表 1 - 续上页

| PyTypeObject 槽 ¹ | Туре | 特殊方法/属性 | | 信息 | [[2 | |
|-----------------------------|--------------|------------|---|-----|---------|---|
| | | | С |) T | D | Т |
| tp_dict | PyObject* | dict | | | ? | |
| tp_descr_get | descrgetfunc | get | | | | X |
| tp_descr_set | descrsetfunc | set,delete | | | | X |
| tp_dictoffset | Py_ssize_t | | | X | | ? |
| tp_init | initproc | init | X | X | | X |
| tp_alloc | allocfunc | | X | | ? | ? |
| tp_new | newfunc | new | X | X | ? | ? |
| tp_free | freefunc | | X | X | ? | ? |
| tp_is_gc | inquiry | | | X | | X |
| <tp_bases></tp_bases> | PyObject* | bases | | | ~ | |
| <tp_mro></tp_mro> | PyObject* | mro | | | ~ | |
| [tp_cache] | PyObject* | | | | | |
| [tp_subclasses] | PyObject* | subclasses | | | | |
| [tp_weaklist] | PyObject* | | | | | |
| (tp_del) | destructor | | | | | |
| [tp_version_tag] | 无符号整型 | | | | • | |
| tp_finalize | destructor | del | | | | X |

如果定义了 COUNT_ALLOCS,则还存在以下(仅内部)字段:

- tp_allocs
- tp_frees
- tp_maxalloc
- tp_prev
- tp_next

2 列:

"O": set on PyBaseObject_Type

"T": set on PyType_Type

"D": default (if slot is set to NULL)

- X PyType_Ready sets this value if it is NULL
- \sim PyType_Ready always sets this value (it should be NULL)
- ? $PyType_Ready$ may set this value depending on other slots

Also see the inheritance column ("I").

"I": inheritance

 ${\tt X}$ - type slot is inherited via PyType_Ready if defined with a NULL value

 $\mbox{\ensuremath{\$}}$ - the slots of the sub-struct are inherited individually

G - inherited, but only in combination with other slots; see the slot's description

? - it's complicated; see the slot's description

Note that some slots are effectively inherited through the normal attribute lookup chain.

¹ A slot name in parentheses indicates it is (effectively) deprecated. Names in angle brackets should be treated as read-only. Names in square brackets are for internal use only. "<R>" (as a prefix) means the field is required (must be non-NULL).

sub-slots

| 槽 | Туре | 特殊方法 |
|----------------------------|---------------|-------------------|
| am_await | unaryfunc | await |
| am_aiter | unaryfunc | aiter |
| am_anext | unaryfunc | anext |
| | | |
| nb_add | binaryfunc | addradd |
| nb_inplace_add | binaryfunc | iadd |
| nb_subtract | binaryfunc | subrsub |
| nb_inplace_subtract | binaryfunc | sub |
| nb_multiply | binaryfunc | mulrmul |
| nb_inplace_multiply | binaryfunc | mul |
| nb_remainder | binaryfunc | modrmod |
| nb_inplace_remainder | binaryfunc | mod |
| nb_divmod | binaryfunc | divmod rdivmod |
| nb_power | ternaryfunc | powrpow |
| b_inplace_power | ternaryfunc | pow |
| nb_negative | unaryfunc | neg |
| ab_positive | unaryfunc | pos |
| nb_absolute | unaryfunc | abs |
| nb_bool | inquiry | bool |
| nb_invert | unaryfunc | invert |
| nb_lshift | binaryfunc | lshiftrlshift_ |
| nb_inplace_lshift | binaryfunc | lshift |
| nb_rshift | binaryfunc | rshift |
| _ | | rrshift |
| nb_inplace_rshift | binaryfunc | rshift |
| nb_and | binaryfunc | and rand |
| nb_inplace_and | binaryfunc | and |
| nb_xor | binaryfunc | xorrxor |
| nb_inplace_xor | binaryfunc | xor |
| nb_or | binaryfunc | orror |
| nb_inplace_or | binaryfunc | or |
| nb_int | unaryfunc | int |
| nb_reserved | void * | |
| nb_float | unaryfunc | float |
| nb_floor_divide | binaryfunc | floordiv |
| nb_inplace_floor_divide | binaryfunc | floordiv |
| nb_true_divide | binaryfunc | truediv |
| nb_inplace_true_divide | binaryfunc | truediv |
| ab_index | unaryfunc | index |
| nb_matrix_multiply | binaryfunc | matmul |
| | | rmatmul |
| nb_inplace_matrix_multiply | binaryfunc | matmul |
| | · | · |
| mp_length | lenfunc | len |
| mp_subscript | binaryfunc | getitem |
| mp_ass_subscript | objobjargproc | setitem, |
| | | delitem |
| ag longth | lonfunc | lan |
| sq_length | lenfunc | len |
| sq_concat | binaryfunc | add |
| sq_repeat | ssizeargfunc | mul 下五444 |

下页继续

表 2 - 续上页

| 槽 | Type | 特殊方法 |
|-------------------|---------------------|----------|
| sq_item | ssizeargfunc | getitem |
| sq_ass_item | ssizeobjargproc | setitem |
| | | delitem |
| sq_contains | objobjproc | contains |
| sq_inplace_concat | binaryfunc | iadd |
| sq_inplace_repeat | ssizeargfunc | imul |
| | | |
| bf_getbuffer | getbufferproc() | |
| bf_releasebuffer | releasebufferproc() | |

slot typedefs

| typedef | 参数类型 | 返回类型 |
|----------------|-----------------------|---------------------------------------|
| allocfunc | | PyObject* |
| | PyTypeObject* | |
| | Py_ssize_t | |
| | | |
| destructor | void * | void |
| freefunc | void * | void |
| traverseproc | | 整型 |
| | void * | |
| | visitproc | |
| | void * | |
| newfunc | | PyObject* |
| | PyObject* | |
| | PyObject* | |
| | PyObject* | |
| | 1 400 1600 | |
| initproc | | 整型 |
| | PyObject* | |
| | PyObject* | |
| | PyObject* | |
| | | |
| reprfunc | PyObject* | PyObject* |
| getattrfunc | | PyObject* |
| | PyObject * | |
| | const char * | |
| | | |
| setattrfunc | | 整型 |
| | PyObject* | |
| | const char * | |
| | PyObject* | |
| getattrofunc | | PyObject* |
| | DryObioot* | |
| | PyObject * PyObject * | |
| | 1 you ject | |
| setattrofunc | | 整型 |
| | PyObject* | |
| | PyObject* | |
| | PyObject* | |
| | 1 y 00 J 000 | |
| descrgetfunc | | PyObject* |
| | PyObject * | |
| | PyObject * | |
| | PyObject * | |
| descrsetfunc | | 整型 |
| uesci seci unc | D 01 / 4 | 五 五 五 五 五 五 五 五 五 五 五 五 五 五 五 五 五 五 五 |
| | PyObject * PyObject * | |
| 82 | PyObject* | Chapter 12. 对象实现支 |
| hashfunc | PyObject* | Py_hash_t |
| richcmpfunc | | PyObject* |

请参阅Slot Type typedefs 里有更多详细信息。

12.3.2 PyTypeObject Definition

The structure definition for PyTypeObject can be found in Include/object.h. For convenience of reference, this repeats the definition found there:

```
typedef struct _typeobject {
   PyObject_VAR_HEAD
    const char *tp_name; /* For printing, in format "<module>.<name>" */
   Py_ssize_t tp_basicsize, tp_itemsize; /* For allocation */
   /* Methods to implement standard operations */
   destructor tp_dealloc;
   Py_ssize_t tp_vectorcall_offset;
    getattrfunc tp_getattr;
    setattrfunc tp_setattr;
   PyAsyncMethods *tp_as_async; /* formerly known as tp_compare (Python 2)
                                    or tp_reserved (Python 3) */
   reprfunc tp_repr;
   /* Method suites for standard classes */
   PyNumberMethods *tp_as_number;
   PySequenceMethods *tp_as_sequence;
   PyMappingMethods *tp_as_mapping;
    /* More standard operations (here for binary compatibility) */
   hashfunc tp_hash;
    ternaryfunc tp_call;
   reprfunc tp_str;
    getattrofunc tp_getattro;
    setattrofunc tp_setattro;
    /* Functions to access object as input/output buffer */
   PyBufferProcs *tp_as_buffer;
    /* Flags to define presence of optional/expanded features */
   unsigned long tp_flags;
   const char *tp_doc; /* Documentation string */
    /* call function for all accessible objects */
   traverseproc tp_traverse;
    /* delete references to contained objects */
   inquiry tp_clear;
    /* rich comparisons */
   richcmpfunc tp_richcompare;
    /* weak reference enabler */
   Py_ssize_t tp_weaklistoffset;
    /* Iterators */
    getiterfunc tp_iter;
    iternextfunc tp_iternext;
    /* Attribute descriptor and subclassing stuff */
```

(下页继续)

(续上页)

```
struct PyMethodDef *tp_methods;
    struct PyMemberDef *tp_members;
    struct PyGetSetDef *tp_getset;
    struct _typeobject *tp_base;
   PyObject *tp_dict;
    descrgetfunc tp_descr_get;
    descrsetfunc tp_descr_set;
   Py_ssize_t tp_dictoffset;
    initproc tp_init;
    allocfunc tp_alloc;
    newfunc tp_new;
    freefunc tp_free; /* Low-level free-memory routine */
    inquiry tp_is_gc; /* For PyObject_IS_GC */
    PyObject *tp_bases;
    PyObject *tp_mro; /* method resolution order */
    PyObject *tp_cache;
    PyObject *tp_subclasses;
   PyObject *tp_weaklist;
    destructor tp_del;
    /* Type attribute cache version tag. Added in version 2.6 */
   unsigned int tp_version_tag;
    destructor tp_finalize;
} PyTypeObject;
```

12.3.3 PyObject Slots

The type object structure extends the PyVarObject structure. The ob_size field is used for dynamic types (created by type_new(), usually called from a class statement). Note that $PyType_Type$ (the metatype) initializes $tp_itemsize$, which means that its instances (i.e. type objects) must have the ob_size field.

```
PyObject* PyObject . _ob_next
PyObject* PyObject . _ob_prev
```

These fields are only present when the macro <code>Py_TRACE_REFS</code> is defined. Their initialization to <code>NULL</code> is taken care of by the <code>PyObject_HEAD_INIT</code> macro. For statically allocated objects, these fields always remain <code>NULL</code>. For dynamically allocated objects, these two fields are used to link the object into a doubly-linked list of <code>all</code> live objects on the heap. This could be used for various debugging purposes; currently the only use is to print the objects that are still alive at the end of a run when the environment variable <code>PYTHONDUMPREFS</code> is set.

Inheritance:

These fields are not inherited by subtypes.

Py_ssize_t PyObject.ob_refcnt

This is the type object's reference count, initialized to 1 by the PyObject_HEAD_INIT macro. Note that for statically allocated type objects, the type's instances (objects whose ob_type points back to the type) do *not* count as references. But for dynamically allocated type objects, the instances *do* count as references.

Inheritance:

This field is not inherited by subtypes.

```
PyTypeObject* PyObject.ob_type
```

This is the type's type, in other words its metatype. It is initialized by the argument to the PyObject_HEAD_INIT macro, and its value should normally be &PyType_Type. However, for dynamically loadable extension modules that must be usable on Windows (at least), the compiler complains that this is not a valid initializer. Therefore, the convention is to pass NULL to the PyObject_HEAD_INIT macro

and to initialize this field explicitly at the start of the module's initialization function, before doing anything else. This is typically done like this:

```
Foo_Type.ob_type = &PyType_Type;
```

This should be done before any instances of the type are created. $PyType_Ready()$ checks if ob_type is NULL, and if so, initializes it to the ob_type field of the base class. $PyType_Ready()$ will not change this field if it is non-zero.

Inheritance:

This field is inherited by subtypes.

12.3.4 PyVarObject Slots

Py_ssize_t PyVarObject.ob_size

For statically allocated type objects, this should be initialized to zero. For dynamically allocated type objects, this field has a special internal meaning.

Inheritance:

This field is not inherited by subtypes.

12.3.5 PyTypeObject Slots

Each slot has a section describing inheritance. If $PyType_Ready()$ may set a value when the field is set to NULL then there will also be a "Default" section. (Note that many fields set on PyBaseObject_Type and $PyType_Type$ effectively act as defaults.)

const char* PyTypeObject.tp_name

Pointer to a NUL-terminated string containing the name of the type. For types that are accessible as module globals, the string should be the full module name, followed by a dot, followed by the type name; for built-in types, it should be just the type name. If the module is a submodule of a package, the full package name is part of the full module name. For example, a type named T defined in module M in subpackage Q in package P should have the tp_name initializer "P.Q.M.T".

For dynamically allocated type objects, this should just be the type name, and the module name explicitly stored in the type dict as the value for key '__module__'.

For statically allocated type objects, the tp_name field should contain a dot. Everything before the last dot is made accessible as the __module__ attribute, and everything after the last dot is made accessible as the __name__ attribute.

If no dot is present, the entire <code>tp_name</code> field is made accessible as the <code>__name_</code> attribute, and the <code>__module_</code> attribute is undefined (unless explicitly set in the dictionary, as explained above). This means your type will be impossible to pickle. Additionally, it will not be listed in module documentations created with pydoc.

This field must not be NULL. It is the only required field in PyTypeObject() (other than potentially $tp_itemsize$).

Inheritance:

This field is not inherited by subtypes.

Py_ssize_t PyTypeObject.tp_basicsize Py_ssize_t PyTypeObject.tp_itemsize

These fields allow calculating the size in bytes of instances of the type.

There are two kinds of types: types with fixed-length instances have a zero $tp_itemsize$ field, types with variable-length instances have a non-zero $tp_itemsize$ field. For a type with fixed-length instances, all instances have the same size, given in $tp_basicsize$.

For a type with variable-length instances, the instances must have an ob_size field, and the instance size is $tp_basicsize$ plus N times $tp_itemsize$, where N is the "length" of the object. The value of N is typically stored in the instance's ob_size field. There are exceptions: for example, ints use a negative ob_size to indicate a negative number, and N is abs (ob_size) there. Also, the presence of an ob_size field in the instance layout doesn't mean that the instance structure is variable-length (for example, the structure for the list type has fixed-length instances, yet those instances have a meaningful ob_size field).

The basic size includes the fields in the instance declared by the macro <code>PyObject_HEAD</code> or <code>PyObject_VAR_HEAD</code> (whichever is used to declare the instance struct) and this in turn includes the <code>_ob_prev</code> and <code>_ob_next</code> fields if they are present. This means that the only correct way to get an initializer for the <code>tp_basicsize</code> is to use the <code>sizeof</code> operator on the struct used to declare the instance layout. The basic size does not include the GC header size.

A note about alignment: if the variable items require a particular alignment, this should be taken care of by the value of $tp_basicsize$. Example: suppose a type implements an array of double. $tp_itemsize$ is sizeof(double). It is the programmer's responsibility that $tp_basicsize$ is a multiple of sizeof(double) (assuming this is the alignment requirement for double).

For any type with variable-length instances, this field must not be NULL.

Inheritance:

These fields are inherited separately by subtypes. If the base type has a non-zero $tp_itemsize$, it is generally not safe to set $tp_itemsize$ to a different non-zero value in a subtype (though this depends on the implementation of the base type).

destructor PyTypeObject.tp_dealloc

A pointer to the instance destructor function. This function must be defined unless the type guarantees that its instances will never be deallocated (as is the case for the singletons None and Ellipsis). The function signature is:

```
void tp_dealloc(PyObject *self);
```

The destructor function is called by the $Py_DECREF()$ and $Py_XDECREF()$ macros when the new reference count is zero. At this point, the instance is still in existence, but there are no references to it. The destructor function should free all references which the instance owns, free all memory buffers owned by the instance (using the freeing function corresponding to the allocation function used to allocate the buffer), and call the type's tp_free function. If the type is not subtypable (doesn't have the $Py_TPFLAGS_BASETYPE$ flag bit set), it is permissible to call the object deallocator directly instead of via tp_free . The object deallocator should be the one used to allocate the instance; this is normally $PyObject_Del()$ if the instance was allocated using $PyObject_New()$ or $PyObject_VarNew()$, or $PyObject_GC_Del()$ if the instance was allocated using $PyObject_GC_New()$ or $PyObject_GC_NewVar()$.

Finally, if the type is heap allocated (Py_TPFLAGS_HEAPTYPE), the deallocator should decrement the reference count for its type object after calling the type deallocator. In order to avoid dangling pointers, the recommended way to achieve this is:

```
static void foo_dealloc(foo_object *self) {
    PyTypeObject *tp = Py_TYPE(self);
    // free references and buffers here
    tp->tp_free(self);
    Py_DECREF(tp);
}
```

Inheritance:

This field is inherited by subtypes.

Py_ssize_t PyTypeObject.tp_vectorcall_offset

An optional offset to a per-instance function that implements calling the object using the *vectorcall* protocol, a more efficient alternative of the simpler tp_call .

This field is only used if the flag _Py_TPFLAGS_HAVE_VECTORCALL is set. If so, this must be a positive integer containing the offset in the instance of a vectorcall func pointer. The signature is the same as for

_PyObject_Vectorcall():

```
PyObject *vectorcallfunc(PyObject *callable, PyObject *const *args, size_t

→nargsf, PyObject *kwnames)
```

The *vectorcallfunc* pointer may be zero, in which case the instance behaves as if _Py_TPFLAGS_HAVE_VECTORCALL was not set: calling the instance falls back to tp_call.

Any class that sets $Py_TPFLAGS_HAVE_VECTORCALL$ must also set tp_call and make sure its behaviour is consistent with the *vectorcallfunc* function. This can be done by setting tp_call to PvVectorcall Call:

PyObject *PyVectorcall_Call (PyObject *callable, PyObject *tuple, PyObject *dict)

Call callable's vectorcallfunc with positional and keyword arguments given in a tuple and dict, respectively.

This function is intended to be used in the tp_call slot. It does not fall back to tp_call and it currently does not check the $_{Py_TPFLAGS_HAVE_VECTORCALL}$ flag. To call an object, use one of the $_{PyObject_Call}$ functions instead.

注解: It is not recommended for *heap types* to implement the vectorcall protocol. When a user sets __call__ in Python code, only tp_call is updated, possibly making it inconsistent with the vectorcall function.

注解: The semantics of the tp_vectorcall_offset slot are provisional and expected to be finalized in Python 3.9. If you use vectorcall, plan for updating your code for Python 3.9.

在 3.8 版更改: This slot was used for print formatting in Python 2.x. In Python 3.0 to 3.7, it was reserved and named tp_print.

Inheritance:

This field is inherited by subtypes together with tp_call : a subtype inherits $tp_vectorcall_offset$ from its base type when the subtype' s tp_call is NULL.

Note that *heap types* (including subclasses defined in Python) do not inherit the _Py_TPFLAGS_HAVE_VECTORCALL flag.

getattrfunc PyTypeObject.tp_getattr

An optional pointer to the get-attribute-string function.

This field is deprecated. When it is defined, it should point to a function that acts the same as the tp_getattro function, but taking a C string instead of a Python string object to give the attribute name.

Inheritance:

```
Group: tp_getattr, tp_getattro
```

This field is inherited by subtypes together with $tp_getattro$: a subtype inherits both $tp_getattr$ and $tp_getattro$ from its base type when the subtype's $tp_getattr$ and $tp_getattro$ are both NULL.

setattrfunc PyTypeObject.tp_setattr

An optional pointer to the function for setting and deleting attributes.

This field is deprecated. When it is defined, it should point to a function that acts the same as the $tp_setattro$ function, but taking a C string instead of a Python string object to give the attribute name.

Inheritance:

```
Group: tp_setattr, tp_setattro
```

This field is inherited by subtypes together with $tp_setattro$: a subtype inherits both $tp_setattr$ and $tp_setattro$ from its base type when the subtype's $tp_setattr$ and $tp_setattro$ are both NULL.

PyAsyncMethods* PyTypeObject.tp_as_async

Pointer to an additional structure that contains fields relevant only to objects which implement *awaitable* and *asynchronous iterator* protocols at the C-level. See *Async Object Structures* for details.

3.5 新版功能: Formerly known as tp_compare and tp_reserved.

Inheritance:

The tp_as_async field is not inherited, but the contained fields are inherited individually.

reprfunc PyTypeObject.tp_repr

An optional pointer to a function that implements the built-in function repr ().

The signature is the same as for PyObject Repr():

```
PyObject *tp_repr(PyObject *self);
```

The function must return a string or a Unicode object. Ideally, this function should return a string that, when passed to eval(), given a suitable environment, returns an object with the same value. If this is not feasible, it should return a string starting with '<' and ending with '>' from which both the type and the value of the object can be deduced.

Inheritance:

This field is inherited by subtypes.

Default:

When this field is not set, a string of the form <%s object at %p> is returned, where %s is replaced by the type name, and %p by the object's memory address.

PyNumberMethods* PyTypeObject.tp_as_number

Pointer to an additional structure that contains fields relevant only to objects which implement the number protocol. These fields are documented in *Number Object Structures*.

Inheritance:

The tp_as_number field is not inherited, but the contained fields are inherited individually.

PySequenceMethods* PyTypeObject.tp_as_sequence

Pointer to an additional structure that contains fields relevant only to objects which implement the sequence protocol. These fields are documented in *Sequence Object Structures*.

Inheritance:

The tp_as_sequence field is not inherited, but the contained fields are inherited individually.

PyMappingMethods* PyTypeObject.tp_as_mapping

Pointer to an additional structure that contains fields relevant only to objects which implement the mapping protocol. These fields are documented in *Mapping Object Structures*.

Inheritance:

The tp_as_mapping field is not inherited, but the contained fields are inherited individually.

hashfunc PyTypeObject.tp_hash

An optional pointer to a function that implements the built-in function hash ().

The signature is the same as for PyObject_Hash():

```
Py_hash_t tp_hash(PyObject *);
```

The value -1 should not be returned as a normal return value; when an error occurs during the computation of the hash value, the function should set an exception and return -1.

When this field is not set (and tp_richcompare is not set), an attempt to take the hash of the object raises TypeError. This is the same as setting it to PyObject_HashNotImplemented().

This field can be set explicitly to PyObject_HashNotImplemented() to block inheritance of the hash method from a parent type. This is interpreted as the equivalent of __hash__ = None at the Python

level, causing isinstance (o, collections. Hashable) to correctly return False. Note that the converse is also true - setting __hash__ = None on a class at the Python level will result in the tp_hash slot being set to $PyObject_HashNotImplemented()$.

Inheritance:

```
Group: tp_hash, tp_richcompare
```

This field is inherited by subtypes together with $tp_richcompare$: a subtype inherits both of $tp_richcompare$ and tp_hash , when the subtype's $tp_richcompare$ and tp_hash are both NULL.

ternaryfunc PyTypeObject.tp_call

An optional pointer to a function that implements calling the object. This should be NULL if the object is not callable. The signature is the same as for PyObject_Call():

```
PyObject *tp_call(PyObject *self, PyObject *args, PyObject *kwargs);
```

Inheritance:

This field is inherited by subtypes.

reprfunc PyTypeObject.tp_str

An optional pointer to a function that implements the built-in operation str(). (Note that str is a type now, and str() calls the constructor for that type. This constructor calls <code>PyObject_Str()</code> to do the actual work, and <code>PyObject_Str()</code> will call this handler.)

The signature is the same as for PyObject_Str():

```
PyObject *tp_str(PyObject *self);
```

The function must return a string or a Unicode object. It should be a "friendly" string representation of the object, as this is the representation that will be used, among other things, by the print () function.

Inheritance:

This field is inherited by subtypes.

Default:

When this field is not set, PyObject_Repr() is called to return a string representation.

getattrofunc PyTypeObject.tp_getattro

An optional pointer to the get-attribute function.

The signature is the same as for PyObject GetAttr():

```
PyObject *tp_getattro(PyObject *self, PyObject *attr);
```

It is usually convenient to set this field to $PyObject_GenericGetAttr()$, which implements the normal way of looking for object attributes.

Inheritance:

```
Group: tp_getattr, tp_getattro
```

This field is inherited by subtypes together with $tp_getattr$: a subtype inherits both $tp_getattr$ and $tp_getattr$ from its base type when the subtype's $tp_getattr$ and $tp_getattr$ 0 are both NULL.

Default:

PyBaseObject_Type uses PyObject_GenericGetAttr().

setattrofunc PyTypeObject.tp_setattro

An optional pointer to the function for setting and deleting attributes.

The signature is the same as for PyObject_SetAttr():

```
PyObject *tp_setattro(PyObject *self, PyObject *attr, PyObject *value);
```

In addition, setting *value* to NULL to delete an attribute must be supported. It is usually convenient to set this field to *PyObject_GenericSetAttr()*, which implements the normal way of setting object attributes.

Inheritance:

Group: tp_setattr, tp_setattro

This field is inherited by subtypes together with $tp_setattr$: a subtype inherits both $tp_setattr$ and $tp_setattr$ from its base type when the subtype's $tp_setattr$ and $tp_setattr$ 0 are both NULL.

Default:

PyBaseObject_Type uses PyObject_GenericSetAttr().

PyBufferProcs* PyTypeObject.tp_as_buffer

Pointer to an additional structure that contains fields relevant only to objects which implement the buffer interface. These fields are documented in *Buffer Object Structures*.

Inheritance:

The tp_as_buffer field is not inherited, but the contained fields are inherited individually.

unsigned long PyTypeObject.tp_flags

This field is a bit mask of various flags. Some flags indicate variant semantics for certain situations; others are used to indicate that certain fields in the type object (or in the extension structures referenced via tp_as_number , $tp_as_sequence$, $tp_as_mapping$, and tp_as_buffer) that were historically not always present are valid; if such a flag bit is clear, the type fields it guards must not be accessed and must be considered to have a zero or NULL value instead.

Inheritance:

Inheritance of this field is complicated. Most flag bits are inherited individually, i.e. if the base type has a flag bit set, the subtype inherits this flag bit. The flag bits that pertain to extension structures are strictly inherited if the extension structure is inherited, i.e. the base type's value of the flag bit is copied into the subtype together with a pointer to the extension structure. The $Py_TPFLAGS_HAVE_GC$ flag bit is inherited together with the $tp_traverse$ and tp_clear fields, i.e. if the $Py_TPFLAGS_HAVE_GC$ flag bit is clear in the subtype and the $tp_traverse$ and tp_clear fields in the subtype exist and have NULL values.

Default:

PyBaseObject_Type uses Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE.

Bit Masks:

The following bit masks are currently defined; these can be ORed together using the | operator to form the value of the tp_flags field. The macro $PyType_HasFeature()$ takes a type and a flags value, tp and f, and checks whether $tp->tp_flags \& f$ is non-zero.

Py TPFLAGS HEAPTYPE

This bit is set when the type object itself is allocated on the heap, for example, types created dynamically using $PyType_FromSpec()$. In this case, the ob_type field of its instances is considered a reference to the type, and the type object is INCREF'ed when a new instance is created, and DECREF'ed when an instance is destroyed (this does not apply to instances of subtypes; only the type referenced by the instance's ob_type gets INCREF'ed or DECREF'ed).

Inheritance:

???

Py_TPFLAGS_BASETYPE

This bit is set when the type can be used as the base type of another type. If this bit is clear, the type cannot be subtyped (similar to a "final" class in Java).

Inheritance:

???

Py_TPFLAGS_READY

This bit is set when the type object has been fully initialized by PyType_Ready().

Inheritance:

???

Py_TPFLAGS_READYING

This bit is set while PyType_Ready () is in the process of initializing the type object.

Inheritance:

222

Py_TPFLAGS_HAVE_GC

This bit is set when the object supports garbage collection. If this bit is set, instances must be created using $PyObject_GC_New()$ and destroyed using $PyObject_GC_Del()$. More information in section 使对象类型支持循环垃圾回收. This bit also implies that the GC-related fields $tp_traverse$ and tp_clear are present in the type object.

Inheritance:

```
Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

The Py_TPFLAGS_HAVE_GC flag bit is inherited together with the tp_traverse and tp_clear fields, i.e. if the Py_TPFLAGS_HAVE_GC flag bit is clear in the subtype and the tp_traverse and tp_clear fields in the subtype exist and have NULL values.

Py TPFLAGS DEFAULT

This is a bitmask of all the bits that pertain to the existence of certain fields in the type object and its extension structures. Currently, it includes the following bits: Py_TPFLAGS_HAVE_STACKLESS_EXTENSION, Py_TPFLAGS_HAVE_VERSION_TAG.

Inheritance:

222

Py_TPFLAGS_METHOD_DESCRIPTOR

This bit indicates that objects behave like unbound methods.

If this flag is set for type (meth), then:

- meth.__get__(obj, cls) (*args, **kwds) (with obj not None) must be equivalent to meth (obj, *args, **kwds).
- meth.__get__(None, cls) (*args, **kwds) must be equivalent to meth(*args, **kwds).

This flag enables an optimization for typical method calls like obj.meth(): it avoids creating a temporary "bound method" object for obj.meth.

3.8 新版功能.

Inheritance:

This flag is never inherited by heap types. For extension types, it is inherited whenever tp_descr_get is inherited.

```
Py_TPFLAGS_LONG_SUBCLASS

Py_TPFLAGS_LIST_SUBCLASS

Py_TPFLAGS_TUPLE_SUBCLASS

Py_TPFLAGS_BYTES_SUBCLASS

Py_TPFLAGS_UNICODE_SUBCLASS

Py_TPFLAGS_DICT_SUBCLASS

Py_TPFLAGS_BASE_EXC_SUBCLASS
```

Py_TPFLAGS_TYPE_SUBCLASS

These flags are used by functions such as $PyLong_Check()$ to quickly determine if a type is a subclass of a built-in type; such specific checks are faster than a generic check, like $PyObject_IsInstance()$. Custom types that inherit from built-ins should have their tp_flags set appropriately, or the code that interacts with such types will behave differently depending on what kind of check is used.

Py_TPFLAGS_HAVE_FINALIZE

This bit is set when the $tp_finalize$ slot is present in the type structure.

3.4 新版功能.

3.8 版后已移除: This flag isn't necessary anymore, as the interpreter assumes the $tp_finalize$ slot is always present in the type structure.

_Py_TPFLAGS_HAVE_VECTORCALL

This bit is set when the class implements the vectorcall protocol. See *tp_vectorcall_offset* for details.

Inheritance:

This bit is set on *static* subtypes if tp_flags is not overridden: a subtype inherits $_Py_TPFLAGS_HAVE_VECTORCALL$ from its base type when the subtype's tp_call is NULL and the subtype's $py_TPFLAGS_HEAPTYPE$ is not set.

Heap types do not inherit _Py_TPFLAGS_HAVE_VECTORCALL.

注解: This flag is provisional and expected to become public in Python 3.9, with a different name and, possibly, changed semantics. If you use vectorcall, plan for updating your code for Python 3.9.

3.8 新版功能.

$const\ char * \ \textbf{PyTypeObject.tp_doc}$

An optional pointer to a NUL-terminated C string giving the docstring for this type object. This is exposed as the __doc__ attribute on the type and instances of the type.

Inheritance:

This field is *not* inherited by subtypes.

traverseproc PyTypeObject.tp_traverse

An optional pointer to a traversal function for the garbage collector. This is only used if the $Py_TPFLAGS_HAVE_GC$ flag bit is set. The signature is:

```
int tp_traverse(PyObject *self, visitproc visit, void *arg);
```

More information about Python's garbage collection scheme can be found in section 使对象类型支持循环垃圾回收.

The $tp_traverse$ pointer is used by the garbage collector to detect reference cycles. A typical implementation of a $tp_traverse$ function simply calls $Py_VISIT()$ on each of the instance's members that are Python objects that the instance owns. For example, this is function <code>local_traverse()</code> from the <code>_thread</code> extension module:

```
static int
local_traverse(localobject *self, visitproc visit, void *arg)
{
    Py_VISIT(self->args);
    Py_VISIT(self->kw);
    Py_VISIT(self->dict);
    return 0;
}
```

Note that $Py_VISIT()$ is called only on those members that can participate in reference cycles. Although there is also a self->key member, it can only be NULL or a Python string and therefore cannot be part of a reference cycle.

On the other hand, even if you know a member can never be part of a cycle, as a debugging aid you may want to visit it anyway just so the gc module's get_referents() function will include it.

警告: When implementing $tp_traverse$, only the members that the instance owns (by having strong references to them) must be visited. For instance, if an object supports weak references via the $tp_weaklist$ slot, the pointer supporting the linked list (what $tp_weaklist$ points to) must **not** be visited as the instance does not directly own the weak references to itself (the weakreference list is there to support the weak reference machinery, but the instance has no strong reference to the elements inside it, as they are allowed to be removed even if the instance is still alive).

Note that $Py_VISIT()$ requires the *visit* and *arg* parameters to local_traverse() to have these specific names; don't name them just anything.

Inheritance:

```
Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear
```

This field is inherited by subtypes together with tp_clear and the $Py_TPFLAGS_HAVE_GC$ flag bit: the flag bit, $tp_traverse$, and tp_clear are all inherited from the base type if they are all zero in the subtype.

inquiry PyTypeObject.tp_clear

An optional pointer to a clear function for the garbage collector. This is only used if the Py_TPFLAGS_HAVE_GC flag bit is set. The signature is:

```
int tp_clear(PyObject *);
```

The tp_clear member function is used to break reference cycles in cyclic garbage detected by the garbage collector. Taken together, all tp_clear functions in the system must combine to break all reference cycles. This is subtle, and if in any doubt supply a tp_clear function. For example, the tuple type does not implement a tp_clear function, because it's possible to prove that no reference cycle can be composed entirely of tuples. Therefore the tp_clear functions of other types must be sufficient to break any cycle containing a tuple. This isn't immediately obvious, and there's rarely a good reason to avoid implementing tp_clear .

Implementations of tp_clear should drop the instance's references to those of its members that may be Python objects, and set its pointers to those members to NULL, as in the following example:

```
static int
local_clear(localobject *self)
{
    Py_CLEAR(self->key);
    Py_CLEAR(self->args);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->kw);
    Py_CLEAR(self->dict);
    return 0;
}
```

The $Py_CLEAR()$ macro should be used, because clearing references is delicate: the reference to the contained object must not be decremented until after the pointer to the contained object is set to NULL. This is because decrementing the reference count may cause the contained object to become trash, triggering a chain of reclamation activity that may include invoking arbitrary Python code (due to finalizers, or weakref callbacks, associated with the contained object). If it's possible for such code to reference self again, it's important that the pointer to the contained object be NULL at that time, so that self knows the contained object can no longer be used. The $Py_CLEAR()$ macro performs the operations in a safe order.

Because the goal of tp_clear functions is to break reference cycles, it's not necessary to clear contained objects like Python strings or Python integers, which can't participate in reference cycles. On the other hand, it may be convenient to clear all contained Python objects, and write the type's $tp_dealloc$ function to invoke tp_clear .

More information about Python's garbage collection scheme can be found in section 使对象类型支持循环垃圾回收.

Inheritance:

Group: Py_TPFLAGS_HAVE_GC, tp_traverse, tp_clear

This field is inherited by subtypes together with $tp_traverse$ and the $Py_TPFLAGS_HAVE_GC$ flag bit: the flag bit, $tp_traverse$, and tp_clear are all inherited from the base type if they are all zero in the subtype.

richcmpfunc PyTypeObject.tp_richcompare

An optional pointer to the rich comparison function, whose signature is:

```
PyObject *tp_richcompare(PyObject *self, PyObject *other, int op);
```

The first parameter is guaranteed to be an instance of the type that is defined by PyTypeObject.

The function should return the result of the comparison (usually Py_True or Py_False). If the comparison is undefined, it must return $Py_NotImplemented$, if another error occurred it must return NULL and set an exception condition.

The following constants are defined to be used as the third argument for $tp_richcompare$ and for $PyObject\ RichCompare$ ():

| 常数 | 对照 |
|-------|-----|
| Py_LT | < |
| Py_LE | <= |
| Py_EQ | == |
| Py_NE | ! = |
| Py_GT | > |
| Py_GE | >= |

定义以下宏是为了简化编写丰富的比较函数:

PyObject *Py_RETURN_RICHCOMPARE (VAL_A, VAL_B, int op)

Return Py_True or Py_False from the function, depending on the result of a comparison. VAL_A and VAL_B must be orderable by C comparison operators (for example, they may be C ints or floats). The third argument specifies the requested operation, as for $PyObject_RichCompare()$.

The return value's reference count is properly incremented.

On error, sets an exception and returns NULL from the function.

3.7 新版功能.

Inheritance:

Group: tp_hash, tp_richcompare

This field is inherited by subtypes together with tp_hash : a subtype inherits $tp_richcompare$ and tp_hash when the subtype's $tp_richcompare$ and tp_hash are both NULL.

Default:

PyBaseObject_Type provides a tp_richcompare implementation, which may be inherited. However, if only tp_hash is defined, not even the inherited function is used and instances of the type will not be able to participate in any comparisons.

Py_ssize_t PyTypeObject.tp_weaklistoffset

If the instances of this type are weakly referenceable, this field is greater than zero and contains the offset in the instance structure of the weak reference list head (ignoring the GC header, if present); this offset is used by PyObject_ClearWeakRefs() and the PyWeakref_*() functions. The instance structure needs to include a field of type PyObject* which is initialized to NULL.

Do not confuse this field with $tp_weaklist$; that is the list head for weak references to the type object itself.

Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype uses a different weak reference list head than the base type. Since the list head is always found via tp_weaklistoffset, this should not be a problem.

When a type defined by a class statement has no __slots__ declaration, and none of its base types are weakly referenceable, the type is made weakly referenceable by adding a weak reference list head slot to the instance layout and setting the tp weaklistoffset of that slot's offset.

When a type's __slots__ declaration contains a slot named __weakref__, that slot becomes the weak reference list head for instances of the type, and the slot's offset is stored in the type's tp_weaklistoffset.

When a type's __slots__ declaration does not contain a slot named __weakref__, the type inherits its tp_weaklistoffset from its base type.

getiterfunc PyTypeObject.tp_iter

An optional pointer to a function that returns an iterator for the object. Its presence normally signals that the instances of this type are iterable (although sequences may be iterable without this function).

This function has the same signature as PyObject_GetIter():

```
PyObject *tp_iter(PyObject *self);
```

Inheritance:

This field is inherited by subtypes.

iternextfunc PyTypeObject.tp_iternext

An optional pointer to a function that returns the next item in an iterator. The signature is:

```
PyObject *tp_iternext(PyObject *self);
```

When the iterator is exhausted, it must return NULL; a StopIteration exception may or may not be set. When another error occurs, it must return NULL too. Its presence signals that the instances of this type are iterators.

Iterator types should also define the tp_iter function, and that function should return the iterator instance itself (not a new iterator instance).

This function has the same signature as PyIter Next().

Inheritance:

This field is inherited by subtypes.

struct PyMethodDef* PyTypeObject.tp_methods

An optional pointer to a static NULL-terminated array of PyMethodDef structures, declaring regular methods of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a method descriptor.

Inheritance:

This field is not inherited by subtypes (methods are inherited through a different mechanism).

struct PyMemberDef* PyTypeObject.tp_members

An optional pointer to a static NULL-terminated array of <code>PyMemberDef</code> structures, declaring regular data members (fields or slots) of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a member descriptor.

Inheritance:

This field is not inherited by subtypes (members are inherited through a different mechanism).

struct PyGetSetDef* PyTypeObject.tp_getset

An optional pointer to a static NULL-terminated array of PyGetSetDef structures, declaring computed attributes of instances of this type.

For each entry in the array, an entry is added to the type's dictionary (see tp_dict below) containing a getset descriptor.

Inheritance:

This field is not inherited by subtypes (computed attributes are inherited through a different mechanism).

PyTypeObject* PyTypeObject.tp_base

An optional pointer to a base type from which type properties are inherited. At this level, only single inheritance is supported; multiple inheritance require dynamically creating a type object by calling the metatype.

注解: Slot initialization is subject to the rules of initializing globals. C99 requires the initializers to be "address constants". Function designators like <code>PyType_GenericNew()</code>, with implicit conversion to a pointer, are valid C99 address constants.

However, the unary '&' operator applied to a non-static variable like PyBaseObject_Type() is not required to produce an address constant. Compilers may support this (gcc does), MSVC does not. Both compilers are strictly standard conforming in this particular behavior.

Consequently, tp_base should be set in the extension module's init function.

Inheritance:

This field is not inherited by subtypes (obviously).

Default:

This field defaults to &PyBaseObject_Type (which to Python programmers is known as the type object).

PyObject* PyTypeObject.tp_dict

The type's dictionary is stored here by <code>PyType_Ready()</code>.

This field should normally be initialized to NULL before PyType_Ready is called; it may also be initialized to a dictionary containing initial attributes for the type. Once $PyType_Ready()$ has initialized the type, extra attributes for the type may be added to this dictionary only if they don't correspond to overloaded operations (like __add__()).

Inheritance:

This field is not inherited by subtypes (though the attributes defined in here are inherited through a different mechanism).

Default:

If this field is NULL, PyType Ready () will assign a new dictionary to it.

警告: It is not safe to use <code>PyDict_SetItem()</code> on or otherwise modify <code>tp_dict</code> with the dictionary C-API.

descrgetfunc PyTypeObject.tp_descr_get

An optional pointer to a "descriptor get" function.

The function signature is:

```
PyObject * tp_descr_get(PyObject *self, PyObject *obj, PyObject *type);
```

Inheritance:

This field is inherited by subtypes.

descrsetfunc PyTypeObject.tp_descr_set

An optional pointer to a function for setting and deleting a descriptor's value.

The function signature is:

```
int tp_descr_set(PyObject *self, PyObject *obj, PyObject *value);
```

The *value* argument is set to NULL to delete the value.

Inheritance:

This field is inherited by subtypes.

Py_ssize_t PyTypeObject.tp_dictoffset

If the instances of this type have a dictionary containing instance variables, this field is non-zero and contains the offset in the instances of the type of the instance variable dictionary; this offset is used by $PyObject_GenericGetAttr()$.

Do not confuse this field with tp_dict ; that is the dictionary for attributes of the type object itself.

If the value of this field is greater than zero, it specifies the offset from the start of the instance structure. If the value is less than zero, it specifies the offset from the *end* of the instance structure. A negative offset is more expensive to use, and should only be used when the instance structure contains a variable-length part. This is used for example to add an instance variable dictionary to subtypes of str or tuple. Note that the $tp_basicsize$ field should account for the dictionary added to the end in that case, even though the dictionary is not included in the basic object layout. On a system with a pointer size of 4 bytes, $tp_dictoffset$ should be set to -4 to indicate that the dictionary is at the very end of the structure.

The real dictionary offset in an instance can be computed from a negative tp_dictoffset as follows:

```
dictoffset = tp_basicsize + abs(ob_size)*tp_itemsize + tp_dictoffset
if dictoffset is not aligned on sizeof(void*):
    round up to sizeof(void*)
```

where $tp_basicsize$, $tp_itemsize$ and $tp_dictoffset$ are taken from the type object, and ob_size is taken from the instance. The absolute value is taken because ints use the sign of ob_size to store the sign of the number. (There's never a need to do this calculation yourself; it is done for you by _PyObject_GetDictPtr().)

Inheritance:

This field is inherited by subtypes, but see the rules listed below. A subtype may override this offset; this means that the subtype instances store the dictionary at a difference offset than the base type. Since the dictionary is always found via $tp_dictoffset$, this should not be a problem.

When a type defined by a class statement has no $__slots_$ declaration, and none of its base types has an instance variable dictionary, a dictionary slot is added to the instance layout and the $tp_dictoffset$ is set to that slot's offset.

When a type defined by a class statement has a $__slots__$ declaration, the type inherits its $tp_dictoffset$ from its base type.

(Adding a slot named __dict__ to the __slots__ declaration does not have the expected effect, it just causes confusion. Maybe this should be added as a feature just like __weakref__ though.)

Default:

This slot has no default. For static types, if the field is NULL then no ___dict__ gets created for instances.

initproc PyTypeObject.tp_init

An optional pointer to an instance initialization function.

This function corresponds to the __init__() method of classes. Like __init__(), it is possible to create an instance without calling __init__(), and it is possible to reinitialize an instance by calling its init __() method again.

The function signature is:

```
int tp_init(PyObject *self, PyObject *args, PyObject *kwds);
```

The self argument is the instance to be initialized; the *args* and *kwds* arguments represent positional and keyword arguments of the call to __init__().

The tp_init function, if not NULL, is called when an instance is created normally by calling its type, after the type's tp_new function has returned an instance of the type. If the tp_new function returns an instance of some other type that is not a subtype of the original type, no tp_init function is called; if tp_new returns an instance of a subtype of the original type, the subtype's tp_init is called.

Returns 0 on success, -1 and sets an exception on error.

Inheritance:

This field is inherited by subtypes.

Default:

For static types this field does not have a default.

allocfunc PyTypeObject.tp_alloc

An optional pointer to an instance allocation function.

The function signature is:

```
PyObject *tp_alloc(PyTypeObject *self, Py_ssize_t nitems);
```

Inheritance:

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement).

Default:

For dynamic subtypes, this field is always set to PyType_GenericAlloc(), to force a standard heap allocation strategy.

For static subtypes, $PyBaseObject_Type$ uses $PyType_GenericAlloc()$. That is the recommended value for all statically defined types.

newfunc PyTypeObject.tp_new

An optional pointer to an instance creation function.

The function signature is:

```
PyObject *tp_new(PyTypeObject *subtype, PyObject *args, PyObject *kwds);
```

The subtype argument is the type of the object being created; the *args* and *kwds* arguments represent positional and keyword arguments of the call to the type. Note that subtype doesn't have to equal the type whose tp_new function is called; it may be a subtype of that type (but not an unrelated type).

The tp_new function should call subtype->tp_alloc(subtype, nitems) to allocate space for the object, and then do only as much further initialization as is absolutely necessary. Initialization that can safely be ignored or repeated should be placed in the tp_init handler. A good rule of thumb is that for immutable types, all initialization should take place in tp_new , while for mutable types, most initialization should be deferred to tp_init .

Inheritance:

This field is inherited by subtypes, except it is not inherited by static types whose tp_base is NULL or &PyBaseObject_Type.

Default:

For static types this field has no default. This means if the slot is defined as NULL, the type cannot be called to create new instances; presumably there is some other way to create instances, like a factory function.

freefunc PyTypeObject.tp_free

An optional pointer to an instance deallocation function. Its signature is:

```
void tp_free(void *self);
```

An initializer that is compatible with this signature is PyObject_Free().

Inheritance:

This field is inherited by static subtypes, but not by dynamic subtypes (subtypes created by a class statement)

Default:

In dynamic subtypes, this field is set to a deallocator suitable to match $PyType_GenericAlloc()$ and the value of the $Py_TPFLAGS_HAVE_GC$ flag bit.

For static subtypes, PyBaseObject_Type uses PyObject_Del.

inquiry PyTypeObject.tp_is_gc

An optional pointer to a function called by the garbage collector.

The garbage collector needs to know whether a particular object is collectible or not. Normally, it is sufficient to look at the object's type's tp_flags field, and check the $Py_TPFLAGS_HAVE_GC$ flag bit. But some types have a mixture of statically and dynamically allocated instances, and the statically allocated instances are not collectible. Such types should define this function; it should return 1 for a collectible instance, and 0 for a non-collectible instance. The signature is:

```
int tp_is_gc(PyObject *self);
```

(The only example of this are types themselves. The metatype, $PyType_Type$, defines this function to distinguish between statically and dynamically allocated types.)

Inheritance:

This field is inherited by subtypes.

Default:

This slot has no default. If this field is NULL, Py_TPFLAGS_HAVE_GC is used as the functional equivalent.

PyObject* PyTypeObject.tp_bases

Tuple of base types.

This is set for types created by a class statement. It should be NULL for statically defined types.

Inheritance:

This field is not inherited.

PyObject* PyTypeObject.tp_mro

Tuple containing the expanded set of base types, starting with the type itself and ending with object, in Method Resolution Order.

Inheritance:

This field is not inherited; it is calculated fresh by PyType_Ready().

PyObject* PyTypeObject.tp_cache

Unused. Internal use only.

Inheritance:

This field is not inherited.

PyObject* PyTypeObject.tp_subclasses

List of weak references to subclasses. Internal use only.

Inheritance:

This field is not inherited.

PyObject* PyTypeObject.tp_weaklist

Weak reference list head, for weak references to this type object. Not inherited. Internal use only.

Inheritance:

This field is not inherited.

destructor PyTypeObject.tp_del

This field is deprecated. Use $tp_finalize$ instead.

unsigned int PyTypeObject.tp_version_tag

Used to index into the method cache. Internal use only.

Inheritance:

This field is not inherited.

destructor PyTypeObject.tp_finalize

An optional pointer to an instance finalization function. Its signature is:

```
void tp_finalize(PyObject *self);
```

If $tp_finalize$ is set, the interpreter calls it once when finalizing an instance. It is called either from the garbage collector (if the instance is part of an isolated reference cycle) or just before the object is deallocated. Either way, it is guaranteed to be called before attempting to break reference cycles, ensuring that it finds the object in a sane state.

tp_finalize should not mutate the current exception status; therefore, a recommended way to write a non-trivial finalizer is:

```
static void
local_finalize(PyObject *self)
{
    PyObject *error_type, *error_value, *error_traceback;

    /* Save the current exception, if any. */
    PyErr_Fetch(&error_type, &error_value, &error_traceback);

    /* ... */

    /* Restore the saved exception. */
    PyErr_Restore(error_type, error_value, error_traceback);
}
```

For this field to be taken into account (even through inheritance), you must also set the Py_TPFLAGS_HAVE_FINALIZE flags bit.

Inheritance:

This field is inherited by subtypes.

3.4 新版功能.

参见:

"Safe object finalization" (PEP 442)

The remaining fields are only defined if the feature test macro COUNT_ALLOCS is defined, and are for internal use only. They are documented here for completeness. None of these fields are inherited by subtypes.

```
Py_ssize_t PyTypeObject.tp_allocs
```

Number of allocations.

$Py_ssize_t \; \textbf{PyTypeObject.tp_frees}$

Number of frees.

$Py_ssize_t \ \textbf{PyTypeObject.tp_maxalloc}$

Maximum simultaneously allocated objects.

PyTypeObject* PyTypeObject.tp_prev

Pointer to the previous type object with a non-zero tp_allocs field.

```
PyTypeObject* PyTypeObject.tp_next
```

Pointer to the next type object with a non-zero tp_allocs field.

Also, note that, in a garbage collected Python, $tp_dealloc$ may be called from any Python thread, not just the thread which created the object (if the object becomes part of a refcount cycle, that cycle might be collected by a garbage collection on any thread). This is not a problem for Python API calls, since the thread on which $tp_dealloc$ is called will own the Global Interpreter Lock (GIL). However, if the object being destroyed in turn destroys objects from some other C or C++ library, care should be taken to ensure that destroying those objects on the thread which called $tp_dealloc$ will not violate any assumptions of the library.

12.3.6 Heap Types

Traditionally, types defined in C code are *static*, that is, a static PyTypeObject structure is defined directly in code and initialized using $PyType_Ready()$.

This results in types that are limited relative to types defined in Python:

- Static types are limited to one base, i.e. they cannot use multiple inheritance.
- Static type objects (but not necessarily their instances) are immutable. It is not possible to add or modify the type object's attributes from Python.
- Static type objects are shared across sub-interpreters, so they should not include any subinterpreter-specific state.

Also, since PyTypeObject is not part of the *stable ABI*, any extension modules using static types must be compiled for a specific Python minor version.

An alternative to static types is *heap-allocated types*, or *heap types* for short, which correspond closely to classes created by Python's class statement.

This is done by filling a PyType_Spec structure and calling PyType_FromSpecWithBases().

12.4 Number Object Structures

PyNumberMethods

This structure holds pointers to the functions which an object uses to implement the number protocol. Each function is used by the function of similar name documented in the 数字协议 section.

Here is the structure definition:

```
typedef struct {
    binaryfunc nb_add;
    binaryfunc nb_subtract;
    binaryfunc nb_multiply;
    binaryfunc nb_remainder;
    binaryfunc nb_divmod;
    ternaryfunc nb_power;
    unaryfunc nb_negative;
    unaryfunc nb_positive;
    unaryfunc nb_absolute;
    inquiry nb_bool;
    unaryfunc nb_invert;
    binaryfunc nb_lshift;
    binaryfunc nb_rshift;
    binaryfunc nb_and;
    binaryfunc nb_xor;
    binaryfunc nb_or;
```

(下页继续)

(续上页)

```
unaryfunc nb_int;
    void *nb_reserved;
    unaryfunc nb_float;
    binaryfunc nb_inplace_add;
    binaryfunc nb_inplace_subtract;
    binaryfunc nb_inplace_multiply;
    binaryfunc nb_inplace_remainder;
    ternaryfunc nb_inplace_power;
    binaryfunc nb_inplace_lshift;
    binaryfunc nb_inplace_rshift;
    binaryfunc nb_inplace_and;
    binaryfunc nb_inplace_xor;
    binaryfunc nb_inplace_or;
    binaryfunc nb_floor_divide;
    binaryfunc nb_true_divide;
    binaryfunc nb_inplace_floor_divide;
    binaryfunc nb_inplace_true_divide;
    unaryfunc nb_index;
    binaryfunc nb_matrix_multiply;
    binaryfunc nb_inplace_matrix_multiply;
} PyNumberMethods;
```

注解: Binary and ternary functions must check the type of all their operands, and implement the necessary conversions (at least one of the operands is an instance of the defined type). If the operation is not defined for the given operands, binary and ternary functions must return Py_NotImplemented, if another error occurred they must return NULL and set an exception.

注解: The nb_reserved field should always be NULL. It was previously called nb_long, and was renamed in Python 3.0.1.

```
binaryfunc PyNumberMethods.nb_add
binaryfunc PyNumberMethods.nb_subtract
binaryfunc PyNumberMethods.nb_multiply
binaryfunc PyNumberMethods.nb_remainder
binaryfunc PyNumberMethods.nb_divmod
ternaryfunc PyNumberMethods.nb_power
unaryfunc PyNumberMethods.nb_negative
unaryfunc PyNumberMethods.nb_positive
unaryfunc PyNumberMethods.nb_absolute
inquiry PyNumberMethods.nb_bool
unaryfunc PyNumberMethods.nb_linvert
binaryfunc PyNumberMethods.nb_lshift
binaryfunc PyNumberMethods.nb_rshift
binaryfunc PyNumberMethods.nb_and
binaryfunc PyNumberMethods.nb_and
```

```
binaryfunc PyNumberMethods.nb_or
unaryfunc PyNumberMethods.nb_int
void *PyNumberMethods.nb_reserved
unaryfunc PyNumberMethods.nb_float
binaryfunc PyNumberMethods.nb_inplace_add
binaryfunc PyNumberMethods.nb_inplace_subtract
binaryfunc PyNumberMethods.nb_inplace_multiply
binaryfunc PyNumberMethods.nb inplace remainder
ternaryfunc PyNumberMethods.nb_inplace_power
binaryfunc PyNumberMethods.nb_inplace_lshift
binaryfunc PyNumberMethods.nb_inplace_rshift
binaryfunc PyNumberMethods.nb_inplace_and
binaryfunc PyNumberMethods.nb_inplace_xor
binaryfunc PyNumberMethods.nb_inplace_or
binaryfunc PyNumberMethods.nb_floor_divide
binaryfunc PyNumberMethods.nb_true_divide
binaryfunc PyNumberMethods.nb_inplace_floor_divide
binaryfunc PyNumberMethods.nb_inplace_true_divide
unaryfunc PyNumberMethods.nb_index
binaryfunc PyNumberMethods.nb_matrix_multiply
binaryfunc PyNumberMethods.nb_inplace_matrix_multiply
```

12.5 Mapping Object Structures

PyMappingMethods

This structure holds pointers to the functions which an object uses to implement the mapping protocol. It has three members:

lenfunc PyMappingMethods.mp length

This function is used by <code>PyMapping_Size()</code> and <code>PyObject_Size()</code>, and has the same signature. This slot may be set to <code>NULL</code> if the object has no defined length.

binaryfunc PyMappingMethods.mp subscript

This function is used by $PyObject_GetItem()$ and $PySequence_GetSlice()$, and has the same signature as $PyObject_GetItem()$. This slot must be filled for the $PyMapping_Check()$ function to return 1, it can be NULL otherwise.

objobjargproc PyMappingMethods.mp_ass_subscript

This function is used by $PyObject_SetItem()$, $PyObject_DelItem()$, $PyObject_DelItem()$, $PyObject_SetSlice()$ and $PyObject_DelSlice()$. It has the same signature as $PyObject_SetItem()$, but v can also be set to NULL to delete an item. If this slot is NULL, the object does not support item assignment and deletion.

12.6 Sequence Object Structures

PySequenceMethods

This structure holds pointers to the functions which an object uses to implement the sequence protocol.

lenfunc PySequenceMethods.sq_length

This function is used by $PySequence_Size()$ and $PyObject_Size()$, and has the same signature. It is also used for handling negative indices via the sq_item and the sq_ass_item slots.

binaryfunc PySequenceMethods.sq concat

This function is used by PySequence_Concat () and has the same signature. It is also used by the + operator, after trying the numeric addition via the nb add slot.

ssizeargfunc PySequenceMethods.sq_repeat

This function is used by $PySequence_Repeat()$ and has the same signature. It is also used by the * operator, after trying numeric multiplication via the $nb_multiply$ slot.

ssizeargfunc PySequenceMethods.sq_item

This function is used by <code>PySequence_GetItem()</code> and has the same signature. It is also used by <code>PyObject_GetItem()</code>, after trying the subscription via the <code>mp_subscript</code> slot. This slot must be filled for the <code>PySequence_Check()</code> function to return 1, it can be <code>NULL</code> otherwise.

Negative indexes are handled as follows: if the sq_length slot is filled, it is called and the sequence length is used to compute a positive index which is passed to sq_item. If sq_length is NULL, the index is passed as is to the function.

ssizeobjargproc PySequenceMethods.sq_ass_item

This function is used by $PySequence_SetItem()$ and has the same signature. It is also used by $PyObject_SetItem()$ and $PyObject_DelItem()$, after trying the item assignment and deletion via the $mp_ass_subscript$ slot. This slot may be left to NULL if the object does not support item assignment and deletion.

objobjproc PySequenceMethods.sq_contains

This function may be used by <code>PySequence_Contains()</code> and has the same signature. This slot may be left to <code>NULL</code>, in this case <code>PySequence_Contains()</code> simply traverses the sequence until it finds a match.

binaryfunc PySequenceMethods.sq inplace concat

This function is used by <code>PySequence_InPlaceConcat()</code> and has the same signature. It should modify its first operand, and return it. This slot may be left to <code>NULL</code>, in this case <code>PySequence_InPlaceConcat()</code> will fall back to <code>PySequence_Concat()</code>. It is also used by the augmented assignment <code>+=</code>, after trying numeric in-place addition via the <code>nb_inplace_add</code> slot.

ssizeargfunc PySequenceMethods.sq_inplace_repeat

This function is used by <code>PySequence_InPlaceRepeat()</code> and has the same signature. It should modify its first operand, and return it. This slot may be left to <code>NULL</code>, in this case <code>PySequence_InPlaceRepeat()</code> will fall back to <code>PySequence_Repeat()</code>. It is also used by the augmented assignment <code>*=</code>, after trying numeric in-place multiplication via the <code>nb_inplace_multiply</code> slot.

12.7 Buffer Object Structures

PyBufferProcs

This structure holds pointers to the functions required by the *Buffer protocol*. The protocol defines how an exporter object can expose its internal data to consumer objects.

getbufferproc PyBufferProcs.bf_getbuffer

The signature of this function is:

```
int (PyObject *exporter, Py_buffer *view, int flags);
```

Handle a request to *exporter* to fill in *view* as specified by *flags*. Except for point (3), an implementation of this function MUST take these steps:

- (1) Check if the request can be met. If not, raise PyExc_BufferError, set view->obj to NULL and return -1.
- (2) Fill in the requested fields.
- (3) Increment an internal counter for the number of exports.
- (4) Set view->obj to exporter and increment view->obj.
- (5) Return 0.

If exporter is part of a chain or tree of buffer providers, two main schemes can be used:

- Re-export: Each member of the tree acts as the exporting object and sets view->obj to a new reference to itself.
- Redirect: The buffer request is redirected to the root object of the tree. Here, view->obj will be a new reference to the root object.

The individual fields of *view* are described in section *Buffer structure*, the rules how an exporter must react to specific requests are in section *Buffer request types*.

All memory pointed to in the Py_buffer structure belongs to the exporter and must remain valid until there are no consumers left. format, shape, strides, suboffsets and internal are read-only for the consumer.

PyBuffer_FillInfo() provides an easy way of exposing a simple bytes buffer while dealing correctly with all request types.

PyObject_GetBuffer () is the interface for the consumer that wraps this function.

releasebufferproc PyBufferProcs.bf_releasebuffer

The signature of this function is:

```
void (PyObject *exporter, Py_buffer *view);
```

Handle a request to release the resources of the buffer. If no resources need to be released, <code>PyBufferProcs.bf_releasebuffer</code> may be <code>NULL</code>. Otherwise, a standard implementation of this function will take these optional steps:

- (1) Decrement an internal counter for the number of exports.
- (2) If the counter is 0, free all memory associated with view.

The exporter MUST use the <code>internal</code> field to keep track of buffer-specific resources. This field is guaranteed to remain constant, while a consumer MAY pass a copy of the original buffer as the <code>view</code> argument.

This function MUST NOT decrement view->obj, since that is done automatically in <code>PyBuffer_Release()</code> (this scheme is useful for breaking reference cycles).

PyBuffer_Release() is the interface for the consumer that wraps this function.

12.8 Async Object Structures

3.5 新版功能.

PyAsyncMethods

This structure holds pointers to the functions required to implement awaitable and asynchronous iterator objects.

Here is the structure definition:

```
typedef struct {
   unaryfunc am_await;
   unaryfunc am_aiter;
   unaryfunc am_anext;
} PyAsyncMethods;
```

unaryfunc PyAsyncMethods.am_await

The signature of this function is:

```
PyObject *am_await(PyObject *self);
```

The returned object must be an iterator, i.e. PyIter_Check () must return 1 for it.

This slot may be set to NULL if an object is not an awaitable.

unaryfunc PyAsyncMethods.am_aiter

The signature of this function is:

```
PyObject *am_aiter(PyObject *self);
```

Must return an awaitable object. See __anext__() for details.

This slot may be set to NULL if an object does not implement asynchronous iteration protocol.

unaryfunc PyAsyncMethods.am_anext

The signature of this function is:

```
PyObject *am_anext(PyObject *self);
```

Must return an awaitable object. See __anext__ () for details. This slot may be set to NULL.

12.9 Slot Type typedefs

```
PyObject * (*allocfunc) (PyTypeObject *cls, Py_ssize_t nitems)
```

The purpose of this function is to separate memory allocation from memory initialization. It should return a pointer to a block of memory of adequate length for the instance, suitably aligned, and initialized to zeros, but with ob_refent set to 1 and ob_type set to the type argument. If the type's $tp_itemsize$ is nonzero, the object's ob_size field should be initialized to *nitems* and the length of the allocated memory block should be $tp_basicsize + nitems*tp_itemsize$, rounded up to a multiple of temsize otherwise, *nitems* is not used and the length of the block should be temsize.

This function should not do any other instance initialization, not even to allocate additional memory; that should be done by tp_new .

```
void (*destructor) (PyObject *)

PyObject * (*vectorcallfunc) (PyObject *callable, PyObject *const *args, size_t nargsf, PyObject *kw-names)

See tp_vectorcall_offset.

Arguments to vectorcallfunc are the same as for _PyObject_Vectorcall().

3.8 新版功能.

void (*freefunc) (void *)

See tp_free.

PyObject * (*newfunc) (PyObject *, PyObject *, PyObject *)

See tp_new.

int (*initproc) (PyObject *, PyObject *, PyObject *)

See tp_init.
```

```
PyObject * (*reprfunc) (PyObject *)
     See tp_repr.
PyObject * (*getattrfunc) (PyObject *self, char *attr)
     Return the value of the named attribute for the object.
int (*setattrfunc) (PyObject *self, char *attr, PyObject *value)
     Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.
PyObject * (*getattrofunc) (PyObject *self, PyObject *attr)
     Return the value of the named attribute for the object.
     See tp_getattro.
int (*setattrofunc) (PyObject *self, PyObject *attr, PyObject *value)
     Set the value of the named attribute for the object. The value argument is set to NULL to delete the attribute.
PyObject * (*descrgetfunc) (PyObject *, PyObject *, PyObject *)
     See tp_descrget.
int (*descrsetfunc) (PyObject *, PyObject *, PyObject *)
     See tp_descrset.
Py_hash_t (*hashfunc) (PyObject *)
     See tp_hash.
PyObject * (*richcmpfunc) (PyObject *, PyObject *, int)
     See tp_richcompare.
PyObject * (*getiterfunc) (PyObject *)
     See tp_iter.
PyObject * (*iternextfunc) (PyObject *)
     See tp_iternext.
Py_ssize_t (*lenfunc) (PyObject *)
int (*getbufferproc) (PyObject *, Py_buffer *, int)
void (*releasebufferproc) (PyObject *, Py_buffer *)
PyObject * (*unaryfunc) (PyObject *)
PyObject * (*binaryfunc) (PyObject *, PyObject *)
PyObject * (*ternaryfunc) (PyObject *, PyObject *, PyObject *)
PyObject * (*ssizeargfunc) (PyObject *, Py_ssize_t)
int (*ssizeobjargproc) (PyObject *, Py_ssize_t)
int (*objobjproc) (PyObject *, PyObject *)
int (*objobjargproc) (PyObject *, PyObject *, PyObject *)
```

12.10 例子

The following are simple examples of Python type definitions. They include common usage you may encounter. Some demonstrate tricky corner cases. For more examples, practical info, and a tutorial, see defining-new-types and new-types-topics.

A basic static type:

12.10. 例子 207

```
typedef struct {
    PyObject_HEAD
    const char *data;
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = "My objects",
    .tp_new = myobj_new,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
};
```

You may also find older code (especially in the CPython code base) with a more verbose initializer:

```
static PyTypeObject MyObject_Type = {
   PyVarObject_HEAD_INIT(NULL, 0)
                                    /* tp_name */
    "mymod.MyObject",
    sizeof(MyObject),
                                    /* tp_basicsize */
                                    /* tp_itemsize */
                                    /* tp_dealloc */
    (destructor) myobj_dealloc,
    0,
                                     /* tp_vectorcall_offset */
                                     /* tp_getattr */
    0,
                                     /* tp_setattr */
    0,
                                     /* tp_as_async */
    0,
                                     /* tp_repr */
    (reprfunc) myobj_repr,
                                     /* tp_as_number */
   0,
                                     /* tp_as_sequence */
                                     /* tp_as_mapping */
    0,
                                     /* tp_hash */
    0,
                                     /* tp_call */
    0,
                                     /* tp_str */
    0,
    0,
                                     /* tp_getattro */
    0,
                                     /* tp_setattro */
    0,
                                     /* tp_as_buffer */
                                     /* tp_flags */
    0,
                                     /* tp_doc */
    "My objects",
                                     /* tp_traverse */
   0,
   0,
                                     /* tp_clear */
    0,
                                     /* tp_richcompare */
                                     /* tp_weaklistoffset */
    0,
                                     /* tp_iter */
    0,
                                     /* tp_iternext */
    0,
                                     /* tp_methods */
    0,
                                     /* tp_members */
    0,
                                     /* tp_getset */
    0,
                                     /* tp_base */
    0,
                                     /* tp_dict */
    0,
   0,
                                     /* tp_descr_get */
   Ο,
                                     /* tp_descr_set */
   Ο,
                                     /* tp_dictoffset */
                                     /* tp_init */
    0,
                                     /* tp_alloc */
    Ο,
   myobj_new,
                                     /* tp_new */
};
```

A type that supports weakrefs, instance dicts, and hashing:

```
typedef struct {
    PyObject_HEAD
    (天面体体)
```

(下页继续)

(续上页)

```
const char *data;
    PyObject *inst_dict;
    PyObject *weakreflist;
} MyObject;
static PyTypeObject MyObject_Type = {
   PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
    .tp_basicsize = sizeof(MyObject),
    .tp_doc = "My objects",
    .tp_weaklistoffset = offsetof(MyObject, weakreflist),
    .tp_dictoffset = offsetof(MyObject, inst_dict),
    .tp_flags = Py_TPFLAGS_DEFAULT | Py_TPFLAGS_BASETYPE | Py_TPFLAGS_HAVE_GC,
    .tp_new = myobj_new,
    .tp_traverse = (traverseproc)myobj_traverse,
    .tp_clear = (inquiry)myobj_clear,
    .tp_alloc = PyType_GenericNew,
    .tp_dealloc = (destructor)myobj_dealloc,
    .tp_repr = (reprfunc)myobj_repr,
    .tp_hash = (hashfunc)myobj_hash,
    .tp_richcompare = PyBaseObject_Type.tp_richcompare,
};
```

A str subclass that cannot be subclassed and cannot be called to create instances (e.g. uses a separate factory func):

```
typedef struct {
    PyUnicodeObject raw;
    char *extra;
} MyStr;

static PyTypeObject MyStr_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyStr",
    .tp_basicsize = sizeof(MyStr),
    .tp_base = NULL, // set to &PyUnicode_Type in module init
    .tp_doc = "my custom str",
    .tp_flags = Py_TPFLAGS_DEFAULT,
    .tp_new = NULL,
    .tp_repr = (reprfunc) myobj_repr,
};
```

The simplest static type (with fixed-length instances):

```
typedef struct {
    PyObject_HEAD
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
    .tp_name = "mymod.MyObject",
};
```

The simplest static type (with variable-length instances):

12.10. 例子

```
typedef struct {
    PyObject_VAR_HEAD
    const char *data[1];
} MyObject;

static PyTypeObject MyObject_Type = {
    PyVarObject_HEAD_INIT(NULL, 0)
```

(下页继续)

209

(续上页)

```
.tp_name = "mymod.MyObject",
   .tp_basicsize = sizeof(MyObject) - sizeof(char *),
   .tp_itemsize = sizeof(char *),
};
```

12.11 使对象类型支持循环垃圾回收

Python 对循环引用的垃圾检测与回收需要"容器"对象类型的支持,此类型的容器对象中可能包含其它容器对象。不保存其它对象的引用的类型,或者只保存原子类型(如数字或字符串)的引用的类型,不需要显式提供垃圾回收的支持。

若要创建一个容器类,类型对象的tp_flags 字段必须包含Py_TPFLAGS_HAVE_GC 并提供一个tp_traverse处理的实现。如果该类型的实例是可变的,还需要实现tp_clear。

Py_TPFLAGS_HAVE_GC

设置了此标志位的类型的对象必须符合此处记录的规则。为方便起见,下文把这些对象称为容器对象。

容器类型的构造函数必须符合两个规则:

- 1. 必须使用PyObject_GC_New() 或PyObject_GC_NewVar() 为这些对象分配内存。
- 2. 初始化了所有可能包含其他容器的引用的字段后,它必须调用PyObject_GC_Track()。

TYPE* PyObject_GC_New (TYPE, PyTypeObject *type)

类似于PyObject_New(),适用于设置了Py_TPFLAGS_HAVE_GC 标签的容器对象。

TYPE* PyObject_GC_NewVar (TYPE, PyTypeObject *type, Py_ssize_t size)

类似于PyObject_NewVar(),适用于设置了Py_TPFLAGS_HAVE_GC 标签的容器对象。

TYPE* PyObject_GC_Resize (TYPE, PyVarObject *op, Py_ssize_t newsize)

为PyObject_NewVar() 所分配对象重新调整大小。返回调整大小后的对象或在失败时返回NULL。op 必须尚未被垃圾回收器追踪。

void PyObject_GC_Track (PyObject *op)

把对象 op 加入到垃圾回收器跟踪的容器对象中。对象在被回收器跟踪时必须保持有效的,因为回收器可能在任何时候开始运行。在 $tp_traverse$ 处理前的所有字段变为有效后,必须调用此函数,通常在靠近构造函数末尾的位置。

同样的,对象的释放器必须符合两个类似的规则:

- 1. 在引用其它容器的字段失效前,必须调用PyObject_GC_UnTrack()。
- 2. 必须使用PyObject_GC_Del()释放对象的内存。

void PyObject_GC_Del (void *op)

释放对象的内存,该对象初始化时由PyObject_GC_New()或PyObject_GC_NewVar()分配内存。

void PyObject_GC_UnTrack (void *op)

从回收器跟踪的容器对象集合中移除 op 对象。请注意可以在此对象上再次调用 $PyObject_GC_Track()$ 以将其加回到被跟踪对象集合。释放器 ($tp_dealloc$ 句柄) 应当在 $tp_traverse$ 句柄所使用的任何字段失效之前为对象调用此函数。

在 3.8 版更改: _PyObject_GC_TRACK() 和 _PyObject_GC_UNTRACK() 宏已从公有 C API 中移除。 tp_traverse 处理接收以下类型的函数形参。

int (*visitproc) (PyObject *object, void *arg)

传给 $tp_traverse$ 处理的访问函数的类型。object 是容器中需要被遍历的一个对象,第三个形参对应于 $tp_traverse$ 处理的 arg 。Python 核心使用多个访问者函数实现循环引用的垃圾检测,不需要用户自行实现访问者函数。

tp traverse 处理必须是以下类型:

int (*traverseproc) (PyObject *self, visitproc visit, void *arg)

用于容器对象的遍历函数。它的实现必须对 self 所直接包含的每个对象调用 visit 函数, visit 的形参为所包含对象和传给处理程序的 arg 值。visit 函数调用不可附带 NULL 对象作为参数。如果 visit 返回非零值,则该值应当被立即返回。

为了简化tp_traverse 处理的实现, Python 提供了一个Py_VISIT() 宏。若要使用这个宏, 必须把tp_traverse 的参数命名为 visit 和 arg。

void Py_VISIT (PyObject *o)

如果 o 不为 NULL,则调用 visit 回调函数,附带参数 o 和 arg。如果 visit 返回一个非零值,则返回该值。使用此宏之后, $tp_traverse$ 处理程序的形式如下:

```
static int
my_traverse(Noddy *self, visitproc visit, void *arg)
{
    Py_VISIT(self->foo);
    Py_VISIT(self->bar);
    return 0;
}
```

tp_clear 处理程序必须为inquiry 类型,如果对象不可变则为 NULL。

int (*inquiry) (PyObject *self)

丢弃产生循环引用的引用。不可变对象不需要声明此方法,因为他们不可能直接产生循环引用。需要注意的是,对象在调用此方法后必须仍是有效的(不能对引用只调用 P_{Y_DECREF} ()方法)。当垃圾回收器检测到该对象在循环引用中时,此方法会被调用。

CHAPTER 13

API 和 ABI 版本管理

PY_VERSION_HEX 是 Python 的版本号的整数形式。

例如,如果 PY_VERSION_HEX 被置为 0x030401a2, 其包含的版本信息可以通过以下方式将其作为一个 32 位数字来处理:

| 字节 | 位数(大 端 字 节 序) | 意义 | | | |
|----|---------------------|----------------------------------------------------------|--|--|--|
| 1 | 1-8 | PY_MAJOR_VERSION (3.4.1a2 中的 3) | | | |
| 2 | 9-16 | PY_MINOR_VERSION (3.4.1a2 中的 4) | | | |
| 3 | 17-24 | PY_MICRO_VERSION (3.4.1a2 中的1) | | | |
| 4 | 25-28 | PY_RELEASE_LEVEL (0xA 是 alpha 版本, 0xB 是 beta 版本, 0xC 发布的 | | | |
| | | 候选版本并且 0xF 是最终版本),在这个例子中这个版本是 alpha 版本。 | | | |
| | 29-32 | PY_RELEASE_SERIAL (3.4.1a2 中的 2 ,最终版本用 0) | | | |

因此 3.4.1a2 的 16 进制版本号是 0x030401a2。

所有提到的宏都定义在 Include/patchlevel.h。

APPENDIX A

术语对照表

>>> 交互式终端中默认的 Python 提示符。往往会显示于能以交互方式在解释器里执行的样例代码之前。

... 可以是指:

- 交互式终端中输入特殊代码行时默认的 Python 提示符,包括:缩进的代码块,成对的分隔符之内(圆括号、方括号、花括号或三重引号),或是指定一个装饰器之后。
- Ellipsis 内置常量。
- **2to3** 一个将 Python 2.x 代码转换为 Python 3.x 代码的工具,能够处理大部分通过解析源码并遍历解析树可检测到的不兼容问题。

2to3 包含在标准库中,模块名为 lib2to3;并提供一个独立人口点 Tools/scripts/2to3。参见 2to3-reference。

abstract base class -- 抽象基类 抽象基类简称 ABC,是对duck-typing 的补充,它提供了一种定义接口的新方式,相比之下其他技巧例如 hasattr()显得过于笨拙或有微妙错误(例如使用魔术方法)。ABC 引入了虚拟子类,这种类并非继承自其他类,但却仍能被 isinstance()和 issubclass()所认可;详见 abc模块文档。Python自带许多内置的 ABC 用于实现数据结构(在 collections.abc模块中)、数字(在 numbers 模块中)、流(在 io 模块中)、导入查找器和加载器(在 importlib.abc模块中)。你可以使用 abc模块来创建自己的 ABC。

annotation -- 注解 关联到某个变量、类属性、函数形参或返回值的标签,被约定作为type hint 来使用。

局部变量的标注在运行时不可访问,但全局变量、类属性和函数的标注会分别存放模块、类和函数的 __annotations__ 特殊属性中。

参见variable annotation、function annotation、PEP 484 和 PEP 526,对此功能均有介绍。

argument -- 参数 在调用函数时传给function(或method)的值。参数分为两种:

• 关键字参数: 在函数调用中前面带有标识符 (例如 name=) 或者作为包含在前面带有 ** 的字典里的值传入。举例来说, 3 和 5 在以下对 complex () 的调用中均属于关键字参数:

```
complex(real=3, imag=5)
complex(**{'real': 3, 'imag': 5})
```

• 位置参数: 不属于关键字参数的参数。位置参数可出现于参数列表的开头以及/或者作为前面带有*的iterable 里的元素被传入。举例来说,3和5在以下调用中均属于位置参数:

```
complex(3, 5)
complex(*(3, 5))
```

参数会被赋值给函数体中对应的局部变量。有关赋值规则参见 calls 一节。根据语法,任何表达式都可用来表示一个参数;最终算出的值会被赋给对应的局部变量。

另参见parameter 术语表条目,常见问题中参数与形参的区别以及 PEP 362。

- **asynchronous context manager -- 异步上下文管理器** 此 种 对 象 通 过 定 义 ___aenter__() 和 ___aexit__() 方法来对 async with 语句中的环境进行控制。由 **PEP 492** 引入。
- **asynchronous generator -- 异步生成器** 返回值为*asynchronous generator iterator* 的函数。它与使用 async def 定义的协程函数很相似,不同之处在于它包含 yield 表达式以产生一系列可在 async for 循环中使用的值。

此术语通常是指异步生成器函数,但在某些情况下则可能是指 异步生成器迭代器。如果需要清楚表达具体含义,请使用全称以避免歧义。

- 一个异步生成器函数可能包含 await 表达式或者 async for 以及 async with 语句。
- asynchronous generator iterator -- 异步生成器迭代器 asynchronous generator 函数所创建的对象。

此对象属于asynchronous iterator,当使用 __anext__() 方法调用时会返回一个可等待对象来执行异步生成器函数的代码直到下一个 yield 表达式。

每个 yield 会临时暂停处理,记住当前位置执行状态 (包括局部变量和挂起的 try 语句)。当该 异步生成器迭代器与其他 __anext__() 返回的可等待对象有效恢复时,它会从离开位置继续执行。参见 PEP 492 和 PEP 525。

- **asynchronous iterable -- 异步可迭代对象** 可在 async for 语句中被使用的对象。必须通过它的 ___aiter___() 方法返回一个 asynchronous iterator。由 PEP 492 引入。
- **asynchronous iterator -- 异步迭代器** 实现了 __aiter__() 和 __anext__() 方法的对象。__anext__ 必须返回一个 *awaitable* 对象。async for 会处理异步迭代器的 __anext__() 方法所返回的可等 待对象,直到其引发一个 StopAsyncIteration 异常。由 **PEP 492** 引入。
- **attribute -- 属性** 关联到一个对象的值,可以使用点号表达式通过其名称来引用。例如,如果一个对象 o 具有一个属性 a,就可以用 o.a 来引用它。
- **awaitable -- 可等待对象** 能在 await 表达式中使用的对象。可以是*coroutine* 或是具有 __await__() 方 法的对象。参见 PEP 492。
- BDFL"终身仁慈独裁者"的英文缩写,即Guido van Rossum, Python的创造者。
- **binary file -- 二进制文件** *file object* 能够读写字节类对象。二进制文件的例子包括以二进制模式 ('rb', 'wb' or 'rb+') 打开的文件、sys.stdin.buffer、sys.stdout.buffer 以及 io.BytesIO 和 gzip.GzipFile 的实例。

另请参见text file 了解能够读写 str 对象的文件对象。

bytes-like object -- 字节类对象 支持缓冲协议 并且能导出 C-contiguous 缓冲的对象。这包括所有 bytes、bytearray 和 array.array 对象,以及许多普通 memoryview 对象。字节类对象可在多种二进制数据操作中使用;这些操作包括压缩、保存为二进制文件以及通过套接字发送等。

某些操作需要可变的二进制数据。这种对象在文档中常被称为"可读写字节类对象"。可变缓冲对象的例子包括 bytearray 以及 bytearray 的 memoryview。其他操作要求二进制数据存放于不可变对象 ("只读字节类对象");这种对象的例子包括 bytes 以及 bytes 对象的 memoryview。

bytecode -- 字节码 Python 源代码会被编译为字节码,即 CPython 解释器中表示 Python 程序的内部代码。字节码还会缓存在 . pyc 文件中,这样第二次执行同一文件时速度更快(可以免去将源码重新编译为字节码)。这种"中间语言"运行在根据字节码执行相应机器码的*virtual machine* 之上。请注意不同Python 虚拟机上的字节码不一定通用,也不一定能在不同Python 版本上兼容。

字节码指令列表可以在 dis 模块的文档中查看。

- class -- 类 用来创建用户定义对象的模板。类定义通常包含对该类的实例进行操作的方法定义。
- class variable -- 类变量 在类中定义的变量,并且仅限在类的层级上修改(而不是在类的实例中修改)。
- **coercion -- 强制类型转换** 在包含两个相同类型参数的操作中,一种类型的实例隐式地转换为另一种类型。例如,int (3.15) 是将原浮点数转换为整型数 3,但在 3+4.5 中,参数的类型不一致(一个是 int, 一个是 float),两者必须转换为相同类型才能相加,否则将引发 TypeError。如果没有强制

类型转换机制,程序员必须将所有可兼容参数归一化为相同类型,例如要写成 float (3) +4.5 而不是 3+4.5。

- complex number -- 复数 对普通实数系统的扩展,其中所有数字都被表示为一个实部和一个虚部的和。虚数是虚数单位(-1 的平方根)的实倍数,通常在数学中写为 i,在工程学中写为 j。Python 内置了对复数的支持,采用工程学标记方式;虚部带有一个 j 后缀,例如 3+1 j。如果需要 math 模块内对象的对应复数版本,请使用 cmath,复数的使用是一个比较高级的数学特性。如果你感觉没有必要,忽略它们也几乎不会有任何问题。
- **context manager -- 上下文管理器** 在 with 语句中使用,通过定义 ___enter___() 和 ___exit___() 方法 来控制环境状态的对象。参见 **PEP 343**。
- context variable -- 上下文变量 一种根据其所属的上下文可以具有不同的值的变量。这类似于在线程局部存储中每个执行线程可以具有不同的变量值。不过,对于上下文变量来说,一个执行线程中可能会有多个上下文,而上下文变量的主要用途是对并发异步任务中变量进行追踪。参见 contextvars。
- **contiguous -- 连续** 一个缓冲如果是 *C* 连续或 *Fortran* 连续就会被认为是连续的。零维缓冲是 C 和 Fortran 连续的。在一维数组中,所有条目必须在内存中彼此相邻地排列,采用从零开始的递增索引顺序。在多维 C-连续数组中,当按内存地址排列时用最后一个索引访问条目时速度最快。但是在 Fortran 连续数组中则是用第一个索引最快。
- **coroutine -- 协程** 协程是子例程的更一般形式。子例程可以在某一点进入并在另一点退出。协程则可以 在许多不同的点上进入、退出和恢复。它们可通过 async def 语句来实现。参见 **PEP 492**。
- **coroutine function -- 协程函数** 返回一个*coroutine* 对象的函数。协程函数可通过 async def 语句来定义,并可能包含 await、async for 和 async with 关键字。这些特性是由 **PEP 492** 引入的。
- **CPython** Python 编程语言的规范实现,在 python.org 上发布。"CPython" 一词用于在必要时将此实现与其他实现例如 Jython 或 IronPython 相区别。
- **decorator -- 装饰器** 返回值为另一个函数的函数,通常使用 @wrapper 语法形式来进行函数变换。装饰器的常见例子包括 classmethod() 和 staticmethod()。

装饰器语法只是一种语法糖,以下两个函数定义在语义上完全等价:

```
def f(...):
    ...
f = staticmethod(f)

@staticmethod
def f(...):
    ...
```

同的样概念也适用于类,但通常较少这样使用。有关装饰器的详情可参见 函数定义和 类定义的文档。

descriptor -- 描述器 任何定义了 __get__(), __set__() 或 __delete__() 方法的对象。当一个类属性为描述器时,它的特殊绑定行为就会在属性查找时被触发。通常情况下,使用 a.b 来获取、设置或删除一个属性时会在 a 的类字典中查找名称为 b 的对象,但如果 b 是一个描述器,则会调用对应的描述器方法。理解描述器的概念是更深层次理解 Python 的关键,因为这是许多重要特性的基础,包括函数、方法、属性、类方法、静态方法以及对超类的引用等等。

有关描述符的方法的详情可参看 descriptors。

- **dictionary -- 字典** 一个关联数组,其中的任意键都映射到相应的值。键可以是任何具有 __hash__() 和 __eq__() 方法的对象。在 Perl 语言中称为 hash。
- **dictionary view -- 字典视图** 从 dict.keys(), dict.values() 和 dict.items() 返回的对象被称为字典视图。它们提供了字典条目的一个动态视图,这意味着当字典改变时,视图也会相应改变。要将字典视图强制转换为真正的列表,可使用 list (dictview)。参见 dict-views。
- **docstring -- 文档字符串** 作为类、函数或模块之内的第一个表达式出现的字符串字面值。它在代码执行时会被忽略,但会被解释器识别并放入所在类、函数或模块的 ___doc___ 属性中。由于它可用于代码内省,因此是对象存放文档的规范位置。

- duck-typing -- 鸭子类型 指一种编程风格,它并不依靠查找对象类型来确定其是否具有正确的接口,而是直接调用或使用其方法或属性("看起来像鸭子,叫起来也像鸭子,那么肯定就是鸭子。")由于强调接口而非特定类型,设计良好的代码可通过允许多态替代来提升灵活性。鸭子类型避免使用type()或isinstance()检测。(但要注意鸭子类型可以使用抽象基类作为补充。)而往往会采用hasattr()检测或是*EAFP*编程。
- EAFP "求原谅比求许可更容易"的英文缩写。这种 Python 常用代码编写风格会假定所需的键或属性存在,并在假定错误时捕获异常。这种简洁快速风格的特点就是大量运用 try 和 except 语句。于其相对的则是所谓*LBYL* 风格,常见于 C 等许多其他语言。
- **expression -- 表达式** 可以求出某个值的语法单元。换句话说,一个表达式就是表达元素例如字面值、名称、属性访问、运算符或函数调用的汇总,它们最终都会返回一个值。与许多其他语言不同,并非所有语言构件都是表达式。还存在不能被用作表达式的*statement*,例如 while。赋值也是属于语句而非表达式。
- **extension module -- 扩展模块** 以 C 或 C++ 编写的模块,使用 Python 的 C API 来与语言核心以及用户代码进行交互。
- **f-string -- f-字符串** 带有 'f' 或 'F' 前缀的字符串字面值通常被称为 "f-字符串"即 格式化字符串字面值的简写。参见 **PEP 498**。
- file object -- 文件对象 对外提供面向文件 API 以使用下层资源的对象 (带有 read() 或 write() 这样的方法)。根据其创建方式的不同,文件对象可以处理对真实磁盘文件,对其他类型存储,或是对通讯设备的访问(例如标准输入/输出、内存缓冲区、套接字、管道等等)。文件对象也被称为 文件类对象或 流。

实际上共有三种类别的文件对象:原始二进制文件,缓冲二进制文件以及文本文件。它们的接口定义均在 io 模块中。创建文件对象的规范方式是使用 open () 函数。

file-like object -- 文件类对象 file object 的同义词。

finder -- 查找器 一种会尝试查找被导入模块的loader 的对象。

从 Python 3.3 起存在两种类型的查找器: 元路径查找器 配合 sys.meta_path 使用,以及path entry finders 配合 sys.path_hooks 使用。

更多详情可参见 PEP 302, PEP 420 和 PEP 451。

- **floor division -- 向下取整除法** 向下舍入到最接近的整数的数学除法。向下取整除法的运算符是 // 。例如,表达式 11 // 4的计算结果是 2,而与之相反的是浮点数的真正除法返回 2.75。注意 (-11) // 4 会返回 -3 因为这是 -2.75 向下舍入得到的结果。见 **PEP 238** 。
- **function -- 函数** 可以向调用者返回某个值的一组语句。还可以向其传入零个或多个参数并在函数体执行中被使用。另见*parameter*, *method* 和 function 等节。
- function annotation -- 函数注解 即针对函数形参或返回值的annotation。

函数标注通常用于类型提示: 例如以下函数预期接受两个 int 参数并预期返回一个 int 值:

```
def sum_two_numbers(a: int, b: int) -> int:
    return a + b
```

函数标注语法的详解见 function 一节。

请参看variable annotation 和 PEP 484 对此功能的描述。

__future__ 一种伪模块,可被程序员用来启用与当前解释器不兼容的新语言特性。

通过导入 __future__ 模块并对其中的变量求值,你可以查看新特性何时首次加入语言以及何时成为默认:

```
>>> import __future__
>>> __future__.division
_Feature((2, 2, 0, 'alpha', 2), (3, 0, 0, 'alpha', 0), 8192)
```

garbage collection -- 垃圾回收 释放不再被使用的内存空间的过程。Python 是通过引用计数和一个能够检测和打破循环引用的循环垃圾回收器来执行垃圾回收的。可以使用 gc 模块来控制垃圾回收器。

generator -- 生成器 返回一个*generator iterator* 的函数。它看起来很像普通函数,不同点在于其包含 yield 表达式以便产生一系列值供给 for-循环使用或是通过 next () 函数逐一获取。

通常是指生成器函数,但在某些情况下也可能是指生成器迭代器。如果需要清楚表达具体含义,请使用全称以避免歧义。

generator iterator -- 生成器迭代器 generator 函数所创建的对象。

每个 yield 会临时暂停处理,记住当前位置执行状态(包括局部变量和挂起的 try 语句)。当该 生成器迭代器恢复时,它会从离开位置继续执行(这与每次调用都从新开始的普通函数差别很大)。

generator expression -- 生成器表达式 返回一个迭代器的表达式。它看起来很像普通表达式后面带有定义了一个循环变量、范围的 for 子句,以及一个可选的 if 子句。以下复合表达式会为外层函数生成一系列值:

```
>>> sum(i*i for i in range(10))  # sum of squares 0, 1, 4, ... 81
285
```

generic function -- 泛型函数 为不同的类型实现相同操作的多个函数所组成的函数。在调用时会由调度 算法来确定应该使用哪个实现。

另请参见single dispatch 术语表条目、functools.singledispatch() 装饰器以及 PEP 443。

- **GIL** 参见global interpreter lock。
- global interpreter lock -- 全局解释器锁 *CPython* 解释器所采用的一种机制,它确保同一时刻只有一个线程在执行 Python *bytecode*。此机制通过设置对象模型(包括 dict 等重要内置类型)针对并发访问的隐式安全简化了 CPython 实现。给整个解释器加锁使得解释器多线程运行更方便,其代价则是牺牲了在多处理器上的并行性。

不过,某些标准库或第三方库的扩展模块被设计为在执行计算密集型任务如压缩或哈希时释放GIL。此外,在执行 I/O 操作时也总是会释放 GIL。

创建一个(以更精细粒度来锁定共享数据的)"自由线程"解释器的努力从未获得成功,因为这会牺牲在普通单处理器情况下的性能。据信克服这种性能问题的措施将导致实现变得更复杂,从而更难以维护。

- hash-based pyc -- 基于哈希的 pyc 使用对应源文件的哈希值而非最后修改时间来确定其有效性的字节码 缓存文件。参见 pyc-invalidation。
- hashable -- 可哈希 一个对象的哈希值如果在其生命周期内绝不改变,就被称为 可哈希(它需要具有 ___hash___() 方法),并可以同其他对象进行比较(它需要具有 ___eq___() 方法)。可哈希对象必 须具有相同的哈希值比较结果才会相同。

可哈希性使得对象能够作为字典键或集合成员使用,因为这些数据结构要在内部使用哈希值。

大多数 Python 中的不可变内置对象都是可哈希的;可变容器(例如列表或字典)都不可哈希;不可变容器(例如元组和 frozenset)仅当它们的元素均为可哈希时才是可哈希的。用户定义类的实例对象默认是可哈希的。它们在比较时一定不相同(除非是与自己比较),它们的哈希值的生成是基于它们的id()。

- **IDLE** Python 的 IDE, "集成开发与学习环境"的英文缩写。是 Python 标准发行版附带的基本编程器和解释器环境。
- **immutable -- 不可变** 具有固定值的对象。不可变对象包括数字、字符串和元组。这样的对象不能被改变。如果必须存储一个不同的值,则必须创建新的对象。它们在需要常量哈希值的地方起着重要作用,例如作为字典中的键。
- **import path -- 导人路径** 由多个位置(或路径条目)组成的列表,会被模块的*path based finder* 用来查找导入目标。在导入时,此位置列表通常来自 sys.path,但对次级包来说也可能来自上级包的___path__ 属性。
- **importing -- 导人** 令一个模块中的 Python 代码能为另一个模块中的 Python 代码所使用的过程。
- **importer -- 导人器** 查找并加载模块的对象;此对象既属于finder 又属于loader。

- **interactive -- 交互** Python 带有一个交互式解释器,即你可以在解释器提示符后输入语句和表达式,立即 执行并查看其结果。只需不带参数地启动 python 命令(也可以在你的计算机开始菜单中选择相 应菜单项)。在测试新想法或检验模块和包的时候用这种方式会非常方便(请记得使用 help(x))。
- **interpreted -- 解释型** Python 一是种解释型语言,与之相对的是编译型语言,虽然两者的区别由于字节码编译器的存在而会有所模糊。这意味着源文件可以直接运行而不必显式地创建可执行文件再运行。解释型语言通常具有比编译型语言更短的开发/调试周期,但是其程序往往运行得更慢。参见*interactive*。
- interpreter shutdown -- 解释器关闭 当被要求关闭时, Python 解释器将进入一个特殊运行阶段并逐步释放所有已分配资源, 例如模块和各种关键内部结构等。它还会多次调用垃圾回收器。这会触发用户定义析构器或弱引用回调中的代码执行。在关闭阶段执行的代码可能会遇到各种异常, 因为其所依赖的资源已不再有效(常见的例子有库模块或警告机制等)。

解释器需要关闭的主要原因有 ___main__ 模块或所运行的脚本已完成执行。

iterable -- 可迭代对象 能够逐一返回其成员项的对象。可迭代对象的例子包括所有序列类型 (例如 list、str 和 tuple) 以及某些非序列类型例如 dict、文件对象 以及定义了 __iter__() 方法或是实现了 Sequence 语义的 __getitem__() 方法的任意自定义类对象。

可迭代对象被可用于 for 循环以及许多其他需要一个序列的地方(zip()、map()…)。当一个可迭代对象作为参数传给内置函数 iter()时,它会返回该对象的迭代器。这种迭代器适用于对值集合的一次性遍历。在使用可迭代对象时,你通常不需要调用 iter()或者自己处理迭代器对象。for 语句会为你自动处理那些操作,创建一个临时的未命名变量用来在循环期间保存迭代器。参见iterator、sequence以及generator。

iterator -- 迭代器 用来表示一连串数据流的对象。重复调用迭代器的 __next__() 方法(或将其传给内置函数 next())将逐个返回流中的项。当没有数据可用时则将引发 StopIteration 异常。到这时迭代器对象中的数据项已耗尽,继续调用其 __next__() 方法只会再次引发 StopIteration 异常。迭代器必须具有 __iter__() 方法用来返回该迭代器对象自身,因此迭代器必定也是可迭代对象,可被用于其他可迭代对象适用的大部分场合。一个显著的例外是那些会多次重复访问迭代项的代码。容器对象(例如 list)在你每次向其传入 iter() 函数或是在 for 循环中使用它时都会产生一个新的迭代器。如果在此情况下你尝试用迭代器则会返回在之前迭代过程中被耗尽的同一迭代器对象,使其看起来就像是一个空容器。

更多信息可查看 typeiter。

key function -- 键函数 键函数或称整理函数,是能够返回用于排序或排位的值的可调用对象。例如,locale.strxfrm()可用于生成一个符合特定区域排序约定的排序键。

Python 中有许多工具都允许用键函数来控制元素的排位或分组方式。其中包括 min(), max(), sorted(), list.sort(), heapq.merge(), heapq.nsmallest(), heapq.nlargest()以及itertools.groupby()。

要创建一个键函数有多种方式。例如, str.lower() 方法可以用作忽略大小写排序的键函数。另外, 键函数也可通过 lambda 表达式来创建, 例如 lambda r: (r[0], r[2])。还有 operator 模块提供了三个键函数构造器: attrgetter()、itemgetter() 和 methodcaller()。请查看如何排序一节以获取创建和使用键函数的示例。

keyword argument -- 关键字参数 参见argument。

- lambda 由一个单独*expression* 构成的匿名内联函数,表达式会在调用时被求值。创建 lambda 函数的句法为 lambda [parameters]: expression
- LBYL"先查看后跳跃"的英文缩写。这种代码编写风格会在进行调用或查找之前显式地检查前提条件。 此风格与*EAFP* 方式恰成对比,其特点是大量使用 if 语句。

在多线程环境中,LBYL 方式会导致"查看"和"跳跃"之间发生条件竞争风险。例如,以下代码 if key in mapping: return mapping[key] 可能由于在检查操作之后其他线程从 mapping 中移除了 key 而出错。这种问题可通过加锁或使用 EAFP 方式来解决。

- **list -- 列表** Python 内置的一种*sequence*。虽然名为列表,但更类似于其他语言中的数组而非链接列表,因为访问元素的时间复杂度为 O(1)。
- **list comprehension -- 列表推导式** 处理一个序列中的所有或部分元素并返回结果列表的一种紧凑写法。 result = ['{:#04x}'.format(x) for x in range(256) if x % 2 == 0] 将生成一

个 0 到 255 范围内的十六进制偶数对应字符串(0x...)的列表。其中 if 子句是可选的,如果省略则 range (256) 中的所有元素都会被处理。

- **loader -- 加载器** 负责加载模块的对象。它必须定义名为 load_module() 的方法。加载器通常由一个*finder* 返回。详情参见 **PEP 302**,对于*abstract base class* 可参见 importlib.abc.Loader。
- magic method -- 魔术方法 special method 的非正式同义词。
- mapping -- 映射 一种支持任意键查找并实现了 Mapping 或 MutableMapping 抽象基类中所规定方法的容器对象。此类对象的例子包括 dict, collections.defaultdict, collections. OrderedDict 以及 collections.Counter。
- **meta path finder -- 元路径查找器** sys.meta_path 的搜索所返回的*finder*。元路径查找器与*path entry finders* 存在关联但并不相同。

请查看 importlib.abc.MetaPathFinder 了解元路径查找器所实现的方法。

metaclass -- 元类 一种用于创建类的类。类定义包含类名、类字典和基类列表。元类负责接受上述三个参数并创建相应的类。大部分面向对象的编程语言都会提供一个默认实现。Python 的特别之处在于可以创建自定义元类。大部分用户永远不需要这个工具,但当需要出现时,元类可提供强大而优雅的解决方案。它们已被用于记录属性访问日志、添加线程安全性、跟踪对象创建、实现单例,以及其他许多任务。

更多详情参见 metaclasses。

- **method** -- 方法 在类内部定义的函数。如果作为该类的实例的一个属性来调用,方法将会获取实例对象作为其第一个*argument* (通常命名为 self)。参见*function* 和*nested scope*。
- **method resolution order -- 方法解析顺序** 方法解析顺序就是在查找成员时搜索全部基类所用的先后顺序。 请查看 Python 2.3 方法解析顺序 了解自 2.3 版起 Python 解析器所用相关算法的详情。
- **module -- 模块** 此对象是 Python 代码的一种组织单位。各模块具有独立的命名空间,可包含任意 Python 对象。模块可通过*importing* 操作被加载到 Python 中。

另见package。

module spec -- 模块规格 一个命名空间,其中包含用于加载模块的相关导入信息。是 importlib. machinery. Module Spec 的实例。

MRO 参见*method resolution order*。

- mutable -- 可变 可变对象可以在其 id() 保持固定的情况下改变其取值。另请参见immutable。
- **named tuple -- 具名元组** 术语 "具名元组"可用于任何继承自元组,并且其中的可索引元素还能使用名 称属性来访问的类型或类。这样的类型或类还可能拥有其他特性。

有些内置类型属于具名元组,包括 time.localtime()和 os.stat()的返回值。另一个例子是 sys.float_info:

```
>>> sys.float_info[1]  # indexed access
1024
>>> sys.float_info.max_exp  # named field access
1024
>>> isinstance(sys.float_info, tuple)  # kind of tuple
True
```

有些具名元组是内置类型(例如上面的例子)。此外,具名元组还可通过常规类定义从 tuple 继承并定义名称字段的方式来创建。这样的类可以手工编写,或者使用工厂函数 collections. namedtuple() 创建。后一种方式还会添加一些手工编写或内置具名元组所没有的额外方法。

- namespace -- 命名空间 命名空间是存放变量的场所。命名空间有局部、全局和内置的,还有对象中的嵌套命名空间(在方法之内)。命名空间通过防止命名冲突来支持模块化。例如,函数 builtins.open与os.open()可通过各自的命名空间来区分。命名空间还通过明确哪个模块实现那个函数来帮助提高可读性和可维护性。例如,random.seed()或itertools.islice()这种写法明确了这些函数是由random与itertools模块分别实现的。
- **namespace package -- 命名空间包 PEP 420** 所引入的一种仅被用作子包的容器的*package*,命名空间包可以没有实体表示物,其描述方式与*regular package* 不同,因为它们没有 ___init___.py 文件。

另可参见module。

- nested scope -- 嵌套作用域 在一个定义范围内引用变量的能力。例如,在另一函数之内定义的函数可以引用前者的变量。请注意嵌套作用域默认只对引用有效而对赋值无效。局部变量的读写都受限于最内层作用域。类似的,全局变量的读写则作用于全局命名空间。通过 nonlocal 关键字可允许写入外层作用域。
- **new-style class -- 新式类** 对于目前已被应于所有类对象的类形式的旧称谓。在早先的 Python 版本中,只有新式类能够使用 Python 新增的更灵活特性,例如 ___slots___、描述符、特征属性、___getattribute___()、类方法和静态方法等。
- **object -- 对象** 任何具有状态(属性或值)以及预定义行为(方法)的数据。object 也是任何*new-style class* 的最顶层基类名。
- **package -- 包** 一种可包含子模块或递归地包含子包的 Python *module*。从技术上说,包是带有 ___path___ 属性的 Python 模块。

另参见regular package 和namespace package。

- **parameter -- 形参** *function* (或方法) 定义中的命名实体,它指定函数可以接受的一个*argument* (或在某些情况下,多个实参)。有五种形参:
 - positional-or-keyword: 位置或关键字,指定一个可以作为位置参数 传入也可以作为关键字参数 传入的实参。这是默认的形参类型,例如下面的 foo 和 bar:

```
def func(foo, bar=None): ...
```

• positional-only: 仅限位置,指定一个只能通过位置传入的参数。仅限位置形参可通过在函数定义的形参列表中它们之后包含一个/字符来定义,例如下面的 posonly1 和 posonly2:

```
def func(posonly1, posonly2, /, positional_or_keyword): ...
```

• *keyword-only*: 仅限关键字,指定一个只能通过关键字传入的参数。仅限关键字形参可通过在函数定义的形参列表中包含单个可变位置形参或者在多个可变位置形参之前放一个*来定义,例如下面的 *kw_only1* 和 *kw_only2*:

```
def func(arg, *, kw_only1, kw_only2): ...
```

• var-positional: 可变位置,指定可以提供由一个任意数量的位置参数构成的序列(附加在其他形参已接受的位置参数之后)。这种形参可通过在形参名称前加缀*来定义,例如下面的 args:

```
def func(*args, **kwargs): ...
```

• var-keyword: 可变关键字,指定可以提供任意数量的关键字参数(附加在其他形参已接受的关键字参数之后)。这种形参可通过在形参名称前加级**来定义,例如上面的kwargs。

形参可以同时指定可选和必选参数,也可以为某些可选参数指定默认值。

另参见argument 术语表条目、参数与形参的区别中的常见问题、inspect.Parameter类、function一节以及 PEP 362。

path entry -- 路径人口 *import path* 中的一个单独位置,会被path based finder 用来查找要导入的模块。

path entry finder -- 路径人口查找器 任一可调用对象使用 sys.path_hooks (即*path entry hook*) 返回 的 *finder*,此种对象能通过 *path entry* 来定位模块。

请参看 importlib.abc.PathEntryFinder 以了解路径人口查找器所实现的各个方法。

- **path entry hook -- 路径人口钩子** 一种可调用对象,在知道如何查找特定*path entry* 中的模块的情况下能够使用 sys.path_hook 列表返回一个*path entry finder*。
- path based finder -- 基于路径的查找器 默认的一种元路径查找器,可在一个import path 中查找模块。
- path-like object -- 路径类对象 代表一个文件系统路径的对象。类路径对象可以是一个表示路径的 str或者 bytes 对象,还可以是一个实现了 os.PathLike 协议的对象。一个支持 os.PathLike

协议的对象可通过调用 os.fspath() 函数转换为 str 或者 bytes 类型的文件系统路径; os.fsdecode() 和 os.fsencode() 可被分别用来确保获得 str 或 bytes 类型的结果。此对象是由 PEP 519 引入的。

PEP "Python 增强提议"的英文缩写。一个 PEP 就是一份设计文档,用来向 Python 社区提供信息,或描述一个 Python 的新增特性及其进度或环境。PEP 应当提供精确的技术规格和所提议特性的原理说明。

PEP 应被作为提出主要新特性建议、收集社区对特定问题反馈以及为必须加入 Python 的设计决策编写文档的首选机制。PEP 的作者有责任在社区内部建立共识,并应将不同意见也记入文档。

参见 PEP 1。

portion -- 部分 构成一个命名空间包的单个目录内文件集合(也可能存放于一个 zip 文件内),具体定义见 PEP 420。

positional argument -- 位置参数 参见argument。

provisional API -- **暂定** API 暂定 API 是指被有意排除在标准库的向后兼容性保证之外的应用编程接口。虽然此类接口通常不会再有重大改变,但只要其被标记为暂定,就可能在核心开发者确定有必要的情况下进行向后不兼容的更改(甚至包括移除该接口)。此种更改并不会随意进行 -- 仅在 API 被加入之前未考虑到的严重基础性缺陷被发现时才可能会这样做。

即便是对暂定 API 来说,向后不兼容的更改也会被视为"最后的解决方案"——任何问题被确认时都会尽可能先尝试找到一种向后兼容的解决方案。

这种处理过程允许标准库持续不断地演进,不至于被有问题的长期性设计缺陷所困。详情见 PEP 411。

provisional package -- 暂定包 参见provisional API。

Python 3000 Python 3.x 发布路线的昵称(这个名字在版本 3 的发布还遥遥无期的时候就已出现了)。有时也被缩写为"Py3k"。

Pythonic 指一个思路或一段代码紧密遵循了 Python 语言最常用的风格和理念,而不是使用其他语言中通用的概念来实现代码。例如,Python 的常用风格是使用 for 语句循环来遍历一个可迭代对象中的所有元素。许多其他语言没有这样的结构,因此不熟悉 Python 的人有时会选择使用一个数字计数器:

```
for i in range(len(food)):
    print(food[i])
```

而相应的更简洁更 Pythonic 的方法是这样的:

```
for piece in food:
   print(piece)
```

qualified name -- 限定名称 一个以点号分隔的名称,显示从模块的全局作用域到该模块中定义的某个类、函数或方法的"路径",相关定义见 PEP 3155。对于最高层级的函数和类,限定名称与对象名称一致:

当被用于引用模块时,完整限定名称意为标示该模块的以点号分隔的整个路径,其中包含其所有的父包,例如 email.mime.text:

```
>>> import email.mime.text
>>> email.mime.text.__name__
'email.mime.text'
```

- **reference count -- 引用计数** 对特定对象的引用的数量。当一个对象的引用计数降为零时,所分配资源将被释放。引用计数对 **Python** 代码来说通常是不可见的,但它是*CPython* 实现的一个关键元素。sys模块定义了一个 getrefcount () 函数,程序员可调用它来返回特定对象的引用计数。
- regular package -- 常规包 传统型的package, 例如包含有一个 __init__.py 文件的目录。

另参见namespace package。

- __slots__ 一种写在类内部的声明,通过预先声明实例属性等对象并移除实例字典来节省内存。虽然这种技巧很流行,但想要用好却并不容易,最好是只保留在少数情况下采用,例如极耗内存的应用程序,并且其中包含大量实例。
- sequence -- 序列 一种iterable,它支持通过 ___getitem___() 特殊方法来使用整数索引进行高效的元素 访问,并定义了一个返回序列长度的 ___len___() 方法。内置的序列类型有 list、str、tuple 和 bytes。注意虽然 dict 也支持 ___getitem___() 和 ___len___(),但它被认为属于映射而非序 列,因为它查找时使用任意的immutable 键而非整数。

collections.abc.Sequence 抽象基类定义了一个更丰富的接口,它超越了 __getitem__()和 __len__(),添加了 count(),index(),__contains__()和 __reversed__()。可以使用 register()显式注册实现此扩展接口的类型。

- **single dispatch -- 单分派** 一种*generic function* 分派形式,其实现是基于单个参数的类型来选择的。
- slice -- 切片 通常只包含了特定sequence 的一部分的对象。切片是通过使用下标标记来创建的,在[]中给出几个以冒号分隔的数字,例如 variable_name[1:3:5]。方括号(下标)标记在内部使用slice 对象。
- **special method -- 特殊方法** 一种由 Python 隐式调用的方法,用来对某个类型执行特定操作例如相加等等。这种方法的名称的首尾都为双下划线。特殊方法的文档参见 specialnames。
- **statement -- 语句** 语句是程序段(一个代码"块")的组成单位。一条语句可以是一个*expression* 或某个带有关键字的结构,例如 if、while 或 for。
- text encoding -- 文本编码 用于将 Unicode 字符串编码为字节串的编码器。
- **text file -- 文本文件** 一种能够读写 str 对象的*file object*。通常一个文本文件实际是访问一个面向字节的数据流并自动处理*text encoding*。文本文件的例子包括以文本模式('r'或'w')打开的文件、sys.stdin、sys.stdout 以及 io.StringIO 的实例。

另请参看binary file 了解能够读写字节类对象 的文件对象。

- triple-quoted string -- 三引号字符串 首尾各带三个连续双引号(")或者单引号(')的字符串。它们在功能上与首尾各用一个引号标注的字符串没有什么不同,但是有多种用处。它们允许你在字符串内包含未经转义的单引号和双引号,并且可以跨越多行而无需使用连接符,在编写文档字符串时特别好用。
- **type -- 类型** 类型决定一个 Python 对象属于什么种类;每个对象都具有一种类型。要知道对象的类型,可以访问它的 __class__ 属性,或是通过 type (obj) 来获取。
- type alias -- 类型别名 一个类型的同义词,创建方式是把类型赋值给特定的标识符。

类型别名的作用是简化类型提示。例如:

```
from typing import List, Tuple

def remove_gray_shades(
          colors: List[Tuple[int, int, int]]) -> List[Tuple[int, int, int]]:
    pass
```

可以这样提高可读性:

```
from typing import List, Tuple

Color = Tuple[int, int, int]

def remove_gray_shades(colors: List[Color]) -> List[Color]:
    pass
```

参见 typing 和 PEP 484, 其中有对此功能的详细描述。

type hint -- 类型提示 annotation 为变量、类属性、函数的形参或返回值指定预期的类型。

类型提示属于可选项, Python 不要求提供, 但其可对静态类型分析工具起作用, 并可协助 IDE 实现代码补全与重构。

全局变量、类属性和函数的类型提示可以使用 typing.get_type_hints() 来访问,但局部变量则不可以。

参见 typing 和 PEP 484, 其中有对此功能的详细描述。

- universal newlines -- 通用换行 一种解读文本流的方式,将以下所有符号都识别为行结束标志: Unix 的行结束约定 '\n'、Windows 的约定 '\r\n' 以及旧版 Macintosh 的约定 '\r'。参见 PEP 278 和 PEP 3116 和 bytes.splitlines() 了解更多用法说明。
- variable annotation -- 变量注解 对变量或类属性的annotation。

在标注变量或类属性时,还可选择为其赋值:

```
class C:
    field: 'annotation'
```

变量标注通常被用作类型提示:例如以下变量预期接受 int 类型的值:

```
count: int = 0
```

变量标注语法的详细解释见 annassign 一节。

请参看function annotation、PEP 484 和 PEP 526, 其中对此功能有详细描述。

virtual environment -- 虚拟环境 一种采用协作式隔离的运行时环境,允许 Python 用户和应用程序在安装和升级 Python 分发包时不会干扰到同一系统上运行的其他 Python 应用程序的行为。 另参见 venv。

- **virtual machine -- 虚拟机** 一台完全通过软件定义的计算机。Python 虚拟机可执行字节码编译器所生成的*bytecode*。
- **Zen of Python -- Python 之禅** 列出 Python 设计的原则与哲学,有助于理解与使用这种语言。查看其具体内容可在交互模式提示符中输入"import this"。

APPENDIX B

文档说明

这些文档生成自 reStructuredText 原文档,由 Sphinx (一个专门为 Python 文档写的文档生成器)创建。本文档和它所用工具链的开发完全是由志愿者完成的,这和 Python 本身一样。如果您想参与进来,请阅读 reporting-bugs 了解如何参与。我们随时欢迎新的志愿者! 非常感谢:

- Fred L. Drake, Jr., 创造了用于早期 Python 文档的工具链,以及撰写了非常多的文档;
- Docutils 软件包 项目, 创建了 reStructuredText 文本格式和 Docutils 软件套件;
- Fredrik Lundh, Sphinx 从他的 Alternative Python Reference 项目中获得了很多好的想法。

B.1 Python 文档贡献者

有很多对 Python 语言,Python 标准库和 Python 文档有贡献的人,随 Python 源代码发布的 Misc/ACKS 文件列出了部分贡献者。

有了 Python 社区的输入和贡献, Python 才有了如此出色的文档 - 谢谢你们!

APPENDIX C

历史和许可证

C.1 该软件的历史

Python 由荷兰数学和计算机科学研究学会(CWI,见 https://www.cwi.nl/)的 Guido van Rossum 于 1990 年代初设计,作为一门叫做 ABC 的语言的替代品。尽管 Python 包含了许多来自其他人的贡献,Guido 仍是其主要作者。

1995 年,Guido 在弗吉尼亚州的国家创新研究公司(CNRI,见 https://www.cnri.reston.va.us/)继续他在Python 上的工作,并在那里发布了该软件的多个版本。

2000 年五月,Guido 和 Python 核心开发团队转到 BeOpen.com 并组建了 BeOpen PythonLabs 团队。同年十月,PythonLabs 团队转到 Digital Creations (现为 Zope Corporation;见 https://www.zope.org/)。2001 年,Python 软件基金会 (PSF,见 https://www.python.org/psf/) 成立,这是一个专为拥有 Python 相关知识产权而创建的非营利组织。Zope Corporation 现在是 PSF 的赞助成员。

所有的 Python 版本都是开源的(有关开源的定义参阅 https://opensource.org/)。历史上,绝大多数 Python 版本是 GPL 兼容的;下表总结了各个版本情况。

| 发布版本 | 源自 | 年份 | 所有者 | GPL 兼容? |
|-------------|-----------|-----------|------------|---------|
| 0.9.0 至 1.2 | n/a | 1991-1995 | CWI | 是 |
| 1.3 至 1.5.2 | 1.2 | 1995-1999 | CNRI | 是 |
| 1.6 | 1.5.2 | 2000 | CNRI | 否 |
| 2.0 | 1.6 | 2000 | BeOpen.com | 否 |
| 1.6.1 | 1.6 | 2001 | CNRI | 否 |
| 2.1 | 2.0+1.6.1 | 2001 | PSF | 否 |
| 2.0.1 | 2.0+1.6.1 | 2001 | PSF | 是 |
| 2.1.1 | 2.1+2.0.1 | 2001 | PSF | 是 |
| 2.1.2 | 2.1.1 | 2002 | PSF | 是 |
| 2.1.3 | 2.1.2 | 2002 | PSF | 是 |
| 2.2 及更高 | 2.1.1 | 2001 至今 | PSF | 是 |

注解: GPL 兼容并不意味着 Python 在 GPL 下发布。与 GPL 不同,所有 Python 许可证都允许您分发修改后的版本,而无需开源所做的更改。GPL 兼容的许可证使得 Python 可以与其它在 GPL 下发布的软件结合使用;但其它的许可证则不行。

感谢众多在 Guido 指导下工作的外部志愿者,使得这些发布成为可能。

C.2 获取或以其他方式使用 Python 的条款和条件

C.2.1 用于 PYTHON 3.8.2 的 PSF 许可协议

- 3.8.2 software in source or binary form and its associated \rightarrow documentation.
- 2. Subject to the terms and conditions of this License Agreement, PSF $_{-}$ \rightarrow hereby
- grants Licensee a nonexclusive, royalty-free, world-wide license to→reproduce,
- analyze, test, perform and/or display publicly, prepare derivative \rightarrow works,
- distribute, and otherwise use Python 3.8.2 alone or in any derivative version, provided, however, that PSF's License Agreement and PSF's ontice of
- copyright, i.e., "Copyright © 2001-2020 Python Software Foundation; All- \rightarrow Rights
- Reserved" are retained in Python 3.8.2 alone or in any derivative—version prepared by Licensee.
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 3.8.2 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee → hereby
- agrees to include in any such work a brief summary of the changes made_ to Python
 3.8.2.
- 4. PSF is making Python 3.8.2 available to Licensee on an "AS IS" basis.
 PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY.
- EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANYWREPRESENTATION OR
- WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR \rightarrow THAT THE
 - USE OF PYTHON 3.8.2 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 3.8.2 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS ALARESULT OF
- - THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 6. This License Agreement will automatically terminate upon a material.

 →breach of
 its terms and conditions.

- 7. Nothing in this License Agreement shall be deemed to create any—relationship
- of agency, partnership, or joint venture between PSF and Licensee. $_$ \rightarrow This License
- Agreement does not grant permission to use PSF trademarks or trade name____in a
- trademark sense to endorse or promote products or services of Licensee, $_$ or any third party.
- 8. By copying, installing or otherwise using Python 3.8.2, Licensee agrees to be bound by the terms and conditions of this License Agreement.

C.2.2 用于 PYTHON 2.0 的 BEOPEN.COM 许可协议

BEOPEN PYTHON 开源许可协议第1版

- 1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at 160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization ("Licensee") accessing and otherwise using this software in source or binary form and its associated documentation ("the Software").
- 2. Subject to the terms and conditions of this BeOpen Python License Agreement, BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use the Software alone or in any derivative version, provided, however, that the BeOpen Python License is retained in the Software, alone or in any derivative version prepared by Licensee.
- 3. BeOpen is making the Software available to Licensee on an "AS IS" basis.
 BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF
 EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR
 WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE
 USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 5. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 6. This License Agreement shall be governed by and interpreted in all respects by the law of the State of California, excluding conflict of law provisions. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between BeOpen and Licensee. This License Agreement does not grant permission to use BeOpen trademarks or trade names in a trademark sense to endorse or promote products or services of Licensee, or any third party. As an exception, the "BeOpen Python" logos available at http://www.pythonlabs.com/logos.html may be used according to the permissions granted on that web page.
- 7. By copying, installing or otherwise using the software, Licensee agrees to be bound by the terms and conditions of this License Agreement.

C.2.3 用于 PYTHON 1.6.1 的 CNRI 许可协议

- 1. This LICENSE AGREEMENT is between the Corporation for National Research Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191 ("CNRI"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 1.6.1 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, CNRI hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 1.6.1 alone or in any derivative version, provided, however, that CNRI's License Agreement and CNRI's notice of copyright, i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version prepared by Licensee. Alternately, in lieu of CNRI's License Agreement, Licensee may substitute the following text (omitting the quotes): "Python 1.6.1 is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement together with Python 1.6.1 may be located on the Internet using the following unique, persistent identifier (known as a handle): 1895.22/1013. This Agreement may also be obtained from a proxy server on the Internet using the following URL: http://hdl.handle.net/1895.22/1013."
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 1.6.1 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 1.6.1.
- 4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 7. This License Agreement shall be governed by the federal intellectual property law of the United States, including without limitation the federal copyright law, and, to the extent such U.S. federal law does not apply, by the law of the Commonwealth of Virginia, excluding Virginia's conflict of law provisions. Notwithstanding the foregoing, with regard to derivative works based on Python 1.6.1 that incorporate non-separable material that was previously distributed under the GNU General Public License (GPL), the law of the Commonwealth of Virginia shall govern this License Agreement only as to issues arising under or with respect to Paragraphs 4, 5, and 7 of this License Agreement. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between CNRI and Licensee. This License Agreement does not grant permission to use CNRI trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.
- 8. By clicking on the "ACCEPT" button where indicated, or by copying, installing or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and conditions of this License Agreement.

C.2.4 用于 PYTHON 0.9.0 至 1.2 的 CWI 许可协议

Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3 被收录软件的许可证与鸣谢

本节是 Python 发行版中收录的第三方软件的许可和致谢清单,该清单是不完整且不断增长的。

C.3.1 Mersenne Twister

_random 模块包含基于 http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/MT2002/emt19937ar.html 下载的代码。以下是原始代码的完整注释(声明):

A C-program for MT19937, with initialization improved 2002/1/26. Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using init_genrand(seed) or init_by_array(init_key, key_length).

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura, All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. The names of its contributors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR

CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Any feedback is very welcome. http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html email: m-mat @ math.sci.hiroshima-u.ac.jp (remove space)

C.3.2 套接字

socket 模块使用 getaddrinfo() 和 getnameinfo() 函数,这些函数源代码在 WIDE 项目(http://www.wide.ad.jp/)的单独源文件中。

Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name of the project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.3 异步套接字服务

asynchat 和 asyncore 模块包含以下声明:

Copyright 1996 by Sam Rushing

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission

notice appear in supporting documentation, and that the name of Sam Rushing not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.4 Cookie 管理

http.cookies 模块包含以下声明:

Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Timothy O'Malley not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.5 执行追踪

trace 模块包含以下声明:

portions copyright 2001, Autonomous Zones Industries, Inc., all rights...

err... reserved and offered to the public under the terms of the

Python 2.2 license.

Author: Zooko O'Whielacronx

http://zooko.com/

mailto:zooko@zooko.com

Copyright 2000, Mojam Media, Inc., all rights reserved.

Author: Skip Montanaro

Copyright 1999, Bioreason, Inc., all rights reserved.

Author: Andrew Dalke

Copyright 1995-1997, Automatrix, Inc., all rights reserved.

Author: Skip Montanaro

Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.

Permission to use, copy, modify, and distribute this Python software and its associated documentation for any purpose without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of neither Automatrix, Bioreason or Mojam Media be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

C.3.6 UUencode 与 UUdecode 函数

uu 模块包含以下声明:

Copyright 1994 by Lance Ellinghouse Cathedral City, California Republic, United States of America. All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Lance Ellinghouse not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Modified by Jack Jansen, CWI, July 1995:

- Use binascii module to do the actual line-by-line conversion between ascii and binary. This results in a 1000-fold speedup. The C version is still 5 times faster, though.
- Arguments more compliant with Python standard

C.3.7 XML 远程过程调用

xmlrpc.client 模块包含以下声明:

The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB Copyright (c) 1999-2002 by Fredrik Lundh

By obtaining, using, and/or copying this software and/or its associated documentation, you agree that you have read, understood, and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and its associated documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appears in

all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Secret Labs AB or the author not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANT-ABILITY AND FITNESS. IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.8 test epoll

test_epoll 模块包含以下声明:

Copyright (c) 2001-2006 Twisted Matrix Laboratories.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

C.3.9 Select kqueue

select 模块关于 kqueue 的接口包含以下声明:

Copyright (c) 2000 Doug White, 2006 James Knight, 2007 Christian Heimes All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS ``AS IS'' AND

ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.10 SipHash24

Python/pyhash.c 文件包含 Marek Majkowski'对 Dan Bernstein 的 SipHash24 算法的实现。它包含以下声明:

```
<MIT License>
Copyright (c) 2013 Marek Majkowski <marek@popcount.org>
Permission is hereby granted, free of charge, to any person obtaining a copy
of this software and associated documentation files (the "Software"), to deal
in the Software without restriction, including without limitation the rights
to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom the Software is
furnished to do so, subject to the following conditions:
The above copyright notice and this permission notice shall be included in
all copies or substantial portions of the Software.
</MIT License>
Original location:
  https://github.com/majek/csiphash/
Solution inspired by code from:
  Samuel Neves (supercop/crypto_auth/siphash24/little)
  djb (supercop/crypto_auth/siphash24/little2)
  Jean-Philippe Aumasson (https://131002.net/siphash/siphash24.c)
```

C.3.11 strtod 和 dtoa

Python/dtoa.c 文件提供了 C 语言的 dtoa 和 strtod 函数,用于将 C 语言的双精度型和字符串进行转换,由 David M. Gay 的同名文件派生而来,该文件当前可从 http://www.netlib.org/fp/ 下载。2009 年 3 月 16 日检索到的原始文件包含以下版权和许可声明:

```
/**************

* The author of this software is David M. Gay.

* Copyright (c) 1991, 2000, 2001 by Lucent Technologies.

* Permission to use, copy, modify, and distribute this software for any

* purpose without fee is hereby granted, provided that this entire notice

* is included in all copies of any software which is or includes a copy

* or modification of this software and in all copies of the supporting

* documentation for such software.

* THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED
```

C.3.12 OpenSSL

如果操作系统可用,则 hashlib, posix, ssl, crypt 模块使用 OpenSSL 库来提高性能。此外,适用于 Python 的 Windows 和 Mac OS X 安装程序可能包括 OpenSSL 库的拷贝,所以在此处也列出了 OpenSSL 许可证的拷贝:

```
LICENSE ISSUES
The OpenSSL toolkit stays under a dual license, i.e. both the conditions of
the OpenSSL License and the original SSLeay license apply to the toolkit.
See below for the actual license texts. Actually both licenses are BSD-style
Open Source licenses. In case of any license issues related to OpenSSL
please contact openssl-core@openssl.org.
OpenSSL License
  * Copyright (c) 1998-2008 The OpenSSL Project. All rights reserved.
   * Redistribution and use in source and binary forms, with or without
   * modification, are permitted provided that the following conditions
   * are met:
   ^{\star} 1. Redistributions of source code must retain the above copyright
      notice, this list of conditions and the following disclaimer.
   * 2. Redistributions in binary form must reproduce the above copyright
       notice, this list of conditions and the following disclaimer in
       the documentation and/or other materials provided with the
       distribution.
   * 3. All advertising materials mentioning features or use of this
       software must display the following acknowledgment:
        "This product includes software developed by the OpenSSL Project
       for use in the OpenSSL Toolkit. (http://www.openssl.org/)"
   * 4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to
       endorse or promote products derived from this software without
       prior written permission. For written permission, please contact
       openssl-core@openssl.org.
   * 5. Products derived from this software may not be called "OpenSSL"
       nor may "OpenSSL" appear in their names without prior written
       permission of the OpenSSL Project.
   * 6. Redistributions of any form whatsoever must retain the following
       acknowledgment:
        "This product includes software developed by the OpenSSL Project
       for use in the OpenSSL Toolkit (http://www.openssl.org/)"
   * THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY
```

```
* EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
    * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
    * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR
    * ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
    * SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT
    * NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
    * LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)
    * HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT,
    * STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
    * ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
    * OF THE POSSIBILITY OF SUCH DAMAGE.
    * This product includes cryptographic software written by Eric Young
    ^{\star} (eay@cryptsoft.com). This product includes software written by Tim
    * Hudson (tjh@cryptsoft.com).
    */
Original SSLeay License
  /* Copyright (C) 1995-1998 Eric Young (eay@cryptsoft.com)
   * All rights reserved.
    * This package is an SSL implementation written
    * by Eric Young (eay@cryptsoft.com).
    ^{\star} The implementation was written so as to conform with Netscapes SSL.
    ^{\star} This library is free for commercial and non-commercial use as long as
    * the following conditions are aheared to. The following conditions
    * apply to all code found in this distribution, be it the RC4, RSA,
    * lhash, DES, etc., code; not just the SSL code. The SSL documentation
    * included with this distribution is covered by the same copyright terms
    * except that the holder is Tim Hudson (tjh@cryptsoft.com).
    * Copyright remains Eric Young's, and as such any Copyright notices in
    * the code are not to be removed.
    * If this package is used in a product, Eric Young should be given attribution
    * as the author of the parts of the library used.
    ^{\star} This can be in the form of a textual message at program startup or
    * in documentation (online or textual) provided with the package.
    * Redistribution and use in source and binary forms, with or without
    * modification, are permitted provided that the following conditions
    * are met:
    * 1. Redistributions of source code must retain the copyright
        notice, this list of conditions and the following disclaimer.
    ^{\star} 2. Redistributions in binary form must reproduce the above copyright
        notice, this list of conditions and the following disclaimer in the
         documentation and/or other materials provided with the distribution.
    * 3. All advertising materials mentioning features or use of this software
        must display the following acknowledgement:
         "This product includes cryptographic software written by
         Eric Young (eay@cryptsoft.com) "
         The word 'cryptographic' can be left out if the rouines from the library
         being used are not cryptographic related :-).
    * 4. If you include any Windows specific code (or a derivative thereof) from
         the apps directory (application code) you must include an acknowledgement:
         "This product includes software written by Tim Hudson (tjh@cryptsoft.com)"
```

```
* THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS'' AND

* ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE

* IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE

* ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE

* FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL

* DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS

* OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)

* HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT

* LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY

* OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF

* SUCH DAMAGE.

* The licence and distribution terms for any publically available version or

* derivative of this code cannot be changed. i.e. this code cannot simply be

* copied and put under another distribution licence

* [including the GNU Public Licence.]

*/
```

C.3.13 expat

除非使用 --with-system-expat 配置了构建,否则 pyexpat 扩展都是用包含 expat 源的拷贝构建的:

Copyright (c) 1998, 1999, 2000 Thai Open Source Software Center Ltd and Clark Cooper

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

C.3.14 libffi

除非使用 --with-system-libffi 配置了构建, 否则 _ctypes 扩展都是包含 libffi 源的拷贝构建的:

Copyright (c) 1996-2008 Red Hat, Inc and others.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the ``Software''), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED ``AS IS'', WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

C.3.15 zlib

如果系统上找到的 zlib 版本太旧而无法用于构建,则使用包含 zlib 源代码的拷贝来构建 zlib 扩展:

Copyright (C) 1995-2011 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

- The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
- Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- 3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly Mark Adler

jloup@gzip.org madler@alumni.caltech.edu

C.3.16 cfuhash

tracemalloc 使用的哈希表的实现基于 cfuhash 项目:

Copyright (c) 2005 Don Owens All rights reserved.

This code is released under the BSD license:

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- * Redistributions in binary form must reproduce the above

copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

* Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.17 libmpdec

除非使用 --with-system-libmpdec 配置了构建,否则 _decimal 模块都是用包含 libmpdec 库的拷贝构建的。

Copyright (c) 2008-2016 Stefan Krah. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.18 W3C C14N 测试套件

test 包 (lib/test/xmltestdata/c14n-20/) 中的 C14N2.0 测试套件来源于 W3C 网站 https://www.w3.org/TR/xml-c14n2-testcases/, 并根据 BSD 许可证(三条款版)发行:

Copyright (c) 2013 W3C(R) (MIT, ERCIM, Keio, Beihang), All Rights Reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of works must retain the original copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the original copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the W3C nor the names of its contributors may be used to endorse or promote products derived from this work without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTIC-ULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

APPENDIX D

版权

Python 与这份文档:

版权所有© 2001-2020 Python 软件基金会。保留所有权利。

版权所有© 2000 BeOpen.com。保留所有权利。

版权所有 © 1995-2000 Corporation for National Research Initiatives。保留所有权利。

版权所有 © 1991-1995 Stichting Mathematisch Centrum。保留所有权利。

有关完整的许可证和许可信息,参见历史和许可证。

246 Appendix D. 版权

| 非字母 | exec_prefix,4 |
|-------------------------------------------------|--------------------------------------|
| , 215 | PATH, 10 |
| 2to3, 215 | prefix,4 |
| >>>, 215 | PYTHON*, 132 |
| all(package variable), 40 | PYTHONCOERCECLOCALE, 160 |
| dict (module attribute), 116 | PYTHONDEBUG, 132 |
| doc (module attribute), 115 | PYTHONDONTWRITEBYTECODE, 132 |
| file (module attribute), 115, 116 | PYTHONDUMPREFS, 184 |
| future, 218 | PYTHONHASHSEED, 132 |
| import | PYTHONHOME, 10, 132, 137, 156 |
| <u></u> | PYTHONINSPECT, 133 |
| loader (module attribute), 115 | PYTHONIOENCODING, 135 |
| main | PYTHONLEGACYWINDOWSFSENCODING, 133 |
| <u></u> | PYTHONLEGACYWINDOWSSTDIO, 133 |
| name (<i>module attribute</i>), 115, 116 | PYTHONMALLOC, 166, 169, 170 |
| nakage (module attribute), 115 | PYTHONMALLOCSTATS, 166 |
| package (mounte unitable), 113slots, 224 | PYTHONNOUSERSITE, 133 |
| | PYTHONOPTIMIZE, 133 |
| _inittab(C 类型), 43 | PYTHONPATH, 10, 132, 156 |
| | PYTHONUNBUFFERED, 133 |
| | PYTHONUTF8, 160 |
| ryc_neg (C 函数), 82 Pycpow (<i>C</i> 函数), 82 | PYTHONVERBOSE, 133 |
| _ry_c_pow(C 函数), 82 _Py_c_prod(C 函数), 82 | ۸ |
| _ry_c_prod (c 函数), 62 _Py_c_quot (C 函数), 82 | A |
| _Fy_c_sum(C函数),82 | abort(),39 |
| _Py_InitializeMain (C函数), 162 | abs |
| _Py_NoneStruct (C 变量), 173 | E 置函数, 61 |
| | abstract base class 抽象基类, 215 |
| 192 | allocfunc (C 类型), 206 |
| _PyBytes_Resize (C 函数), 85 | annotation 注解, 215 |
| | argument 参数, 215 |
| _PyCFunctionFastWithKeywords (C 类型), | argv (in module sys), 137 |
| 175 | ascii |
| _PyImport_Fini(<i>C</i> 函数),42 | E 置函数,57 |
| PyImport_Init (C函数),42 | asynchronous context manager 异 步 |
| _ PyObject_FastCallDict (C 函数),59 | 上下文管理器, 216 |
| _ PyObject_New (<i>C</i> 函数), 173 | asynchronous generator 异步生成器, |
| _ PyObject_NewVar(C函数),173 | 216 |
| _ PyObject_Vectorcall(C函数),58 | asynchronous generator iterator 异 |
| _ PyTuple_Resize (C 函数), 105 | 步生成器迭代器,216 |
| _thread | asynchronous iterable 异步可迭代对 |
| 模块, 140 | 象, 216 |
| 环境变量 | asynchronous iterator 异步迭代器,216 |
| | attribute 属性. 216 |

| awaitable 可等待对象,216 | dictionary 字典, 217 |
|---------------------------------------------------------------------------------------------|-----------------------------------------|
| П | dictionary view 字典视图, 217 |
| В | divmod |
| BDFL, 216 | E置函数, 61 |
| binary file 二进制文件, 216 | docstring 文档字符串, 217 |
| binaryfunc (C 类型), 207 | duck-typing 鸭子类型,218 |
| buffer interface | E |
| (see buffer protocol),66 | _ |
| buffer object | EAFP, 218 |
| (see buffer protocol),66 | EOFError (built-in exception), 115 |
| buffer protocol, 66 | exc_info() (in module sys), 9 |
| builtins 地比 10 124 142 | exec_module (C 函数), 119 |
| 模块, 10, 134, 143 | exec_prefix,4 |
| bytearray 对象,85 | executable (in module sys), 136 |
| 対象, 65 bytecode 字节码, 216 | exit(),39 expression 表达式, 218 |
| bytes | extension module 扩展模块, 218 |
| F 置函数, 57 | excension module — √ 成疾失,210 |
| 对象, 83 | F |
| bytes-like object 字节类对象, 216 | |
| bytes like object 1 Nama, 210 | f-string f-字符串, 218 file |
| C | 对象,114 |
| calloc(), 165 | file object 文件对象, 218 |
| Capsule | file-like object 文件类对象, 218 |
| 对象, 124 | finder 查找器, 218 |
| C-contiguous, 69, 217 | float |
| class **, 216 | E 置函数,63 |
| class variable 类变量, 216 | floating point |
| classmethod | 对象,81 |
| F置函数, 176 | floor division 向下取整除法, 218 |
| cleanup functions, 39 | Fortran contiguous, 69, 217 |
| close() (in module os), 144 | free(),165 |
| CO_FUTURE_DIVISION (C 变量), 19 | freefunc(C类型),206 |
| code object, 114 | freeze utility, 42 |
| coercion 强制类型转换, 216 | frozenset |
| compile | 对象,110 |
| - - - - - - - - - - - - - - - - - - - | function |
| complex number | 对象,111 |
| 对象,82 | function 函数, 218 |
| complex number 复数,217 | function annotation 函数注解, 218 |
| context manager 上下文管理器,217 | 0 |
| context variable 上下文变量, 217 | G |
| contiguous, 69 | garbage collection 垃圾回收, 218 |
| contiguous 连续, 217 | generator, 218 |
| copyright (in module sys), 136 | generator 生成器, 219 |
| coroutine 协程, 217 | generator expression, 219 |
| coroutine function 协程函数, 217 | generator expression 生成器表达式 |
| CPython, 217 | 219 |
| create_module (C函数), 118 | generator iterator 生成器迭代器, 219 |
| D | generic function 泛型函数, 219 |
| | getattrfunc(C 类型), 207 |
| decorator 装饰器, 217 | getattrofunc(C 类型), 207 |
| descrgetfunc(C类型),207 | getbufferproc(C类型),207 |
| descriptor 描述器, 217 | getiterfunc(C类型),207 |
| descrsetfunc (C 类型), 207 | GIL, 219 |
| destructor (C 类型), 206 | global interpreter lock, 138 |
| dictionary | global interpreter lock 全局解释器 |
| 对象, 108 | 锁, 219 |

| H | mapping |
|---------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| hash | 对象, 108 |
| F 置函数, 59, 188 | mapping 映射, 221 |
| hash-based pyc 基于哈希的 pyc,219 | memoryview |
| hashable 可哈希, 219 | 对象, 123 |
| hashfunc (C 类型), 207 | meta path finder 元路径查找器, 221 metaclass 元类, 221 |
| | METH_CLASS (<u>F</u> 置变量), 176 |
| IDLE, 219 | METH_COEXIST (<u>F</u> 置变量), 176 |
| immutable 不可变, 219 | METH_FASTCALL (匠置变量), 175 |
| import path 导入路径, 219 | METH_NOARGS (臣置变量), 176 |
| importer 导入器, 219 | METH_O (下 置变量), 176 |
| importing 导入, 219 | METH_STATIC (尼置变量), 176 |
| $incr_item(), 9, 10$ | METH_VARARGS (臣置变量), 175 |
| initproc(<i>C</i> 类型), 206 | method magic, 221 |
| inquiry(C类型),211 | special, 224 |
| instancemethod | 对象,113 |
| 对象, 112 | method 方法, 221 |
| int | method resolution order 方法解析顺 |
| 上 置函数,63 | 序, 221 |
| integer | MethodType (in module types), 111, 113 |
| 对象, 78 | module |
| interactive 交互, 220 | search path, 10, 134, 136 |
| interpreted 解释型,220 interpreter lock,138 | 对象,115 |
| interpreter shutdown 解释器关闭, 220 | module 模块, 221 |
| iterable 可迭代对象, 220 | module spec 模块规格, 221 |
| iterator 迭代器, 220 | modules (in module sys), 40, 134 |
| iternextfunc(C类型), 207 | ModuleType (in module types), 115 |
| K | MRO, 221 mutable 可变, 221 |
| key function 键函数, 220 | N |
| KeyboardInterrupt (built-in exception), 28 | |
| keyword argument 关键字参数, 220 | named tuple 具名元组, 221 |
| | namespace 命名空间,221 |
| L | namespace package 命名空间包,221 |
| lambda, 220 | nested scope 嵌套作用域, 222 |
| LBYL, 220 | new-style class 新式类, 222 newfunc(C类型), 206 |
| len | None |
| 国 函数, 60, 63, 65, 107, 109, 111 | 对象,78 |
| lenfunc(C类型),207 | |
| 7.5 - 4 | numeric |
| list | numeric 对象,78 |
| 对象,106 | numeric 对象,78 |
| 对象,106 list 列表, 220 | |
| 对象,106 list 列表, 220 list comprehension 列表推导式, 220 | 对象, 78 〇 |
| 对象,106 list 列表, 220 list comprehension 列表推导式, 220 loader 加载器, 221 | 对象,78 |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 | 对象,78 〇 object |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer | 对象,78 O object code,114 |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 | 对象,78 O object code,114 object 对象,222 |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 LONG_MAX,79 | 对象,78 O object code,114 object 对象,222 objobjargproc(C类型),207 |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 | 対象,78 O object code,114 object 対象,222 objobjargproc(C类型),207 objobjproc(C类型),207 OverflowError(built-in exception),79,80 |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 LONG_MAX,79 | 対象,78 O object code,114 object 対象,222 objobjargproc(C类型),207 objobjproc(C类型),207 OverflowError(built-in exception),79,80 P |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 LONG_MAX,79 | 对象,78 O object code,114 object 对象,222 objobjargproc(C类型),207 objobjproc(C类型),207 OverflowError(built-in exception),79,80 P package 包,222 |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 LONG_MAX,79 M magic | 对象,78 O object code,114 object 对象,222 objobjargproc(C类型),207 objobjproc(C类型),207 OverflowError(built-in exception),79,80 P package 包,222 package variable |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 LONG_MAX,79 M magic method,221 | 对象,78 O object code,114 object 对象,222 objobjargproc(C类型),207 objobjproc(C类型),207 OverflowError(built-in exception),79,80 P package 包,222 package variableall,40 |
| 对象,106 list 列表,220 list comprehension 列表推导式,220 loader 加载器,221 lock, interpreter,138 long integer 对象,78 LONG_MAX,79 M magic method,221 magic method 魔术方法,221 | 对象,78 O object code,114 object 对象,222 objobjargproc(C类型),207 objobjproc(C类型),207 OverflowError(built-in exception),79,80 P package 包,222 package variable |

| path | Py_EndInterpreter (C 函数), 144 |
|--------------------------------------|--------------------------------------------------------|
| module search, 10, 134, 136 | Py_EnterRecursiveCall (C 函数), 31 |
| path (in module sys), 10, 134, 136 | Py_eval_input (C 变量), 18 |
| path based finder 基于路径的查找器, | Py_Exit (C 函数), 39 |
| 222 | Py_ExitStatusException (C 函数), 151 |
| path entry 路径入口,222 | Py_False (C 变量), 81 |
| path entry finder 路径入口查找器,222 | Py_FatalError(C 函数), 39 |
| path entry hook 路径入口钩子,222 | Py_FatalError(),137 |
| path-like object 路径类对象,222 | Py_FdIsInteractive (C 函数), 35 |
| PEP, 223 | Py_file_input (C变量),18 |
| platform (in module sys), 136 | Py_Finalize (C 函数), 134 |
| portion 部分, 223 | Py_FinalizeEx(C 函数), 134 |
| positional argument 位置参数, 223 | Py_FinalizeEx(), 39, 134, 144 |
| pow | Py_FrozenFlag(C 变量), 132 |
| E 置函数, 61, 62 | Py_GetBuildInfo (C 函数), 137 |
| prefix,4 | Py_GetCompiler (C 函数), 136 |
| provisional API 暂定 API, 223 | Py_GetCopyright (C 函数), 136 |
| provisional package 暂定包,223 | Py_GETENV (C 宏), 4 |
| Py_ABS (C 宏), 4 | Py_GetExecPrefix (C 函数), 135 |
| Py_AddPendingCall (C 函数), 145 | Py_GetExecPrefix(),10 |
| Py_AddPendingCall(), 145 | Py_GetPath (<i>C</i> 函数), 136 |
| Py_AtExit (C 函数), 39 | Py_GetPath(), 10, 135, 136 |
| Py_BEGIN_ALLOW_THREADS, 138 | $Py_GetPlatform(C函数),136$ |
| Py_BEGIN_ALLOW_THREADS (C 宏), 141 | Py_GetPrefix (C 函数), 135 |
| Py_BLOCK_THREADS (C 宏), 141 | Py_GetPrefix(),10 |
| Py_buffer (C 类型),67 | Py_GetProgramFullPath(C 函数), 136 |
| Py_buffer.buf(C 成员),67 | Py_GetProgramFullPath(),10 |
| Py_buffer.format $(C 成员)$, 68 | Py_GetProgramName (C 函数), 135 |
| Py_buffer.internal (C 成员), 68 | Py_GetPythonHome (C 函数), 137 |
| Py_buffer.itemsize(C成员),67 | Py_GetVersion (C 函数), 136 |
| Py_buffer.len(C 成员),67 | Py_HashRandomizationFlag(C 变量), 132 |
| Py_buffer.ndim(C 成员),68 | Py_IgnoreEnvironmentFlag(C 变量), 132 |
| Py_buffer.obj(C 成员),67 | Py_INCREF (C 函数), 21 |
| Py_buffer.readonly(C成员),67 | Py_INCREF(),5 |
| Py_buffer.shape (C 成员), 68 | Py_Initialize (C 函数), 134 |
| Py_buffer.strides (C 成员), 68 | Py_Initialize(), 10, 135, 144 |
| Py_buffer.suboffsets (C 成员), 68 | Py_InitializeEx(C 函数), 134 |
| Py_BuildValue (C 函数), 49 | Py_InitializeFromConfig(C 函数), 158 |
| Py_BytesMain (C 函数), 15 | Py_InspectFlag (C变量), 132 |
| Py_BytesWarningFlag(C变量),132 | Py_InteractiveFlag(C 变量), 133 |
| Py_CHARMASK (C 宏), 4 | Py_IsInitialized (C 函数), 134 |
| Py_CLEAR (C 函数), 21 | Py_IsInitialized(), 10 |
| Py_CompileString(C函数),17 | Py_IsolatedFlag(C 变量), 133 |
| Py_CompileString(), 18, 19 | Py_LeaveRecursiveCall(C 函数), 31 |
| Py_CompileStringExFlags(C函数),18 | $_{\text{Py_LegacyWindowsFSEncodingFlag}}^{\text{-}}$ |
| Py_CompileStringFlags (C函数), 18 | 133 |
| Py_CompileStringObject (C函数), 18 | Py_LegacyWindowsStdioFlag(C 变量), 133 |
| Py_complex (C 类型), 82 | Py_Main (C 函数), 15 |
| Py_DebugFlag (C 变量), 132 | Py_MAX (C 宏), 4 |
| Py_DecodeLocale (C函数), 36 | $Py_MEMBER_SIZE(C 宏), 4$ |
| Py_DECREF (C 函数), 21 | Py_MIN (C 宏), 4 |
| Py_DECREF(),5 | Py_mod_create(C变量),118 |
| Py_DEPRECATED (C 宏), 5 | Py_mod_exec (C 变量), 119 |
| Py_DontWriteBytecodeFlag(C变量),132 | Py_NewInterpreter (C函数), 143 |
| Py_Ellipsis (C 变量), 123 | Py_None (C 变量), 78 |
| Py_EncodeLocale (C函数), 37 | Py_NoSiteFlag (C变量), 133 |
| Py_END_ALLOW_THREADS, 138 | Py_NotImplemented (C变量), 55 |
| Py_END_ALLOW_THREADS (C 宏), 141 | Py_NoUserSiteDirectory (C变量), 133 |

| Py_OptimizeFlag(C变量),133 | Py_UNICODE_IS_LOW_SURROGATE (C 宏), 89 |
|-------------------------------------------|-------------------------------------------------------------------------|
| Py_PreInitialize(C函数),153 | Py_UNICODE_IS_SURROGATE (C 宏), 89 |
| Py_PreInitializeFromArgs (C函数), 153 | Py_UNICODE_ISALNUM(C函数),89 |
| Py_PreInitializeFromBytesArgs (C 函数), | Py_UNICODE_ISALPHA(C函数),89 |
| 153 | Py_UNICODE_ISDECIMAL (C函数), 88 |
| Py_PRINT_RAW, 115 | Py_UNICODE_ISDIGIT(C函数),89 |
| Py_QuietFlag (C变量), 133 | Py_UNICODE_ISLINEBREAK (C 函数), 88 |
| Py_REFCNT (C 宏), 174 | Py_UNICODE_ISLOWER (C 函数), 88 |
| Py_ReprEnter (C 函数), 31 | Py_UNICODE_ISNUMERIC (C函数), 89 |
| Py_ReprLeave (C函数), 31 | Py_UNICODE_ISPRINTABLE (C 函数), 89 |
| Py_RETURN_FALSE (C 宏), 81 | Py_UNICODE_ISSPACE (C 函数), 88 |
| Py_RETURN_NONE (C 宏), 78 | Py_UNICODE_ISTITLE (C 函数), 88 |
| Py_RETURN_NOTIMPLEMENTED (C 宏), 55 | Py_UNICODE_ISUPPER(C函数),88 |
| Py_RETURN_RICHCOMPARE (C函数), 194 | Py_UNICODE_JOIN_SURROGATES (C 宏), 89 |
| Py_RETURN_TRUE (C 宏), 81 | Py_UNICODE_TODECIMAL (C函数), 89 |
| Py_RunMain (C函数), 162 | Py_UNICODE_TODIGIT (C 函数), 89 |
| Py_SetPath (C函数), 136 | Py_UNICODE_TOLOWER (C 函数), 89 |
| Py_SetPath(), 136 | Py_UNICODE_TONUMERIC (C函数), 89 |
| Py_SetProgramName (C函数), 135 | Py_UNICODE_TOTITLE (C函数), 89 |
| Py_SetProgramName(), 10, 134136 | Py_UNICODE_TOUPPER(C函数), 89 |
| Py_SetPythonHome (C函数), 137 | Py_UNREACHABLE ($C \otimes \chi$), 4 |
| $Py_SetStandardStreamEncoding$ (C 函数), | Py_UNUSED (C 宏), 5 |
| 135 | $\text{Py_onosed}(C \Delta)$, S Py_VaBuildValue (C 函数), S 0 |
| Py_single_input (C变量), 19 | $PY_{VECTORCALL_ARGUMENTS_OFFSET$ (C 变量), |
| | FI_VECTORCALL_ARGOMENTS_OFF SET (C 文里), 59 |
| Py_SIZE (C 宏), 174 | |
| PY_SSIZE_T_MAX, 80 | Py_VerboseFlag (C 变量), 133 |
| Py_STRINGIFY (C 宏), 4 | Py_VISIT (C 函数), 211 |
| Py_TPFLAGS_BASE_EXC_SUBCLASS (F置变量), | Py_XDECREF (C 函数), 21 |
| 191 | Py_XDECREF(), 10 |
| Py_TPFLAGS_BASETYPE (F置变量), 190 | Py_XINCREF (C 函数), 21 |
| Py_TPFLAGS_BYTES_SUBCLASS (F置变量), 191 | PyAnySet_Check (C 函数), 110 |
| Py_TPFLAGS_DEFAULT (F 置变量), 191 | PyAnySet_CheckExact (C 函数), 110 |
| Py_TPFLAGS_DICT_SUBCLASS (โ置变量), 191 | PyArg_Parse (C 函数), 48 |
| Py_TPFLAGS_HAVE_FINALIZE (F置变量), 192 | PyArg_ParseTuple (C函数), 48 |
| Py_TPFLAGS_HAVE_GC (F置变量), 191 | PyArg_ParseTupleAndKeywords(C函数),48 |
| Py_TPFLAGS_HEAPTYPE (F置变量), 190 | PyArg_UnpackTuple (C函数),48 |
| Py_TPFLAGS_LIST_SUBCLASS (臣置变量), 191 | PyArg_ValidateKeywordArguments (C 函数), |
| Py_TPFLAGS_LONG_SUBCLASS (F置变量), 191 | 48 |
| Py_TPFLAGS_METHOD_DESCRIPTOR (臣置变量), | PyArg_VaParse (C函数),48 |
| 191 | PyArg_VaParseTupleAndKeywords (C 函数), |
| Py_TPFLAGS_READY (F置变量), 190 | 48 |
| Py_TPFLAGS_READYING (F置变量), 191 | PyASCIIObject (C 类型), 86 |
| Py_TPFLAGS_TUPLE_SUBCLASS (臣置变量), 191 | PyAsyncMethods (C 类型), 205 |
| Py_TPFLAGS_TYPE_SUBCLASS (臣置变量), 191 | PyAsyncMethods.am_aiter(C 成员), 206 |
| Py_TPFLAGS_UNICODE_SUBCLASS (匠置变量), | PyAsyncMethods.am_anext(C 成员), 206 |
| 191 | PyAsyncMethods.am_await(C 成员), 206 |
| Py_tracefunc (C 类型), 145 | PyBool_Check (C 函数), 81 |
| Py_True (C 变量), 81 | PyBool_FromLong(C 函数), 81 |
| Py_tss_NEEDS_INIT (C 宏), 147 | PyBUF_ANY_CONTIGUOUS (C 宏), 69 |
| Py_tss_t (<i>C</i> 类型), 147 | PyBUF_C_CONTIGUOUS (C 宏), 69 |
| Py_TYPE (C 宏), 174 | PyBUF_CONTIG (C $\dot{\mathbf{z}}$), 70 |
| Py_UCS1 (C 类型), 86 | PyBUF_CONTIG_RO (C 宏), 70 |
| Py_UCS2 (C 类型), 86 | PyBUF_F_CONTIGUOUS (C 宏), 69 |
| Py_UCS4 (C 类型), 86 | PyBUF_FORMAT ($C \gtrsim 1,69$ |
| Py_UNBLOCK_THREADS (C 宏), 141 | PyBUF_FULL (C 宏), 70 |
| Py_UnbufferedStdioFlag(C变量), 133 | PyBUF_FULL_RO $(C \hat{\mathbf{x}})$, 70 |
| Py_UNICODE (C 类型), 86 | PyBUF_INDIRECT (C 宏), 69 |
| Py_UNICODE_IS_HIGH_SURROGATE (C 宏), 89 | PyBUF_ND (C 宏), 69 |
| | _ \ \ - \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ |

| PyBUF_RECORDS (C 宏), 70 | PyCapsule_GetDestructor (C 函数), 125 |
|------------------------------------------|-------------------------------------------|
| PyBUF_RECORDS_RO (C 宏), 70 | PyCapsule_GetName (C 函数), 125 |
| PyBUF_SIMPLE (C 宏), 69 | PyCapsule_GetPointer (C 函数), 125 |
| PyBUF_STRIDED (C 宏), 70 | PyCapsule_Import (C 函数), 125 |
| PyBUF_STRIDED_RO (C 宏), 70 | PyCapsule_IsValid (\emph{C} 函数), 125 |
| PyBUF_STRIDES (C 宏), 69 | PyCapsule_New (C 函数), 124 |
| PyBUF_WRITABLE (C 宏), 69 | PyCapsule_SetContext (C 函数), 125 |
| PyBuffer_FillContiguousStrides (C函数), | PyCapsule_SetDestructor (C 函数), 125 |
| 72 | PyCapsule_SetName (C 函数), 125 |
| PyBuffer_FillInfo (C 函数),72 | PyCapsule_SetPointer (C 函数), 126 |
| PyBuffer_FromContiguous (C函数),72 | PyCell_Check (C 函数), 113 |
| PyBuffer_GetPointer(C函数),72 | PyCell_GET (<i>C</i> 函数), 113 |
| PyBuffer_IsContiguous (C 函数),72 | PyCell_Get (<i>C</i> 函数), 113 |
| PyBuffer_Release (C 函数),71 | PyCell_New (C 函数), 113 |
| PyBuffer_SizeFromFormat(C 函数),72 | PyCell_SET (C 函数), 114 |
| PyBuffer_ToContiguous (C 函数),72 | PyCell_Set (C 函数), 114 |
| PyBufferProcs, 66 | PyCell_Type (C变量), 113 |
| PyBufferProcs (C 类型), 204 | PyCellObject (C 类型), 113 |
| PyBufferProcs.bf_getbuffer(C 成员), 204 | PyCFunction (C 类型), 175 |
| PyBufferProcs.bf_releasebuffer $(C$ 成员), | PyCFunctionWithKeywords(C 类型), 175 |
| 205 | PyCode_Check (C 函数), 114 |
| PyByteArray_AS_STRING(C 函数),86 | PyCode_GetNumFree(C 函数), 114 |
| PyByteArray_AsString (C 函数), 85 | PyCode_New (C 函数), 114 |
| PyByteArray_Check (C 函数), 85 | PyCode_NewEmpty (C 函数), 114 |
| PyByteArray_CheckExact (C 函数), 85 | PyCode_NewWithPosOnlyArgs(C 函数), 114 |
| PyByteArray_Concat (C 函数), 85 | PyCode_Type (C变量), 114 |
| PyByteArray_FromObject(C 函数), 85 | PyCodec_BackslashReplaceErrors (C 函数), |
| PyByteArray_FromStringAndSize (C 函数), | 53 |
| 85 | PyCodec_Decode (C 函数), 52 |
| PyByteArray_GET_SIZE(C 函数),86 | PyCodec_Decoder (C 函数), 53 |
| PyByteArray_Resize (C 函数), 85 | PyCodec_Encode (C 函数), 52 |
| PyByteArray_Size(C函数),85 | PyCodec_Encoder (C 函数), 53 |
| PyByteArray_Type (C 变量), 85 | PyCodec_IgnoreErrors (C 函数), 53 |
| PyByteArrayObject (C 类型), 85 | PyCodec_IncrementalDecoder(C 函数), 53 |
| PyBytes_AS_STRING (C 函数), 84 | PyCodec_IncrementalEncoder(C 函数), 53 |
| PyBytes_AsString (C 函数), 84 | PyCodec_KnownEncoding (C 函数), 52 |
| PyBytes_AsStringAndSize (C 函数), 84 | PyCodec_LookupError(C 函数), 53 |
| PyBytes_Check (C 函数), 83 | PyCodec_NameReplaceErrors(C 函数), 54 |
| PyBytes_CheckExact (C 函数), 83 | PyCodec_Register(C 函数), 52 |
| PyBytes_Concat (C 函数), 85 | PyCodec_RegisterError(C 函数), 53 |
| PyBytes_ConcatAndDel(C 函数), 85 | PyCodec_ReplaceErrors (C 函数), 53 |
| PyBytes_FromFormat (C 函数), 84 | PyCodec_StreamReader(C 函数), 53 |
| PyBytes_FromFormatV(C 函数),84 | PyCodec_StreamWriter(C 函数), 53 |
| PyBytes_FromObject(C 函数), 84 | PyCodec_StrictErrors (C 函数), 53 |
| PyBytes_FromString (C 函数), 83 | PyCodec_XMLCharRefReplaceErrors (C 🕉 |
| PyBytes_FromStringAndSize(C 函数), 83 | 数),53 |
| PyBytes_GET_SIZE (C 函数), 84 | PyCodeObject (C 类型),114 |
| PyBytes_Size(C函数),84 | PyCompactUnicodeObject (C 类型), 86 |
| PyBytes_Type (C变量),83 | PyCompilerFlags (C 类型), 19 |
| PyBytesObject (C 类型),83 | PyCompilerFlags.cf_feature_version (C |
| PyCallable_Check (C函数), 57 | 成员), 19 |
| PyCallIter_Check (C 函数), 121 | PyCompilerFlags.cf_flags(C 成员), 19 |
| PyCallIter_New (C函数), 121 | PyComplex_AsCComplex(C函数),83 |
| PyCallIter_Type (C变量), 121 | PyComplex_Check (C函数), 83 |
| PyCapsule (C 类型), 124 | PyComplex_CheckExact (C 函数), 83 |
| PyCapsule_CheckExact (C 函数), 124 | PyComplex_FromCComplex(C函数),83 |
| PyCapsule_Destructor (C 类型), 124 | PyComplex_FromDoubles (C函数), 83 |
| PyCapsule GetContext (C 函数) 125 | PyComplex ImagAsDouble(C函数).83 |

| Pycomplex.RealAsDouble (C為美), 83 PycomplexObject (C表雙), 83 PycomplexObject (C表雙), 83 PycomplexObject (C表雙), 83 Pyconfig_Clear (C 壽稅), 154 Pyconfig_Loll LisolatedConfig (C 壽敎), 154 Pyconfig_InitPythonConfig (C 壽敎), 154 Pyconfig_Eschayu (C 壽稅), 154 Pyconfig_Sechayu (C 壽稅), 154 Pyconfig_Devidetring (C 壽稅), 155 Pyconfig_Dase_Executable (C 歲稅), 155 Pyconfig_base_executable (C 歲稅), 155 Pyconfig_base_executable (C 歲稅), 155 Pyconfig_obse_executable (C 歲Ი), 155 | Discompley Deally Double (C 或数) 92 | Disconfig above allog count (C & B) 157 |
|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------|-----------------------------------------|
| PyConfig (C 表型), 154 PyConfig_Clear (C 高载), 154 PyConfig_InitPythonConfig (C 高载), 154 PyConfig_Eschapt (C 高载), 154 PyConfig_Sechapt (C 高载), 154 PyConfig_Sechapt (C 高载), 154 PyConfig_Set PytesArgy (C 高载), 155 PyConfig_Set PytesArgy (C 高载), 156 PyConfig_Set PytesArgy (C 高载), 156 PyConfig_Set PytesArgy (C 高载), 156 PyConfig_Set PytesArgy (C name PytesArgy (C name Pyt | | |
| Pyconfig (\mathcal{E} , \mathcal{E}), 154 Pyconfig_InitIsolatedConfig (\mathcal{E} , \mathcal{E}), 157 Pyconfig_InitIsolatedConfig (\mathcal{E} , \mathcal{E}), 157 Pyconfig_EstArgy (\mathcal{E} , \mathcal{E}), 154 Pyconfig_SetArgy (\mathcal{E} , \mathcal{E}), 154 Pyconfig_SetArgy (\mathcal{E} , \mathcal{E}), 154 Pyconfig_SetBytesArgy (\mathcal{E} , \mathcal{E}), 154 Pyconfig_SetBytesArgy (\mathcal{E} , \mathcal{E}), 154 Pyconfig_SetBytesArgy (\mathcal{E} , \mathcal{E}), 155 Pyconfig_SetString (\mathcal{E} , \mathcal{E}), 155 Pyconfig_SetSetString (\mathcal{E} , \mathcal{E}), 155 Pyconfig_SetString (| | |
| PyConfig_Clear(C病検), 154 PyConfig_InitPythonConfig(C病検), 154 PyConfig_Read(C病検), 154 PyConfig_SetArgy(C病検), 154 PyConfig_SetArgy(C病検), 154 PyConfig_SetBytesArgy(C病検), 154 PyConfig_SetBytesArgy(C病検), 154 PyConfig_SetWideString(C病検), 154 PyConfig_SetWideString(C病検), 155 PyConfig_SetWideString(C病検), 155 PyConfig_argy(C成黄), 155 PyConfig_base_exec_prefix(C成黄), 155 PyConfig_base_exec_prefix(C成黄), 155 PyConfig_base_exec_prefix(C成黄), 155 PyConfig_base_exec_prefix(C成黄), 155 PyConfig_obutFared_stdio(C成黄), 155 PyConfig_check_hash_pycs_mode(C成黄), 155 PyConfig_configure_c_stdio(C成黄), 155 PyConfig_cexec_prefix(C成黄), 155 PyConfig_dev_mode(C成黄), 155 PyConfig_filesystem_errors(C成黄), 155 PyConfig_filesystem_errors(C成黄), 155 PyConfig_inport_time(C成贵), 156 PyConfig_install_signal_handlers(C成青), 156 PyConfig_install_signal_handlers(C成青), 156 PyConfig_install_signal_handlers(C成青), 156 PyConfig_install_signal_handlers(C成青), 156 PyConfig_install_signal_handlers(C成青), 156 PyConfig_nation_level(C成黄), 156 PyConfig_nation_level(C成青), 156 PyConfig_nation_level(C成青), 156 PyConfig_nation_level(C成青), 156 PyConfig_nation_level(C成青), 156 PyConfig_nation_level(C成青), 156 PyConfig_nation_level(C成青), 157 PyConfig_nation_level(C成青), 156 PyConfig_nation_level(C成青), 157 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 157 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 157 PyConfig_nation_level(Ckgh), 157 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 157 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 156 PyConfig_nation_level(Ckgh), 157 PyC | | |
| PyConfig.InitEvalatedConfig (C 為致), 154 PyConfig.actio_encoding (C 成贵), 157 PyConfig.Read(C 函致), 154 PyConfig.Read(C 函致), 154 PyConfig.SetAytesArgy (C 函数), 154 PyConfig.SetBytesArgy (C 函数), 154 PyConfig.SetBytesArgy (C 函数), 154 PyConfig.SetString(C 函数), 154 PyConfig.SetString(C 函数), 155 PyConfig.SetString(C 函数), 155 PyConfig.base_exec_prefix(C 成贵), 155 PyConfig.base_exec_troor(C 成贵), 155 PyConfig.base_exec_troor(C 成贵), 155 PyConfig.base_exec_troor(C 成贵), 155 PyConfig.base_exec_troor(C 成贵), 155 PyConfig.check_hash_pycs_mode(C 成贵), 155 PyConfig.check_hash_pycs_mode(C 成贵), 155 PyConfig.dev_mode(C 成贵), 155 PyConfig.dev_mode(C 成贵), 155 PyConfig.cence_bash_pycs_mode(C | | |
| PyConfig_InitPythonConfig(\hat{C} 高载), 154 PyConfig_Read(\hat{C} 高载), 154 PyConfig_SethytesArgy(\hat{C} 高载), 155 PyConfig_SethytesArgy(\hat{C} 高载), 155 PyConfig_argy(\hat{C} 高载), 155 PyConfig_argy(\hat{C} 高载), 155 PyConfig_argy(\hat{C} 高载), 155 PyConfig_argy(\hat{C} 高载), 155 PyConfig_base_prefix(\hat{C} 成员), 155 PyConfig_base_prefix(\hat{C} 成员), 155 PyConfig_buffered_statio(\hat{C} 成员), 155 PyConfig_config_rec_stdio(\hat{C} 成员), 155 PyConfig_configure_stdio(\hat{C} 成员), 155 PyConfig_configure_stdio(\hat{C} 成员), 155 PyConfig_configure_stdio(\hat{C} 成员), 155 PyConfig_configure_stdio(\hat{C} 成员), 155 PyConfig_config_executable(\hat{C} 成员), 155 PyConfig_filesystem_errors(\hat{C} 成员), 155 PyConfig_insport_time(\hat{C} 成员), 156 PyConfig_install_signal_handlers(\hat{C} 成员), 156 PyConfig_install_signal_handlers(\hat{C} 成员), 156 PyConfig_install_signal_handlers(\hat{C} 成员), 156 PyConfig_nodule_search_paths(\hat{C} 成员), 156 PyConfig_nodule_search_paths(\hat{C} 成员), 156 PyConfig_nodule_search_paths(\hat{C} 成员), 156 PyConfig_parser_debug(\hat{C} 成员), 156 PyConfig_parser_debug(\hat{C} 成员), 157 PyConfig_program_name(\hat{C} 成员), 157 PyConfig_quiet(\hat{C} 成员), 157 PyConfig_quiet(\hat{C} 成员), 157 PyConfig_quiet(\hat{C} 成员), 157 PyConfig_program_name(\hat{C} 成员), 157 PyConfig_quiet(\hat{C} | | |
| PyConfig_Read (C 為我), 154 PyConfig_SetArgv (C 為教), 154 PyConfig_SetString (C 為教), 154 PyConfig_SetString (C 為教), 154 PyConfig_SetString (C 為教), 154 PyConfig_SetString (C 為教), 155 PyConfig_setString (C 成贵), 155 PyConfig_base_exec_prefix (C 成贵), 155 PyConfig_base_exec_trefix (C 成贵), 155 PyConfig_base_executable (C 成贵), 155 PyConfig_base_executable (C 成贵), 155 PyConfig_buffered_stdio (C 成贵), 155 PyConfig_chek_bash_pycs_mode (C 成贵), 155 PyConfig_chek_bash_pycs_mode (C 成贵), 155 PyConfig_dev_mode (C 成贵), 155 PyConfig_dev_mode (C 成贵), 155 PyConfig_dev_mode (C 成贵), 155 PyConfig_dev_mode (C 成贵), 155 PyConfig_executable (C 成贵), 155 PyConfig_stalthandler (C 成贵), 155 PyConfig_filesystem_encoding (C 成贵), 155 PyConfig_install_signal_handlers (C 成贵), 156 PyConfig_install_signal_handlers (C 成贵), 156 PyConfig_module_search_paths_set (C 成贵), 156 PyConfig_module_search_paths_set (C 成贵), 156 PyConfig_nodule_search_paths_set (C 成贵), 156 PyConfig_parse_argv (C 成贵), 156 PyConfig_parse_argv (C 成贵), 156 PyConfig_parse_rdebug (C 成贵), 156 PyConfig_parse_rdebug (C 成贵), 156 PyConfig_program_name (C 成贵), 157 PyConfig_program_name (C k贵), 1 | | |
| PyConfig_SetBytesArgv(C 為教), 154 PyConfig_SetBytesArgv(C 為教), 154 PyConfig_SetBytesArgv(C 為教), 154 PyConfig_SetString(C 為教), 154 PyConfig_SetString(C 為教), 155 PyConfig_SetWideString(C 為教), 155 PyConfig_argv(C 成页), 155 PyConfig_base_exec_prefix(C 成页), 155 PyConfig_base_exec_table(C 成页), 155 PyConfig_obets_warning(C 成页), 155 PyConfig_obets_warning(C 成页), 155 PyConfig_configure_c_stdic(C 成页), 155 PyConfig_configure_c_stdic(C 成页), 155 PyConfig_dev_mode(C 成页), 155 PyConfig_dev_mode(C 成页), 155 PyConfig_faulthandler(C 成页), 155 PyConfig_faulthandler(C 成页), 155 PyConfig_faulthandler(C 成页), 155 PyConfig_insprt_time(C 成页), 156 PyConfig_insprt_time(C 成页), 156 PyConfig_insprt_time(C 成页), 156 PyConfig_insprt_time(C 成页), 156 PyConfig_module_search_paths_set(C 成页), 156 PyConfig_module_search_paths_set(C 成页), 156 PyConfig_oprogram_name(C 成页), 156 PyConfig_parser_debug(C 成页), 156 PyConfig_parser_debug(C 成页), 156 PyConfig_program_name(C 成页), 157 PyConfig_program_name(C 成页), 157 PyConfig_program_name(C 成页), 157 PyConfig_program_name(C 成页), 157 PyConfig_qprogram_name(C 成页), 157 PyConfig_qprogram_name(C 成页), 157 PyConfig_qprogram_name(C 成页), 157 PyConfig_quiet(C 成页), 157 PyConfig_qprogram_name(C mander debug not program_name(C mander debug not program_name(C mander debug not program_name(C mander debug not program_name(C mander debug not program_name(| | |
| PyConfig_SetBytesAtyry(C 函数), 154 PyConfig_SetWidesString(C 函数), 154 PyConfig_SetWidesString(C 函数), 155 PyConfig_Largy(C 成员), 155 PyConfig_base_exec_prefix(C 成员), 155 PyConfig_bytes_warning(C 成员), 155 PyConfig_bytes_warning(C 成员), 155 PyConfig_check_hash_pycs_mode(C 成员), 155 PyConfig_calump_refs(C 成员), 155 PyConfig_dawp_refs(C 成员), 155 PyConfig_dawp_refs(C 成员), 155 PyConfig_exec_prefix(C 成员), 155 PyConfig_exec_prefix(C 成员), 155 PyConfig_sileasystem_encoding(C 成员), 155 PyConfig_fileasystem_encoding(C 成员), 155 PyConfig_fileasystem_encoding(C 成员), 155 PyConfig_inport_time(C 成员), 156 PyConfig_inpart_time(C 成员), 156 PyConfig_inpart_time(C 成员), 156 PyConfig_inpart_time(C 成员), 156 PyConfig_inpart_time(C 成员), 156 PyConfig_indows_stdio(C 成员), 156 PyConfig_malloc_stats(C 成员), 156 PyConfig_malloc_stats(C 成员), 156 PyConfig_parse_argy(C 成员), 156 PyConfig_parse_argy(C 成员), 156 PyConfig_parse_argy(C 成员), 156 PyConfig_parse_argy(C 成员), 157 PyConfig_prefix(C 成员), 157 PyConfig_prefix(C 成员), 157 PyConfig_predix(C 成员), 157 PyConfig_predix(C 成员), 157 PyConfig_prefix(C 成员), 157 PyConfig_prefix(C 成员), 157 PyConfig_predix(C 成员), 157 PyConfig_predix(C 成员), 157 PyConfig_predix(C 成员), 157 PyConfig_prefix(C 成员), 157 PyConfig_predix(C K K K K K K K K K K K K K K K K K K K | | |
| PyConfig_SetBytesString(C 為我), 154 PyConfig_SetWideStringList (C 函裁), 155 PyConfig_argv (C 成员), 155 PyConfig_base_exec_prefix (C 成员), 155 PyConfig_base_prefix (C 成员), 155 PyConfig_base_prefix (C 成员), 155 PyConfig_check_hash_pycs_mode (C 成员), 155 PyConfig_check_hash_pycs_mode (C 成员), 155 PyConfig_check_hash_pycs_mode (C 成员), 155 PyConfig_dump_refs (C 成员), 155 PyConfig_dump_refs (C 成员), 155 PyConfig_dump_refs (C 成员), 155 PyConfig_sexec_prefix (C 成员), 155 PyConfig_sexec_prefix (C 成员), 155 PyConfig_filesystem_ercordin (C 成员), 155 PyConfig_filesystem_ercordin (C 成员), 155 PyConfig_inbate (C 成员), 156 PyConfig_inbate (C 成员), 156 PyConfig_insport_time (C 成员), 156 PyConfig_insport_time (C 成员), 156 PyConfig_insolation_level (C 成员), 156 PyConfig_indle_search_paths_c(C 成员), 156 PyConfig_nalloc_stats (C 成员), 157 PyConfig_nalloc_stats (C 成员), 156 PyConfig_nalloc_stats (C 成员), 156 PyConfig_nalloc_stats (C 成员), 157 PyConfig_nalloc_stats (C 成员), 157 PyConfig_nalloc_stats (C 成员), 156 PyConfig_nalloc_stats (C 成员), 157 PyConfig_nalloc_stats (C 成员), 157 PyConfig_nalloc_stats (C 成员), 157 PyConfig_nalloc_stats (C | | |
| PyConfig_SetString(C 為敎), 154 PyConfig_sary(C 為敎), 155 PyConfig_hase_exec_prefix(C 歲敎), 155 PyConfig_hase_exec_prefix(C 歲敎), 155 PyConfig_base_exec_prefix(C 歲敎), 155 PyConfig_check_hash_pycs_mode(C 歲敎), 155 PyConfig_check_hash_pycs_mode(C 歲敎), 155 PyConfig_configure_c_stdio(C 歲敎), 155 PyConfig_dump_refs(C 歲敎), 155 PyConfig_dump_refs(C 歲敎), 155 PyConfig_dump_refs(C 歲敎), 155 PyConfig_exec_prefix(C 歲敎), 155 PyConfig_faulthandler(C 成敎), 155 PyConfig_faulthandler(C 成敎), 155 PyConfig_faulthandler(C 成敎), 155 PyConfig_filesystem_errors(C 成敎), 156 PyConfig_inport_Lime(C 歲敎), 156 PyConfig_inport_Lime(C 成敎), 156 PyConfig_inslatlal_signal_handlers(C 成敎), 156 PyConfig_inslated(C 成敎), 156 PyConfig_inslated(C k dô), 156 PyConfig_module_search_paths_set(C 成敎), 156 PyConfig_module_search_paths_set(C 成敎), 156 PyConfig_naser_debug(C 成敎), 156 PyConfig_parse_argv(C 成敎), 156 PyConfig_parse_argv(C 成敎), 156 PyConfig_parse_argv(C 成敎), 156 PyConfig_parse_refix(C 成敎), 157 PyConfig_prefix(C 成敎), 157 PyConfig_prefix(C 成敎), 157 PyConfig_prefix(C 成敎), 157 PyConfig_prefix(C 成敎), 157 PyConfig_rum_command(C 成敎), 157 PyConfig_rum_command(C c ondown), 157 PyConfig_rum_command(C c ondown), 158 PyConfig_rum_command(C c ondown), 158 PyConfig_rum_command(C c ondown), 155 PyConfig_rum_command(C c ondown), 155 PyConfig_rum_command(C c ondown), 155 PyConfig_rum_command(C c ondown), 156 Py | | |
| PyConfig.SetWideStringList(C 函数), 154 PyConfig.argw(C 成页), 155 PyConfig.base_exec_prefix(C 成页), 155 PyConfig.base_exectable (C 成页), 155 PyConfig.base_pexetuable (C 成页), 155 PyConfig.base_pexetuable (C 成页), 155 PyConfig.base_pexetuable (C 成页), 155 PyConfig.bytes_warning(C 成页), 155 PyConfig.check_hash_pycs_mode (C 成页), 155 PyConfig.check_hash_pycs_mode (C 成页), 155 PyConfig.check_hash_pycs_mode (C 成页), 155 PyConfig.check_hash_pycs_mode (C 成页), 155 PyConfig.dwmp_refs(C 成页), 155 PyConfig.fileaystem_encoding (C 成页), 155 PyConfig.fileaystem_encoding (C 成页), 155 PyConfig.fileaystem_errors(C 成页), 155 PyConfig.inport_time(C 成页), 156 PyConfig.inport_time(C 成页), 156 PyConfig.install_signal_handlers(C 成页), 156 PyConfig.install_signal_handlers(C 成页), 156 PyConfig.install_signal_handlers(C 成页), 156 PyConfig.malloc_stats(C 成页), 156 PyConfig.malloc_stats(C 成页), 156 PyConfig.module_search_paths_set(C 成页), 156 PyConfig.module_search_paths_set(C 成页), 156 PyConfig.parse_argw(C 成页), 157 PyConfig.pycache_Drefix(C 成页), 157 PyConfig.pycache_Drefix(C 成页), 157 PyConfig.pycache_Drefix(C 成页), 157 PyConfig.quiet(C 成页), 157 PyConfig.pycache_Drefix(C 成页), | | |
| PyConfig. argy (C 成员), 155 PyConfig. base_exec_utable (C 成员), 155 PyConfig. base_executable (C 成员), 155 PyConfig. base_prefix (C 成员), 155 PyConfig. buffered_stdio (C 成员), 155 PyConfig. bytes_warning (C 成员), 155 PyConfig. check_hash_pycs_mode (C 成员), 155 PyConfig. comptage (C 成员), 155 PyConfig. dev_mode (C 成员), 155 PyConfig. dev_mode (C 成员), 155 PyConfig. executable (C 成员), 155 PyConfig. fallehandler (C 成员), 155 PyConfig. fallehandler (C 成员), 155 PyConfig. filesystem_encoding (C 成员), 155 PyConfig. insport_time (C 成员), 156 PyConfig. insport_time (C 成员), 156 PyConfig. insport_compand(C 成员), 156 PyConfig. parse_argy (C 成员), 157 PyConfig. prefix (C 成员), 157 PyConfig. program_name (C 成员), 157 PyConfig. pythonpath_env (C 成员), 157 PyConfig. run_command (C | | |
| PyConfig. base_exec_prefix (C 成员), 155 PyConfig. base_prefix (C 成员), 155 PyConfig. bufered_stdio (C 成员), 155 PyConfig. bytes_warning (C 成员), 155 PyConfig. check_hash_pycs_mode (C 成员), 155 PyConfig. check_hash_pycs_mode (C 成员), 155 PyConfig. configure_c_stdio (C 成员), 155 PyConfig. dev_mode (C 成员), 155 PyConfig. filesystem_ercoding (C 成员), 155 PyConfig. filesystem_ercoding (C 成员), 155 PyConfig. inspect (C 成员), 156 PyConfig. inspect (C 成员), 156 PyConfig. inspect (C 成员), 156 PyConfig. interactive (C 成员), 156 PyConfig. interactive (C 成员), 156 PyConfig. module_search_paths_ct (C 成员), 156 PyConfig. parse_argy (C 成员), 157 PyConfig. prefix (C 成员), 157 PyConfig. prefix (C 成员), 157 PyConfig. prefix (C 成员), 157 PyConfig. quiet (C 成员), 157 PyConfig. quiet (C 成员), 157 PyConfig. run_command (C 成员), 157 PyConfig. run_comma | | |
| PyConfig. base_executable (C 成 页), 155 PyConfig. buffered_stdio (C 成 页), 155 PyConfig. buffered_stdio (C 成 页), 155 PyConfig. bytes_warning (C 成 页), 155 PyConfig. check_hash_pycs_mode (C 成 页), 155 PyConfig. configure_c_stdio (C 成 页), 155 PyConfig. dev_mode (C 成 页), 155 PyConfig. dev_mode (C 成 页), 155 PyConfig. dev_mode (C 成 页), 155 PyConfig. deve_mode (C 成 页), 155 PyConfig. deve_prefix (C 成 页), 155 PyConfig. dexecutable (C 成 页), 155 PyConfig. faulthandler (C 成 页), 155 PyConfig. faulthandler (C 成 页), 155 PyConfig. filesystem_enrooding (C 成 页), 155 PyConfig. filesystem_errors (C 成 页), 155 PyConfig. inspect (C 成 页), 156 PyConfig. inspect (C 成 页), 156 PyConfig. inspect (C 成 页), 156 PyConfig. install_signal_handlers (C 成 页), 156 PyConfig. install_signal_handlers (C 成 页), 156 PyConfig. install_signal_handlers (C 成 页), 156 PyConfig. module_search_paths_ct (C 成 页), 156 PyConfig. module_search_paths_ct (C 成 页), 156 PyConfig. parse_argy (C 成 页), 157 PyConfig. program_name (C 成 页), 157 PyConfig. program_name (C 成 页), 157 PyConfig. quiet (C 成 页), 157 PyConfig. run_command (C 成 页), 157 PyConfig. run_ | | |
| PyConfig.base_prefix (C 成员), 155 PyConfig.buffered_stdio (C 成员), 155 PyConfig.check_hash_pycs_mode (C 成员), 155 PyConfig.check_hash_pycs_mode (C 成员), 155 PyConfig.check_mode (C 成员), 155 PyConfig.dev_mode (C 成员), 155 PyConfig.dwmp_refs (C 成员), 155 PyConfig.dwmp_refs (C 成员), 155 PyConfig.exec_prefix (C 成员), 155 PyConfig.exec_table (C 成员), 155 PyConfig.exec_table (C 成员), 155 PyConfig.faulthandler (C 成员), 155 PyConfig.filesystem_errors (C 成员), 155 PyConfig.filesystem_errors (C 成员), 155 PyConfig.insence (C 成员), 155 PyConfig.insence (C 成员), 155 PyConfig.insence (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.install_signal_handlers (C 成员), 156 PyConfig.interactive (C 成员), 156 PyConfig.interactive (C 成员), 156 PyConfig.module_search_paths_ct (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.program_name (C 成员), 156 PyConfig.parser_debug (C 成员), 157 PyConfig.pycache_prefix (C 成员), 157 PyConfig.pycache_prefix (C 成员), 157 PyConfig.quiet (| | |
| PyConfig. buffered_stdio (C 成员), 155 PyConfig. bytes_warning (C 成员), 155 PyConfig.check_hash_pycs_mode (C 成员), 155 PyConfig.configure_c_stdio (C 成员), 155 PyConfig.dev_mode (C 成员), 155 PyConfig.dev_mode (C 成员), 155 PyConfig.dwmp_refs (C 成员), 155 PyConfig.dwmp_refs (C 成员), 155 PyConfig.dwmp_refs (C 成员), 155 PyConfig.faulthandler (C 成员), 155 PyConfig.faulthandler (C 成员), 155 PyConfig.filesystem_encoding (C 成员), 155 PyConfig.filesystem_encoding (C 成员), 155 PyConfig.shash_seed (C 成员), 155 PyConfig.inber(C 成员), 156 PyConfig.import_time (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.inedule_search_paths_set (C 成员), 156 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths_set (C 成员), 156 PyConfig.optimization_level (C 成员), 156 PyConfig.parser_debug (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.qui | | |
| PyConfig. bytes_warning (C 成 员), 155 PyConfig. check_hash_pycs_mode (C 成 员), 155 PyConfig. configure_c_stdio (C 成 员), 155 PyConfig. configure_c_stdio (C 成 员), 155 PyConfig. dev_mode (C 成 员), 155 PyConfig. dev_mode (C 成 员), 155 PyConfig. damp_refs (C 成 员), 155 PyConfig. exec_prefix (C 成 员), 155 PyConfig. faulthandler (C 成 员), 155 PyConfig. faulthandler (C 成 员), 155 PyConfig. filesystem_encoding (C 成 员), 155 PyConfig. filesystem_errors (C 成 员), 155 PyConfig. inlesystem_errors (C 成 员), 155 PyConfig. hash_seed (C 成 员), 156 PyConfig. inspect (C 成 员), 156 PyConfig. inspect (C 成 员), 156 PyConfig. install_signal_handlers (C 成 员), 156 PyConfig. interactive (C 成 员), 156 PyConfig. interactive (C 成 员), 156 PyConfig. malloc_stats (C 成 员), 156 PyConfig. module_search_paths (C 成 员), 156 PyConfig. module_search_paths (C 成 员), 156 PyConfig. parser_debug (C 成 员), 157 PyConfig. pycache_prefix (C 成 员), 157 PyConfig. quiet (C 成 员), 157 PyConfig. run_command (C 成 B), 157 PyConfig. run_command (C M B), 157 PyConfi | | |
| PyConfig.check_hash_pycs_mode (C 成 页), 155 PyConfig.configure_c_stdio(C 成 页), 155 PyConfig.dow_mode(C 成 页), 155 PyConfig.dwp_refs(C 成 页), 155 PyConfig.dwp_refs(C 成 页), 155 PyConfig.dwp_refs(C 成 页), 155 PyConfig.exec_prefix(C 成 页), 155 PyConfig.faulthandler(C 成 页), 155 PyConfig.faulthandler(C 成 页), 155 PyConfig.fallesystem_encoding(C 成 页), 155 PyConfig.filesystem_errors(C 成 页), 155 PyConfig.hash_seed(C 成 页), 155 PyConfig.hash_seed(C 成 页), 156 PyConfig.import_time(C 成 页), 156 PyConfig.inspect(C 成 页), 156 PyConfig.inspect(C 成 页), 156 PyConfig.interactive(C 成 页), 156 PyConfig.stall_signal_handlers(C 成 页), 156 PyConfig.malloc_stats(C 成 页), 156 PyConfig.malloc_stats(C 成 页), 156 PyConfig.module_search_paths_set(C 成 页), 156 PyConfig.module_search_paths_set(C 成 页), 156 PyConfig.parse_argv(C 成 页), 157 PyConfig.program_name(C 成 页), 157 PyConfig.pycache_prefix(C 成 页), 157 PyConfig.pycache_prefix(C 成 页), 157 PyConfig.pycache_prefix(C 成 页), 157 PyConfig.quiet(C 成 页), 157 PyConfig.quiet(C 成 页), 157 PyConfig.program_name(C 成 页), 157 PyConfig.quiet(C 成 页), 157 PyConfig.quiet(C 成 页), 157 PyConfig.promand(C 成 页), 1 | - | |
| PyConfig.configure_o_stdio(C成员),155 PyConfig.dev_mode(C成员),155 PyConfig.dev_mode(C成员),155 PyConfig.dump_refs(C成员),155 PyConfig.dump_refs(C成员),155 PyConfig.exec_prefix(C成员),155 PyConfig.exec_prefix(C成员),155 PyConfig.faulthandler(C成员),155 PyConfig.filesystem_encoding(C成员),155 PyConfig.filesystem_errors(C成员),155 PyConfig.filesystem_errors(C成员),155 PyConfig.home(C成员),155 PyConfig.inspect(C成员),155 PyConfig.import_time(C成员),156 PyConfig.inspect(C成员),156 PyConfig.inspect(C成员),156 PyConfig.inspect(C成员),156 PyConfig.inspect(C成员),156 PyConfig.inspect(C成员),156 PyConfig.malloc_stats(C成员),156 PyConfig.malloc_stats(C成员),156 PyConfig.module_search_paths (C成员),156 PyConfig.optimization_level(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.parse_debug(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.parse_argv(C成员),157 PyConfig.profix(C成员),157 PyConfig.pycache_prefix(C成员),157 PyConfig.pycache_prefix(C成员),157 PyConfig.quiet(C成员),157 PyConfig.quiet(Codd),156 PyCorolig.quiet(Codd),156 PyCorolig | | |
| PyConfig.configure_c_stdio(C成员), 155 PyConfig.dwmp_refs(C成员), 155 PyConfig.exec_prefix(C成员), 155 PyConfig.exec_prefix(C成员), 155 PyConfig.executable(C成员), 155 PyConfig.faulthandler(C成员), 155 PyConfig.filesystem_encoding(C成员), 155 PyConfig.filesystem_errors(C成员), 155 PyConfig.filesystem_errors(C成员), 155 PyConfig.inlesystem_errors(C成员), 156 PyConfig.inlesystem_errors(Comd), 156 PyConfig.inl | | |
| PyConfig.dump_refs (C 成员), 155 PyConfig.dump_refs (C 成员), 155 PyConfig.exec_prefix (C 成员), 155 PyConfig.exec_prefix (C 成员), 155 PyConfig.faulthandler (C 成员), 155 PyConfig.faulthandler (C 成员), 155 PyConfig.filesystem_encoding (C 成员), 155 PyConfig.filesystem_errors (C 成员), 155 PyConfig.home (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.install_signal_handlers (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.parser_debug (C 成员), 156 PyConfig.parser_debug (C 成员), 156 PyConfig.parser_debug (C 成员), 156 PyConfig.parser_debug (C 成员), 157 PyConfig.pythonpath_env (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyConfig.run_filen | | |
| PyConfig.dump_refs(C成员),155 PyConfig.exec_prefix(C成员),155 PyConfig.executable(C成员),155 PyConfig.faulthandler(C成员),155 PyConfig.filesystem_encoding(C成员),155 PyConfig.filesystem_errors(C成员),155 PyConfig.filesystem_errors(C成员),155 PyConfig.hash_seed(C成员),155 PyConfig.hash_seed(C成员),156 PyConfig.import_time(C成员),156 PyConfig.import_C(C成员),156 PyConfig.inspect(C成员),156 PyConfig.inspect(C成员),156 PyConfig.install_signal_handlers(C成员),156 PyConfig.interactive(C成员),156 PyConfig.interactive(C成员),156 PyConfig.malloc_stats(C成员),156 PyConfig.module_search_paths(C成员),156 PyConfig.module_search_paths(C成员),156 PyConfig.module_search_paths_set(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.parse_argv(C成员),156 PyConfig.partenfig.warnings(C成员),156 PyConfig.partenfig.warnings(C成员),157 PyConfig.pycache_prefix(C成员),157 PyConfig.quiet(C成员),157 PyConfig.quiet(C成员),157 PyConfig.run_command(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_command(C成员),157 PyConfig.run_filename(C成员),157 PyDateTime_FromDateAndTimeAndFold(C函PyDateTime_FromDateAndTimeAndFold(C函PyDateTime_FromDateAndTimeAndFold(C函PyDateTime_FromDateAndTimeAndFold(C函PyDateTime_FromDateAndTimeAndFold(C函PyDateTime_FromDateAndTimeAndFold(C函PyDateTime_FromDateAndTimeAndFold(C函PyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAndTimeAndFold(ComPyDateTime_FromDateAnd | | |
| PyConfig.exec_prefix(C成员),155 PyConfig.executable(C成员),155 PyConfig.faulthandler(C成员),155 PyConfig.filesystem_encoding(C成员),155 PyConfig.filesystem_errors(C成员),155 PyConfig.filesystem_errors(C成员),155 PyConfig.hash_seed(C成员),155 PyConfig.home(C成员),156 PyConfig.import_time(C成员),156 PyConfig.inspect(C成员),156 PyConfig.install_signal_handlers(C成员),156 PyConfig.install_signal_handlers(C成员),156 PyConfig.interactive(C成员),156 PyConfig.interactive(C成员),156 PyConfig.stalted(C成员),156 PyConfig.module_search_paths(C成员),156 PyConfig.module_search_paths(C成员),156 PyConfig.module_search_paths(C成员),156 PyConfig.pathconfig_warnings(C成员),156 PyConfig.pathconfig_warnings(C成员),156 PyConfig.pathconfig_warnings(C成员),156 PyConfig.pathconfig_warnings(C成员),156 PyConfig.pathconfig_warnings(C成员),156 PyConfig.pathconfig_warnings(C成员),156 PyConfig.program_name(C成员),157 PyConfig.quiet(C成员),157 PyConfig.quiet(C成员),157 PyConfig.run_command(C成员),157 PyConfig.run_command(C成员),157 PyConfig.run_command(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_filename(C成员),157 PyConfig.run_filename(C成员),157 PyDateTime_pDateAndTimeAndTold(C函 | | |
| PyConfig.executable (C 成员), 155 PyConfig.faulthandler (C 成员), 155 PyConfig.filesystem_encoding (C 成员), 155 PyConfig.filesystem_errors (C 成员), 155 PyConfig.filesystem_errors (C 成员), 155 PyConfig.hash_seed (C 成员), 155 PyConfig.hash_seed (C 成员), 156 PyConfig.import_time (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.install_signal_handlers (C 成员), 156 PyConfig.interactive (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.madloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.partendebug (C 成员), 156 PyConfig.partendebug (C 成员), 156 PyConfig.partendebug (C 成员), 157 PyConfig.pycache_prefix (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 | | |
| PyConfig.faulthandler (C 成员), 155 PyConfig.filesystem_encoding (C 成员), 155 PyConfig.filesystem_errors (C 成员), 155 PyConfig.filesystem_errors (C 成员), 155 PyConfig.hash_seed(C 成员), 156 PyConfig.import_time (C 成员), 156 PyConfig.inspect(C 成员), 156 PyConfig.inspect(C 成员), 156 PyConfig.interactive (C 成员), 156 PyConfig.interactive (C 成员), 156 PyConfig.sioalated(C 成员), 156 PyConfig.malloc_stats(C 成员), 156 PyConfig.malloc_stats(C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.optimization_level(C 成员), 156 PyConfig.parse_argv(C 成员), 157 PyConfig.pycache_prefix(C 成员), 157 PyConfig.quiet(C 成员), | | |
| PyConfig.filesystem_encoding (C 成 页), 155 PyConfig.filesystem_errors (C 成 页), 155 PyConfig.filesystem_errors (C 成 页), 155 PyConfig.hash_seed(C 成 页), 156 PyConfig.hash_seed(C 成 页), 156 PyConfig.import_time (C 成 页), 156 PyConfig.inspect (C 成 页), 156 PyConfig.inspect (C 成 页), 156 PyConfig.install_signal_handlers (C 成 页), 156 PyConfig.isolated(C 成 页), 156 PyConfig.isolated(C 成 页), 156 PyConfig.legacy_windows_stdio (C 成 页), 156 PyConfig.madloc_stats (C 成 页), 156 PyConfig.module_search_paths (C 成 页), 156 PyConfig.optimization_level(C 成 页), 156 PyConfig.parse_argv(C 成 页), 156 PyConfig.parse_argv(C 成 页), 156 PyConfig.partenderice(C 成 页), 157 PyConfig.pythonpath_env(C 成 页), 157 PyConfig.quiet(C | | |
| PyConfig.filesystem_errors (C 成 员), 155 PyConfig.filesystem_errors (C 成 员), 155 PyConfig.shash_seed (C 成 员), 156 PyConfig.inshal_seed (C 成 员), 156 PyConfig.imspect (C 成 员), 156 PyConfig.inspect (C 成 员), 156 PyConfig.install_signal_handlers (C 成 员), 156 PyConfig.interactive (C 成 员), 156 PyConfig.isolated (C 成 员), 156 PyConfig.isolated (C 成 员), 156 PyConfig.isolated (C 成 员), 156 PyConfig.malloc_stats (C 成 员), 156 PyConfig.module_search_paths (C 成 员), 156 PyConfig.module_search_paths (C 成 员), 156 PyConfig.optimization_level (C 成 员), 156 PyConfig.optimization_level (C 成 员), 156 PyConfig.parser_debug (C 成 员), 156 PyConfig.parser_debug (C 成 员), 156 PyConfig.prefix (C 成 员), 157 PyConfig.pythonpath_env (C 成 员), 157 PyConfig.quiet (C 成 员), 157 PyConfig.quiet (C 成 员), 157 PyConfig.quiet (C 成 员), 157 PyConfig.run_command (C 成 员), 157 PyConfig.run_filename (C 成 B), 157 | | |
| PyConfig.filesystem_errors (C 成员), 155 PyConfig.hash_seed (C 成员), 156 PyConfig.import_time (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.install_signal_handlers (C 成员), 156 PyConfig.interactive (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.legacy_windows_stdio (C 成员), 156 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.optimization_level (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parser_debug (C 成员), 156 PyConfig.parser_debug (C 成员), 156 PyConfig.perfix (C 成员), 157 PyConfig.pythonpath_env (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 | | |
| PyConfig.import_time (C 成员), 156 PyConfig.import_time (C 成员), 156 PyConfig.inspect (C 成员), 156 PyConfig.install_signal_handlers (C 成员), 156 PyConfig.interactive (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.legacy_windows_stdio (C 成员), 156 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.optimization_level (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parse_debug (C 成员), 156 PyConfig.parse_debug (C 成员), 156 PyConfig.parse_debug (C 成员), 157 PyConfig.pucache_prefix (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 | PyConfig.filesystem_errors(C 成员), 155 | |
| PyConfig.import_time (C成员), 156 PyConfig.inspect (C成员), 156 PyConfig.install_signal_handlers (C成员), 156 PyConfig.interactive (C成员), 156 PyConfig.interactive (C成员), 156 PyConfig.isolated (C成员), 156 PyConfig.legacy_windows_stdio (C成员), 156 PyConfig.malloc_stats (C成员), 156 PyConfig.malloc_stats (C成员), 156 PyConfig.module_search_paths (C成员), 156 PyConfig.module_search_paths_set (C成员), 156 PyConfig.optimization_level (C成员), 156 PyConfig.parse_argy (C成员), 156 PyConfig.parser_debug (C成员), 156 PyConfig.prefix (C成员), 157 PyConfig.pycache_prefix (C成员), 157 PyConfig.quiet (C成员), 157 PyConfig.run_command (C成员), 157 PyConfig.run_command (C成员), 157 PyConfig.run_filename (C成员), 157 | | |
| PyConfig.inspect (C 成员), 156 PyConfig.install_signal_handlers (C 成 页), 156 PyConfig.interactive (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.legacy_windows_stdio (C 成员), 156 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成 页), 156 PyConfig.optimization_level(C成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parse_debug (C 成员), 156 PyConfig.parthconfig_warnings (C 成 页), 156 PyConfig.program_name (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_filename (C 成员), 157 | PyConfig.home (C 成员), 156 | PyContextVar_New(C 函数), 128 |
| PyConfig.install_signal_handlers (C 成 页), 156 PyConfig.interactive (C 成 页), 156 PyConfig.isolated (C 成 页), 156 PyConfig.legacy_windows_stdio (C 成 页), 156 PyConfig.malloc_stats (C 成 页), 156 PyConfig.module_search_paths (C 成 页), 156 PyConfig.module_search_paths_set (C 成 页), 156 PyConfig.optimization_level (C 成 页), 156 PyConfig.parse_argv (C 成 页), 156 PyConfig.parse_debug (C 成 页), 156 PyConfig.parser_debug (C 成 页), 157 PyConfig.pycache_prefix (C 成 页), 157 PyConfig.quiet (C 成 页), 157 PyConfig.run_command (C 成 页), 157 PyConfig.run_command (C 成 页), 157 PyConfig.run_command (C 成 页), 157 PyConfig.run_filename (C 成 页), 157 | PyConfig.import_time(C 成员), 156 | PyContextVar_Reset (C 函数), 128 |
| PyConfig.interactive (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.legacy_windows_stdio (C 成员), 156 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths_set (C 成员), 156 PyConfig.module_search_paths_set (C 成员), 156 PyConfig.optimization_level (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parse_debug (C 成员), 156 PyConfig.parser_debug (C 成员), 156 PyConfig.prefix (C 成员), 157 PyConfig.pycache_prefix (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyConfig | PyConfig.inspect (C 成员), 156 | PyContextVar_Set (C 函数), 128 |
| PyConfig.interactive (C 成员), 156 PyConfig.isolated (C 成员), 156 PyConfig.legacy_windows_stdio (C 成员), 156 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths_set (C 成员), 156 PyConfig.optimization_level (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parser_debug (C 成员), 157 PyConfig.program_name (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 | PyConfig.install_signal_handlers (C 成 | PyContextVar_Type (C 变量), 127 |
| PyConfig.isolated(C成员), 156 PyConfig.legacy_windows_stdio(C成员), 156 PyConfig.malloc_stats(C成员), 156 PyConfig.module_search_paths(C成员), 156 PyConfig.module_search_paths(C成员), 156 PyConfig.module_search_paths_set(C成员), 156 PyConfig.module_search_paths_set(C成员), 156 PyConfig.potimization_level(C成员), 156 PyConfig.parse_argv(C成员), 156 PyConfig.parser_debug(C成员), 156 PyConfig.parser_debug(C成员), 156 PyConfig.parser_debug(C成员), 156 PyConfig.prefix(C成员), 157 PyConfig.pycache_prefix(C成员), 157 PyConfig.pythonpath_env(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_filename(C成员), 157 | 员), 156 | PyCoro_CheckExact (C 函数), 126 |
| PyConfig.legacy_windows_stdio (C 成 员), PyCoroObject (C 类型), 126 PyConfig.malloc_stats (C 成 员), 156 PyConfig.module_search_paths (C 成 员), PyDate_CheckExact (C 函数), 128 PyConfig.module_search_paths (C 成 员), 156 PyConfig.module_search_paths_set (C 成 员), 156 PyConfig.optimization_level (C 成 员), 156 PyConfig.parse_argv (C 成 员), 156 PyConfig.parser_debug (C 成 员), 156 PyConfig.parser_debug (C 成 员), 156 PyConfig.parser_debug (C 成 员), 156 PyConfig.prefix (C 成 员), 157 PyConfig.program_name (C 成 员), 157 PyConfig.quiet (C 成 员), 157 PyConfig.quiet (C 成 员), 157 PyConfig.run_command (C 成 员), 157 PyConfig.run_command (C 成 员), 157 PyConfig.run_filename (C 成 B), 156 PyDate_fromDate (C 函 B), 128 P | PyConfig.interactive(C 成员), 156 | PyCoro_New (C 函数), 126 |
| PyDate_Check (C 函数), 128 PyConfig.malloc_stats (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths_set (C 成员), 156 PyConfig.module_search_paths_set (C 成员), 156 PyConfig.optimization_level (C 成员), 156 PyConfig.parse_argv (C 成员), 156 PyConfig.parser_debug (C 成员), 156 PyConfig.pathconfig_warnings (C 成员), 156 PyConfig.prefix (C 成员), 157 PyConfig.program_name (C 成员), 157 PyConfig.pythonpath_env (C 成员), 157 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyDateTime_DELTA_GET_MICROSECONDS (C 函数), 130 PyDateTime_DELTA_GET_MICROSECONDS (C 函数), 130 PyDateTime_DELTA_GET_MICROSECONDS (C 函数), 130 PyDateTime_DELTA_GET_MICROSECONDS (C 函数), 130 PyDateTime_DELTA_GET_SECONDS (C 函数), 129 PyDateTime_FromDateAndTime (C 函数), 129 PyDateTime_FromDateAndTimeAndFold (C 函数), 129 | PyConfig.isolated(C 成员), 156 | PyCoro_Type (C 变量), 126 |
| PyConfig.malloc_stats(C成员), 156 PyConfig.module_search_paths (C 成员), 156 PyConfig.module_search_paths_set (C 成 员), 156 PyConfig.module_search_paths_set (C 成 局), 156 PyConfig.optimization_level(C成员), 156 PyConfig.parse_argv(C成员), 156 PyConfig.parser_debug(C成员), 156 PyConfig.pathconfig_warnings (C 成员), 156 PyConfig.prefix(C成员), 157 PyConfig.pycache_prefix(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(Common documents), 130 PyDateTime_Delta_GET_MICROSEC | PyConfig.legacy_windows_stdio (C 成员), | PyCoroObject (C 类型), 126 |
| PyConfig.module_search_paths (C 成 员), PyDate_FromDate (C 函数), 129 PyConfig.module_search_paths_set (C 成 员), 156 PyConfig.optimization_level (C 成 员), 156 PyConfig.parse_argv (C 成 员), 156 PyConfig.parser_debug (C 成 员), 156 PyConfig.pathconfig_warnings (C 成 员), 156 PyConfig.prefix (C 成 员), 157 PyConfig.program_name (C 成 员), 157 PyConfig.pythonpath_env (C 成 员), 157 PyConfig.quiet (C 成 员), 157 PyConfig.run_command (C 成 员), 157 PyConfig.run_filename (C 成 员), 157 PyDateTime_DateAndTime(C 函数), 129 PyDateTime_Delta_Get_Minute (C 函数), 130 PyDateTime_Delta_Get_Minute (C 函数), 130 PyDateTime_Delta_Get_Minute (C 函数), 130 PyDateTime_Delta_Get_Minute (C 函数), 130 PyDateTime_Delta_Get_Seconds (C 函数), 129 PyDateTime_FromDateAndTime (C 函数), 129 PyDateTime_FromDateAndTime (C 函数), 129 PyDateTime_FromDateAndTimeAndFold (C 函数) | | |
| PyDate_FromTimestamp (C 函数), 130 PyConfig.module_search_paths_set (C 成 页), 156 PyConfig.optimization_level(C 成页), 156 PyConfig.parse_argv(C 成页), 156 PyConfig.parser_debug(C 成页), 156 PyConfig.parser_debug(C 成页), 156 PyConfig.parthconfig_warnings (C 成页), 156 PyConfig.prefix(C 成页), 157 PyConfig.program_name(C 成页), 157 PyConfig.pycache_prefix(C 成页), 157 PyConfig.quiet(C 成页), 157 PyConfig.run_command(C 成页), 157 PyConfig.run_command(C 成页), 157 PyConfig.run_filename(C 成页), 157 PyDateTime_DELTA_GET_MICROSECONDS(C 函 数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C 函 数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C 函 数), 130 PyDateTime_DELTA_GET_SECONDS(C 函 数), 130 PyDateTime_DELTA_GET_SECONDS(C 函 数), 129 PyDateTime_FromDateAndTime(C 函数), 129 PyDateTime_FromDateAndTimeAndFold(C 函 | | |
| PyConfig.module_search_paths_set (C 成 页), 156 PyConfig.optimization_level(C 成 页), 156 PyConfig.parse_argv(C 成 页), 156 PyConfig.parser_debug(C 成 页), 156 PyConfig.pathconfig_warnings(C 成 页), 156 PyConfig.prefix(C 成 页), 157 PyConfig.program_name(C 成 页), 157 PyConfig.pycache_prefix(C 成 页), 157 PyConfig.pythonpath_env(C 成 页), 157 PyConfig.quiet(C 成 页), 157 PyConfig.run_command(C 成 页), 157 PyConfig.run_command(C 成 页), 157 PyConfig.run_filename(C 成 页), 157 PyConfig.run_filename(C 成 页), 157 PyConfig.run_filename(C 成 页), 157 PyConfig.run_filename(C 成 页), 157 PyDateTime_Check(C 函数), 128 PyDateTime_DATE_GET_HOUR(C 函数), 130 PyDateTime_DATE_GET_MINUTE(C 函数), 130 PyDateTime_DELTA_GET_DAYS(C 函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C 函数), 130 PyDateTime_DELTA_GET_SECONDS(C 函数), 130 PyDateTime_DELTA_GET_SECONDS(C 函数), 129 PyDateTime_FromDateAndTime(C 函数), 129 PyDateTime_FromDateAndTimeAndFold(C 函 | | |
| PyConfig.optimization_level(C成员), 156 PyConfig.parse_argv(C成员), 156 PyConfig.parser_debug(C成员), 156 PyConfig.pathconfig_warnings (C成员), 156 PyConfig.prefix(C成员), 157 PyConfig.program_name(C成员), 157 PyConfig.pycache_prefix(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_SECONDS(C函数), 130 PyDateTime_DELTA_GET_SECONDS(C 函数), 130 PyDateTime_DELTA_GET_SECONDS(C MMA) | | |
| PyConfig.optimization_level(C成员), 156 PyConfig.parse_argv(C成员), 156 PyConfig.parser_debug(C成员), 156 PyConfig.pathconfig_warnings(C成员), 156 PyConfig.prefix(C成员), 157 PyConfig.program_name(C成员), 157 PyConfig.pycache_prefix(C成员), 157 PyConfig.pythonpath_env(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyDateTime_DATE_GET_MICROSECOND (C函数), 130 PyDateTime_DELTA_GET_DAYS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_SECONDS(C函数), 130 PyDateTime_DELTA_GET_SECONDS(C函数), 130 PyDateTime_FromDateAndTime(C函数), 129 PyDateTime_FromDateAndTimeAndFold(C函 | | |
| PyConfig.parse_argv(C成员), 156 PyConfig.parser_debug(C成员), 156 PyConfig.pathconfig_warnings (C成员), 156 PyConfig.prefix(C成员), 157 PyConfig.program_name(C成员), 157 PyConfig.pycache_prefix(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.quiet(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyDateTime_DATE_GET_MICROSECOND (C函数), 130 PyDateTime_DELTA_GET_DAYS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_MICROSECOND (C函数), 130 PyDateTime_DATE_GET_MICROSECOND (C函数), 130 PyDateTime_DELTA_GET_MICROSECOND (Common del Mandrian del Mandr | * */* | |
| PyConfig.parser_debug(C成员), 156 PyConfig.pathconfig_warnings (C成员), 156 PyConfig.prefix(C成员), 157 PyConfig.program_name(C成员), 157 PyConfig.pycache_prefix(C成员), 157 PyConfig.pythonpath_env(C成员), 156 PyConfig.quiet(C成员), 157 PyConfig.run_command(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyConfig.run_filename(C成员), 157 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_MICROSECONDS(C函数), 130 PyDateTime_DELTA_GET_SECONDS(C函数), 130 PyDateTime_DELTA_GET_SECONDS(C 函数), 130 PyDateTime_DELTA_GET_SECONDS(C 函数), 130 PyDateTime_DELTA_GET_SECONDS(C 函数), 130 PyDateTime_DELTA_GET_SECONDS(C 函数), 130 | | |
| PyConfig.pathconfig_warnings (C 成 员), 156 PyConfig.prefix (C 成员), 157 PyConfig.program_name (C 成员), 157 PyConfig.pycache_prefix (C 成员), 157 PyConfig.pythonpath_env (C 成员), 156 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyDateTime_DATE_GET_MINUTE (C 函数), 130 PyDateTime_DELTA_GET_MICROSECONDS (C 函数), 130 PyDateTime_DELTA_GET_SECONDS (C 函数), 120 PyDateTime_FromDateAndTime (C 函数), 129 PyDateTime_FromDateAndTimeAndFold (C 函 | | |
| PyDateTime_DATE_GET_SECOND (C 函数), 130 PyConfig.prefix (C 成员), 157 PyConfig.program_name (C 成员), 157 PyConfig.pycache_prefix (C 成员), 157 PyConfig.pythonpath_env (C 成员), 156 PyConfig.quiet (C 成员), 157 PyConfig.run_command (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyConfig.run_filename (C 成员), 157 PyDateTime_DELTA_GET_MICROSECONDS (C 函数), 130 PyDateTime_DELTA_GET_SECONDS (C 函数), 130 PyDateTime_DELTA_GET_SECONDS (C 函数), 129 PyDateTime_FromDateAndTime (C 函数), 129 PyDateTime_FromDateAndTimeAndFold (C 函 | | |
| PyConfig.prefix $(C$ 成员), 157 PyConfig.program_name $(C$ 成员), 157 PyConfig.pycache_prefix $(C$ 成员), 157 PyConfig.pythonpath_env $(C$ 成员), 156 PyConfig.quiet $(C$ 成员), 157 PyConfig.run_command $(C$ 成员), 157 PyConfig.run_filename $(C$ 成员), 157 PyConfig.run_filename $(C$ 成员), 157 PyConfig.run_filename $(C$ 成员), 157 PyDateTime_DELTA_GET_MICROSECONDS $(C$ 函数), 130 PyDateTime_DELTA_GET_SECONDS $(C$ 函数), 130 PyDateTime_DELTA_GET_SECONDS $(C$ 函数), 129 PyDateTime_FromDateAndTime $(C$ 函数), 129 PyDateTime_FromDateAndTimeAndFold $(C$ 函 | | = |
| PyConfig.program_name (C 成员), 157 PyConfig.pycache_prefix(C 成员), 157 PyConfig.pythonpath_env(C 成员), 156 PyConfig.quiet(C 成员), 157 PyConfig.run_command(C 成员), 157 PyConfig.run_filename(C 成员), 157 PyConfig.run_filename(C 成员), 157 PyDateTime_FromDateAndTime(C 函数), 129 PyDateTime_FromDateAndTimeAndFold(C 函 | | |
| PyConfig.pycache_prefix $(C$ 成员), 157 PyConfig.pythonpath_env $(C$ 成员), 156 PyConfig.quiet $(C$ 成员), 157 PyConfig.run_command $(C$ 成员), 157 PyConfig.run_filename $(C$ 成员), 157 PyConfig.run_filename $(C$ 成员), 157 PyDateTime_FromDateAndTime $(C$ 函数), 129 PyDateTime_FromDateAndTimeAndFold $(C$ 函 | | |
| PyConfig.pythonpath_env(C 成员), 156 PyConfig.quiet(C 成员), 157 PyConfig.run_command(C 成员), 157 PyConfig.run_filename(C 成员), 157 PyConfig.run_filename(C 成员), 157 PyDateTime_FromDateAndTime(C 函数), 129 PyDateTime_FromDateAndTimeAndFold(C 函 | | |
| PyConfig.quiet $(C$ 成员), 157 130 PyConfig.run_command $(C$ 成员), 157 PyConfig.run_filename $(C$ 成员), 157 PyDateTime_FromDateAndTime $(C$ 函数), 129 PyDateTime_FromDateAndTimeAndFold $(C$ 函 | | |
| PyConfig.run_command (C 成员), 157 | | |
| PyConfig.run_filename(C 成员),157 PyDateTime_FromDateAndTimeAndFold(C 函 | | |
| | | |
| xyConity.run_modute (C 放火), 13/ 数), 129 | | |
| | ryconrig.run_modute(C 成贝), 13/ | 3X.J, 147 |

| PyDateTime_FromTimestamp(C 函数), 130 | PyErr_NewExceptionWithDoc(\emph{C} 函数), 29 |
|------------------------------------------------------------|-------------------------------------------------|
| PyDateTime_GET_DAY(C 函数), 129 | PyErr_NoMemory (C 函数), 24 |
| PyDateTime_GET_MONTH(C 函数), 129 | PyErr_NormalizeException(C 函数), 28 |
| PyDateTime_GET_YEAR(C 函数), 129 | PyErr_Occurred (C 函数), 27 |
| PyDateTime_TIME_GET_HOUR(C函数),130 | PyErr_Occurred(),8 |
| PyDateTime_TIME_GET_MICROSECOND (C 函 | PyErr_Print (C 函数), 24 |
| 数), 130 | PyErr_PrintEx (C函数), 23 |
| PyDateTime_TIME_GET_MINUTE(C函数),130 | PyErr_ResourceWarning (C 函数), 27 |
| PyDateTime_TIME_GET_SECOND (C 函数), 130 | PyErr_Restore (C函数), 27 |
| PyDateTime_TimeZone_UTC(C变量), 128 | |
| | PyErr_SetExcFromWindowsErr(C函数), 25 |
| PyDelta_Check (C 函数), 128 | PyErr_SetExcFromWindowsErrWithFilename |
| PyDelta_CheckExact (C 函数), 129 | (C函数), 25 |
| PyDelta_FromDSU(C函数),129 | PyErr_SetExcFromWindowsErrWithFilenameObject |
| PyDescr_IsData (C 函数), 121 | (C函数), 25 |
| PyDescr_NewClassMethod(C 函数), 121 | PyErr_SetExcFromWindowsErrWithFilenameObjects |
| PyDescr_NewGetSet (C 函数), 121 | (C函数), 25 |
| PyDescr_NewMember(C 函数), 121 | PyErr_SetExcInfo (C 函数), 28 |
| PyDescr_NewMethod(\emph{C} 函数), 121 | PyErr_SetFromErrno(C 函数), 24 |
| PyDescr_NewWrapper(C 函数), 121 | PyErr_SetFromErrnoWithFilename(C 函数), |
| PyDict_Check (C 函数), 108 | 25 |
| PyDict_CheckExact (C 函数), 108 | PyErr_SetFromErrnoWithFilenameObject |
| PyDict_Clear (C 函数), 108 | (C函数), 24 |
| PyDict_ClearFreeList (C 函数), 110 | PyErr_SetFromErrnoWithFilenameObjects |
| PyDict_Contains (C 函数), 108 | · C 函数), 25 |
| PyDict_Copy (C 函数), 108 | PyErr_SetFromWindowsErr (C 函数), 25 |
| PyDict_DelItem (C 函数), 108 | PyErr_SetFromWindowsErrWithFilename (C |
| PyDict_DelItemString(C函数), 108 | 函数), 25 |
| PyDict_GetItem(C函数), 108 | PyErr_SetImportError(C函数), 25 |
| PyDict_GetItem(C 函数), 108 PyDict_GetItemString(C 函数), 108 | PyErr_SetImportErrorSubclass (C函数), 26 |
| PyDict_GetItemWithError(C函数),108 | PyErr_SetInterrupt (C函数), 28 |
| | |
| PyDict_Items (C函数), 109 | PyErr_SetNone (C函数), 24 |
| PyDict_Keys (C函数), 109 | PyErr_SetObject (C函数), 24 |
| PyDict_Merge (C 函数), 109 | PyErr_SetString (C 函数), 24 |
| PyDict_MergeFromSeq2 (C函数),110 | PyErr_SetString(),8 |
| PyDict_New (C 函数), 108 | PyErr_SyntaxLocation (C 函数), 26 |
| PyDict_Next (C 函数), 109 | PyErr_SyntaxLocationEx(C 函数), 26 |
| PyDict_SetDefault (\emph{C} 函数), 109 | PyErr_SyntaxLocationObject(C 函数), 25 |
| PyDict_SetItem(C 函数), 108 | PyErr_WarnEx(C 函数), 26 |
| PyDict_SetItemString(\emph{C} 函数), 108 | PyErr_WarnExplicit(C 函数), 26 |
| PyDict_Size (C 函数), 109 | PyErr_WarnExplicitObject(C 函数), 26 |
| PyDict_Type (C 变量), 108 | PyErr_WarnFormat (C 函数), 26 |
| PyDict_Update (C 函数), 109 | PyErr_WriteUnraisable (C 函数), 24 |
| PyDict_Values (C 函数), 109 | PyEval_AcquireLock (C 函数), 143 |
| PyDictObject (C 类型), 108 | PyEval_AcquireThread (C 函数), 142 |
| PyDictProxy_New (C函数), 108 | PyEval_AcquireThread(),140 |
| PyErr_BadArgument (C函数), 24 | PyEval_EvalCode (C函数), 18 |
| PyErr_BadInternalCall (C 函数), 26 | PyEval_EvalCodeEx(C函数), 18 |
| PyErr_CheckSignals (C 函数), 28 | PyEval_EvalFrame (C函数), 18 |
| PyErr_Clear (C函数), 23 | PyEval_EvalFrameEx(C函数), 18 |
| PyErr_Clear(), 8, 10 | PyEval_GetBuiltins (C 函数), 52 |
| PyErr_ExceptionMatches (C函数), 27 | |
| | PyEval_GetFrame (C函数), 52 |
| PyErr_ExceptionMatches(), 10 | PyEval_GetFuncDesc(C函数),52 |
| PyErr_Fetch (C函数), 27 | PyEval_GetFuncName (C函数),52 |
| PyErr_Format (C函数), 24 | PyEval_GetGlobals (C 函数), 52 |
| PyErr_FormatV(C函数),24 | PyEval_GetLocals (C 函数),52 |
| PyErr_GetExcInfo(C函数), 28 | PyEval_InitThreads (C 函数), 140 |
| PyErr_GivenExceptionMatches (C 函数), 27 | PyEval_InitThreads(),134 |
| PyErr_NewException (C 函数), 29 | PyEval_MergeCompilerFlags(C 函数), 18 |

| PyEval_ReleaseLock (C 函数), 143 | PyExc_StopIteration, 31 |
|------------------------------------------------------|--------------------------------------------|
| PyEval_ReleaseThread(C 函数), 143 | PyExc_SyntaxError, 31 |
| PyEval_ReleaseThread(), 140 | PyExc_SyntaxWarning,33 |
| PyEval_RestoreThread (C 函数), 140 | PyExc_SystemError, 31 |
| PyEval_RestoreThread(), 138, 140 | PyExc_SystemExit, 31 |
| PyEval_SaveThread (C 函数), 140 | PyExc_TabError, 31 |
| PyEval_SaveThread(), 138, 140 | PyExc_TimeoutError, 31 |
| PyEval_SetProfile (C 函数), 146 | PyExc_TypeError, 31 |
| PyEval_SetTrace (C函数), 146 | PyExc_UnboundLocalError, 31 |
| PyEval_ThreadsInitialized(C函数),140 | PyExc_UnicodeDecodeError,31 |
| PyExc_ArithmeticError, 31 | PyExc_UnicodeEncodeError, 31 |
| PyExc_AssertionError, 31 | PyExc_UnicodeError, 31 |
| PyExc_AttributeError, 31 | PyExc_UnicodeTranslateError, 31 |
| PyExc_BaseException, 31 | PyExc_UnicodeWarning, 33 |
| PyExc_BlockingIOError, 31 | PyExc_UserWarning, 33 |
| PyExc_BrokenPipeError, 31 | PyExc_ValueError, 31 |
| PyExc_BufferError, 31 | PyExc_Warning, 33 |
| PyExc_BytesWarning, 33 | PyExc_WindowsError, 32 |
| PyExc_ChildProcessError, 31 | PyExc_ZeroDivisionError, 31 |
| PyExc_ConnectionAbortedError, 31 | PyException_GetCause (C 函数), 29 |
| PyExc_ConnectionError, 31 | PyException_GetContext (C 函数), 29 |
| PyExc_ConnectionRefusedError, 31 | PyException_GetTraceback (C 函数), 29 |
| PyExc_ConnectionResetError, 31 | PyException_SetCause (C 函数), 29 |
| PyExc_DeprecationWarning, 33 | |
| <u> </u> | PyException_SetContext (C 函数), 29 |
| PyExc_EnvironmentError, 32 | PyException_SetTraceback(C函数), 29 |
| PyExc_EOFError, 31 | PyFile_FromFd(C函数),114 |
| PyExc_Exception, 31 | PyFile_GetLine (C 函数), 115 |
| PyExc_FileExistsError, 31 | PyFile_SetOpenCodeHook (C 函数), 115 |
| PyExc_FileNotFoundError, 31 | PyFile_WriteObject(C函数),115 |
| PyExc_FloatingPointError, 31 | PyFile_WriteString(C函数),115 |
| PyExc_FutureWarning, 33 | PyFloat_AS_DOUBLE (C函数),81 |
| PyExc_GeneratorExit, 31 | PyFloat_AsDouble (C 函数), 81 |
| PyExc_ImportError, 31 | PyFloat_Check (C 函数), 81 |
| PyExc_ImportWarning, 33 | PyFloat_CheckExact (C 函数), 81 |
| PyExc_IndentationError, 31 | PyFloat_ClearFreeList (C 函数), 82 |
| PyExc_IndexError, 31 | PyFloat_FromDouble(\emph{C} 函数), 81 |
| PyExc_InterruptedError, 31 | PyFloat_FromString(C 函数), 81 |
| PyExc_IOError, 32 | PyFloat_GetInfo (C 函数), 81 |
| PyExc_IsADirectoryError, 31 | PyFloat_GetMax(C 函数), 82 |
| PyExc_KeyboardInterrupt, 31 | PyFloat_GetMin (C 函数), 82 |
| PyExc_KeyError, 31 | PyFloat_Type (C 变量), 81 |
| PyExc_LookupError, 31 | PyFloatObject (C 类型), 81 |
| PyExc_MemoryError, 31 | PyFrame_GetLineNumber(C 函数), 52 |
| PyExc_ModuleNotFoundError, 31 | PyFrameObject (C 类型), 18 |
| PyExc_NameError, 31 | PyFrozenSet_Check (C 函数), 110 |
| PyExc_NotADirectoryError, 31 | PyFrozenSet_CheckExact (C 函数), 110 |
| PyExc_NotImplementedError, 31 | PyFrozenSet_New(C函数),110 |
| PyExc_OSError, 31 | PyFrozenSet_Type (C变量),110 |
| PyExc_OverflowError, 31 | PyFunction_Check (C函数), 111 |
| PyExc_PendingDeprecationWarning, 33 | PyFunction_GetAnnotations (C函数), 112 |
| PyExc_PermissionError, 31 | PyFunction_GetClosure(C函数), 112 |
| PyExc_ProcessLookupError, 31 | PyFunction_GetCode(C函数),112 |
| PyExc_RecursionError, 31 | PyFunction_GetDefaults (C函数), 112 |
| PyExc_ReferenceError, 31 | PyFunction_GetGlobals (C函数), 112 |
| PyExc_ResourceWarning, 33 | PyFunction_GetModule (C函数), 112 |
| PyExc_RuntimeError, 31 | PyFunction_New (C 函数), 112 |
| PyExc_RuntimeWarning, 33 | PyFunction_NewWithQualName (C 函数), 112 |
| PyExc_StopAsyncIteration, 31 | PyFunction_SetAnnotations (C 函数), 112 |
| r y in no _ o copris y i c i c c c a c i o i i , o i | I y I direction_becommodations (C 四文), 112 |

| PyFunction_SetClosure (C 函数), 112 | PyInterpreterState_New(C 函数), 142 |
|------------------------------------------------------------------------|-----------------------------------------------------------|
| PyFunction_SetDefaults (C 函数), 112 | PyInterpreterState_Next(C 函数), 146 |
| PyFunction_Type (C 变量), 111 | PyInterpreterState_ThreadHead (C 函数), |
| PyFunctionObject (C 类型), 111 | 146 |
| PyGen_Check (C 函数), 126 | PyIter_Check (C 函数),66 |
| PyGen_CheckExact (C函数), 126 | PyIter_Next (C 函数),66 |
| PyGen_New (C 函数), 126 | PyList_Append (C函数), 107 |
| PyGen_NewWithQualName (C函数), 126 | PyList_AsTuple (C 函数), 107 |
| PyGen_Type (C 变量), 126 | PyList_Check (C 函数), 106 |
| PyGenObject (C类型), 126 | PyList_CheckExact (C 函数), 106 |
| PyGetSetDef(C类型),177 | PyList_ClearFreeList (C函数), 107 |
| PyGILState_Check (C函数), 141 | PyList_GET_ITEM (C 函数), 107 |
| PyGILState_Ensure (C 函数), 140 | PyList_GET_SIZE (C 函数), 107 |
| PyGILState_GetThisThreadState (C 函数), | PyList_GetItem(C函数), 107 |
| 141 | PyList_GetItem(),7 |
| PyGILState_Release (C 函数), 141 | PyList_GetSlice(C函数), 107 |
| PyImport_AddModule(C函数),41 | PyList_Insert (C 函数), 107 |
| PyImport_AddModuleObject (C函数), 40 | PyList_New (C函数), 106 |
| PyImport_AppendInittab (C 函数), 42 PyImport_Cleanup (C 函数), 42 | PyList_Reverse (C 函数), 107 PyList_SET_ITEM (C 函数), 107 |
| PyImport_ExecCodeModule (C 函数), 41 | PyList_SetItem(C函数), 107 PyList_SetItem(C函数), 107 |
| PyImport_ExecCodeModuleEx(C函数),41 PyImport_ExecCodeModuleEx(C函数),41 | PyList_SetItem(),6 |
| PyImport_ExecCodeModuleObject (C 函数), | PyList_SetSlice (C函数), 107 |
| 41 | PyList_Size (C 函数), 106 |
| PyImport_ExecCodeModuleWithPathnames | PyList_Sort (C函数), 107 |
| (C函数), 41 | PyList_Type (C 变量), 106 |
| PyImport_ExtendInittab (C函数), 43 | PyListObject (C 类型), 106 |
| PyImport_FrozenModules (C 变量), 42 | PyLong_AsDouble (C函数), 80 |
| PyImport_GetImporter(C函数),42 | PyLong_AsLong (C函数), 79 |
| PyImport_GetMagicNumber(C函数),41 | PyLong_AsLongAndOverflow (C函数),79 |
| PyImport_GetMagicTag(C函数),42 | PyLong_AsLongLong (C 函数), 79 |
| PyImport_GetModule (C函数),42 | PyLong_AsLongLongAndOverflow (C函数),79 |
| PyImport_GetModuleDict(C函数),42 | PyLong_AsSize_t (C函数), 80 |
| PyImport_Import (C函数), 40 | PyLong_AsSsize_t (C函数), 80 |
| PyImport_ImportFrozenModule(C函数),42 | PyLong_AsUnsignedLong (C函数), 80 |
| PyImport_ImportFrozenModuleObject(C函 | PyLong_AsUnsignedLongLong(C函数),80 |
| 数), 42 | PyLong_AsUnsignedLongLongMask (C 函数), |
| PyImport_ImportModule (C 函数), 40 | 80 |
| PyImport_ImportModuleEx(C函数),40 | PyLong_AsUnsignedLongMask (C 函数), 80 |
| PyImport_ImportModuleLevel(C函数),40 | PyLong_AsVoidPtr(C函数),81 |
| PyImport_ImportModuleLevelObject (C 🕉 | PyLong_Check (C 函数), 78 |
| 数), 40 | PyLong_CheckExact (C 函数), 78 |
| PyImport_ImportModuleNoBlock (C 函数), 40 | PyLong_FromDouble(C 函数), 78 |
| PyImport_ReloadModule (C 函数), 40 | PyLong_FromLong (C 函数), 78 |
| PyIndex_Check (C 函数), 63 | PyLong_FromLongLong (C 函数), 78 |
| PyInstanceMethod_Check (\emph{C} 函数), 112 | PyLong_FromSize_t(C 函数), 78 |
| PyInstanceMethod_Function (C 函数), 112 | PyLong_FromSsize_t(C 函数), 78 |
| PyInstanceMethod_GET_FUNCTION (C 函数), | PyLong_FromString(C 函数), 78 |
| 113 | PyLong_FromUnicode (C 函数), 79 |
| PyInstanceMethod_New(C 函数), 112 | PyLong_FromUnicodeObject(C 函数), 79 |
| PyInstanceMethod_Type (C 变量), 112 | PyLong_FromUnsignedLong(C 函数), 78 |
| PyInterpreterState (C 类型), 140 | PyLong_FromUnsignedLongLong(C 函数), 78 |
| PyInterpreterState_Clear(C函数),142 | PyLong_FromVoidPtr(C函数),79 |
| PyInterpreterState_Delete (C函数), 142 | PyLong_Type (C变量),78 |
| PyInterpreterState_GetDict(C函数), 142 | PyLongObject (C 类型),78 |
| PyInterpreterState_GetID (C函数), 142 | PyMapping_Check (C函数), 65 |
| PyInterpreterState_Head(C函数),146 | PyMapping_DelItem(C 函数),65 |
| PyInterpreterState Main (C 函数) 146 | PyMapping DelItemString(C函数).65 |

| PyMapping_GetItemString(C函数),65 | PyMethod_New (C 函数), 113 |
|-------------------------------------------|---------------------------------------------|
| PyMapping_HasKey (C 函数), 65 | PyMethod_Self(C 函数), 113 |
| PyMapping_HasKeyString(C函数),65 | PyMethod_Type (C变量), 113 |
| PyMapping_Items (C函数),66 | PyMethodDef(C类型),175 |
| PyMapping_Keys (C函数),65 | PyModule_AddFunctions (C 函数), 119 |
| PyMapping_Length (C 函数), 65 | PyModule_AddIntConstant (C 函数), 120 |
| PyMapping_SetItemString(C 函数), 65 | PyModule_AddIntMacro (C 函数), 120 |
| PyMapping_Size (C 函数), 65 | PyModule_AddObject (C 函数), 120 |
| PyMapping_Values (C 函数), 65 | PyModule_AddStringConstant (C 函数), 120 |
| PyMappingMethods (C 类型), 203 | PyModule_AddStringMacro(C函数),120 |
| PyMappingMethods.mp_ass_subscript (C 成 | PyModule_Check (C 函数), 115 |
| 员), 203 | PyModule_CheckExact (C 函数), 115 |
| PyMappingMethods.mp_length(C 成员), 203 | PyModule_Create(C函数),117 |
| PyMappingMethods.mp_subscript $(C$ 成员), | PyModule_Create2(C 函数),117 |
| 203 | PyModule_ExecDef (C 函数), 119 |
| PyMarshal_ReadLastObjectFromFile (C 函 | PyModule_FromDefAndSpec(C 函数), 119 |
| 数), 43 | PyModule_FromDefAndSpec2(C 函数), 119 |
| PyMarshal_ReadLongFromFile(C 函数), 43 | PyModule_GetDef(C 函数), 116 |
| PyMarshal_ReadObjectFromFile(C 函数),43 | PyModule_GetDict (C 函数), 116 |
| $PyMarshal_ReadObjectFromString(C函数),$ | PyModule_GetFilename(C 函数), 116 |
| 44 | PyModule_GetFilenameObject (C 函数), 116 |
| PyMarshal_ReadShortFromFile(C函数),43 | PyModule_GetName (C 函数), 116 |
| $PyMarshal_WriteLongToFile(C函数),43$ | PyModule_GetNameObject(C函数),116 |
| PyMarshal_WriteObjectToFile(C 函数),43 | PyModule_GetState(C函数),116 |
| PyMarshal_WriteObjectToString (C 函数), | PyModule_New (C 函数), 116 |
| 43 | PyModule_NewObject (C 函数), 115 |
| PyMem_Calloc(C函数),167 | PyModule_SetDocString(C函数),119 |
| PyMem_Del (<i>C</i> 函数), 167 | PyModule_Type (C变量), 115 |
| PYMEM_DOMAIN_MEM (C变量), 169 | PyModuleDef (C 类型), 116 |
| PYMEM_DOMAIN_OBJ (C变量), 170 | PyModuleDef_Init (C函数), 118 |
| PYMEM_DOMAIN_RAW (C变量), 169 | PyModuleDef_Slot (C 类型), 118 |
| PyMem_Free (C函数), 167 | PyModuleDef_Slot.slot(C成员),118 |
| PyMem_GetAllocator (C函数), 170 | PyModuleDef_Slot.value(C成员),118 |
| PyMem_Malloc(C函数), 167 | PyModuleDef.m_base(C成员),116 |
| PyMem_New (C 函数), 167 | PyModuleDef.m_clear(C成员),117 |
| PyMem_RawCalloc (C 函数), 166 | PyModuleDef.m_doc(C成员),116 |
| PyMem_RawFree(C函数),166 | PyModuleDef.m_free(C成员),117 |
| PyMem_RawMalloc(C函数), 166 | PyModuleDef.m_methods(C成员),117 |
| PyMem_RawRealloc(C函数), 166 | PyModuleDef.m_name(C成员),116 |
| PyMem_Realloc(C函数),167 | PyModuleDef.m_reload(C成员),117 |
| PyMem_Resize (C函数), 167 | PyModuleDef.m_size(C成员),117 |
| PyMem_SetAllocator (C函数), 170 | PyModuleDef.m_slots(C成员),117 |
| PyMem_SetupDebugHooks (C函数), 170 | PyModuleDef.m_traverse(C成员),117 |
| PyMemAllocatorDomain (C类型), 169 | PyNumber_Absolute (C函数), 61 |
| PyMemAllocatorEx(C类型),169 | PyNumber_Add(C函数),61 |
| PyMemberDef (C 类型), 176 | PyNumber_And (C函数),62 |
| PyMemoryView_Check (C 函数), 123 | PyNumber_AsSsize_t(C函数),63 |
| PyMemoryView_FromBuffer (C函数), 123 | PyNumber_Check (C函数), 61 |
| PyMemoryView_FromMemory(C函数), 123 | PyNumber_Divmod (C函数),61 |
| PyMemoryView_FromObject (C函数), 123 | PyNumber_Float (C函数),63 |
| PyMemoryView_GET_BASE (C 函数), 123 | PyNumber_FloorDivide (C函数),61 |
| PyMemoryView_GET_BUFFER (C 函数), 123 | PyNumber_Index(C函数),63 |
| PyMemoryView_GetContiguous (C函数), 123 | PyNumber_InPlaceAdd(C函数),62 |
| PyMethod_Check (C 函数), 113 | PyNumber_InPlaceAnd (C函数), 62 |
| PyMethod_ClearFreeList (C函数), 113 | PyNumber_InPlaceFloorDivide (C函数), 62 |
| PyMethod_Function (C 函数), 113 | PyNumber_InPlaceLshift (C函数), 62 |
| PyMethod_GET_FUNCTION (C函数), 113 | PyNumber_InPlaceMatrixMultiply(C函数) |
| PyMethod GET SELF (C 系数) 113 | 62 |

| (G 7 du) (O | |
|--------------------------------------------------------------------|--------------------------------------------------------------------------|
| PyNumber_InPlaceMultiply(C函数),62 | PyNumberMethods.nb_inplace_xor(C 成员), |
| PyNumber_InPlaceOr(C函数),63 PyNumber_InPlacePower(C函数),62 | 203 PyNumberMethods.nb_int(C成员),203 |
| PyNumber_InPlaceRemainder (C函数), 62 | PyNumberMethods.nb_invert(C成员),202 |
| PyNumber_InPlaceRshift (C函数), 62 | PyNumberMethods.nb_lshift(C成员),202 |
| PyNumber_InPlaceSubtract (C函数), 62 | PyNumberMethods.nb_matrix_multiply (C |
| PyNumber_InPlaceTrueDivide (C 函数), 62 | 成员), 203 |
| PyNumber_InPlaceXor(C函数),63 | PyNumberMethods.nb_multiply(C成员),202 |
| PyNumber_Invert (C函数),61 | PyNumberMethods.nb_negative(C成员),202 |
| PyNumber_Long(C 函数), 63 | PyNumberMethods.nb_or(C 成员), 202 |
| PyNumber_Lshift (C 函数), 61 | PyNumberMethods.nb_positive(C 成员), 202 |
| PyNumber_MatrixMultiply(C 函数), 61 | PyNumberMethods.nb_power(C 成员), 202 |
| PyNumber_Multiply(C函数),61 | PyNumberMethods.nb_remainder $(C$ 成员), |
| PyNumber_Negative (C函数),61 | 202 |
| PyNumber_Or (C函数),62 | PyNumberMethods.nb_reserved(C成员),203 |
| PyNumber_Positive(C函数),61 | PyNumberMethods.nb_rshift(C成员),202 |
| PyNumber_Power (C函数), 61 | PyNumberMethods.nb_subtract(C成员),202 |
| PyNumber_Remainder (C 函数), 61 PyNumber_Rshift (C 函数), 62 | PyNumberMethods.nb_true_divide(C 成员), 203 |
| PyNumber_Subtract(C函数),61 | PyNumberMethods.nb_xor(C成员),202 |
| PyNumber_ToBase (C 函数), 63 | PyObject (C 类型), 174 |
| PyNumber_TrueDivide(C函数),61 | PyObject_AsCharBuffer (C函数),72 |
| PyNumber_Xor (C 函数), 62 | PyObject_ASCII (C函数),57 |
| PyNumberMethods (C 类型), 201 | PyObject_AsFileDescriptor (C函数), 115 |
| PyNumberMethods.nb_absolute(C 成员), 202 | PyObject_AsReadBuffer (C函数),72 |
| PyNumberMethods.nb_add(C 成员), 202 | PyObject_AsWriteBuffer(C 函数), 73 |
| PyNumberMethods.nb_and(C 成员), 202 | PyObject_Bytes (C 函数), 57 |
| PyNumberMethods.nb_bool(C 成员), 202 | PyObject_Call (C 函数), 57 |
| PyNumberMethods.nb_divmod(C 成员), 202 | PyObject_CallFunction (C 函数), 58 |
| PyNumberMethods.nb_float(C 成员),203 | PyObject_CallFunctionObjArgs (C函数),58 |
| PyNumberMethods.nb_floor_divide (C 成 | PyObject_CallMethod (C函数), 58 |
| 员), 203 | PyObject_CallMethodObjArgs (C函数),58 |
| PyNumberMethods.nb_index(C成员), 203 | PyObject_Callobject (C函数),58 |
| PyNumberMethods.nb_inplace_add(C 成员), 203 | PyObject_Calloc (C 函数), 168 PyObject_CheckBuffer (C 函数), 71 |
| PyNumberMethods.nb_inplace_and(C 成员), | PyObject_CheckReadBuffer(C函数),73 |
| 203 | PyObject_Del (C 函数), 173 |
| PyNumberMethods.nb_inplace_floor_divid | |
| (C 成员), 203 | PyObject_DelAttrString(C函数),56 |
| PyNumberMethods.nb_inplace_lshift(C成 | PyObject_DelItem(C函数),60 |
| 员), 203 | PyObject_Dir (C 函数), 60 |
| PyNumberMethods.nb_inplace_matrix_mult | ipylOpbject_Free (C 函数), 168 |
| (C成员), 203 | PyObject_GC_Del (C 函数), 210 |
| PyNumberMethods.nb_inplace_multiply(C | PyObject_GC_New (C 函数), 210 |
| 成员), 203 | PyObject_GC_NewVar(C函数),210 |
| PyNumberMethods.nb_inplace_or $(C$ 成员), | PyObject_GC_Resize(C函数),210 |
| 203 | PyObject_GC_Track (C函数), 210 |
| PyNumberMethods.nb_inplace_power (C \dot{R} | PyObject_GC_UnTrack (C函数), 210 |
| 页),203 PyNumberMethods.nb_inplace_remainder | PyObject_GenericGetAttr(C 函数),56 PyObject_GenericGetDict(C 函数),56 |
| (C 成员), 203 | PyObject_GenericSetAttr(C函数),56 |
| PyNumberMethods.nb_inplace_rshift(C 成 | PyObject_GenericSetDict (C函数), 56 |
| 员), 203 | PyObject_GetArenaAllocator(C 函数), 171 |
| PyNumberMethods.nb_inplace_subtract(C | PyObject_GetAttr(C函数),55 |
| 成员), 203 | PyObject_GetAttrString(C函数),56 |
| PyNumberMethods.nb_inplace_true_divide | |
| (C成员), 203 | PyObject_GetItem(C 函数), 60 |
| | PyObject_GetIter (C 函数), 60 |

| PyObject_HasAttr(C 函数), 55 | PyParser_SimpleParseStringFlagsFilename |
|----------------------------------------------|-------------------------------------------------|
| PyObject_HasAttrString(C 函数), 55 | (C 函数), 17 |
| PyObject_Hash (C 函数), 59 | PyPreConfig (C 类型), 152 |
| PyObject_HashNotImplemented(C 函数),59 | PyPreConfig_InitIsolatedConfig(C 函数), |
| PyObject_HEAD (C 宏), 174 | 152 |
| PyObject_HEAD_INIT (C 宏), 174 | PyPreConfig_InitPythonConfig (C 函数), |
| PyObject_Init (C函数), 173 | 152 |
| PyObject_InitVar(C函数),173 | PyPreConfig.allocator (C 成员), 152 |
| PyObject_IsInstance(C函数),57 | PyPreConfig.coerce_c_locale(C 成员), 152 |
| PyObject_IsSubclass (C 函数), 57 | PyPreConfig.coerce_c_locale_warn (C 成 |
| PyObject_IsTrue (C 函数), 59 | 员), 152 |
| PyObject_Length (C 函数), 60 | PyPreConfig.configure_locale $(C$ 成员), |
| PyObject_LengthHint (C 函数), 60 | 152 |
| PyObject_Malloc(C 函数), 168 | PyPreConfig.dev_mode(C 成员),152 |
| PyObject_New (C 函数), 173 | PyPreConfig.isolated (C 成员), 152 |
| PyObject_NewVar(C函数),173 | PyPreConfig.legacy_windows_fs_encoding |
| PyObject_Not (C 函数), 60 | (C成员), 153 |
| PyObjectob_next (C 成员), 184 | PyPreConfig.parse_argv(C 成员), 153 |
| PyObjectob_prev(C 成员), 184 | PyPreConfig.use_environment (C 成员), 153 |
| PyObject_Print (C 函数),55 | PyPreConfig.utf8_mode(C 成员), 153 |
| PyObject_Realloc(C 函数), 168 | PyProperty_Type (C 变量), 121 |
| PyObject_Repr(C 函数),57 | PyRun_AnyFile (C 函数), 15 |
| PyObject_RichCompare (C 函数), 56 | PyRun_AnyFileEx (C 函数), 15 |
| PyObject_RichCompareBool(C 函数), 56 | PyRun_AnyFileExFlags (C 函数), 15 |
| PyObject_SetArenaAllocator (C 函数), 171 | PyRun_AnyFileFlags (C 函数), 15 |
| PyObject_SetAttr(C 函数),56 | PyRun_File (C 函数), 17 |
| PyObject_SetAttrString(C 函数), 56 | PyRun_FileEx (C 函数), 17 |
| PyObject_SetItem(C 函数), 60 | PyRun_FileExFlags (C 函数), 17 |
| PyObject_Size (C 函数), 60 | PyRun_FileFlags (C 函数), 17 |
| PyObject_Str(C函数),57 | PyRun_InteractiveLoop(C 函数), 16 |
| PyObject_Type (C 函数), 60 | PyRun_InteractiveLoopFlags (C 函数), 16 |
| PyObject_TypeCheck (C 函数), 60 | PyRun_InteractiveOne(C 函数), 16 |
| PyObject_VAR_HEAD (C 宏), 174 | PyRun_InteractiveOneFlags(\emph{C} 函数), 16 |
| PyObjectArenaAllocator(C 类型), 171 | PyRun_SimpleFile (C 函数), 16 |
| PyObject.ob_refcnt (C 成员), 184 | PyRun_SimpleFileEx(C 函数), 16 |
| PyObject.ob_type (C 成员), 184 | PyRun_SimpleFileExFlags(C 函数), 16 |
| PyOS_AfterFork (C 函数), 36 | PyRun_SimpleString(C 函数), 16 |
| PyOS_AfterFork_Child(C 函数), 36 | PyRun_SimpleStringFlags (C 函数), 16 |
| PyOS_AfterFork_Parent (C 函数), 35 | PyRun_String (C 函数), 17 |
| PyOS_BeforeFork (C 函数), 35 | PyRun_StringFlags (C 函数), 17 |
| PyOS_CheckStack(C函数),36 | PySeqIter_Check (C 函数), 121 |
| PyOS_double_to_string (C 函数), 51 | PySeqIter_New (C 函数), 121 |
| PyOS_FSPath (C 函数), 35 | PySeqIter_Type (C 变量), 121 |
| PyOS_getsig(C 函数), 36 | PySequence_Check (C 函数), 63 |
| PyOS_InputHook (C 变量), 16 | PySequence_Concat (C 函数), 63 |
| PyOS_ReadlineFunctionPointer (C 变量), 16 | PySequence_Contains (C 函数), 64 |
| PyOS_setsig(C 函数), 36 | PySequence_Count (C 函数), 64 |
| PyOS_snprintf(C 函数), 51 | PySequence_DelItem(C 函数), 64 |
| PyOS_stricmp(C函数),52 | PySequence_DelSlice (C 函数), 64 |
| PyOS_string_to_double (C 函数), 51 | PySequence_Fast (C 函数), 64 |
| PyOS_strnicmp (C 函数), 52 | PySequence_Fast_GET_ITEM(C 函数), 65 |
| PyOS_vsnprintf(C 函数), 51 | PySequence_Fast_GET_SIZE(C 函数), 64 |
| PyParser_SimpleParseFile(C 函数), 17 | PySequence_Fast_ITEMS (C 函数), 65 |
| PyParser_SimpleParseFileFlags (C 函数), | PySequence_GetItem(C 函数), 64 |
| 17 | <pre>PySequence_GetItem(),7</pre> |
| PyParser_SimpleParseString(C 函数), 17 | PySequence_GetSlice (C 函数), 64 |
| PyParser_SimpleParseStringFlags (C 🕸 | PySequence_Index (C 函数), 64 |
| 数), 17 | PySequence_InPlaceConcat (C 函数), 63 |

| PySequence_InPlaceRepeat (C 函数), 64 | PyStructSequence_GET_ITEM(C 函数), 106 |
|----------------------------------------------------|--------------------------------------------|
| PySequence_ITEM(C 函数), 65 | PyStructSequence_GetItem(C 函数), 106 |
| PySequence_Length (C 函数), 63 | PyStructSequence_InitType (C 函数), 105 |
| PySequence_List (C 函数), 64 | PyStructSequence_InitType2(C 函数), 105 |
| PySequence_Repeat (C 函数), 63 | PyStructSequence_New (C 函数), 106 |
| PySequence_SetItem(C 函数), 64 | PyStructSequence_NewType(C 函数), 105 |
| PySequence_SetSlice (C 函数), 64 | PyStructSequence_SET_ITEM(C 函数), 106 |
| PySequence_Size (C 函数), 63 | PyStructSequence_SetItem(C 函数), 106 |
| PySequence_Tuple (C 函数), 64 | PyStructSequence_UnnamedField (C 变量) |
| PySequenceMethods (C 类型), 204 | 106 |
| PySequenceMethods.sq_ass_item $(C$ 成员), | PySys_AddAuditHook(C 函数), 39 |
| 204 | PySys_AddWarnOption(C 函数), 38 |
| PySequenceMethods.sq_concat(C 成员), 204 | PySys_AddWarnOptionUnicode (C 函数), 38 |
| PySequenceMethods.sq_contains (C 成员), | PySys_AddXOption (C 函数), 38 |
| 204 | PySys_Audit (C 函数), 38 |
| ${\tt PySequenceMethods.sq_inplace_concat} \ (C$ | PySys_FormatStderr(C 函数), 38 |
| 成员), 204 | PySys_FormatStdout(C 函数), 38 |
| PySequenceMethods.sq_inplace_repeat (C | PySys_GetObject (C 函数), 37 |
| 成员), 204 | PySys_GetXOptions (C 函数), 38 |
| PySequenceMethods.sq_item(C 成员), 204 | PySys_ResetWarnOptions (C 函数), 37 |
| PySequenceMethods.sq_length(C 成员), 204 | PySys_SetArgv (C函数), 137 |
| PySequenceMethods.sq_repeat(C 成员), 204 | PySys_SetArgv(), 134 |
| PySet_Add (C函数), 111 | PySys_SetArgvEx(C函数),137 |
| | PySys_SetArgvEx(), 10, 134 |
| PySet_Clear (C函数),111 | PySys_SetObject (C函数),37 |
| PySet_ClearFreeList (C函数), 111 | PySys_SetPath (C函数), 38 |
| PySet_Contains (C 函数), 111 | PySys_WriteStderr(C函数),38 |
| PySet_Discard (C函数), 111 | PySys_WriteStdout (C函数),38 |
| PySet_GET_SIZE(C函数),111 | Python 3000, 223 |
| PySet_New (C函数), 110 | Python 提高建议 |
| PySet_Pop (C函数), 111 | PEP 1, 223 |
| PySet_Size (C 函数), 111 | PEP 7,3 |
| PySet_Type (C变量), 110 | PEP 238, 19, 218 |
| PySetObject (C 类型), 110 | PEP 278, 225 |
| PySignal_SetWakeupFd(C函数),29 | PEP 302, 218, 221 |
| PySlice_AdjustIndices (C函数), 123 | PEP 343,217 |
| PySlice_Check (C函数), 122 | PEP 362, 216, 222 |
| PySlice_GetIndices (C函数), 122 | PEP 383,93,94 |
| PySlice_GetIndicesEx(C函数),122 | PEP 384,13 |
| PySlice_New (C 函数), 122 | PEP 393, 86, 92 |
| PySlice_Type (C变量), 122 | PEP 411, 223 |
| PySlice_Unpack (C函数), 122 | PEP 420, 218, 221, 223 |
| PyState_AddModule(C函数),120 | PEP 432,162 |
| PyState_FindModule (C函数), 120 | PEP 442,200 |
| PyState_RemoveModule(C函数),121 | PEP 443,219 |
| PyStatus (<i>C</i> 类型), 151 | PEP 451, 118, 218 |
| PyStatus_Error(C函数), 151 | PEP 484, 215, 218, 225 |
| PyStatus_Exception (C函数), 151 | PEP 489,119 |
| PyStatus_Exit (C 函数), 151 | PEP 492, 216, 217 |
| PyStatus_IsError (C函数), 151 | PEP 498,218 |
| PyStatus_IsExit (C函数), 151 | PEP 519,223 |
| PyStatus_NoMemory(C函数),151 | PEP 525, 216 |
| PyStatus_Ok (C 函数), 151 | PEP 526, 215, 225 |
| PyStatus.err_msg(C 成员), 151 | PEP 528, 133 |
| PyStatus.exitcode (C成员), 151 | PEP 529, 94, 133 |
| PyStatus.func (C 成员), 151 | PEP 538, 160 |
| PyStructSequence_Desc (C 类型), 105 | PEP 539, 147 |
| PyStructSequence_Field(C类型), 105 | PEP 540, 160 |
| - 1 | |

| PEP 552, 155 | PyTimeZone_FromOffsetAndName (C 函数), |
|---------------------------------------------|-----------------------------------------------------------------------------|
| PEP 578,39 | 129 |
| PEP 587, 150 | PyTrace_C_CALL(<i>C</i> 变量),146 |
| PEP 3116, 225 | PyTrace_C_EXCEPTION(C变量),146 |
| PEP 3119,57 | PyTrace_C_RETURN (C变量), 146 |
| PEP 3121, 117 | PyTrace_CALL(C变量),145 |
| PEP 3147,42 | PyTrace_EXCEPTION (C 变量), 146 |
| PEP 3151,32 | PyTrace_LINE (C 变量), 146 |
| PEP 3155, 223 | PyTrace_OPCODE (C变量), 146 |
| PYTHON*, 132 | PyTrace_RETURN (C 变量), 146 |
| PYTHONCOERCECLOCALE, 160 | PyTraceMalloc_Track(C函数), 171 |
| PYTHONDEBUG, 132 | PyTraceMalloc_Untrack(C函数),171 |
| PYTHONDONTWRITEBYTECODE, 132 | PyTuple_Check (C 函数), 104 |
| PYTHONDUMPREFS, 184 | PyTuple_CheckExact (C 函数), 104 |
| PYTHONHASHSEED, 132 | PyTuple_ClearFreeList (C函数), 105 |
| PYTHONHOME, 10, 132, 137, 156 | PyTuple_GET_ITEM(C函数), 104 |
| Pythonic, 223 | PyTuple_GET_SIZE (<i>C</i> 函数), 104 PyTuple_GetItem (<i>C</i> 函数), 104 |
| PYTHONINSPECT, 133 PYTHONIOENCODING, 135 | PyTuple_GetSlice(C函数), 104 PyTuple_GetSlice(C函数), 104 |
| PYTHONLEGACYWINDOWSFSENCODING, 133 | PyTuple_New (C 函数), 104 PyTuple_New (C 函数), 104 |
| PYTHONLEGACYWINDOWSSTDIO, 133 | PyTuple_Pack (C函数), 104 PyTuple_Pack (C函数), 104 |
| PYTHONMALLOC, 166, 169, 170 | PyTuple_SET_ITEM(C函数), 105 |
| PYTHONMALLOCSTATS, 166 | PyTuple_SetItem(C函数), 105 |
| PYTHONNOUSERSITE, 133 | PyTuple_SetItem(),6 |
| PYTHONOPTIMIZE, 133 | PyTuple_Size (C 函数), 104 |
| PYTHONPATH, 10, 132, 156 | PyTuple_Type (C变量), 104 |
| PYTHONUNBUFFERED, 133 | PyTupleObject (C 类型), 104 |
| PYTHONUTF8, 160 | PyType_Check (C 函数),75 |
| PYTHONVERBOSE, 133 | PyType_CheckExact (C 函数), 75 |
| PyThread_create_key (C 函数), 148 | PyType_ClearCache (C 函数), 75 |
| PyThread_delete_key (C函数), 148 | PyType_FromSpec (C函数), 76 |
| PyThread_delete_key_value (C函数), 148 | PyType_FromSpecWithBases(C函数),76 |
| PyThread_get_key_value (C函数), 148 | PyType_GenericAlloc (C 函数), 76 |
| PyThread_ReInitTLS (C 函数), 148 | PyType_GenericNew(C 函数), 76 |
| PyThread_set_key_value(C函数),148 | PyType_GetFlags (C 函数), 75 |
| PyThread_tss_alloc(C函数),147 | PyType_GetSlot (C函数),76 |
| PyThread_tss_create(C函数),148 | PyType_HasFeature (C 函数), 76 |
| PyThread_tss_delete (C 函数), 148 | PyType_IS_GC (C 函数), 76 |
| PyThread_tss_free (C 函数), 147 | PyType_IsSubtype (C 函数), 76 |
| PyThread_tss_get (C 函数), 148 | PyType_Modified (C 函数), 76 |
| PyThread_tss_is_created (C 函数), 148 | PyType_Ready (C 函数), 76 |
| PyThread_tss_set (C 函数), 148 | PyType_Slot (C 类型), 77 |
| PyThreadState, 138 | PyType_Slot.PyType_Slot.pfunc (C 成员) |
| PyThreadState (C 类型), 140 | 77 |
| PyThreadState_Clear (C 函数), 142 | PyType_Slot.PyType_Slot.slot(C 成员), 77 |
| PyThreadState_Delete(\emph{C} 函数), 142 | PyType_Spec (C 类型), 76 |
| PyThreadState_Get (C 函数), 140 | PyType_Spec.PyType_Spec.basicsize(C 成 |
| PyThreadState_GetDict(C 函数), 142 | 员),76 |
| PyThreadState_New (C 函数), 142 | PyType_Spec.PyType_Spec.flags (C 成员) |
| PyThreadState_Next (C 函数), 146 | 77 |
| PyThreadState_SetAsyncExc(C 函数), 142 | PyType_Spec.PyType_Spec.itemsize (C 成 |
| PyThreadState_Swap (C 函数), 140 | 员),77 |
| PyTime_Check (C函数), 128 | PyType_Spec.PyType_Spec.name $(C$ 成员),76 |
| PyTime_CheckExact (C 函数), 128 | PyType_Spec.PyType_Spec.slots (C 成员) |
| PyTime_FromTime (C函数), 129 | 77 |
| PyTime_FromTimeAndFold(C函数), 129 | PyType_Type (C变量), 75 |
| PyTimeZone_FromOffset (C 函数), 129 | PyTypeObject (C类型),75 |
| | PyTypeObject.tp_alloc(C 成员), 198 |

| PyTypeObject.tp_allocs(C 成员), 200 | PyUnicode_2BYTE_KIND(C 宏), 87 |
|---------------------------------------------|-------------------------------------------------|
| PyTypeObject.tp_as_async(C 成员), 187 | PyUnicode_4BYTE_DATA (C 函数), 87 |
| PyTypeObject.tp_as_buffer(C 成员), 190 | PyUnicode_4BYTE_KIND (C 宏), 87 |
| PyTypeObject.tp_as_mapping(C 成员), 188 | PyUnicode_AS_DATA (C 函数), 88 |
| PyTypeObject.tp_as_number(C 成员), 188 | PyUnicode_AS_UNICODE (C 函数), 88 |
| PyTypeObject.tp_as_sequence(C 成员), 188 | PyUnicode_AsASCIIString (C 函数), 101 |
| PyTypeObject.tp_base(C 成员), 196 | PyUnicode_AsCharmapString(C 函数), 101 |
| PyTypeObject.tp_bases (C 成员), 199 | PyUnicode_AsEncodedString(C 函数), 96 |
| PyTypeObject.tp_basicsize(C 成员), 185 | PyUnicode_AsLatin1String(\emph{C} 函数), 100 |
| PyTypeObject.tp_cache(C 成员), 199 | PyUnicode_AsMBCSString (C 函数), 102 |
| PyTypeObject.tp_call(C 成员),189 | PyUnicode_AsRawUnicodeEscapeString (C |
| PyTypeObject.tp_clear(C 成员), 193 | 函数), 100 |
| PyTypeObject.tp_dealloc(C 成员), 186 | PyUnicode_AsUCS4 (C 函数), 92 |
| PyTypeObject.tp_del(C 成员), 200 | PyUnicode_AsUCS4Copy (C 函数), 92 |
| PyTypeObject.tp_descr_get(C 成员), 196 | PyUnicode_AsUnicode (\emph{C} 函数), 93 |
| PyTypeObject.tp_descr_set(C 成员), 196 | PyUnicode_AsUnicodeAndSize (C 函数), 93 |
| PyTypeObject.tp_dict(C 成员), 196 | PyUnicode_AsUnicodeCopy (C 函数), 93 |
| PyTypeObject.tp_dictoffset(C 成员), 197 | PyUnicode_AsUnicodeEscapeString (C 🕸 |
| PyTypeObject.tp_doc(C 成员), 192 | 数), 100 |
| PyTypeObject.tp_finalize(C 成员), 200 | PyUnicode_AsUTF8 (C 函数), 97 |
| PyTypeObject.tp_flags(C 成员), 190 | PyUnicode_AsUTF8AndSize(C 函数), 97 |
| PyTypeObject.tp_free(C 成员),198 | PyUnicode_AsUTF8String (C 函数), 97 |
| PyTypeObject.tp_frees(C 成员), 200 | PyUnicode_AsUTF16String(C 函数), 99 |
| PyTypeObject.tp_getattr(C 成员), 187 | PyUnicode_AsUTF32String(C 函数), 98 |
| PyTypeObject.tp_getattro(C 成员), 189 | PyUnicode_AsWideChar(C 函数), 95 |
| PyTypeObject.tp_getset(C 成员), 195 | PyUnicode_AsWideCharString(C 函数), 95 |
| PyTypeObject.tp_hash(C 成员),188 | PyUnicode_Check (C 函数), 87 |
| PyTypeObject.tp_init(C 成员),197 | PyUnicode_CheckExact (C 函数), 87 |
| PyTypeObject.tp_is_gc(C 成员), 199 | PyUnicode_ClearFreeList (C 函数), 88 |
| PyTypeObject.tp_itemsize(C 成员), 185 | PyUnicode_Compare (C 函数), 103 |
| PyTypeObject.tp_iter(C 成员), 195 | PyUnicode_CompareWithASCIIString (C 🕸 |
| PyTypeObject.tp_iternext(C 成员), 195 | 数), 103 |
| PyTypeObject.tp_maxalloc(C 成员), 200 | PyUnicode_Concat (C 函数), 102 |
| PyTypeObject.tp_members (C 成员), 195 | PyUnicode_Contains (C 函数), 104 |
| PyTypeObject.tp_methods(C 成员),195 | PyUnicode_CopyCharacters (C 函数), 92 |
| PyTypeObject.tp_mro(C 成员),199 | PyUnicode_Count (C 函数), 103 |
| PyTypeObject.tp_name(C成员),185 | - PyUnicode_DATA (C 函数), 87 |
| PyTypeObject.tp_new(C 成员), 198 | PyUnicode_Decode (C 函数), 96 |
| PyTypeObject.tp_next(C成员),201 | PyUnicode_DecodeASCII (C 函数), 101 |
| PyTypeObject.tp_prev(C成员),200 | PyUnicode_DecodeCharmap(C函数),101 |
| PyTypeObject.tp_repr(C成员),188 | PyUnicode_DecodeFSDefault (C 函数), 95 |
| PyTypeObject.tp_richcompare(C成员),194 | PyUnicode_DecodeFSDefaultAndSize (C 🕸 |
| PyTypeObject.tp_setattr(C成员),187 | 数),94 |
| PyTypeObject.tp_setattro(C成员),189 | PyUnicode_DecodeLatin1 (C 函数), 100 |
| PyTypeObject.tp_str(C成员),189 | PyUnicode_DecodeLocale (C函数), 94 |
| PyTypeObject.tp_subclasses(C成员),199 | PyUnicode_DecodeLocaleAndSize (C 函数), |
| PyTypeObject.tp_traverse(C成员),192 | 93 |
| PyTypeObject.tp_vectorcall_offset(C成 | PyUnicode_DecodeMBCS (C 函数), 102 |
| 页), 186 | PyUnicode_DecodeMBCSStateful (C 函数), |
| PyTypeObject.tp_version_tag(C 成员), 200 | 102 |
| PyTypeObject.tp_weaklist(C成员), 199 | PyUnicode_DecodeRawUnicodeEscape (C 🕉 |
| PyTypeObject.tp_weaklistoffset $(C$ 成员), | 数), 100 |
| 194 | PyUnicode_DecodeUnicodeEscape (C 函数), |
| PyTZInfo_Check (C 函数), 129 | 100 |
| PyTZInfo_CheckExact (C函数), 129 | PyUnicode_DecodeUTF7 (C函数), 99 |
| PyUnicode_1BYTE_DATA(C函数),87 | PyUnicode_DecodeUTF7Stateful (C 函数), 99 |
| PyUnicode_1BYTE_KIND (C 宏), 87 | PyUnicode_DecodeUTF8 (C函数), 97 |
| PyUnicode_2BYTE_DATA(C函数),87 | PyUnicode_DecodeUTF8Stateful (C 函数), 97 |

| | (0.7 14) 400 |
|--------------------------------------------------------------------------|---------------------------------------------------|
| PyUnicode_DecodeUTF16 (C 函数), 98 | PyUnicode_Tailmatch(C 函数), 103 |
| PyUnicode_DecodeUTF16Stateful (C 函数), | PyUnicode_TransformDecimalToASCII $(C$ 函 |
| 98 | 数), 93 |
| PyUnicode_DecodeUTF32(C 函数), 97 | PyUnicode_Translate (C 函数), $101,103$ |
| PyUnicode_DecodeUTF32Stateful (C 函数), | PyUnicode_TranslateCharmap(C 函数), 101 |
| 98 | PyUnicode_Type (C变量), 86 |
| PyUnicode_Encode (C 函数), 96 | PyUnicode_WCHAR_KIND (C 宏), 87 |
| PyUnicode_EncodeASCII (C函数), 101 | PyUnicode_WRITE (C函数), 87 |
| PyUnicode_EncodeCharmap (C函数), 101 | PyUnicode_WriteChar(C函数),92 |
| PyUnicode_EncodeCodePage (C函数), 101 PyUnicode_EncodeCodePage (C函数), 102 | |
| - | PyUnicodeDecodeError_Create (C函数), 30 |
| PyUnicode_EncodeFSDefault (C函数), 95 | PyUnicodeDecodeError_GetEncoding (C 函 |
| PyUnicode_EncodeLatin1 (C函数), 100 | 数),30 |
| PyUnicode_EncodeLocale (C函数), 94 | PyUnicodeDecodeError_GetEnd(C函数),30 |
| PyUnicode_EncodeMBCS (C函数), 102 | PyUnicodeDecodeError_GetObject (C 函数), |
| PyUnicode_EncodeRawUnicodeEscape (C 🕉 | 30 |
| 数), 100 | PyUnicodeDecodeError_GetReason (C 函数), |
| PyUnicode_EncodeUnicodeEscape (C 函数), | 30 |
| 100 | PyUnicodeDecodeError_GetStart (C 函数), |
| PyUnicode_EncodeUTF7 (C 函数), 99 | 30 |
| PyUnicode_EncodeUTF8 (C 函数), 97 | PyUnicodeDecodeError_SetEnd(C 函数), 30 |
| PyUnicode_EncodeUTF16(C 函数), 99 | PyUnicodeDecodeError_SetReason (C 函数), |
| PyUnicode_EncodeUTF32 (C 函数), 98 | 30 |
| PyUnicode_Fill (C 函数), 92 | PyUnicodeDecodeError_SetStart (C 函数), |
| PyUnicode_Find (C 函数), 103 | 30 |
| PyUnicode_FindChar (C函数), 103 | PyUnicodeEncodeError_Create (C 函数), 30 |
| PyUnicode_Format (C函数), 104 | PyUnicodeEncodeError_GetEncoding (C 函 |
| PyUnicode_FromEncodedObject (C函数),91 | 数), 30 |
| PyUnicode_FromFormat (C函数), 90 | PyUnicodeEncodeError_GetEnd(C函数),30 |
| PyUnicode_FromFormatV(C函数),91 | PyUnicodeEncodeError_GetObject (C函数), |
| PyUnicode_FromKindAndData(C函数),90 | 30 |
| PyUnicode_FromObject(C函数),93 | PyUnicodeEncodeError_GetReason (C 函数), |
| PyUnicode_FromString (C 函数), 90 | 30 |
| | PyUnicodeEncodeError_GetStart (C 函数), |
| PyUnicode_FromString(), 108 | 30 30 |
| PyUnicode_FromStringAndSize(C函数),90 | |
| PyUnicode_FromUnicode (C函数), 92 | PyUnicodeEncodeError_SetEnd(C函数),30 |
| PyUnicode_FromWideChar(C函数),95 | PyUnicodeEncodeError_SetReason (C 函数), |
| PyUnicode_FSConverter (C 函数), 94 | 30 |
| PyUnicode_FSDecoder (C函数), 94 | PyUnicodeEncodeError_SetStart (C 函数), |
| PyUnicode_GET_DATA_SIZE (C 函数), 88 | 30 |
| PyUnicode_GET_LENGTH (C 函数), 87 | PyUnicodeObject (C 类型), 86 |
| PyUnicode_GET_SIZE (C 函数), 88 | PyUnicodeTranslateError_Create(C 函数), |
| PyUnicode_GetLength (C 函数), 91 | 30 |
| PyUnicode_GetSize (C 函数), 93 | PyUnicodeTranslateError_GetEnd(C 函数), |
| PyUnicode_InternFromString(\emph{C} 函数), 104 | 30 |
| PyUnicode_InternInPlace(C 函数), 104 | PyUnicodeTranslateError_GetObject(C 函 |
| PyUnicode_Join (C 函数), 103 | 数), 30 |
| PyUnicode_KIND (C 函数), 87 | PyUnicodeTranslateError_GetReason(C 函 |
| - PyUnicode_MAX_CHAR_VALUE (C 函数), 88 | 数),30 |
| PyUnicode_New (C 函数), 90 | PyUnicodeTranslateError_GetStart (C 函 |
| PyUnicode_READ (C函数), 87 | 数), 30 |
| PyUnicode_READ_CHAR (C 函数), 87 | PyUnicodeTranslateError_SetEnd(C 函数), |
| PyUnicode_ReadChar(C函数),92 | 30 |
| PyUnicode_READY (C函数), 87 | PyUnicodeTranslateError_SetReason(C 🖄 |
| PyUnicode_Replace (C函数), 103 | 数), 30 |
| PyUnicode_RichCompare (C 函数), 103 | 数),50 PyUnicodeTranslateError_SetStart (C 函 |
| PyUnicode_Split (C函数), 103 | 数), 30 |
| | |
| PyUnicode_Splitlines(C函数),102 | PyVarObject (C 类型), 174 |
| PyUnicode_Substring (C 函数), 92 | PyVarObject_HEAD_INIT(C 宏), 175 |

| PyVarObject.ob_size(C成员), 185 PyVectorcall_Call(C函数), 187 PyVectorcall_NARGS(C函数), 59 PyWeakref_Check(C函数), 124 PyWeakref_CheckProxy(C函数), 124 PyWeakref_CheckRef(C函数), 124 PyWeakref_GET_OBJECT(C函数), 124 PyWeakref_GetObject(C函数), 124 PyWeakref_NewProxy(C函数), 124 PyWeakref_NewProxy(C函数), 124 PyWeakref_NewRef(C函数), 124 PyWideStringList(C类型), 150 PyWideStringList_Append(C函数), 150 PyWideStringList.items(C成员), 150 PyWideStringList.items(C成员), 150 PyWideStringList.length(C成员), 150 PyWrapper_New(C函数), 121 | stderr (in module sys), 143 stdin stdout sdterr, 135 stdin (in module sys), 143 stdout sdterr, stdin, 135 stdout (in module sys), 143 strerror(), 24 string PyObject_Str (C function), 57 sum_list(), 8 sum_sequence(), 8, 9 sys 模块, 10, 134, 143 SystemError (built-in exception), 116 |
|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Q | T |
| | ternaryfunc (C 类型), 207 |
| qualified name 限定名称, 223 R | text encoding 文本编码, 224 text file 文本文件, 224 traverseproc(C类型),210 |
| realloc(),165 | triple-quoted string 三引号字符串 |
| reference count 引用计数, 224 | 224 |
| regular package 常规包, 224 | tuple |
| releasebufferproc(C 类型), 207 | E 置函数, 64, 107 |
| repr | 对象, 104 |
| E 置函数, 57, 188 | type |
| reprfunc(C类型), 206 | E 置函数, 60 |
| richcmpfunc(C 类型), 207 | 对象, 5, 75 |
| S | type 类型, 224 |
| S | type alias 类型别名, 224 type hint 类型提示, 225 |
| sdterr | type nint 矢型灰小,225 |
| stdin stdout, 135 | U |
| search | |
| path, module, 10, 134, 136 | ULONG_MAX, 80 |
| sequence | unaryfunc(<i>C</i> 类型),207 universal newlines 通用换行, 225 |
| 对象,83 | universal newlines 通用狭11,225 |
| sequence 序列, 224 | V |
| set 对象,110 | ····································· |
| 対象 ,110 set_all(),7 | variable annotation 变量注解, 225 卫 置函数 |
| set_aff(), / setattrfunc(<i>C</i> 类型), 207 | import,40 |
| setattrofunc (C 类型), 207 | abs, 61 |
| setswitchinterval() (in module sys), 138 | ascii,57 |
| SIGINT, 28 | bytes, 57 |
| signal | classmethod, 176 |
| 模块, 28 | compile, 41 |
| single dispatch 单分派, 224 | divmod, 61 |
| SIZE_MAX, 80 | float, 63 |
| slice 切片, 224 | hash, 59, 188 |
| special | int,63 |
| method, 224 | len, 60, 63, 65, 107, 109, 111 |
| special method 特殊方法, 224 | pow, 61, 62 |
| ssizeargfunc(C 类型), 207 | repr, 57, 188 |
| ssizeobjargproc $(C$ 类型), 207 | staticmethod, 176 |
| statement 语句, 224 | tuple, 64, 107 |
| staticmethod | type, 60 |
| E 置函数, 176 | vectorcallfunc (C 类型), 206 |

```
version (in module sys), 136, 137
virtual environment -- 虚拟环境,225
virtual machine -- 虚拟机,225
visitproc(C类型),210
对象
   bytearray, 85
   bytes, 83
   Capsule, 124
   complex number, 82
   dictionary, 108
    file, 114
    floating point, 81
    frozenset, 110
    function, 111
    instancemethod, 112
    integer, 78
   list, 106
   long integer, 78
   mapping, 108
   memoryview, 123
   method, 113
   module, 115
   None, 78
   numeric, 78
   sequence, 83
   set, 110
   tuple, 104
    type, 5, 75
W
模块
   __main__, 10, 134, 143
    _thread, 140
   builtins, 10, 134, 143
    signal, 28
    sys, 10, 134, 143
Ζ
Zen of Python -- Python 之禅,225
```