# **Installation Guide**

ref https://docs.openstack.org/install-guide

Ubuntu was chosen as host OS.

"It's a good way to learn by installing it manually for as many services as you could :-)."

Wey Gu

#### **Installation Guide**

Security

Host networking

My network solution

**Base Machine** 

**Controller actions** 

management network eth0 (enp0s3)

hostname and hosts

**SQL** database

Message queue

Memcached

Compute actions

management network eth0 (enp0s3)

configure NTP by editing /etc/chrony/chrony.conf

Keystone installation

Configure the Apache HTTP server

Finalize the installation

Create a domain, projects, users, and roles

Verify operation

Create OpenStack client environment scripts

Creating the scripts

Using the scripts

**Glance** installation

Install and configure

Prerequisites

Install and configure components

Finalize installation

Verify operation

Nova installation

Nova install and configure controller node

**Prerequisites** 

<u>Install</u> and configure components

Finalize installation

Nova Install and configure a compute node

Install and configure components

Finalize installation

Add the compute node to the cell database

Neutron installation

Neutron Install and configure controller node

**Prerequisites** 

Configure networking options Networking Option 1: Provider networks <u>Install the components</u> Configure the server component Configure the Modular Layer 2 (ML2) plug-in Configure the Linux bridge agent Configure the DHCP agent Configure the metadata agent Configure the Compute service to use the Networking service Finalize installation Verify operation Neutron Install and configure compute node <u>Install the components</u> Configure the common component Configure networking options Configure the Linux bridge agent Configure the Compute service to use the Networking service Finalize installation Verify operation Congratulations! Let's try booting an instance Create provider network/subnetwork Create flavor Add security group rules Launch an instance **Determine instance options** Launch the instance Access the instance using the virtual console Access the instance remotely [ISSUE] DHCP failure in VM troubleshooting Conclusion: Cinder on controller Install and configure controller node **Prerequisites** <u>Install and configure components</u> Configure Compute to use Block Storage Finalize installation Cinder on storage backend node configure storage network for compute Create cinder machine: storage Storage actions & cinder on storage node Management net eth0 (enp0s3) and storage net eth2 (enp0s9) configure NTP by editing /etc/chrony/chrony.conf Check new disk was there already

Install and configure a storage node

**Prerequisites** 

<u>Install and configure components</u>

Finalize installation

Verify operation

Let's try something on block storage!

Create a volume

Attach the volume to an instance

# **Security**

ref: https://docs.openstack.org/install-guide/environment-security.html

```
$ openssl rand -hex 10
```

# Host networking

ref: https://docs.openstack.org/install-guide/environment-networking.html

ref: https://help.ubuntu.com/lts/serverguide/network-configuration.html

The example architectures assume use of the following networks:

• Management on 10.0.0.0/24 with gateway 10.0.0.1

This network requires a gateway to provide Internet access to all nodes for administrative purposes such as package installation, security updates, DNS, and NTP.

Provider on 203.0.113.0/24 with gateway 203.0.113.1

This network requires a gateway to provide Internet access to instances in your OpenStack environment.

## My network solution

```
Net0:
        Network name: VirtualBox host-only Ethernet Adapter
        Purpose: administrator / management network
        IP block: 10.20.0.0/24
        DHCP: disable
        Linux device: eth0
Net1:
        Network name: VirtualBox host-only Ethernet Adapter#2
        Purpose: Provider network
        DHCP: disable
        IP block: 172.16.0.0/24
        Linux device: eth1
Net2:
        Network name: VirtualBox host-only Ethernet Adapter#3
        Purpose: Storage network
        DHCP: disable
        IP block: 192.168.199.0/24
        Linux device: eth2
Net3:
        Network name: VirtualBox Bridged // for accessing network or remote access purpose
        Purpose: Internet
        DHCP: enable
        IP block: 192.168.199.0/24
        Linux device: eth3
```

Edit the /etc/network/interfaces file to contain the following:

Replace Interface\_Name with the actual interface name. For example, eth1 or ens224.

```
# The provider network interface
auto INTERFACE_NAME
iface INTERFACE_NAME inet manual
up ip link set dev $IFACE up
down ip link set dev $IFACE down
```

#### **Base Machine**

- download image from <a href="https://launchpad.net/ubuntu/+mirror/mirrors.neusoft.edu.cn-release">https://launchpad.net/ubuntu/+mirror/mirrors.neusoft.edu.cn-release</a>
- Change root password

```
$ sudo su
# passwd
```

• Allow root ssh with password

```
# vi /etc/ssh/sshd_config
PermitRootLogin yes
```

• Check nic names

```
root@ubuntu:~# dmesg | grep rename

[ 2.799294] e1000 0000:00:09.0 enp0s9: renamed from eth2

[ 2.800192] e1000 0000:00:0a.0 enp0s10: renamed from eth3

[ 2.801072] e1000 0000:00:08.0 enp0s8: renamed from eth1

[ 2.804067] e1000 0000:00:03.0 enp0s3: renamed from eth0
```

• configure management network as a dummy one

```
# vi /etc/network/interfaces
auto enp0s3
iface enp0s3 inet static
address 10.20.0.11
netmask 255.255.255.0
```

- NTP
  - o install chrony

```
install chrony
```

• Edit the /etc/chrony/chrony.conf file and add, change, or remove these keys as necessary for your environment:

```
allow 10.20.0.0/24
```

restart service

```
# service chrony restart
```

• Install OpenStack packages

```
ref: https://docs.openstack.org/install-guide/environment-packages.html
```

Enable the OpenStack repository

```
# apt install software-properties-common
# add-apt-repository cloud-archive:ocata
```

Upgrade the packages on all nodes:

Set apt proxy before doing that will help save your life

```
# vi /etc/apt/apt.conf.d/90proxy
Acquire::http::Proxy "http://www-proxy.exu.ericsson.se:8080";
Acquire::https::Proxy "http://www-proxy.exu.ericsson.se:8080";
# sed -i -e 's/cn/us/g' /etc/apt/sources.list
```

```
# apt update && apt dist-upgrade -y
```

Install the OpenStack client:

```
# apt install python-openstackclient -y
```

# **Controller actions**

management network eth0 (enp0s3)

```
# vi /etc/network/interfaces

auto enp0s3
iface enp0s3 inet static
address 10.20.0.10
netmask 255.255.255.0
# ifup enp0s3
```

#### hostname and hosts

### **SQL** database

Install package

```
# apt install mariadb-server python-pymysql -y
```

Create and edit the /etc/mysql/mariadb.conf.d/99-openstack.cnf file and complete the following actions:

Create a [mysqld] section, and set the bind-address key to the management IP address of the controller node to enable access by other nodes via the management network. Set additional keys to enable useful options and the UTF-8 character set:

```
[mysqld]
bind-address = 10.20.0.10

default-storage-engine = innodb
innodb_file_per_table = on
max_connections = 4096
collation-server = utf8_general_ci
character-set-server = utf8
```

restart database service

```
# service mysql restart
```

Secure the database service by running the <code>mysql\_secure\_installation</code> script. In particular, choose a suitable password for the database <code>root</code> account:

```
# mysql_secure_installation
```

## Message queue

Install the package:

```
# apt install rabbitmq-server
```

Add the openstack user:

```
# rabbitmqctl add_user openstack RABBIT_PASS

Creating user "openstack" ...
```

Replace RABBIT\_PASS with a suitable password.

Permit configuration, write, and read access for the openstack user:

```
# rabbitmqctl set_permissions openstack ".*" ".*"
Setting permissions for user "openstack" in vhost "/" ...
```

#### Memcached

Install the packages:

```
# apt install memcached python-memcache
```

Edit the /etc/memcached.conf file and configure the service to use the management IP address of the controller node. This is to enable access by other nodes via the management network:

```
-1 10.20.0.10
```

Change the existing line that had -1 127.0.0.1.

Restart the Memcached service:

```
# service memcached restart
```

# **Compute actions**

# management network eth0 (enp0s3)

```
# vi /etc/network/interfaces

auto enp0s3
iface enp0s3 inet static
address 10.20.0.10
netmask 255.255.255.0
# ifup enp0s3
```

# configure NTP by editing /etc/chrony/chrony.conf

```
server 10.20.0.10 iburst
```

change hostname and hosts

# **Keystone installation**

ref: https://docs.openstack.org/newton/install-guide-ubuntu/keystone.html

Before you configure the OpenStack Identity service, you must create a database and an administration token.

To create the database, complete the following actions:

• Use the database access client to connect to the database server as the root user:

```
$ mysql -u root -p
```

In 16.04 LTS local access need no user/psw

```
# mysql
```

• Create the keystone database:

```
mysql> CREATE DATABASE keystone;
```

• Grant proper access to the keystone database:

```
mysql> GRANT ALL PRIVILEGES ON keystone.* TO 'keystone'@'localhost' \
    IDENTIFIED BY 'KEYSTONE_DBPASS';
mysql> GRANT ALL PRIVILEGES ON keystone.* TO 'keystone'@'%' \
    IDENTIFIED BY 'KEYSTONE_DBPASS';
```

Replace KEYSTONE\_DBPASS with a suitable password.

• Exit the database access client.

Run the following command to install the packages:

```
# apt install keystone -y
```

1. Edit the /etc/keystone/keystone.conf file and complete the following actions:

• In the [database] section, configure database access:

```
[database]
...
connection = mysql+pymysql://keystone:KEYSTONE_DBPASS@controller/keystone
```

Replace KEYSTONE\_DBPASS with the password you chose for the database.

Comment out or remove any other connection options in the [database] section.

• In the [token] section, configure the Fernet token provider:

```
[token]
...
provider = fernet
```

2. Populate the Identity service database:

```
# su -s /bin/sh -c "keystone-manage db_sync" keystone
```

3. Initialize Fernet key repositories:

```
# keystone-manage fernet_setup --keystone-user keystone --keystone-group keystone
# keystone-manage credential_setup --keystone-user keystone --keystone-group keystone
```

4. Bootstrap the Identity service:

```
# keystone-manage bootstrap --bootstrap-password ADMIN_PASS \
    --bootstrap-admin-url http://controller:35357/v3/ \
    --bootstrap-internal-url http://controller:35357/v3/ \
    --bootstrap-public-url http://controller:5000/v3/ \
    --bootstrap-region-id RegionOne
```

Replace ADMIN\_PASS with a suitable password for an administrative user.

# **Configure the Apache HTTP server**

1. Edit the /etc/apache2/apache2.conf file and configure the ServerName option to reference the controller node:

```
ServerName controller
```

#### Finalize the installation

1. Restart the Apache service and remove the default SQLite database:

```
# service apache2 restart
# rm -f /var/lib/keystone/keystone.db
```

1. Configure the administrative account

```
$ export OS_USERNAME=admin
$ export OS_PASSWORD=ADMIN_PASS
$ export OS_PROJECT_NAME=admin
$ export OS_USER_DOMAIN_NAME=Default
$ export OS_PROJECT_DOMAIN_NAME=Default
$ export OS_AUTH_URL=http://controller:35357/v3
$ export OS_IDENTITY_API_VERSION=3
```

Replace ADMIN\_PASS with the password used in the keystone-manage bootstrap command from the section called <u>Install and configure</u>.

## Create a domain, projects, users, and roles

The Identity service provides authentication services for each OpenStack service. The authentication service uses a combination of <u>domains</u>, <u>projects</u>, <u>users</u>, and <u>roles</u>.

1. This guide uses a service project that contains a unique user for each service that you add to your environment. Create the service project:

- 2. Regular (non-admin) tasks should use an unprivileged project and user. As an example, this guide creates the demo project and user.
  - Create the demo project:

Do not repeat this step when creating additional users for this project.

Create the demo user:

• Create the user role:

• Add the user role to the demo project and user:

```
$ openstack role add --project demo --user demo user
```

For security reasons, disable the temporary authentication token mechanism:

```
Edit the /etc/keystone/keystone-paste.ini file and remove admin_token_auth from the [pipeline:public_api], [pipeline:admin_api], and [pipeline:api_v3] sections.
```

Unset the temporary OS\_AUTH\_URL and OS\_PASSWORD environment variable:

```
$ unset OS_AUTH_URL OS_PASSWORD
```

As the admin user, request an authentication token:

This command uses the password for the admin user. As we gave above it's ADMIN\_PASS.

As the demo user, request an authentication token:

This command uses the password for the demo user and API port 5000 which only allows regular (non-admin) access to the Identity service API.

# **Create OpenStack client environment scripts**

The previous section used a combination of environment variables and command options to interact with the Identity service via the openstack client. To increase efficiency of client operations, OpenStack supports simple client environment scripts also known as OpenRC files. These scripts typically contain common options for all clients, but also support unique options. For more information, see the OpenStack End User Guide.

#### **Creating the scripts**

Create client environment scripts for the admin and demo projects and users. Future portions of this guide reference these scripts to load appropriate credentials for client operations.

1. Edit the admin-openro file and add the following content:

```
export OS_PROJECT_DOMAIN_NAME=Default
export OS_USER_DOMAIN_NAME=Default
export OS_PROJECT_NAME=admin
export OS_USERNAME=admin
export OS_PASSWORD=ADMIN_PASS
export OS_AUTH_URL=http://controller:35357/v3
export OS_IDENTITY_API_VERSION=3
export OS_IMAGE_API_VERSION=2
```

Replace ADMIN\_PASS with the password you chose for the admin user in the Identity service.

2. Edit the demo-openro file and add the following content:

```
export OS_PROJECT_DOMAIN_NAME=Default
export OS_USER_DOMAIN_NAME=Default
export OS_PROJECT_NAME=demo
export OS_USERNAME=demo
export OS_PASSWORD=demo
export OS_AUTH_URL=http://controller:5000/v3
export OS_IDENTITY_API_VERSION=3
export OS_IMAGE_API_VERSION=2
```

Replace OS\_PASSWORD=demo with the password you chose for the demo user in the Identity service.

### Using the scripts

To run clients as a specific project and user, you can simply load the associated client environment script prior to running them. For example:

1. Load the admin-openro file to populate environment variables with the location of the Identity service and the admin project and user credentials:

```
$ . admin-openrc
```

2. Request an authentication token:

### **Glance installation**

ref: https://docs.openstack.org/newton/install-guide-ubuntu/glance.html

For simplicity, this guide describes configuring the Image service to use the file back end, which uploads and stores in a directory on the controller node hosting the Image service. By default, this directory is \[ \frac{\frac{1}{1}}{\frac{1}{2}} \]

Before you proceed, ensure that the controller node has at least several gigabytes of space available in this directory. Keep in mind that since the file back end is often local to a controller node, it is not typically suitable for a multi-node glance deployment.

For information on requirements for other back ends, see **Configuration Reference**.

## Install and configure

This section describes how to install and configure the Image service, code-named glance, on the controller node. For simplicity, this configuration stores images on the local file system.

# **Prerequisites**

Before you install and configure the Image service, you must create a database, service credentials, and API endpoints.

- 1. To create the database, complete these steps:
  - Use the database access client to connect to the database server as the root user:

```
$ mysql -u root -p
```

• Create the glance database:

```
mysql> CREATE DATABASE glance;
```

• Grant proper access to the glance database:

```
mysql> GRANT ALL PRIVILEGES ON glance.* TO 'glance'@'localhost' \
    IDENTIFIED BY 'GLANCE_DBPASS';
mysql> GRANT ALL PRIVILEGES ON glance.* TO 'glance'@'%' \
    IDENTIFIED BY 'GLANCE_DBPASS';
```

Replace GLANCE\_DBPASS with a suitable password.

- o Exit the database access client.
- 2. Source the admin credentials to gain access to admin-only CLI commands:

```
$ . admin-openrc
```

- 3. To create the service credentials, complete these steps:
  - Create the glance user:

• Add the admin role to the glance user and service project:

```
$ openstack role add --project service --user glance admin
```

This command provides no output.

• Create the glance service entity:

4. Create the Image service API endpoints:

```
$ openstack endpoint create --region RegionOne \
 image public http://controller:9292
+-----+
      | Value
+-----
| interface | public
| region | RegionOne
| region_id | RegionOne
| service_name | glance
| service_type | image
   http://controller:9292
+-----
$ openstack endpoint create --region RegionOne \
 image internal http://controller:9292
+----+
| Field | Value
+----+
| interface | internal
region RegionOne
| region_id | RegionOne
| service_name | glance
| service_type | image
    http://controller:9292
+-----
$ openstack endpoint create --region RegionOne \
 image admin http://controller:9292
+----+
| Field | Value
+----
| enabled | True |
| id | 0c37ed58103f4300a84ff125a539032d |
| interface | admin
| region | RegionOne
| region_id | RegionOne
| service_name | glance
| service_type | image
url http://controller:9292
```

## Install and configure components

Install the packages:

```
# apt install glance -y
```

- 1. Edit the /etc/glance/glance-api.conf file and complete the following actions:
  - In the [database] section, configure database access:

```
[database]
...
connection = mysql+pymysql://glance:GLANCE_DBPASS@controller/glance
```

Replace GLANCE\_DBPASS with the password you chose for the Image service database.

• In the [keystone\_authtoken] and [paste\_deploy] sections, configure Identity service access:

```
[keystone_authtoken]
...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = Default
user_domain_name = Default
project_name = service
username = glance
password = glance

[paste_deploy]
...
flavor = keystone
```

Replace password = glance with the password you chose for the glance user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

• In the [glance\_store] section, configure the local file system store and location of image files:

```
[glance_store]
...
stores = file,http
default_store = file
filesystem_store_datadir = /var/lib/glance/images/
```

- 2. Edit the /etc/glance/glance-registry.conf file and complete the following actions:
  - In the [database] section, configure database access:

```
[database]
...
connection = mysql+pymysql://glance:GLANCE_DBPASS@controller/glance
```

Replace GLANCE\_DBPASS with the password you chose for the Image service database.

• In the [keystone\_authtoken] and [paste\_deploy] sections, configure Identity service access:

```
[keystone_authtoken]
...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = Default
user_domain_name = Default
project_name = service
username = glance
password = glance

[paste_deploy]
...
flavor = keystone
```

Replace password = glance with the password you chose for the glance user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

Populate the Image service database:

```
# su -s /bin/sh -c "glance-manage db_sync" glance
```

Ignore any deprecation messages in this output.

#### Finalize installation

Restart the Image services:

```
# service glance-registry restart
# service glance-api restart
```

## **Verify operation**

Verify operation of the Image service using <u>CirrOS</u>, a small Linux image that helps you test your OpenStack deployment.

For more information about how to download and build images, see <u>OpenStack Virtual Machine Image</u> <u>Guide</u>. For information about how to manage images, see the <u>OpenStack End User Guide</u>.

1. Source the admin credentials to gain access to admin-only CLI commands:

```
$ . admin-openro
```

2. Download the source image:

```
$ wget http://download.cirros-cloud.net/0.3.4/cirros-0.3.4-x86_64-disk.img

tip: add proxy to improve speed in office network

$ export http_proxy=http://www-proxy.exu.ericsson.se:8080

// after wget

$ unset http_proxy
```

Install wget if your distribution does not include it.

3. Upload the image to the Image service using the <a href="QCOW2">QCOW2</a> disk format, <a href="bare">bare</a> container format, and public visibility so all projects can access it:

```
$ openstack image create "cirros" \
--file cirros-0.3.4-x86_64-disk.img \
--disk-format qcow2 --container-format bare \
--public
     | Value
Field
+-----
| container_format | bare
| id
       cc5c6982-4910-471e-b864-1098015901b5
      | 0
min_disk
| min_ram
       0
cirros
       /v2/schemas/image
schema
size
       13200896
       active
status
tags
visibility
       | public
```

For information about the **openstack image create** parameters, see <u>Create or update an image</u> (<u>glance</u>) in the <u>OpenStack UserGuide</u>.

For information about disk and container formats for images, see <u>Disk and container formats for images</u> in the OpenStack VirtualMachine Image Guide.

OpenStack generates IDs dynamically, so you will see different values in the example command output.

4. Confirm upload of the image and validate attributes:

## **Nova installation**

ref: https://docs.openstack.org/newton/install-guide-ubuntu/nova.html

# Nova install and configure controller node

# **Prerequisites**

Before you install and configure the Compute service, you must create databases, service credentials, and API endpoints.

- 1. To create the databases, complete these steps:
  - Use the database access client to connect to the database server as the root user:

```
# mysql
```

• Create the nova\_api , nova , and nova\_cell0 databases:

```
MariaDB [(none)]> CREATE DATABASE nova_api;
MariaDB [(none)]> CREATE DATABASE nova;
MariaDB [(none)]> CREATE DATABASE nova_cell0;
```

• Grant proper access to the databases:

```
MariaDB [(none)]> GRANT ALL PRIVILEGES ON nova_api.* TO 'nova'@'localhost' \
    IDENTIFIED BY 'NOVA_DBPASS';
MariaDB [(none)]> GRANT ALL PRIVILEGES ON nova_api.* TO 'nova'@'%' \
    IDENTIFIED BY 'NOVA_DBPASS';

MariaDB [(none)]> GRANT ALL PRIVILEGES ON nova.* TO 'nova'@'localhost' \
    IDENTIFIED BY 'NOVA_DBPASS';
MariaDB [(none)]> GRANT ALL PRIVILEGES ON nova.* TO 'nova'@'%' \
    IDENTIFIED BY 'NOVA_DBPASS';

MariaDB [(none)]> GRANT ALL PRIVILEGES ON nova_cell0.* TO 'nova'@'localhost' \
    IDENTIFIED BY 'NOVA_DBPASS';
MariaDB [(none)]> GRANT ALL PRIVILEGES ON nova_cell0.* TO 'nova'@'%' \
    IDENTIFIED BY 'NOVA_DBPASS';
```

Replace NOVA\_DBPASS with a suitable password.

- Exit the database access client.
- 2. Source the admin credentials to gain access to admin-only CLI commands:

```
$ . admin-openrc
```

- 3. Create the Compute service credentials:
  - o Create the nova user:

• Add the admin role to the nova user:

```
$ openstack role add --project service --user nova admin
```

This command provides no output.

O Create the nova service entity:

4. Create the Compute API service endpoints:

```
$ openstack endpoint create --region RegionOne \
 compute public http://controller:8774/v2.1
+-----
| Field
        | Value
+-----
| enabled | True
| id | 3c1ca
        3c1caa473bfe4390a11e7177894bcc7b
| interface | public
| region | RegionOne
| region_id | RegionOne
| service_name | nova
| service_type | compute
url http://controller:8774/v2.1
$ openstack endpoint create --region RegionOne \
 compute internal http://controller:8774/v2.1
| Field
        Value
+----
| interface | internal | region | RegionOne
| region_id | RegionOne
| service_name | nova
| service_type | compute
      http://controller:8774/v2.1
$ openstack endpoint create --region RegionOne \
 compute admin http://controller:8774/v2.1
| Field | Value
+-----
| interface | admin
| region | RegionOne
| region_id | RegionOne
| service_name | nova
| service_type | compute
url http://controller:8774/v2.1
```

6. Add the Placement user to the service project with the admin role:

```
$ openstack role add --project service --user placement admin
```

This command provides no output.

7. Create the Placement API entry in the service catalog:

8. Create the Placement API service endpoints:

```
$ openstack endpoint create --region RegionOne placement public http://controller:8778
+-----+
        | Value
+-----
| enabled | True |
| id | 2b1b2637908b4137a9c2e0470487cbc0 |
| interface | public
| region | RegionOne
| region_id | RegionOne
| service_name | placement
| service_type | placement
url http://controller:8778
+-----+
$ openstack endpoint create --region RegionOne placement internal http://controller:8778
+-----+
        | Value
+----+
| enabled | True |
| id | 02bcda9a150a4bd7993ff4879df971ab |
| interface | internal
region RegionOne
| region_id | RegionOne
| service_name | placement
| service_type | placement
url http://controller:8778
+-----
$ openstack endpoint create --region RegionOne placement admin http://controller:8778
+-----
        | Value
+-----
| enabled | True |
| id | 3d71177b9e0f406f98cbff198d74b182 |
| interface | admin
region RegionOne
| region_id | RegionOne
| service_id | 2d1a27022e6e4185b86adac4444c495f |
| service_name | placement
| service_type | placement
url http://controller:8778
```

# Install and configure components

Default configuration files vary by distribution. You might need to add these sections and options rather than modifying existing sections and options. Also, an ellipsis (...) in the configuration snippets indicates potential default configuration options that you should retain.

1. Install the packages:

```
# apt install nova-api nova-conductor nova-consoleauth \
  nova-novncproxy nova-scheduler nova-placement-api
```

- 1. Edit the /etc/nova/nova.conf file and complete the following actions:
  - In the [api\_database] and [database] sections, configure database access:

```
[api_database]
# ...
connection = mysql+pymysql://nova:NOVA_DBPASS@controller/nova_api

[database]
# ...
connection = mysql+pymysql://nova:NOVA_DBPASS@controller/nova
```

Replace NOVA\_DBPASS with the password you chose for the Compute databases.

• In the [DEFAULT] section, configure RabbitMQ message queue access:

```
[DEFAULT]
# ...
transport_url = rabbit://openstack:RABBIT_PASS@controller
```

Replace RABBIT\_PASS with the password you chose for the openstack account in RabbitMQ.

• In the [api] and [keystone\_authtoken] sections, configure Identity service access:

```
[api]
# ...
auth_strategy = keystone

[keystone_authtoken]
# ...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = default
user_domain_name = default
project_name = service
username = nova
password = nova
```

Replace nova with the password you chose for the nova user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

• In the [DEFAULT] section, configure the my\_ip option to use the management interface IP address of the controller node:

```
[DEFAULT]
# ...
my_ip = 10.0.0.11
```

• In the [DEFAULT] section, enable support for the Networking service:

```
[DEFAULT]
# ...
use_neutron = True
firewall_driver = nova.virt.firewall.NoopFirewallDriver
```

By default, Compute uses an internal firewall driver. Since the Networking service includes a firewall driver, you must disable the Compute firewall driver by using the nova.virt.firewall.NoopFirewallDriver firewall driver.

• In the [vnc] section, configure the VNC proxy to use the management interface IP address of the controller node:

```
[vnc]
enabled = true
# ...
vncserver_listen = $my_ip
vncserver_proxyclient_address = $my_ip
```

• In the [glance] section, configure the location of the Image service API:

```
[glance]
# ...
api_servers = http://controller:9292
```

• In the [oslo\_concurrency] section, configure the lock path:

```
[oslo_concurrency]
# ...
lock_path = /var/lib/nova/tmp
```

- Due to a packaging bug, remove the log\_dir option from the [DEFAULT] section.
- In the [placement] section, configure the Placement API:

```
[placement]
# ...
os_region_name = RegionOne
project_domain_name = Default
project_name = service
auth_type = password
user_domain_name = Default
auth_url = http://controller:35357/v3
username = placement
password = PLACEMENT_PASS
```

Replace PLACEMENT\_PASS with the password you choose for the placement user in the Identity service. Comment out any other options in the [placement] section.

1. Populate the nova-api database:

```
# su -s /bin/sh -c "nova-manage api_db sync" nova
```

Ignore any deprecation messages in this output.

2. Register the cello database:

```
# su -s /bin/sh -c "nova-manage cell_v2 map_cell0" nova
```

3. Create the cell1 cell:

```
# su -s /bin/sh -c "nova-manage cell_v2 create_cell --name=cell1 --verbose" nova 109e1d4b-536a-40d0-83c6-5f121b82b650
```

4. Populate the nova database:

```
# su -s /bin/sh -c "nova-manage db sync" nova
```

5. Verify nova cell0 and cell1 are registered correctly:

```
# nova-manage cell_v2 list_cells
+-----+
| Name | UUID |
+-----+
| cell1 | 109e1d4b-536a-40d0-83c6-5f121b82b650 |
| cell0 | 0000000-0000-0000-00000000000 |
+-----+
```

#### Finalize installation

• Restart the Compute services:

```
# service nova-api restart
# service nova-consoleauth restart
# service nova-scheduler restart
# service nova-conductor restart
# service nova-novncproxy restart
```

# Nova Install and configure a compute node

This section describes how to install and configure the Compute service on a compute node. The service supports several <a href="https://www.nyervisors">hypervisors</a> to deploy <a href="https://www.nyervisors">instances</a> or <a href="https://www.nyervisors">VMs</a>. For simplicity, this configuration uses the <a href="https://www.nyervisors">QEMU</a> hypervisor with the <a href="https://www.nyervisors">KVM</a> extension on compute nodes that support hardware acceleration for virtual machines.

## Install and configure components

1. Install the packages:

```
# apt install nova-compute
```

- 1. Edit the /etc/nova/nova.conf file and complete the following actions:
  - In the [DEFAULT] section, configure RabbitMQ message queue access:

```
[DEFAULT]
...
transport_url = rabbit://openstack:RABBIT_PASS@controller
```

Replace RABBIT\_PASS with the password you chose for the openstack account in RabbitMQ.

• In the [DEFAULT] and [keystone\_authtoken] sections, configure Identity service access:

```
[DEFAULT]
...
auth_strategy = keystone

[keystone_authtoken]
...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = Default
user_domain_name = Default
project_name = service
username = nova
password = nova
```

Replace password = nova with the password you chose for the nova user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

• In the [DEFAULT] section, configure the my\_ip option:

```
[DEFAULT]
...
my_ip = MANAGEMENT_INTERFACE_IP_ADDRESS
```

Replace MANAGEMENT\_INTERFACE\_IP\_ADDRESS with the IP address of the management network interface on your compute node, typically 10.0.0.31 for the first node in the example architecture.

here our compute is 10.20.0.20

• In the [DEFAULT] section, enable support for the Networking service:

```
[DEFAULT]
...
use_neutron = True
firewall_driver = nova.virt.firewall.NoopFirewallDriver
```

By default, Compute uses an internal firewall service. Since Networking includes a firewall service, you must disable the Compute firewall service by using the nova.virt.firewall.NoopFirewallDriver
firewall driver.

• In the [vnc] section, enable and configure remote console access:

```
[vnc]
...
enabled = True
vncserver_listen = 0.0.0.0
vncserver_proxyclient_address = $my_ip
novncproxy_base_url = http://controller:6080/vnc_auto.html
```

The server component listens on all IP addresses and the proxy component only listens on the management interface IP address of the compute node.

The base URL indicates the location where you can use a web browser to access remote consoles of instances on this compute node.

If the web browser to access remote consoles resides on a host that cannot resolve the controller hostname, you must replace controller with the management interface IP address of the controller node.

• In the [glance] section, configure the location of the Image service API:

```
[glance]
...
api_servers = http://controller:9292
```

• In the [oslo\_concurrency] section, configure the lock path:

```
[oslo_concurrency]
...
lock_path = /var/lib/nova/tmp
```

- Due to a packaging bug, remove the log-dir option from the [DEFAULT] section.
- In the [placement] section, configure the Placement API:

```
[placement]
# ...
os_region_name = RegionOne
project_domain_name = Default
project_name = service
auth_type = password
user_domain_name = Default
auth_url = http://controller:35357/v3
username = placement
password = placement
```

Replace placement with the password you choose for the placement user in the Identity service. Comment out any other options in the [placement] section.

#### Finalize installation

Determine whether your compute node supports hardware acceleration for virtual machines:

```
$ egrep -c '(vmx|svm)' /proc/cpuinfo
```

If this command returns a value of one or greater, your compute node supports hardware acceleration which typically requires no additional configuration.

If this command returns a value of zero, your compute node does not support hardware acceleration and you must configure libvirt to use QEMU instead of KVM.

• Edit the [libvirt] section in the /etc/nova/nova-compute.conf file as follows:

```
[libvirt]
...
virt_type = qemu
```

Restart the Compute service:

```
# service nova-compute restart
```

# Add the compute node to the cell database

Run the following commands on the **controller** node.

1. Source the admin credentials to enable admin-only CLI commands, then confirm there are compute hosts in the database:

2. Discover compute hosts:

```
# su -s /bin/sh -c "nova-manage cell_v2 discover_hosts --verbose" nova

Found 2 cell mappings.
Skipping cell0 since it does not contain hosts.
Getting compute nodes from cell 'cell1': ad5a5985-a719-4567-98d8-8d148aaae4bc
Found 1 computes in cell: ad5a5985-a719-4567-98d8-8d148aaae4bc
Checking host mapping for compute host 'compute': fe58ddc1-1d65-4f87-9456-bc040dc106b3
Creating host mapping for compute host 'compute': fe58ddc1-1d65-4f87-9456-bc040dc106b3
```

When you add new compute nodes, you must run nova-manage cell\_v2 discover\_hosts on the controller node to register those new compute nodes. Alternatively, you can set an appropriate interval in /etc/nova/nova.conf:

```
[scheduler]
discover_hosts_in_cells_interval = 300
```

## **Neutron installation**

ref: https://docs.openstack.org/newton/install-guide-ubuntu/neutron.html

This chapter explains how to install and configure the Networking service (neutron) using the <u>provider</u> networks.

For more information about the Networking service including virtual networking components, layout, and traffic flows, see the <a href="OpenStack Networking Guide">OpenStack Networking Guide</a>.

# Neutron Install and configure controller node

# **Prerequisites**

Before you configure the OpenStack Networking (neutron) service, you must create a database, service credentials, and API endpoints.

- 1. To create the database, complete these steps:
  - Use the database access client to connect to the database server as the root user:

```
$ mysql -u root -p
```

o Create the neutron database:

```
mysql> CREATE DATABASE neutron;
```

• Grant proper access to the neutron database, replacing NEUTRON\_DBPASS with a suitable password:

```
mysql> GRANT ALL PRIVILEGES ON neutron.* TO 'neutron'@'localhost' \
    IDENTIFIED BY 'NEUTRON_DBPASS';
mysql> GRANT ALL PRIVILEGES ON neutron.* TO 'neutron'@'%' \
    IDENTIFIED BY 'NEUTRON_DBPASS';
```

- Exit the database access client.
- 2. Source the admin credentials to gain access to admin-only CLI commands:

```
$ . admin-openrc
```

- 3. To create the service credentials, complete these steps:
  - Create the neutron user:

• Add the admin role to the neutron user:

```
$ openstack role add --project service --user neutron admin
```

This command provides no output.

• Create the neutron service entity:

4. Create the Networking service API endpoints:

```
$ openstack endpoint create --region RegionOne \
 network public http://controller:9696
+----+
| Field | Value
| 85d80a6d02fc4b7683f611d7fc1493a3 |
| interface | public
| region | RegionOne
| region_id | RegionOne
| service_name | neutron
| service_type | network
url http://controller:9696
$ openstack endpoint create --region RegionOne \
 network internal http://controller:9696
| Field | Value
+-----
| enabled | True |
| id | 09753b537ac74422a68d2d791cf3714f |
| interface | internal
| region | RegionOne
| region_id | RegionOne
| service_name | neutron
| service_type | network
url http://controller:9696
$ openstack endpoint create --region RegionOne \
 network admin http://controller:9696
| Field | Value
+-----+
| enabled | True |
| id | 1ee14289c9374dffb5db92a5c112fc4e |
| interface | admin
| region | RegionOne
region_id RegionOne
| service_name | neutron
| service_type | network
url http://controller:9696
```

## **Configure networking options**

You can deploy the Networking service using one of two architectures represented by options 1 and 2.

Option 1 deploys the simplest possible architecture that only supports attaching instances to provider (external) networks. No self-service (private) networks, routers, or floating IP addresses. Only the admin or other privileged user can manage provider networks.

• Networking Option 1: Provider networks

Here we choose Option 1.

## **Networking Option 1: Provider networks**

Install and configure the Networking components on the *controller* node.

### Install the components

```
# apt install neutron-server neutron-plugin-m12 \
  neutron-linuxbridge-agent neutron-dhcp-agent \
  neutron-metadata-agent -y
```

## Configure the server component

The Networking server component configuration includes the database, authentication mechanism, message queue, topology change notifications, and plug-in.

- Edit the /etc/neutron/neutron.conf | file and complete the following actions:
  - In the [database] section, configure database access:

```
[database]
...
connection = mysql+pymysql://neutron:NEUTRON_DBPASS@controller/neutron
```

Replace NEUTRON\_DBPASS with the password you chose for the database.

Comment out or remove any other connection options in the [database] section.

• In the [DEFAULT] section, enable the Modular Layer 2 (ML2) plug-in and disable additional plugins:

```
[DEFAULT]
...
core_plugin = m12
service_plugins =
```

• In the [DEFAULT] section, configure RabbitMQ message queue access:

```
[DEFAULT]
...
transport_url = rabbit://openstack:RABBIT_PASS@controller
```

Replace RABBIT\_PASS with the password you chose for the openstack account in RabbitMQ.

• In the [DEFAULT] and [keystone authtoken] sections, configure Identity service access:

```
[DEFAULT]
...
auth_strategy = keystone

[keystone_authtoken]
...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = Default
user_domain_name = Default
project_name = service
username = neutron
password = neutron
```

Replace password = neutron with the password you chose for the neutron user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

• In the [DEFAULT] and [nova] sections, configure Networking to notify Compute of network topology changes:

```
[DEFAULT]
...
notify_nova_on_port_status_changes = True
notify_nova_on_port_data_changes = True

[nova]
...
auth_url = http://controller:35357
auth_type = password
project_domain_name = Default
user_domain_name = Default
region_name = RegionOne
project_name = service
username = nova
password = nova
```

Replace password = nova with the password you chose for the nova user in the Identity service.

## Configure the Modular Layer 2 (ML2) plug-in

The ML2 plug-in uses the Linux bridge mechanism to build layer-2 (bridging and switching) virtual networking infrastructure for instances.

- Edit the /etc/neutron/plugins/m12/m12\_conf.ini file and complete the following actions:
  - o In the [ml2] section, enable flat and VLAN networks:

```
[ml2]
...
type_drivers = flat,vlan
```

• In the [m12] section, disable self-service networks:

```
[m12]
...
tenant_network_types =
```

• In the [ml2] section, enable the Linux bridge mechanism:

```
[ml2]
...
mechanism_drivers = linuxbridge
```

After you configure the ML2 plug-in, removing values in the type\_drivers option can lead to database inconsistency.

• In the [ml2] section, enable the port security extension driver:

```
[m12]
...
extension_drivers = port_security
```

• In the [m12\_type\_flat] section, configure the provider virtual network as a flat network:

```
[ml2_type_flat]
...
flat_networks = provider
```

• In the [securitygroup] section, enable <u>ipset</u> to increase efficiency of security group rules:

```
[securitygroup]
...
enable_ipset = True
```

## Configure the Linux bridge agent

The Linux bridge agent builds layer-2 (bridging and switching) virtual networking infrastructure for instances and handles security groups.

- Edit the /etc/neutron/plugins/ml2/linuxbridge\_agent.ini | file and complete the following actions:
  - In the [linux\_bridge] section, map the provider virtual network to the provider physical network interface:

```
[linux_bridge]
physical_interface_mappings = provider:PROVIDER_INTERFACE_NAME
```

Replace PROVIDER\_INTERFACE\_NAME with the name of the underlying provider physical network interface. See <u>Host networking</u> for more information.

in our case it is: enp0s10, the bridged nic of controller network.

• In the [vxlan] section, disable VXLAN overlay networks:

```
[vxlan]
enable_vxlan = False
```

• In the [securitygroup] section, enable security groups and configure the Linux bridge <u>iptables</u> firewall driver:

```
[securitygroup]
...
enable_security_group = True
firewall_driver = neutron.agent.linux.iptables_firewall.IptablesFirewallDriver
```

#### **Configure the DHCP agent**

The **DHCP** agent provides DHCP services for virtual networks.

- Edit the /etc/neutron/dhcp\_agent.ini file and complete the following actions:
  - In the <code>[DEFAULT]</code> section, configure the Linux bridge interface driver, Dnsmasq DHCP driver, and enable isolated metadata so instances on provider networks can access metadata over the network:

```
[DEFAULT]
...
interface_driver = neutron.agent.linux.interface.BridgeInterfaceDriver
dhcp_driver = neutron.agent.linux.dhcp.Dnsmasq
enable_isolated_metadata = True
```

Return to Networking controller node configuration.

#### Configure the metadata agent

The metadata agent provides configuration information such as credentials to instances.

- Edit the /etc/neutron/metadata\_agent.ini | file and complete the following actions:
  - In the [DEFAULT] section, configure the metadata host and shared secret:

```
[DEFAULT]
...
nova_metadata_ip = controller
metadata_proxy_shared_secret = METADATA_SECRET
```

Replace METADATA\_SECRET with a suitable secret for the metadata proxy.

#### Configure the Compute service to use the Networking service

- Edit the /etc/nova/nova.conf file and perform the following actions:
  - In the <a href="Ineutron">In the <a href="Ineutron">Ineutron<a href="Ineutron">In

```
[neutron]
...
url = http://controller:9696
auth_url = http://controller:35357
auth_type = password
project_domain_name = Default
user_domain_name = Default
region_name = RegionOne
project_name = service
username = neutron
password = neutron
service_metadata_proxy = True
metadata_proxy_shared_secret = METADATA_SECRET
```

Replace password = neutron with the password you chose for the neutron user in the Identity service.

Replace METADATA\_SECRET with the secret you chose for the metadata proxy.

#### Finalize installation

1. Populate the database:

```
# su -s /bin/sh -c "neutron-db-manage --config-file /etc/neutron/neutron.conf \
    --config-file /etc/neutron/plugins/ml2/ml2_conf.ini upgrade head" neutron
```

Database population occurs later for Networking because the script requires complete server and plug-in configuration files.

2. Restart the Compute API service:

```
# service nova-api restart
```

3. Restart the Networking services.

For both networking options:

```
# service neutron-server restart
# service neutron-linuxbridge-agent restart
# service neutron-dhcp-agent restart
# service neutron-metadata-agent restart
```

For networking option 2, also restart the layer-3 service:

```
# service neutron-13-agent restart
```

## **Verify operation**

ID	Agent Type	Host	Availability Zone	Alive	State	Binary
1d661145	-+   Linux	controll	None	+   True	   UP	neutron-
-0941	bridge	er		ĺ		linuxbri
-411d-9b	agent	1				dge-
18-b3371	1	1				agent
fe57c4b		1				
7502e1a3	DHCP agent	controll	nova	True	UP	neutron-
-998d-	1	er				dhcp-
4aca-91e	1	1				agent
4-ca17e1	1	1				
b10c82	1	1				
7c47ac70	Metadata	controll	None	True	UP	neutron-
-5de2-44	agent	er				metadata
42-8fc1-						-agent
91fe97ae						
120f						

# Neutron Install and configure compute node

The compute node handles connectivity and <u>security groups</u> for instances.

## **Install the components**

```
# apt install neutron-linuxbridge-agent -y
```

# Configure the common component

The Networking common component configuration includes the authentication mechanism, message queue, and plug-in.

- Edit the /etc/neutron/neutron.conf | file and complete the following actions:
  - In the <code>[database]</code> section, comment out any connection options because compute nodes do not directly access the database.
  - In the [DEFAULT] section, configure RabbitMQ message queue access:

```
[DEFAULT]
...
transport_url = rabbit://openstack:RABBIT_PASS@controller
```

Replace RABBIT\_PASS with the password you chose for the openstack account in RabbitMQ.

• In the [DEFAULT] and [keystone\_authtoken] sections, configure Identity service access:

```
[DEFAULT]
...
auth_strategy = keystone

[keystone_authtoken]
...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = Default
user_domain_name = Default
project_name = service
username = neutron
password = neutron
```

Replace password = neutron with the password you chose for the neutron user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

#### **Configure networking options**

Choose the same networking option that you chose for the controller node to configure services specific to it. Afterwards, return here and proceed to <u>Configure the Compute service</u> to <u>use the Networking service</u>.

• Networking Option 1: Provider networks

## Configure the Linux bridge agent

The Linux bridge agent builds layer-2 (bridging and switching) virtual networking infrastructure for instances and handles security groups.

- Edit the /etc/neutron/plugins/ml2/linuxbridge\_agent.ini | file and complete the following actions:
  - In the [linux\_bridge] section, map the provider virtual network to the provider physical network interface:

```
[linux_bridge]
physical_interface_mappings = provider:PROVIDER_INTERFACE_NAME
```

Replace PROVIDER\_INTERFACE\_NAME with the name of the underlying provider physical network interface. See <u>Host networking</u> for more information.

• In the [vxlan] section, disable VXLAN overlay networks:

```
[vxlan]
enable_vxlan = False
```

• In the [securitygroup] section, enable security groups and configure the Linux bridge <u>iptables</u> firewall driver:

```
[securitygroup]
...
enable_security_group = True
firewall_driver = neutron.agent.linux.iptables_firewall.IptablesFirewallDriver
```

Return to Networking compute node configuration.

#### Configure the Compute service to use the Networking service

- Edit the /etc/nova/nova.conf file and complete the following actions:
  - In the [neutron] section, configure access parameters:

```
[neutron]
...
url = http://controller:9696
auth_url = http://controller:35357
auth_type = password
project_domain_name = Default
user_domain_name = Default
region_name = RegionOne
project_name = service
username = neutron
password = neutron
```

Replace password = neutron with the password you chose for the neutron user in the Identity service.

#### Finalize installation

1. Restart the Compute service:

```
# service nova-compute restart
```

2. Restart the Linux bridge agent:

```
# service neutron-linuxbridge-agent restart
```

## **Verify operation**

Perform these commands on the controller node.

1. Source the admin credentials to gain access to admin-only CLI commands:

```
$ . admin-openrc
```

2. List loaded extensions to verify successful launch of the neutron-server process:

neutron ext-list	
<b>+</b>	
alias	name
default-subnetpools	+    Default Subnetpools
' '	Network IP Availability
	Network Availability Zone
auto-allocated-topology	Auto Allocated Topology Services
ext-gw-mode	Neutron L3 Configurable external gateway mode
binding	Port Binding
agent	agent
subnet_allocation	Subnet Allocation
13_agent_scheduler	L3 Agent Scheduler
. – - –	Tag support
tag   external-net	Neutron external network
net-mtu	Network MTU
availability_zone	Availability Zone
	Quota management support
quotas   13-ha	HA Router extension
13-11a   flavors	Neutron Service Flavors
provider	Provider Network
' '	Multi Provider Network
multi-provider	
address-scope extraroute	Address scope   Neutron Extra Route
timestamp_core	Time Stamp Fields addition for core resources
router	Neutron L3 Router
	·
extra_dhcp_opt	Neutron Extra DHCP opts
·	DNS Integration
· ·	security-group
· · - ·	DHCP Agent Scheduler
router_availability_zone	Router Availability Zone
rbac-policies	RBAC Policies
standard-attr-description	
port-security	Port Security
allowed-address-pairs	Allowed Address Pairs   Distributed Virtual Router
dvr	Distributed Altitual Konter

3. List agents to verify successful launch of the neutron agents:

ot@controller:~# openstack network agent listmax-width 70									
	gent Type	Host	Availability Zone	Alive	State	Binary			
+ L43d7731   L	inux	compute	None	True	   UP	neutron-li			
9227-4b   b	ridge	I				nuxbridge-			
af-9052-   a	igent					agent			
292d7aea			1						
5992			1						
ld661145   L	inux	controll	None	True	UP	neutron-li			
·0941   b	ridge	er	1			nuxbridge-			
411d-9b   a	igent		1			agent			
L8-b3371									
e57c4b		I							
7502e1a3   D	HCP agent	controll	nova	True	UP	neutron-			
·998d-		er				dhcp-agent			
laca-91e				- 1					
l-ca17e1				- 1					
10c82	I		I						
'c47ac70   M	letadata	controll	None	True	UP	neutron-			
-5de2-44   a	igent	er				metadata-			
2-8fc1-						agent			
1fe97ae									
120f									

The output should indicate three agents on the controller node and one agent on each compute node.

# Congratulations! Let's try booting an instance

## Create provider network/subnetwork

ref: <a href="https://docs.openstack.org/newton/install-guide-ubuntu/launch-instance-networks-provider.html">https://docs.openstack.org/newton/install-guide-ubuntu/launch-instance-networks-provider.html</a>

The --provider:physical\_network provider and --provider:network\_type flat options connect the flat virtual network to the flat (native/untagged) physical network on the eth1 interface on the host

标注: 下边的创建网络里,参数:

```
--provider-network-type flat \
--provider-physical-network provider
```

对应的是:

```
/etc/neutron/plugins/ml2/ml2_conf.ini
[ml2_type_flat]
flat_networks = provider

/etc/neutron/plugins/ml2/linuxbridge_agent.ini
[linux_bridge]
physical_interface_mappings = provider:enp0s10
```

```
root@controller:~# . admin-openrc
root@controller:~# openstack network create --share --external \
> --provider-physical-network provider \
> --provider-network-type flat provider
+-----
                  Value
admin_state_up
                 UP
availability_zone_hints
availability_zones
created at
                 2017-08-23T17:14:21Z
description
                 None
dns_domain
| id
                  2a33434f-ba29-4645-9b5d-24f1509066f1
| ipv4_address_scope
ipv6_address_scope
                 None
                  None
is_default
                  1500
mtu
name
                  provider
| port_security_enabled
                  | True
                  78c9c849237649a3a8c4526167427589
| project id
                 | flat
| provider:network_type
| provider:physical_network | provider
| provider:segmentation_id | None
                 None
qos_policy_id
revision number
                  4
| router:external
                  External
segments
                  None
shared
                  True
                  ACTIVE
status
subnets
updated at
                  2017-08-23T17:14:21Z
+-----
root@controller:~# neutron net-list
neutron CLI is deprecated and will be removed in the future. Use openstack CLI instead.
+-----
                          name
                                | tenant id
                                                         subnets
+-----+
2a33434f-ba29-4645-9b5d-24f1509066f1 | provider | 78c9c849237649a3a8c4526167427589 |
+-----
root@controller:~# openstack network list
                         Name
                                Subnets
+-----+
| 2a33434f-ba29-4645-9b5d-24f1509066f1 | provider |
+----+
root@controller:~# openstack subnet create --network provider \
> --allocation-pool start=146.11.41.230,end=146.11.41.233 \
> --dns-nameserver 147.128.5.12 --gateway 146.11.40.1 \
 --subnet-range 146.11.40.1/23 provider
+-----+
Field
             | Value
```

#### **Create flavor**

The smallest default flavor consumes 512 MB memory per instance. For environments with compute nodes containing less than 4 GB memory, we recommend creating the m1.nano flavor that only requires 64 MB per instance. Only use this flavor with the CirrOS image for testing purposes.

#### Add security group rules

By default, the default security group applies to all instances and includes firewall rules that deny remote access to instances. For Linux images such as CirrOS, we recommend allowing at least ICMP (ping) and secure shell (SSH).

- Add rules to the default security group:
  - Permit <u>ICMP</u> (ping):

```
$ openstack security group rule create --proto icmp default
+-----
Field
         Value
+----+
description
direction
         ingress
         | IPv4
ethertype
headers
    6ee8d630-9803-4d3d-9aea-8c795abbedc2
id
| remote_group_id | None
| remote_ip_prefix | 0.0.0.0/0
revision_number | 1
| security_group_id | 4ceee3d4-d2fe-46c1-895c-382033e87b0d |
| updated_at | 2016-10-05T09:52:31Z
```

• Permit secure shell (SSH) access:

```
$ openstack security group rule create --proto tcp --dst-port 22 default
+-----+
Field
           Value
+-----
| created_at | 2016-10-05T09:54:50Z
description
           direction
           ingress
ethertype
           IPv4
headers
         3cd0a406-43df-4741-ab29-b5e7dcb7469d
| port_range_max | 22
| port_range_min | 22
| tcp
protocol
| remote_group_id | None
| remote_ip_prefix | 0.0.0.0/0
revision_number | 1
| security_group_id | 4ceee3d4-d2fe-46c1-895c-382033e87b0d |
| updated_at | 2016-10-05T09:54:50Z
```

#### Launch an instance

ref: Launch an instance on the provider network

#### **Determine instance options**

To launch an instance, you must at least specify the flavor, image name, network, security group, key, and instance name.

1. On the controller node, source the demo credentials to gain access to user-only CLI commands:

```
$ . demo-openro
```

2. A flavor specifies a virtual resource allocation profile which includes processor, memory, and storage. List available flavors:

You can also reference a flavor by ID.

3. List available images:

This instance uses the cirros image.

4. List available networks:

This instance uses the **provider** provider network. However, you must reference this network using the ID instead of the name.

5. List available security groups:

This instance uses the default security group.

#### Launch the instance

1. Launch the instance:

Replace PROVIDER\_NET\_ID with the ID of the provider provider network.

If you chose option 1 and your environment contains only one network, you can omit the \_--nic option because OpenStack automatically chooses the only network available.

```
root@controller:~# openstack server create --flavor m1.nano --image cirros \
> --nic net-id=2a33434f-ba29-4645-9b5d-24f1509066f1 --security-group default provider-
instance
+-----
Field
                    | Value
+-----
               MANUAL
OS-DCF:diskConfig
OS-EXT-AZ:availability_zone
OS-SRV-USG:terminated_at | None
accessIPv4
accessIPv6
addresses
                    | MnjXdXf3qHia
adminPass
config_drive
                    2017-08-23T17:29:04Z
created
flavor
                    m1.nano (0)
hostId
id
                    02f54ef9-e867-4c1a-88f9-8eddd144da6f
image
                     cirros (c17e391e-93e1-4480-9cf3-bf8623063e61)
key_name
                     None
name
                     | provider-instance
progress
                     | cb015df53fb34d90b077e4c36ce35826
| project_id
properties
| security_groups
                    | name='default'
status
                    | BUILD
updated
                     2017-08-23T17:29:05Z
| user_id
                     | cb98fad69e84459bb48f42130d5c0ce5
volumes_attached
```

2. Check the status of your instance:

The status changes from BUILD to ACTIVE when the build process successfully completes.

## Access the instance using the virtual console

1. Obtain a <u>Virtual Network Computing (VNC)</u> session URL for your instance and access it from a web browser:

If your web browser runs on a host that cannot resolve the controller host name, you can replace controller with the IP address of the management interface on your controller node.

The CirrOS image includes conventional user name/password authentication and provides these credentials at the login prompt. After logging into CirrOS, we recommend that you verify network connectivity using ping.

2. Verify access to the provider physical network gateway:

```
$ ping -c 4 203.0.113.1
PING 203.0.113.1 (203.0.113.1) 56(84) bytes of data.
64 bytes from 203.0.113.1: icmp_req=1 ttl=64 time=0.357 ms
64 bytes from 203.0.113.1: icmp_req=2 ttl=64 time=0.473 ms
64 bytes from 203.0.113.1: icmp_req=3 ttl=64 time=0.504 ms
64 bytes from 203.0.113.1: icmp_req=4 ttl=64 time=0.470 ms
--- 203.0.113.1 ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 2998ms
rtt min/avg/max/mdev = 0.357/0.451/0.504/0.055 ms
```

3. Verify access to the internet:

```
$ ping -c 4 openstack.org
PING openstack.org (174.143.194.225) 56(84) bytes of data.
64 bytes from 174.143.194.225: icmp_req=1 ttl=53 time=17.4 ms
64 bytes from 174.143.194.225: icmp_req=2 ttl=53 time=17.5 ms
64 bytes from 174.143.194.225: icmp_req=3 ttl=53 time=17.7 ms
64 bytes from 174.143.194.225: icmp_req=4 ttl=53 time=17.5 ms
--- openstack.org ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 3003ms
rtt min/avg/max/mdev = 17.431/17.575/17.734/0.143 ms
```

#### Access the instance remotely

1. Verify connectivity to the instance from the controller node or any host on the provider physical network:

```
$ ping -c 4 203.0.113.103
PING 203.0.113.103 (203.0.113.103) 56(84) bytes of data.
64 bytes from 203.0.113.103: icmp_req=1 ttl=63 time=3.18 ms
64 bytes from 203.0.113.103: icmp_req=2 ttl=63 time=0.981 ms
64 bytes from 203.0.113.103: icmp_req=3 ttl=63 time=1.06 ms
64 bytes from 203.0.113.103: icmp_req=4 ttl=63 time=0.929 ms
--- 203.0.113.103 ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 3002ms
rtt min/avg/max/mdev = 0.929/1.539/3.183/0.951 ms
```

2. Access your instance using SSH from the controller node or any host on the provider physical network:

```
$ ssh cirros@203.0.113.103

The authenticity of host '203.0.113.102 (203.0.113.102)' can't be established.

RSA key fingerprint is ed:05:e9:e7:52:a0:ff:83:68:94:c7:d1:f2:f8:e2:e9.

Are you sure you want to continue connecting (yes/no)? yes

Warning: Permanently added '203.0.113.102' (RSA) to the list of known hosts.
```

If your instance does not launch or seem to work as you expect, see the <u>Instance Boot Failures</u> section in OpenStack Operations Guide for more information or use one of the <u>many other options</u> to seek assistance. We want your first installation to work!

Return to Launch an instance.

## [ISSUE] DHCP failure in VM troubleshooting

ref: https://docs.openstack.org/neutron/pike/admin/intro-basic-networking.html

in VM console (initial dhcp discover)

```
$ ifup eth0
udhcpc (v1.20.1) started
Sending discover...
Sending discover...
Sending discover...
Usage: /sbin/cirros-dhcpc <up|down>
No lease, failing
```

in controller console (monitor log)

```
root@controller:~# tail -f /var/log/syslog
Aug 24 03:06:30 controller dhclient[1166]: DHCPREQUEST of 146.11.41.129 on enp0s10 to
147.128.5.12 port 67 (xid=0x5d38ef7e)
Aug 24 03:06:30 controller dhclient[1166]: DHCPACK of 146.11.41.129 from 147.128.5.12
Aug 24 03:06:30 controller dhclient[1166]: Invalid domain list.
Aug 24 03:06:30 controller dhclient[1166]: suspect value in domain_search option - discarded
Aug 24 03:06:30 controller dhclient[1166]: Invalid domain list.
Aug 24 03:06:30 controller dhclient[1166]: suspect value in domain_search option - discarded
Aug 24 03:06:30 controller dhclient[1166]: Invalid domain list.
Aug 24 03:06:30 controller dhclient[1166]: bound to 146.11.41.129 -- renewal in 12824 seconds.
Aug 24 03:12:18 controller dnsmasq-dhcp[18894]: DHCPDISCOVER(ns-a6e0220e-ec) fa:16:3e:bb:c6:13
Aug 24 03:12:18 controller dnsmasq-dhcp[18894]: DHCPOFFER(ns-a6e0220e-ec) 146.11.41.232
fa:16:3e:bb:c6:13
Aug 24 03:13:19 controller dnsmasq-dhcp[18894]: DHCPDISCOVER(ns-a6e0220e-ec) fa:16:3e:bb:c6:13
Aug 24 03:13:19 controller dnsmasq-dhcp[18894]: DHCPOFFER(ns-a6e0220e-ec) 146.11.41.232
Aug 24 03:14:19 controller dnsmasq-dhcp[18894]: DHCPDISCOVER(ns-a6e0220e-ec) fa:16:3e:bb:c6:13
Aug 24 03:14:19 controller dnsmasq-dhcp[18894]: DHCPOFFER(ns-a6e0220e-ec) 146.11.41.232
fa:16:3e:bb:c6:13
```

By tcpdump from controllor bridge, it's found the DHCPOFFER was sent to VM:

```
root@controller:~# tcpdump -i brq2a33434f-ba -vv port 67 or port 68 -e -n
tcpdump: listening on brq2a33434f-ba, link-type EN10MB (Ethernet), capture size 262144 bytes
04:04:22.830138 fa:16:3e:bb:c6:13 > ff:ff:ff:ff:ff, ethertype IPv4 (0x0800), length 332: (tos
0x0, ttl 64, id 0, offset 0, flags [none], proto UDP (17), length 318)
    0.0.0.0.68 > 255.255.255.255.67: [udp sum ok] BOOTP/DHCP, Request from fa:16:3e:bb:c6:13,
length 290, xid 0x1fac2751, Flags [none] (0x0000)
         Client-Ethernet-Address fa:16:3e:bb:c6:13
         Vendor-rfc1048 Extensions
            Magic Cookie 0x63825363
            DHCP-Message Option 53, length 1: Discover
            Client-ID Option 61, length 7: ether fa:16:3e:bb:c6:13
            MSZ Option 57, length 2: 576
            Parameter-Request Option 55, length 9:
              Subnet-Mask, Default-Gateway, Domain-Name-Server, Hostname
             Domain-Name, MTU, BR, NTP
             Classless-Static-Route
            Vendor-Class Option 60, length 12: "udhcp 1.20.1"
            Hostname Option 12, length 6: "cirros"
04:04:22.831801 fa:16:3e:8b:53:5e > fa:16:3e:bb:c6:13, ethertype IPv4 (0x0800), length 370: (tos
0xc0, ttl 64, id 3044, offset 0, flags [none], proto UDP (17), length 356)
    146.11.41.230.67 > 146.11.41.232.68: [udp sum ok] BOOTP/DHCP, Reply, length 328, xid
0x1fac2751, Flags [none] (0x0000)
         Your-IP 146.11.41.232
         Server-IP 146.11.41.230
         Client-Ethernet-Address fa:16:3e:bb:c6:13
         Vendor-rfc1048 Extensions
            Magic Cookie 0x63825363
            DHCP-Message Option 53, length 1: Offer
            Server-ID Option 54, length 4: 146.11.41.230
            Lease-Time Option 51, length 4: 86400
            RN Option 58, length 4: 43200
            RB Option 59, length 4: 75600
            Subnet-Mask Option 1, length 4: 255.255.254.0
            BR Option 28, length 4: 146.11.41.255
            Domain-Name Option 15, length 14: "openstacklocal"
            Default-Gateway Option 3, length 4: 146.11.40.1
            Classless-Static-Route Option 121, length 14: (169.254.169.254/32:146.11.41.230),
(default:146.11.40.1)
            Domain-Name-Server Option 6, length 4: 147.128.5.12
            MTU Option 26, length 2: 1500
04:04:52.504181 08:2e:5f:5d:63:00 > ff:ff:ff:ff:ff; ethertype IPv4 (0x0800), length 358: (tos
0x0, ttl 120, id 5320, offset 0, flags [DF], proto UDP (17), length 344)
```

While from compute , tcpdump the br-int bridge shows it's not received

```
root@compute:~# tcpdump -i brq2a33434f-ba -vv port 67 or port 68 -e -n
tcpdump: listening on brq2a33434f-ba, link-type EN10MB (Ethernet), capture size 262144 bytes
03:51:04.456668 fa:16:3e:bb:c6:13 > ff:ff:ff:ff:ff; ethertype IPv4 (0x0800), length 332: (tos
0x0, ttl 64, id 0, offset 0, flags [none], proto UDP (17), length 318)
    0.0.0.0.68 > 255.255.255.255.67: [udp sum ok] BOOTP/DHCP, Request from fa:16:3e:bb:c6:13,
length 290, xid 0xe5e8f024, Flags [none] (0x0000)
         Client-Ethernet-Address fa:16:3e:bb:c6:13
         Vendor-rfc1048 Extensions
           Magic Cookie 0x63825363
           DHCP-Message Option 53, length 1: Discover
           Client-ID Option 61, length 7: ether fa:16:3e:bb:c6:13
           MSZ Option 57, length 2: 576
           Parameter-Request Option 55, length 9:
              Subnet-Mask, Default-Gateway, Domain-Name-Server, Hostname
             Domain-Name, MTU, BR, NTP
             Classless-Static-Route
           Vendor-Class Option 60, length 12: "udhcp 1.20.1"
           Hostname Option 12, length 6: "cirros"
03:51:30.022360 08:2e:5f:5d:63:00 > ff:ff:ff:ff:ff; ethertype IPv4 (0x0800), length 358: (tos
0x0, ttl 120, id 29901, offset 0, flags [DF], proto UDP (17), length 344)
    147.128.5.12.67 > 255.255.255.255.68: [udp sum ok] BOOTP/DHCP, Reply, length 316, xid
0x4a42e788, Flags [Broadcast] (0x8000)
         Client-IP 146.11.40.250
         Gateway-IP 146.11.40.1
         Client-Ethernet-Address d0:bf:9c:df:7a:a5
         Vendor-rfc1048 Extensions
           Magic Cookie 0x63825363
           DHCP-Message Option 53, length 1: ACK
           Server-ID Option 54, length 4: 147.128.5.12
           Subnet-Mask Option 1, length 4: 255.255.254.0
           Vendor-Option Option 43, length 5: 220.3.78.65.80
           Domain-Name Option 15, length 18: "cn.ao.ericsson.se^@"
           Default-Gateway Option 3, length 4: 146.11.40.1
           Domain-Name-Server Option 6, length 12: 147.128.5.12,193.181.14.11,193.181.14.10
           Netbios-Name-Server Option 44, length 8: 146.11.115.50,146.11.116.30
           Netbios-Node Option 46, length 1: h-node
03:51:30.023490 2c:76:8a:1f:47:00 > ff:ff:ff:ff:ff, ethertype IPv4 (0x0800), length 358: (tos
0x0, ttl 119, id 2187, offset 0, flags [DF], proto UDP (17), length 344)
```

#### **Conclusion:**

the DHCP offer was sent out from DHCP agent dnsmasq, but the package cannot be captured from host bridge connecting to vm eth0. the issue is located in the provider network router, the ECN router 146.11.40.1 in our office.

By searching online, there is a tech called DHCP snooping to prevent multiple dhcp server in one LAN from router, which makes sense.

## Cinder on controller

Here we provide a iSCSI driver backend cinder practice

#### ref: https://docs.openstack.org/ocata/install-guide-ubuntu/cinder.html

The OpenStack Block Storage service (cinder) adds persistent storage to a virtual machine. Block Storage provides an infrastructure for managing volumes, and interacts with OpenStack Compute to provide volumes for instances. The service also enables management of volume snapshots, and volume types.

The Block Storage service consists of the following components:

• cinder-api

Accepts API requests, and routes them to the cinder-volume for action.

cinder-volume

Interacts directly with the Block Storage service, and processes such as the <code>cinder-scheduler</code>. It also interacts with these processes through a message queue. The <code>cinder-volume</code> service responds to read and write requests sent to the Block Storage service to maintain state. It can interact with a variety of storage providers through a driver architecture.

cinder-scheduler daemon

Selects the optimal storage provider node on which to create the volume. A similar component to the nova-scheduler.

• cinder-backup daemon

The cinder-backup service provides backing up volumes of any type to a backup storage provider. Like the cinder-volume service, it can interact with a variety of storage providers through a driver architecture.

Messaging queue

Routes information between the Block Storage processes.

#### Install and configure controller node

This section describes how to install and configure the Block Storage service, code-named cinder, on the controller node. This service requires at least one additional storage node that provides volumes to instances.

## **Prerequisites**

Before you install and configure the Block Storage service, you must create a database, service credentials, and API endpoints.

- 1. To create the database, complete these steps:
  - Use the database access client to connect to the database server as the root user:

```
# mysql
```

• Create the cinder database:

```
MariaDB [(none)]> CREATE DATABASE cinder;
```

• Grant proper access to the cinder database:

```
MariaDB [(none)]> GRANT ALL PRIVILEGES ON cinder.* TO 'cinder'@'localhost' \
   IDENTIFIED BY 'CINDER_DBPASS';
MariaDB [(none)]> GRANT ALL PRIVILEGES ON cinder.* TO 'cinder'@'%' \
   IDENTIFIED BY 'CINDER_DBPASS';
```

Replace CINDER\_DBPASS with a suitable password.

- Exit the database access client.
- 2. Source the admin credentials to gain access to admin-only CLI commands:

```
$ . admin-openrc
```

- 3. To create the service credentials, complete these steps:
  - Create a cinder user:

• Add the admin role to the cinder user:

```
$ openstack role add --project service --user cinder admin
```

This command provides no output.

• Create the cinderv2 and cinderv3 service entities:

The Block Storage services require two service entities.

4. Create the Block Storage service API endpoints:

```
$ openstack endpoint create --region RegionOne \
 volumev2 public http://controller:8776/v2/%\(project_id\)s
+-----
| Field
         | Value
+-----
| enabled | True
         513e73819e14460fb904163f41ef3759
| interface | public
       | RegionOne
region
| region_id | RegionOne
| service_name | cinderv2
| service_type | volumev2
url http://controller:8776/v2/%(project_id)s
$ openstack endpoint create --region RegionOne \
 volumev2 internal http://controller:8776/v2/%\(project_id\)s
+-----+
Field
         Value
| interface | internal
| region | RegionOne
| region_id | RegionOne
| service_id | eb9fd245bdbc414695952e93f29fe3ac
| service_name | cinderv2
| service_type | volumev2
         | http://controller:8776/v2/%(project_id)s |
$ openstack endpoint create --region RegionOne \
 volumev2 admin http://controller:8776/v2/%\(project_id\)s
+-----+
| Field
       | Value
+-----
e652cf84dd334f359ae9b045a2c91d96
| interface | admin
region
        | RegionOne
| region_id | RegionOne
| service_name | cinderv2
| service_type | volumev2
url | http://controller:8776/v2/%(project_id)s |
```

```
$ openstack endpoint create --region RegionOne \
 volumev3 public http://controller:8776/v3/%\(project_id\)s
+-----
Field
         | Value
+-----
| enabled | True
         03fa2c90153546c295bf30ca86b1344b
| interface | public
| region | RegionOne
| region_id | RegionOne
| service_name | cinderv3
| service_type | volumev3
url http://controller:8776/v3/%(project_id)s |
$ openstack endpoint create --region RegionOne \
 volumev3 internal http://controller:8776/v3/%\(project_id\)s
Field
         Value
| interface | internal
| region | RegionOne
| region_id | RegionOne
| service_name | cinderv3
| service_type | volumev3
      | http://controller:8776/v3/%(project_id)s |
$ openstack endpoint create --region RegionOne \
 volumev3 admin http://controller:8776/v3/%\(project_id\)s
+-----
| Field | Value
+-----
| enabled | True
| id | 4511c
         4511c28a0f9840c78bacb25f10f62c98
| interface | admin
        | RegionOne
region
| region_id | RegionOne
| service_name | cinderv3
| service_type | volumev3
url | http://controller:8776/v3/%(project_id)s |
```

The Block Storage services require endpoints for each service entity.

#### Install and configure components

Install the packages:

```
# apt install cinder-api cinder-scheduler
```

Edit the /etc/cinder/cinder.conf file and complete the following actions:

• In the [database] section, configure database access:

```
[database]
# ...
connection = mysql+pymysql://cinder:CINDER_DBPASS@controller/cinder
```

Replace CINDER\_DBPASS with the password you chose for the Block Storage database.

• In the [DEFAULT] section, configure RabbitMQ message queue access:

```
[DEFAULT]
# ...
transport_url = rabbit://openstack:RABBIT_PASS@controller
```

Replace RABBIT\_PASS with the password you chose for the openstack account in RabbitMQ.

• In the [DEFAULT] and [keystone\_authtoken] sections, configure Identity service access:

```
[DEFAULT]
# ...
auth_strategy = keystone

[keystone_authtoken]
# ...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = default
user_domain_name = default
project_name = service
username = cinder
password = cinder
```

Replace password with the password you chose for the cinder user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

• In the <code>[DEFAULT]</code> section, configure the <code>my\_ip</code> option to use the management interface IP address of the controller node:

```
[DEFAULT]
# ...
my_ip = 10.20.0.10
```

• In the [oslo\_concurrency] section, configure the lock path:

```
[oslo_concurrency]
# ...
lock_path = /var/lib/cinder/tmp
```

Populate the Block Storage database:

```
# su -s /bin/sh -c "cinder-manage db sync" cinder
```

Ignore any deprecation messages in this output.

#### **Configure Compute to use Block Storage**

• Edit the /etc/nova/nova.conf file and add the following to it:

```
[cinder]
os_region_name = RegionOne
```

#### Finalize installation

1. Restart the Compute API service:

```
# service nova-api restart
```

2. Restart the Block Storage services:

```
# service cinder-scheduler restart
# service apache2 restart
```

# Cinder on storage backend node

## configure storage network for compute

Check nic name

```
root@compute:~# dmesg | grep renamed

[ 2.730898] e1000 0000:00:09.0 enp0s9: renamed from eth2

[ 2.731826] e1000 0000:00:08.0 enp0s8: renamed from eth1

[ 2.732819] e1000 0000:00:0a.0 enp0s10: renamed from eth3

[ 2.735645] e1000 0000:00:03.0 enp0s3: renamed from eth0
```

```
eth2 was named as enp0s9
```

Edit /etc/network/interfaces

```
# storage network eth2
auto enp0s9
iface enp0s9 inet static
address 192.168.199.20
netmask 255.255.255.0
```

```
# ifup enp0s9
```

#### Create cinder machine: storage

# Storage actions & cinder on storage node

Clone it from base VM and add a virtual disk for storage vm

#### Management net eth0 (enp0s3) and storage net eth2 (enp0s9)

Edit /etc/network/interfaces

```
# management network eth0

auto enp0s3
iface enp0s3 inet static
address 10.20.0.30
netmask 255.255.255.0
```

```
# storage network eth2
auto enp0s9
iface enp0s9 inet static
address 192.168.199.30
netmask 255.255.255.0
```

```
//start the two nics
# ifup enp0s3
# ifup enp0s9
```

# configure NTP by editing /etc/chrony/chrony.conf

```
server 10.20.0.10 iburst
```

change hostname and hosts

#### Check new disk was there already

check by fdisk -1, /dev/sdb is there :-).

```
root@storage:~# fdisk -1
Disk /dev/sda: 50 GiB, 53687091200 bytes, 104857600 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disklabel type: dos
Disk identifier: 0x3ce50a75
Device Boot Start End Sectors Size Id Type
/dev/sda1 * 2048 999423 997376 487M 83 Linux
            1001470 104855551 103854082 49.5G 5 Extended
/dev/sda2
/dev/sda5
             1001472 104855551 103854080 49.5G 8e Linux LVM
Disk /dev/sdb: 50 GiB, 53687091200 bytes, 104857600 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk /dev/mapper/ubuntu--vg-root: 45.5 GiB, 48876224512 bytes, 95461376 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk /dev/mapper/ubuntu--vg-swap_1: 4 GiB, 4294967296 bytes, 8388608 sectors
Units: sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

#### Install and configure a storage node

This section describes how to install and configure storage nodes for the Block Storage service. For simplicity, this configuration references one storage node with an empty local block storage device. The instructions use /dev/sdb, but you can substitute a different value for your particular node.

The service provisions logical volumes on this device using the <u>LVM</u> driver and provides them to instances via <u>iSCSI</u> transport. You can follow these instructions with minor modifications to horizontally scale your environment with additional storage nodes.

## **Prerequisites**

Before you install and configure the Block Storage service on the storage node, you must prepare the storage device.

Perform these steps on the storage node.

1. Install the supporting utility packages:

```
# apt install lvm2
```

Some distributions include LVM by default.

2. Create the LVM physical volume /dev/sdb:

```
# pvcreate /dev/sdb

Physical volume "/dev/sdb" successfully created
```

3. Create the LVM volume group cinder-volumes:

```
# vgcreate cinder-volumes /dev/sdb
Volume group "cinder-volumes" successfully created
```

The Block Storage service creates logical volumes in this volume group.

- 4. Only instances can access Block Storage volumes. However, the underlying operating system manages the devices associated with the volumes. By default, the LVM volume scanning tool scans the /dev directory for block storage devices that contain volumes. If projects use LVM on their volumes, the scanning tool detects these volumes and attempts to cache them which can cause a variety of problems with both the underlying operating system and project volumes. You must reconfigure LVM to scan only the devices that contain the cinder-volumes volume group. Edit the /etc/lvm/lvm.conf file and complete the following actions:
  - o In the devices section, add a filter that accepts the /dev/sdb device and rejects all other devices:

```
devices {
...
filter = [ "a/sdb/", "r/.*/"]
```

Each item in the filter array begins with a for **accept** or r for **reject** and includes a regular expression for the device name. The array must end with r/.\*/ to reject any remaining devices. You can use the **vgs -vvvv** command to test filters.

If your storage nodes use LVM on the operating system disk, you must also add the associated device to the filter. For example, if the /dev/sda device contains the operating system:

```
filter = [ "a/sda/", "a/sdb/", "r/.*/"]
```

Similarly, if your compute nodes use LVM on the operating system disk, you must also modify the filter in the /etc/lvm/lvm.conf file on those nodes to include only the operating system disk. For example, if the /dev/sda device contains the operating system:

```
filter = [ "a/sda/", "r/.*/"]
```

## Install and configure components

Install the packages:

```
# apt install cinder-volume -y
```

- 1. Edit the /etc/cinder/cinder.conf | file and complete the following actions:
  - In the [database] section, configure database access:

```
[database]
# ...
connection = mysql+pymysql://cinder:CINDER_DBPASS@controller/cinder
```

Replace CINDER\_DBPASS with the password you chose for the Block Storage database.

• In the [DEFAULT] section, configure RabbitMQ message queue access:

```
[DEFAULT]
# ...
transport_url = rabbit://openstack:RABBIT_PASS@controller
```

Replace RABBIT\_PASS with the password you chose for the openstack account in RabbitMQ.

• In the [DEFAULT] and [keystone\_authtoken] sections, configure Identity service access:

```
[DEFAULT]
# ...
auth_strategy = keystone

[keystone_authtoken]
# ...
auth_uri = http://controller:5000
auth_url = http://controller:35357
memcached_servers = controller:11211
auth_type = password
project_domain_name = default
user_domain_name = default
project_name = service
username = cinder
password = cinder
```

Replace password with the password you chose for the cinder user in the Identity service.

Comment out or remove any other options in the [keystone\_authtoken] section.

• In the [DEFAULT] section, configure the my\_ip option:

```
[DEFAULT]
# ...
my_ip = STORAGE_INTERFACE_IP_ADDRESS
```

Replace STORAGE\_INTERFACE\_IP\_ADDRESS with the IP address of the storage network (eth2).

o In the [lvm] section, configure the LVM back end with the LVM driver, cinder-volumes volume group, iSCSI protocol, and appropriate iSCSI service:

```
[lvm]
# ...
volume_driver = cinder.volume.drivers.lvm.LVMVolumeDriver
volume_group = cinder-volumes
iscsi_protocol = iscsi
iscsi_helper = tgtadm
```

• In the [DEFAULT] section, enable the LVM back end:

```
[DEFAULT]
# ...
enabled_backends = lvm
```

Back-end names are arbitrary. As an example, this guide uses the name of the driver as the name of the back end.

• In the [DEFAULT] section, configure the location of the Image service API:

```
[DEFAULT]
# ...
glance_api_servers = http://controller:9292
```

• In the [oslo\_concurrency] section, configure the lock path:

```
[oslo_concurrency]
# ...
lock_path = /var/lib/cinder/tmp
```

#### **Finalize installation**

1. Restart the Block Storage volume service including its dependencies:

```
# service tgt restart
# service cinder-volume restart
```

# **Verify operation**

Verify operation of the Block Storage service.

Perform these commands on the controller node.

1. Source the admin credentials to gain access to admin-only CLI commands:

```
$ . admin-openrc
```

2. List service components to verify successful launch of each process:

# Let's try something on block storage!

#### Create a volume

1. Source the demo credentials to perform the following steps as a non-administrative project:

```
$ . demo-openro
```

2. Create a 1 GB volume:

```
$ openstack volume create --size 1 volume1
attachments []
| availability_zone | nova
| bootable | false
| consistencygroup_id | None
description
         None
| volume1
| replication_status | disabled
         | 1
size
status
         creating
type
         None
         None
updated_at
```

3. After a short time, the volume status should change from creating to available:

ID	+
	ed to
81ffed40-ed71-495d-bfa9-8fb8c72cf222   volume1	

4. check where it is?

```
root@storage:~# lvdisplay
 --- Logical volume ---
 LV Path
                        /dev/ubuntu-vg/root
 LV Name
                        root
                        ubuntu-vg
 VG Name
 LV UUID
                        NA7DgH-V0Sv-cH8E-wvej-aJmP-6EB0-joX00C
 LV Write Access
                        read/write
 LV Creation host, time ubuntu, 2017-08-23 16:30:36 +0800
 LV Status
                       available
 # open
                       45.52 GiB
 LV Size
 Current LE
                       11653
 Segments
                       1
 Allocation
                      inherit
 Read ahead sectors
                      auto
 - currently set to 256
 Block device
                       252:0
 --- Logical volume ---
                       /dev/ubuntu-vg/swap_1
 LV Path
 LV Name
                       swap_1
 VG Name
                       ubuntu-vg
 LV UUID
                       Vtixi8-qKcP-f1LH-bHqM-E73h-NN7z-eSD2zk
                        read/write
 LV Write Access
 LV Creation host, time ubuntu, 2017-08-23 16:30:36 +0800
 LV Status
                      available
 # open
 LV Size
                      4.00 GiB
 Current LE
                        1024
 Segments
 Allocation
                       inherit
 Read ahead sectors
                      auto
 - currently set to
                      256
 Block device
                        252:1
 --- Logical volume ---
                        /dev/cinder-volumes/volume-81ffed40-ed71-495d-bfa9-8fb8c72cf222
 LV Path
                       volume-81ffed40-ed71-495d-bfa9-8fb8c72cf222
 LV Name
 VG Name
                        cinder-volumes
 LV UUID
                        6jbPGA-i3Eo-O4ng-8Mf3-IoeF-9WF7-g1DGEA
 LV Write Access
                        read/write
 LV Creation host, time storage, 2017-08-24 22:38:28 +0800
 LV Status
                       available
 # open
 LV Size
                       1.00 GiB
 Current LE
                      256
 Segments
                       1
                      inherit
 Allocation
 Read ahead sectors
                       auto
 - currently set to
                      256
 Block device
                        252:2
```

# Attach the volume to an instance

1. Attach a volume to an instance:

\$ openstack server add volume INSTANCE\_NAME VOLUME\_NAME

Replace INSTANCE\_NAME with the name of the instance and VOLUME\_NAME with the name of the volume you want to attach to it.

#### Example

Attach the volume1 volume to the provider-instance instance:

\$ openstack server add volume provider-instance volume1

This command provides no output.

2. List volumes:

```
root@controller:~# openstack volume list
+-----
| ID
                               | Display Name | Status | Size | Attached to
+------
| 81ffed40-ed71-495d-bfa9-8fb8c72cf222 | volume1 | in-use | 1 | Attached to
provider-instance on /dev/vdb
+-----
----+
root@storage:~# lvdisplay
 --- Logical volume ---
 LV Path
                   /dev/ubuntu-vg/root
 LV Name
                  root
 VG Name
                   ubuntu-vg
 LV UUID
                  NA7DgH-V0Sv-cH8E-wvej-aJmP-6EBO-joX00C
 LV Write Access
                  read/write
 LV Creation host, time ubuntu, 2017-08-23 16:30:36 +0800
 LV Status
                  available
 # open
 LV Size
                  45.52 GiB
 Current LE
                  11653
 Segments
 Allocation
                  inherit
 Read ahead sectors auto
 - currently set to 256
 Block device
                   252:0
 --- Logical volume ---
 LV Path
                   /dev/ubuntu-vg/swap_1
 LV Name
                  swap_1
 VG Name
                   ubuntu-vg
 LV UUID
                   Vtixi8-qKcP-f1LH-bHqM-E73h-NN7z-eSD2zk
 LV Write Access
                   read/write
 LV Creation host, time ubuntu, 2017-08-23 16:30:36 +0800
 LV Status
                   available
 # open
 LV Size
                   4.00 GiB
 Current LE
                  1024
 Segments
                   1
 Allocation
                  inherit
 Read ahead sectors
                   auto
 - currently set to 256
 Block device
                   252:1
 --- Logical volume ---
 LV Path
                   /dev/cinder-volumes/volume-81ffed40-ed71-495d-bfa9-8fb8c72cf222
 LV Name
                   volume-81ffed40-ed71-495d-bfa9-8fb8c72cf222
 VG Name
                   cinder-volumes
 LV UUID
                   6jbPGA-i3Eo-O4ng-8Mf3-IoeF-9WF7-g1DGEA
 LV Write Access
                   read/write
```

```
LV Creation host, time storage, 2017-08-24 22:38:28 +0800
LV Status
                    available
# open
LV Size
                    1.00 GiB
Current LE
                   256
Segments
                    1
Allocation
                   inherit
Read ahead sectors auto

    currently set to

                   256
Block device
                     252:2
```

3. Access your instance using SSH or virsh console and use the fdisk command to verify presence of the volume as the /dev/vdb block storage device:

```
$ sudo fdisk -1
Disk /dev/vda: 1073 MB, 1073741824 bytes
255 heads, 63 sectors/track, 130 cylinders, total 2097152 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
Device Boot Start End Blocks Id System
/dev/vda1 * 16065 2088449 1036192+ 83 Linux
                             End Blocks Id System
Disk /dev/vdb: 1073 MB, 1073741824 bytes
16 heads, 63 sectors/track, 2080 cylinders, total 2097152 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
Disk /dev/vdb doesn't contain a valid partition table
```

- 4. Check from storage node on iSCSI target point of view, it's found
  - o Initiator: iqn.1993-08.org.debian:01:e7b693dedcab alias: compute
  - LUN 1: Backing store path: /dev/cinder-volumes/volume-81ffed40-ed71-495d-bfa9-8fb8c72cf222

```
root@storage:~# tgtadm --lld iscsi --op show --mode target
Target 1: iqn.2010-10.org.openstack:volume-81ffed40-ed71-495d-bfa9-8fb8c72cf222
    System information:
        Driver: iscsi
        State: ready
    I_T nexus information:
        I_T nexus: 1
            Initiator: iqn.1993-08.org.debian:01:e7b693dedcab alias: compute
            Connection: 0
                IP Address: 192.168.199.20
    LUN information:
        LUN: 0
            Type: controller
            SCSI ID: IET
                            00010000
            SCSI SN: beaf10
            Size: 0 MB, Block size: 1
            Online: Yes
            Removable media: No
            Prevent removal: No
            Readonly: No
            SWP: No
            Thin-provisioning: No
            Backing store type: null
            Backing store path: None
            Backing store flags:
        LUN: 1
            Type: disk
            SCSI ID: IET
                           00010001
            SCSI SN: beaf11
            Size: 1074 MB, Block size: 512
            Online: Yes
            Removable media: No
            Prevent removal: No
            Readonly: No
            SWP: No
            Thin-provisioning: No
            Backing store type: rdwr
            Backing store path: /dev/cinder-volumes/volume-81ffed40-ed71-495d-bfa9-
8fb8c72cf222
            Backing store flags:
    Account information:
        7jTnhhxXsVM4BwqxG979
    ACL information:
        ALL
```

5. Checking from compute via virsh dumpxml <instance-id>

It's shown the device from initiator point of view: