
Data Link Layer: Error Detection

Kameswari Chebrolu

All the figures used as part of the slides are either self created or from the public domain with either 'creative commons' or 'public domain dedication' licensing. The public sites from which some of the figures have been picked include: http://commons.wikimedia.org (Wikipedia, Wikimedia and workbooks); http://www.sxc.hu and http://www.pixabay.com

Recap

- Frame-by-Frame next-hop delivery
- Covered framing and overview of error-control
 - Hamming distance of a code determines the error detection and correction capabilities




General Approach

- Add redundant information to a frame
- At Sender:
 - Add k bits of redundant data to a m bit message
 - $k \ll m; k = 32; m = 12,000 \text{ for Ethernet}$
 - k derived from original message through some algorithm
- At Receiver:
 - Reapply same algorithm as sender to detect errors; take corrective action if necessary

Parity Bit

- Even Parity: 1100, send 1100<u>0</u>
- Detects odd number of errors

Two Dimensional Parity



Parity Bits

Data

- Used by BISYNC protocol for ASCII characters
- "N + 8" bits of redundancy for
 "N" ASCII characters (character is 7 bits)
- Catches all 1, 2, 3 bit errors and most 4 bit errors

Internet Checksum

• Used at the network layer (IP header)

• Algorithm:

- View data to be transmitted as a sequence of 16-bit integers.
- Add the integers using 16 bit one's complement arithmetic.
- Take the one's complement of the result this result is the checksum
- Receiver performs same calculation on received data and compares result with received checksum

Example

- Sender: IPV4 header in hexadecimal
 - 4500 0073 0000 4000 4011 c0a8 0001 c0a8 00c7 (16-bit words)
 - Sum up the words (can use 32 bits): 0002 479c
 - Add carry to the 16-bit sum: 479e
 - Take the complement: $b861 \rightarrow checksum$
- Receiver:
 - Sum up the words including checksum (use 32 bits): 2fffd
 - Add carry to the 16 bit sum: ffff (= 0 in 1's complement) → no error was detected

Internet Checksum

- Not very strong in detecting errors
 - Pair of single-bit errors, one which increments a word, other decrements a word by same amount
- Why is it used still?
 - Very easy to implement in software
 - Majority of errors picked by CRC at link-level (implemented in hardware)

Cyclic Redundancy Check (CRC)

- Used by many link-level protocols: HDLC, DDCMP, Ethernet, Token-Ring
- Uses powerful math based on finite fields
- Background: Polynomial Arithmetic

Polynomial Arithmetic

- Represent a m bit message with a polynomial of degree "m-1"
- $-11000101 = x^7 + x^6 + x^2 + 1$
- Arithmetic over the field of integers modulo 2 (coefficients are 1 or 0)
- Addition or subtraction are identical: XOR

Polynomial Arithmetic

- Polynomial division (very similar to integer division)
 - X/Y is X = q*Y + r
 - For integers: 0<=r<Y</pre>
 - For polynomials: degree of r (remainder polynomial) is less than divisor polynomial

Cyclic Redundancy Check (CRC)

- Message polynomial M(x): m bit message represented with a polynomial of degree "m-1";
 - $-11000101 = x^7 + x^6 + x^2 + 1$
- Sender and receiver agree on a divisor polynomial C(x) of degree k
 - k: Number of redundancy bit
 - E.g. $C(x) = x^3 + x^2 + 1$ (degree k = 3)
 - Choice of C(x) significantly effects error detection and is derived carefully based on observed error patterns
 - Ethernet uses CRC of 32 bits, HDLC, DDCMP use 16 bits
 - Ethernet: $x^{32}+x^{26}+x^{23}+x^{22}+x^{16}+x^{12}+x^{11}+x^{10}+x^8+x^7+x^5+x^4+x^2+x+1$

Idea

- Sender sends m+k bits => Transmitted message P(x)
- Contrive to make P(x) exactly divisibly by C(x)
- Received message R(x)
 - No errors: R(x) = P(x), exactly divisible by C(x)
 - Errors: $R(x) \sim P(x)$; likely not divisible by C(x)

Generate P(x)

- You have M(x) and C(x). Generate P(x)
- Multiply M(x) by x^k to get T(x)
 - Add k zeros at the end of the message
- Divide T(x) by C(x) to get remainder R(x)
- Subtract remainder R(x) from T(x) to get P(x)
- P(x) is now exactly divisible by C(x)

Details

- $T(x) = x^k M(x) = Q(x) C(x) + R(x)$
- $P(x) = x^k M(x) R(x) = x^k M(x) + R(x)$ = Q(x)C(x)
 - Coefficients of R(x) are the redundant bits
 - Transmitted Bits: Messaged (n) bits, followed by redundant bits (k)

Example

- Message (M): 11001011
- Divisor (C): 1101
- T: 11001011000
- Remainder (R): 101
- Transmitted Bits (P): 11001011101

Error Detection

- Received polynomial = P(x) + E(x)
 - E(x) captures bit map of the positions of errors
- Cannot detect errors if E(x) is also divisible by C(x)
- Goal: Design C(x) such that for anticipated error patterns, E(x) is not divisible by C(x)

Example

- Detect all instances of odd number of bit errors
- E(x) contains odd number of terms with coefficient of '1'
 - Implies E(1) = 1
- If C(x) were a factor of E(x), then C(1) would also have to be 1
- If C(1) = 0, we can conclude C(x) does not divide E(x)
- If C(x) has some factor of the form x^i+1 , then C(1)=0

Capabilities

- All single-bit errors, if x^k and x⁰ have non-zero coefficients
 - All double-bit errors, if C(x) has at least three terms
- All odd bit errors, if C(x) contains the factor (x + 1)
- Any bursts of length <= k, if C(x) includes a constant term (x⁰ term)
- · CRC is easily implementable on shift registers

Summary

- Important to detect errors in frames
- Many techniques exist (simple to complex)
 - Parity, Checksum, CRC
- Going Forward: Error Recovery