



LINMA2710 Scientific Computing

ISSAMBRE L'HERMITE DUMONT
SIMON DESMIDT

Academic year 2024-2025 - Q2



Contents

1 Shared-Memory Multiprocessing	2
1.1 How memory works	2
1.2 Parallelism	6
1.3 Amdahl's law	7
2 Single Instruction Multiple Data (SIMD)	9
2.1 What is SIMD?	9
2.2 How does it work?	9
2.3 Pros and cons	10
3 Distributed Computing with MPI	11
3.1 Single Program Multiple Data (SPMD)	11
3.2 Collectives	12
3.3 Point-to-point communication	17
4 Scientific computing on GPU	19
4.1 What is a GPU?	19
5 Power consumption of computing	22
5.1 Power consumption of the components	22
5.2 Reducing power consumption	23
6 Useful tools	25
6.1 OpenMP	25
6.2 Slurm	25
6.3 OpenCL	26
7 PAA - PDEs	27
7.1 Introduction	27
7.2 Finite differences methods	27
7.3 Finite volume methods	32
7.4 Summary	34
7.5 Hyperbolic equations in 1 space dimension	34

Shared-Memory Multiprocessing

1.1 How memory works

1.1.1 Memory hierarchy

To store the data that it will use, the CPU uses memory. Memory is hierarchical like a pyramid. The higher it is, the faster it goes, but the less space there is.




Figure 1.1: Memory hierarchy

First we need to define a cycle. It's an unit of time that is defined like this: $cycle = \frac{1}{CPU\ freq}$. For example, for the CPU *AMD Ryzen 5 5600X*, the maximum frequency is $4.6GHz$, so the cycle is $cycle = \frac{1}{4.6GHz} \approx 0.217ns$. The **bandwidth** is the number of bytes that can be transferred in one cycle. And the **latency** is the number of cycles required to access a level of memory. There's also the **latency** but for a number of bytes, its formula is $\alpha + \beta n$ where α is the level latency, β is the inverse of the bandwidth and n is the number of bytes.

Level	Level Latency [cycle]	Bandwidth [bytes/cycle]	Size	What is stored	Example
Register	3	No limit	$\approx 192B$	"Immediate" data for the CPU	Results of addition, memory address
Cache L1	15	32 – 64	$\approx 64KB$	Instructions and "Immediate" data	Local variable
Cache L2	57	16 – 32	$\approx 512KB$	Data used recently	Data struct, code part
Cache L3	230 – 360	4 – 10	$\approx 64MB$	Data shared between core	Global variable
RAM	300 – 500	9 – 50GB/s	$\geq 4GB$	Running programs	Running software, open document
Disks	$\geq 10^5$	Usually $\leq 3GB/s$	$\geq 128GB$	Persistent data	Document, OS, etc

1.1.2 Caches lines and prefetching

A **cache line** is a small fixed-size contiguous block of memory, usually 64 or 128 bytes. It's not necessarily stored in the cache. We use them to organize the memory, because it is easier to deal with fixed size block. When the CPU need to access a memory location, it loads the entire cache line into the cache of the CPU. If the wanted data is not in the cache, there will be a **cache miss**. After that the CPU will load the entire cache line into the cache.

The **prefetching** is the fact that the CPU will load the cache line that is next to the one that is needed. It's because of the spacial locality. Spacial locality is the reason why we use cache lines. For example, if we store an array of data, it may use some space greater than one cache line so for precaution, the CPU will load the next cache line too. And so we save time, by anticipating.

The data locality is important for at least the two following reasons:

- **Temporal locality:** If a data is used frequently, we will keep it in the cache.
- **Spacial locality:** If a data is used, the data next to it could be useful too.

1.1.3 Arithmetic intensity

The **arithmetic intensity** is a concept in performance analysis for memory-bound and compute-bound programs. Let's consider a program that does o arithmetic operations and m memory operations, we define:

- **Arithmetic intensity:**

$$a = \frac{o}{m} \quad (1.1)$$

It helps find if the program is limited by a compute-bound or memory-bound.

- **Arithmetic time:**

$$t_{arith} = \frac{o}{\text{CPU freq}} \quad (1.2)$$

It's the time needed to perform o operations.

- **Memory transfer time:**

$$t_{mem} = \frac{m}{\text{bandwidth}} = \frac{o}{a \times \text{bandwidth}} \quad (1.3)$$

It's the time needed to do m memory operations.

The overall performance of a program is thus defined by the worst component of the PC, and so we get the **time per iteration**:

$$\min \left(\frac{t_{arith}}{o}, \frac{t_{mem}}{o} \right) \quad (1.4)$$

With some algebra, we can find the **number of operations per second**:

$$\max (\text{CPU freq}, a \times \text{bandwidth}) \quad (1.5)$$


To resume:

- If a is low then the performance is memory-bounded \Rightarrow **Need cache optimization**.
- If a is high then the performance is compute-bounded \Rightarrow **Need more CPU cores or vectorization**.

The arithmetic intensity can be represented with the **roofline model** which we'll talk about now.

1.1.4 The roofline model

The two following graphs link the performances of a program with the arithmetic intensity. The "performances" means the number of operations per second and the "arithmetic intensity" is the number of operations per byte of memory transferred. The left graph is the case where we consider a perfect usage of the PC, and the right graph is the case where we consider a bad usage of the PC.



As we can clearly see, we have two limitations:

- Bandwidth limit (sloped line)
- Computing limit (flat line)

These two limit lines are upper bounds for performances and are limited from above by the hardware (we can't do better than what our CPU can do), but they can be lower if the program is not optimized. For example the sloped line can be lower if we don't use the cache correctly. The flat line can be lower if we don't use the CPU correctly (e.g. not using SIMD).

1.1.5 Cache hierarchy for a multi-core CPU

In the case where we have a multi-core CPU, the organization of the memory isn't always the same, it depends of the CPU architecture. For example, we can have a hierarchy like this:



Figure 1.3: Cache hierarchy for a multi-core CPU

Here the L1 cache is private to each core, the L2 cache is shared between two cores and the L3 cache is shared between all cores, as well as the RAM.

1.2 Parallelism

In this course, we use *OpenMP* to parallelize our code instead of *lpthread*. The advantages of *OpenMP* are detailed in the chapter **useful tools** at the section 6.1.

Parallelism is a very useful tool to optimize the performances of a program. It allows to use multiple cores of the CPU to do multiple tasks at the same time. But sometimes it may arise some problems of performances or computational error.

1.2.1 Computational error

When using multi-threading, we may modify and use some variables at the same time which could cause computational error. So to avoid that we can either protect the variable (with some adapted tools) but this option is not very efficient because it takes some time to *lock* and *unlock* and to wait for the variable to be available. Or we can make each thread use its own version of the variable, this introduces the next problems.

1.2.2 Race condition

The race condition is a problem that occurs when two or more threads try to modify the same variable at the same time, here there are no computational error possible. For example if all the threads want to modify a variable at the same time, they will need to wait for the variable to be available, and it is a waste of time. The solution for that, as we said before is to make each thread use its own version of the variable. Let's say they need to compute the sum of an array. The solution is to make each thread compute the

sum of a part of the array and then by "reduction" sum all the sums. We will see this in more detail in the next chapter.

1.2.3 False sharing

As we say before, in the section 1.1.2 about cache lines, the CPU loads the entire cache line into the cache when it need to use some data that is on the cache line. So here is the problem, let's say that all of the partial sum of the array are stored in the same cache line, when a thread modify its partial sum, the entire cache line is loaded into the cache of the CPU, and so the other threads will have to wait for the cache line to be available. The solution is to make each thread use its own cache line. We can solve this by adding some padding (shift the data) to the data structure.

1.3 Amdahl's law

First let's define the **speedup** of a program, it represents the improvement of running time while using p threads. It is defined by:

$$S_p = \frac{T_1}{T_p} \quad (1.6)$$

Where T_1 is the time needed to run the program with one thread and T_p is the time needed to run the program with p threads.

Then let's define the **efficiency** of a program, is measures how well the parallelization is done. It is defined by:

$$E_p = \frac{S_p}{p} \quad (1.7)$$

Where S_p is the speedup of the program with p threads. We get 3 cases:

- If $E_p = 1 \Rightarrow$ **Ideal case**, the parallelization is perfect.
- If $E_p < 1 \Rightarrow$ **Realistic case**, there's some inefficiency.
- If $E_p > 1 \Rightarrow$ **Unrealistic case**, would imply a super-linear speedup.

We can now define **Amdahl's law**, which explain the limitation of parallelization due to the presence of a sequential portion in a program. It is defined like this:

$$T_p = F_s T_1 + \frac{(1 - F_s) T_1}{p} \quad (1.8)$$

F_s is the percentage of the program that is sequential (impossible to parallelize). With that we can redefine the **speedup** and the **efficiency** of a program:

$$S_p = \frac{T_1}{F_s T_1 + \frac{(1 - F_s) T_1}{p}} = \frac{1}{F_s + \frac{1 - F_s}{p}} \Rightarrow \lim_{p \rightarrow \infty} S_p = \frac{1}{F_s} \quad (1.9)$$

And

$$E_p = \frac{S_p}{p} = \frac{1}{p F_s + 1 - F_s} = \frac{1}{F_s(p - 1) + 1} \quad (1.10)$$




Figure 1.4: Amdahl's law

1.3.1 Application of Amdahl's law to parallel sum

Let's consider the sum of an array, we want to parallelize it. The time without parallelization is n and with parallelization is $\frac{n}{p} + \log_2(p)$, the log term is the time needed to sum all the partial sums. So the speedup is:

$$S_p = \frac{n}{\frac{n}{p} + \log_2(p)} = \frac{1}{\frac{1}{p} + \frac{\log_2(p)}{n}} \quad (1.11)$$

And the efficiency is:

$$E_p = \frac{S_p}{p} = \frac{1}{1 + \frac{p}{n} \log_2(p)} \quad (1.12)$$

We clearly see that if we use more than n processes the efficiency will decrease. Because if $p \geq n$ then we have $T_p = \log_2(n)$ and $\lim_{p \rightarrow \infty} S_p = \frac{1}{\log_2(n)}$ and $F_s = \log_2(n)$.

Single Instruction Multiple Data (SIMD)

2.1 What is SIMD?

SIMD (Single Instruction Multiple Data) is a parallel computing architecture used to process multiple data simultaneously with a single instruction.

2.2 How does it work?

SIMD takes advantages of **vector registers**, to perform the same operation on multiple data elements in parallel within a single CPU cycle. It uses an extension of a CPU architecture that features specific register and set of instructions. So it stores the vector on a specific register and uses the optimized instructions on it. It increases the throughput of processed data.

SIMD uses sets of instructions and registers to increase performances, for example AVX512 is an extension of a CPU architecture that features a specific set of instructions designed to work with wider registers than AVX2. Possible extensions are: SSE, AVX, AVX2, AVX512, NEON, etc.

Let's do a little example, consider the following code:

```
1 int a[] = {...};  
2 int b[] = {...};  
3 int c[size];  
4 for(int i = 0; i < size; i++) {  
5     c[i] = a[i] + b[i];  
6 }
```

Here we use `int` which is 32 bits so if we use SIMD with AVX2, we can store $(256/32) = 8$ integers in an AVX2 register. And so SIMD, with that type of set of instructions, will automatically translate the previous code to:

```
1 int a[] = {...};  
2 int b[] = {...};  
3 int c[size];  
4 for (int i = 0 ; i < size; i += 8) {  
5     __m256i va = _mm256_load_si256((__m256i*)&a[i]);  
6     __m256i vb = _mm256_load_si256((__m256i*)&b[i]);  
7     __m256i vc = _mm256_add_epi32(va, vb);  
8     _mm256_store_si256((__m256i*)&c[i], vc);  
9 }
```

We can write the code with the intrinsics (all the function with `_` before), for manual control, but it's not necessary. The compiler will do it for you. Here we reduce the number of loop iteration by a factor of 8, but we increase the number of instructions.

We can thus use SIMD to speed up the code. To use it, we need to ask the compiler for it with flags. Here are some examples (certain flags aren't available for some compiler):

Purpose	Flags
Optimization level	-O2, -O3
Sets of instructions of architectures	-mavx, -mavx2, -mavx512f, etc.
Maximum optimization for own CPU	-march=native

2.3 Pros and cons

Pros	Cons
Speedup of about 8, for supported operations	Data must be aligned in memory
Energetic efficiency because fewer optimized instructions	Not fitted for all algorithm (especially with data dependencies)
Better usage of the CPU, especially memory wise	If intrinsics are used, code is less portable
Simple to add to an existing code	Order of operation can be changed, possible floating point inaccuracies.

Distributed Computing with MPI

3.1 Single Program Multiple Data (SPMD)

Single Program Multiple Data means that we make multiple processes execute the same program but operate on different data. It's a kind of parallel computing that we call distributed computing.

3.1.1 Message Passing Interface (MPI)

MPI is a standardized and portable message-passing system used to enable parallel computing across multiple nodes. Here are some key steps with MPI:

- Initialization: `MPI_Init(&argc, &argv);`, initialize MPI and the processes.
- Getting the number of processes: `MPI_Comm_size(MPI_COMM_WORLD, &nprocs);`, determines how many processes are running (`nprocs` is the same for all processes.)
- Getting the rank of the process: `MPI_Comm_rank(MPI_COMM_WORLD, &procid);` Give a unique ID (rank) to each process, which allows them to perform different tasks despite running the same program.
- Finalizing MPI: `MPI_Finalize();`, finalize MPI and free the resources.

3.2 Collectives

Let's consider a system that can support 4 processes for the explicit examples (tables). And for the bounds consider as usual p process and the variables defined for the latency 1.1.1 (α, β, n) and an arithmetic intensity parameter (γ). Here is some illustration of how collectives work:




Figure 3.1: Collectives

3.2.1 Broadcast

Broadcast makes a process gives a variable to the other processes.

Before				⇒	After					
procid	0	1	2	3		procid	0	1	2	3
	x					x	x	x	x	

Using *spanning tree algorithm*, we can **broadcast** in $\log_2(p)(\alpha + \beta n)$. The function to use **broadcast** is:

```

1 int MPI_Bcast(
2     void *buffer,           // Data buffer (send/receive)
3     int count,              // Number of elements in buffer
4     MPI_Datatype datatype, // Type of each element (e.g. MPI_INT)
5     int root,                // Rank of root process broadcasting data
6     MPI_Comm comm            // Communicator (usually MPI_COMM_WORLD)
7 )

```

3.2.2 Gather

Gather makes a process gather the variables of the other processes.

Before				⇒	After				
procid	0	1	2	3	procid	0	1	2	3
	x_0					x_0			
		x_1				x_1			
			x_2			x_2			
				x_3		x_3			

Using *spanning tree algorithm*, we **gather** in $\log_2(p)\alpha + \beta n$. The function to use **gather** when we have same buffer size is:

```

1 int MPI_Gather(
2     const void *sendbuf,      // Data to send from each process
3     int sendcount,           // Number of elements to send
4     MPI_Datatype sendtype,   // Type of sent elements
5     void *recvbuf,           // Buffer to collect all data
6     int recvcount,           // Number of elements received from each process
7     MPI_Datatype recvtype,   // Type of received elements
8     int root,                // Rank of collecting process
9     MPI_Comm comm            // Communicator (usually MPI_COMM_WORLD)
10 )

```

And when we have different buffer size, we use:

```

1 int MPI_Gatherv(
2     const void *sendbuf,
3     int sendcount,
4     MPI_Datatype sendtype,
5     void *recvbuf,
6     const int *recvcounts,    // Array: how much to receive from each process
7     const int *displs,        // Array: where to place each chunk in recvbuf
8     MPI_Datatype recvtype,
9     int root,
10    MPI_Comm comm
11 )

```

3.2.3 Scatter

Scatter makes a process send a part of its informations to the others processes.

Before				⇒	After				
procid	0	1	2	3	procid	0	1	2	3
	x_0					x_0			
	x_1					x_1			
		x_2					x_2		
			x_3					x_3	

Using *spanning tree algorithm*, we **scatter** in $\log_2(p)\alpha + \beta n$. The function to use **scatter** when we have same buffer size is:

```

1 int MPI_Scatter(
2     const void *sendbuf,           // Data to distribute (used only at root)
3     int sendcount,               // Number of items sent to each process
4     MPI_Datatype sendtype,       // Type of sent elements
5     void *recvbuf,              // Where each process receives its data
6     int recvcount,               // Number of items received
7     MPI_Datatype recvtype,       // Type of received elements
8     int root,                   // Rank of sending process
9     MPI_Comm comm               // Communicator (usually MPI_COMM_WORLD)
10 )

```

And when we have different buffer size, we use:

```

1 int MPI_Scatterv(
2     const void *sendbuf,
3     const int *sendcounts, // Array: number of items to send to each
process
4     const int *displs,    // Array: offsets in sendbuf for each process
5     MPI_Datatype sendtype,
6     void *recvbuf,
7     int recvcount,
8     MPI_Datatype recvtype,
9     int root,
10    MPI_Comm comm
11 )

```

3.2.4 Reduce

Reduce sums up all the values of the variables on the different processes and store the sum on one process.

Before				⇒	After					
procid	0	1	2	3		procid	0	1	2	3
	x_0	x_1	x_2	x_3						$\sum_{i=0}^3 x_i$

Using *spanning tree algorithm*, we can **reduce** in $\log_2(p)(\alpha + \beta n) + \log_2(p)\gamma n$. To simplify we have: $\log_2(p)(\alpha + (\beta + \gamma)n)$. The function to use **reduce** is:

```

1 int MPI_Reduce(
2     const void *sendbuf,           // Data to send from each process
3     void *recvbuf,               // Where data is collected at root
4     int count,                  // Number of elements in each process
5     MPI_Datatype datatype,       // Type of elements
6     MPI_Op op,                  // Reduction operation (e.g. MPI_SUM)
7     int root,                   // Rank of collecting process
8     MPI_Comm comm               // Communicator (usually MPI_COMM_WORLD)
9 )

```

3.2.5 All gather

All gather is a sort of combination of **gather** and **broadcast**. It gathers all the variables of the processes and broadcast them to all the processes but more efficiently.

Before				⇒	After				
procid	0	1	2	3	procid	0	1	2	3
	x_0					x_0	x_0	x_0	x_0
		x_1				x_1	x_1	x_1	x_1
			x_2			x_2	x_2	x_2	x_2
				x_3		x_3	x_3	x_3	x_3

Using *spanning tree algorithm*, we can **all gather** in $\log_2(p)\alpha + \beta n$. The function to use **all gather** when we have same buffer size is:

```

1 int MPI_Allgather(
2     const void *sendbuf,           // Data to send from each process
3     int sendcount,                // Number of elements to send from each process
4     MPI_Datatype sendtype,        // Type of sent elements
5     void *recvbuf,               // Buffer to collect all data
6     int recvcount,                // Number of elements received by each process
7     MPI_Datatype recvtype,        // Type of received elements
8     MPI_Comm comm                // Communicator (usually MPI_COMM_WORLD)
9 )

```

And when we have different buffer size, we use:

```

1 int MPI_Allgatherv(
2     const void *sendbuf,
3     int sendcount,
4     MPI_Datatype sendtype,
5     void *recvbuf,
6     const int *recvcounts, // Array: number of items to receive from each
7     process
8     const int *displs,    // Array: offsets in recvbuf for each process
9     MPI_Datatype recvtype,
10    MPI_Comm comm
11 )

```

3.2.6 Reduce scatter

Reduce scatter is a sort of combination of **reduce** and **scatter**. It reduces the variables of the processes and scatter them to all the processes, but more efficiently.

Before				\Rightarrow	After				
procid	0	1	2	3	procid	0	1	2	3
$x_{0,0}$	$x_{0,1}$	$x_{0,2}$	$x_{0,3}$			$\sum_{j=0}^3 x_{0,j}$			
$x_{1,0}$	$x_{1,1}$	$x_{1,2}$	$x_{1,3}$				$\sum_{j=0}^3 x_{1,j}$		
$x_{2,0}$	$x_{2,1}$	$x_{2,2}$	$x_{2,3}$					$\sum_{j=0}^3 x_{2,j}$	
$x_{3,0}$	$x_{3,1}$	$x_{3,2}$	$x_{3,3}$						$\sum_{j=0}^3 x_{3,j}$

Using *spanning tree algorithm*, we can **reduce scatter** in $\log_2(p)\alpha + (\beta + \gamma)n$. The function to use **reduce scatter** is:

```

1 int MPI_Reduce_scatter(
2     const void *sendbuf,           // Data to send from each process
3     void *recvbuf,                // Where data is collected for each process
4     const int *recvcounts,         // Array: result segment size for each process
5     MPI_Datatype datatype,        // Type of elements
6     MPI_Op op,                  // Reduction operation (e.g. MPI_SUM)
7     MPI_Comm comm                // Communicator (usually MPI_COMM_WORLD)
8 )

```

3.2.7 All reduce

All reduce is a sort of combination of **reduce** and **broadcast**.

Before				\Rightarrow	After				
procid	0	1	2	3	procid	0	1	2	3
x_0	x_1	x_2	x_3			$\sum_{i=0}^3 x_i$	$\sum_{i=0}^3 x_i$	$\sum_{i=0}^3 x_i$	$\sum_{i=0}^3 x_i$

We explained above that we can do a combination of **reduce** and **broadcast**, but we can **all reduce** more efficiently doing **reduce scatter** then **all gather**, and we can do it in $\log_2(p)\alpha + \beta n$. The function to use **all reduce** is:

```

1 int MPI_Allreduce(
2     const void *sendbuf,           // Data to send from each process
3     void *recvbuf,                // Where data is collected for each process
4     int count,                   // Number of elements in each process
5     MPI_Datatype datatype,        // Type of elements
6     MPI_Op op,                  // Reduction operation (e.g. MPI_SUM)
7     MPI_Comm comm                // Communicator (usually MPI_COMM_WORLD)
8 )

```

3.3 Point-to-point communication




Figure 3.2: Point-to-point blocking communication

This figure shows the problem of point-to-point blocking communication in MPI. As we can see, the left process is waiting for the right process to send the data, and thus is idling and wasting time. It does that because the sender cannot continue until the message is completely transferred. And in the case of a too big message that can't be stored in the buffer then the sender must wait for the receiver.

There are two ways to solve this problem:

- **Rendezvous protocol:** It works like a handshake process, so we have:
 - The sender sends a header to notify the receiver that he will send data.
 - The receiver replies with a "ready-to-send" signal.
 - The sender sends the actual data.
- **Eager protocol:** The message is quickly buffered in the sender's buffer to allow `MPI_Send()` to finish "eagerly" and when the receiver is ready, it can receive the message. The sender doesn't wait for the receiver to be ready. It's useful when the message is small and thus fit in the buffer.

The eager protocol can be represented like this:




Figure 3.3: Eager protocol

Scientific computing on GPU

4.1 What is a GPU?

4.1.1 GPU vs CPU

A GPU (Graphics Processing Unit) is simply a CPU but specialized for parallel computing and is commonly used for matrix computations. In order to understand why let's do a little comparison between CPU and GPU:

	CPU	GPU
Purpose	brain of the PC	graphic rendering
Number of cores/threads	a few 2 – 32	thousands
Processing	serial work	parallel work
Memory (global)	RAM (8 – 64 < GB)	VRAM (4 – 24 < GB)
Memory (local)	cache L1, L2, L3 (cf 1.1)	32 – 128KB per block
Frequency	high (3 – 5GHz)	low (1 – 2GHz)
Flexibility	versatile	specialized

So to summarize, the CPU is a group of a few powerful worker that do different work each while the GPU have an army of workers that do the same simple task in parallel to contribute to a greater goal.

GPU are used commonly for graphics rendering, but it's not the only thing that they can do, we can use them for any kind of parallel computing. For example: machine learning, deep learning, simulations, etc. To do that we can run code using different "translation platforms" like **CUDA** (NVIDIA only), **ROCm** (AMD only) or open source alternative like **OpenCL**.

4.1.2 Hierarchy

The hierarchy is pretty simple, we have the host that send the jobs to the rest of the CPU and GPU. After that, we have the computing devices. All of the cores of the CPU are managed as one, and each GPU is an independant computing device. After that, we have the computing units. Typically, for a CPU each core is a computing unit, and for a GPU each computing unit is composed a block of processors that can run multiples threads at the same time. And at the lowest level is the processing elements, it is an ALU (Arithmetic Logic Unit), to simplify it's a single thread that does basic operations.




Figure 4.1: Hierarchy

And we can get informations from all of those levels by the following functions:

	Compute device	Compute unit	Processing element
Get id	get_global_id	get_group_id	get_local_id
Get quantity	get_global_size	get_num_groups	get_local_size

4.1.3 Memory hierarchy

The memory hierarchy follows the same principle as the hierarchy. The host has its own memory (RAM). The global memory is the memory of the GPU, it is shared between all the threads of the GPU but is "slow" (VRAM). The local memory is shared between all the threads of a computing unit, and is faster than the global memory. And finally the private memory is the memory of a thread, it is the fastest memory. The size of the memory is decreasing as its locality increases.




Figure 4.2: Memory hierarchy

Power consumption of computing

5.1 Power consumption of the components

First we need to define the Thermal Design Power (TDP), it is the maximum amount of heat (in Watts) that a component is designed to dissipate. It is a useful measure to estimate the power consumption but also to design the cooling system.

5.1.1 CPU

The power of a CPU is approximately proportional to its utilisation until below 10%, so we can compute it like this:

$$Power = TDP \times \max(0.1, load) \quad (5.1)$$

For example, for the CPU *AMD Ryzen 5 5600X*, the TDP is 65W, so we have this power curve:




Figure 5.1: Power consumption of the CPU

5.1.2 RAM

A slot of RAM consumes about $2 - 5\text{W}$ while being used, when in sleep mode it drops at 1W .

5.1.3 GPU

The power consumption of a GPU is more complex to compute but can be estimated by using the same formula as the CPU:

$$Power = TDP \times \max(0.1, \text{load}) \quad (5.2)$$

5.2 Reducing power consumption

5.2.1 Understanding the factors

The power consumption of a component is the sum of two sources:

- Static power: Minimum power consumed to keep the component on plus tiny leaks. High voltage induce more leaks.
- Dynamic power: Power consumed due to the activity, it's given by the formula:

$$P = CV^2 Af \quad (5.3)$$

where C is the capacitance, V is the voltage, A is the activity factor (number of switches of transistors per clock cycle) and f is the frequency.

High frequency induce high voltage. Which leads us to the concept of Dynamic voltage and frequency scaling (DVFS). This technique allows to reduce the power consumption of a component by reducing the voltage and frequency when we doesn't need it. Thus we dynamically change voltage to adapt to the component load required.

→ NB: the performance of a program is affected only if it's compute-bounded not if it's bandwidth-bounded.

5.2.2 Gating

Gating is a way to save power when a CPU (or GPU) core is idling. The idea is to reduce or cut off power to unused parts of the chip in steps, depending on how long it's been in idle.

1. **Clock gating:** Make some parts of the chip stop receiving clock signals (idle mode for them).
2. **Voltage Reduction (deeper idle):** Reduce the voltage for the idle parts of the chip or the whole chip.
3. **Power Gating (deepest idle):** The chip turns off parts of the circuit (cuts off the power supply entirely).

5.2.3 Reducing the power consumption of a program

DVFS and gating are done automatically so how can we reduce the power consumption of a program?

- Limits the number of threads, especially if the program is bandwidth-bounded.
- Use shared memory instead of global memory to reduce the number of accesses to the global memory. It helps to improve the time of computing and the power efficiency.
- TODO: Talk about warps and interleaving count

Useful tools

6.1 OpenMP

TODO: Improve

OpenMP is a library that allows to parallelize code, it is better than *lpthread* for multiple reasons:

- Easy to add to an existing code, because of the compilation directives (`#pragma omp`). It's an implicit gestion of the threads unlike *lpthreads* that require an explicit gestion. It allows to parallelize a code without changing the whole structure of the code.
- Automatic gestion of the threads, for example if you want to parallelize a loop, you don't have to create the threads, the library will do it for you and optimize the number of threads.
- Simplified synchronization with tools. *OpenMP* provides tools to synchronize the threads like `critical`, `atomic`, `barrier`, etc. They help to protect the shared data between the threads.
- Optimized use of the cache
- Compatible with *SIMD*
- Portability: it is compatible with *Windows*, *Linux*, *MacOS*. With multiple CPU architectures like *Intel*, *AMD*, *ARM*, etc.

6.1.1 OpenMP and PRAGMA

6.2 Slurm

6.2.1 What is Slurm?

Slurm stands for *Simple Linux Utility for Resource Management*. It is an open-source job scheduler used in high-performance computing environments, such as university clusters or research supercomputers.

6.2.2 How to use Slurm?

6.2.3 Slurm Topology

6.3 OpenCL

PAA - PDEs

7.1 Introduction

Throughout this chapter, we will use the simple example of the diffusion equation. It is expressed as

$$\partial_t u(x, y, z, t) = \kappa \nabla^2 u(x, y, z, t) + f(t, x, y, z) \quad (7.1)$$

To that, we add an initial condition and boundary conditions:

- Initial condition: $u(0, x, y, z) = u_0(x, y, z);$
- General boundary condition: $n \cdot \nabla u = 0$ on $\Omega;$
 - Dirichlet boundary condition: $u(t, 0)$ given for all $t \geq 0;$
 - Neumann boundary condition: $\partial_x u(t, 0)$ given for all $t \geq 0;$

This equation can represent the diffusion of heat, particles, pollutants, etc. It is derived from two basic laws of physics:

- Fourier law for heat: $\vec{q} = -\kappa \nabla u;$
- Conservation law: $\partial_t u = -\partial_x \vec{q};$

7.2 Finite differences methods

We will now consider more specifically the 1D case:

$$u_t(t, x) = u_{xx}(t, x) \quad x \in [0, 1] \quad t \geq 0 \quad (7.2)$$

with conditions

$$\begin{cases} u(t, 0) = u(t, 1) = 0 & \forall t \\ u(0, x) = u^0(x) \end{cases} \quad (7.3)$$

There is usually no analytical solution to the equation, and this is why we can use numerical method to find the solution.

7.2.1 The θ -method

In finite differences, we discretize the domain in a mesh, like displayed on figure 7.1.




Figure 7.1: Discretization of the domain

The θ -method consists in taking a linear combination of two approximations of the derivatives through finite differences:

$$\frac{u_j^{n+1} - u_j^n}{\Delta t} = (1 - \theta) \frac{u_{j+1}^n - 2u_j^n + u_{j-1}^n}{\Delta x^2} + \theta \frac{u_{j+1}^{n+1} - 2u_j^{n+1} + u_{j-1}^{n+1}}{\Delta x^2} + T_j^n \quad (7.4)$$

Where u_j^n denotes the exact value of the function $u(\cdot)$ at the given point, and T_j^n is called the truncation error.


Using a truncation, i.e. using approximate values and deleting the truncation error term, the formula is

$$\frac{U_j^{n+1} - U_j^n}{\Delta t} = (1 - \theta) \frac{U_{j+1}^n - 2U_j^n + U_{j-1}^n}{\Delta x^2} + \theta \frac{U_{j+1}^{n+1} - 2U_j^{n+1} + U_{j-1}^{n+1}}{\Delta x^2} \quad (7.5)$$

7.2.2 Analysis principles of FD methods

To be valid, a finite differences method needs to verify some basic principles:

- Consistency along a refinement path: $T_j^n \xrightarrow{h \rightarrow 0} 0$;



- Accuracy: $|T_j^n| \leq c(\Delta t^p + \Delta x^q)$, for all $\Delta t, \Delta x$ small, c a constant and p, q some accuracy parameters;
- Stability along a refinement path: For all solutions v, w of the method and for all $t_F > 0$, $\exists K_{t_F}$ such that $\|V^n - W^n\| \leq K_{t_F} \|V^0 - W^0\|$ for all n such that $n\Delta t \leq t_F$, for t_F the biggest time value;
- Lyapunov stability;
- Convergence along a refinement path: $U_j^n \xrightarrow{h \rightarrow 0} u(t, x)$ when $j\Delta x \rightarrow x$ and $n\Delta t \rightarrow t$.

7.2.3 Value of θ

$\theta = 0$: FTCS (forward time, centered space)

The formula becomes, when defining $\mu := \kappa\Delta t / \Delta x^2$,

$$U_j^{n+1} = \mu U_{j+1}^n + (1 - 2\mu)U_j^n + \mu U_{j-1}^n \quad (7.6)$$




Figure 7.2: Points used in the FTCS scheme.

$\theta = 1$: BTCS (backward time, centered space)

The formula becomes

$$U_j^n = -\mu U_{j+1}^{n+1} + (1 + 2\mu) U_j^{n+1} - \mu U_{j-1}^{n+1} \quad (7.7)$$




Figure 7.3: Points used in the BTCS scheme.

$\theta = 1/2$: Crank-Nicholson

Crank Nicholson uses both the backward and forward time specifications. The formula is determined by replacing the value of θ but is tedious to write. The points it uses are displayed on figure 7.4




Figure 7.4: Points used in the Crank-Nicholson scheme.

7.2.4 Truncation error

By definition, the truncation error term is given by

$$T_j^n = \frac{\delta_t u_j^{n+\frac{1}{2}}}{\Delta t} - \frac{\theta \delta_x^2 u_j^{n+1} + (1 - \theta) \delta_x^2 u_j^n}{\Delta x^2} \quad (7.8)$$

where we define $\delta_t u_j^{n+\frac{1}{2}} = u_j^{n+1} - u_j^n$ and $\delta_x^2 u_j^n = u_{j+1}^n - 2u_j^n + u_{j-1}^n$. Using a Taylor development series for each of the u_j^n , with reference point $(t_{n+\frac{1}{2}}, x_j)$, we can show that

$$T_j^n = \left(\left(\frac{1}{2} - \theta \right) \Delta t - \frac{1}{2} \Delta x^2 \right) u_{xxxx} - \frac{1}{12} \Delta t^2 u_{ttt} + \dots = \mathcal{O}(\Delta t, \Delta x^2) \quad (7.9)$$

And for Crank-Nicholson, this becomes $\mathcal{O}(\Delta t^2, \Delta x^2)$.

7.2.5 Fourier stability analysis

From equation (7.5), we see that U^{n+1} depends linearly in U^n and we can make the guess that the solution will thus have the form

$$U_j^n = (\lambda(k))^n e^{ikj\Delta x} \quad k \in \mathbb{R} \quad (7.10)$$

Replacing in equation (7.5) and solving for $\lambda(k)$, we get

$$\lambda(k) = \frac{1 - 4\mu(1 - \theta) \sin^2 \frac{k\Delta x}{2}}{1 + 4\mu\theta \sin^2 \frac{k\Delta x}{2}} \quad (7.11)$$

By the discrete Fourier transform, every solution can be written

$$U_j^n = \sum_k c_k (\lambda(k))^n e^{ikj\Delta x} \quad (7.12)$$

We know that, if $|\lambda(k)| \leq 1$ for all k , then the θ -scheme is Lyapunov stable. This condition is equivalent to

$$\mu(1 - 2\theta) \leq \frac{1}{2} \quad (7.13)$$

→ Note: this property is sufficient but not necessary.

Let us now define the matrix

$$C(\beta) = \begin{bmatrix} 1 - 2\beta & \beta & & \ddots \\ \beta & 1 - 2\beta & \beta & \ddots \\ 0 & \beta & 1 - 2\beta & \beta \\ & & \ddots & \ddots & \ddots \\ & & \beta & 1 - 2\beta & \beta \\ & & & \beta & 1 - 2\beta \end{bmatrix} \in \mathbb{R}^{J-1 \times J-1} \quad (7.14)$$

The θ -scheme can be written in matrix form:

$$\underbrace{C(-\mu\theta)}_{=:B_1} U^{n+1} = \underbrace{C(\mu(1 - \theta))}_{=:B_0} U^n \iff U^{n+1} = \underbrace{(C(-\mu\theta))^{-1} C(\mu(1 - \theta))}_{=:B_1^{-1} B_0 =: A} U^n \quad (7.15)$$

We can show that the eigenvalues of $C(\beta)$ and their corresponding eigenvectors are

$$v_\ell = 1 - 4\beta \sin^2 \frac{\pi\ell}{2J} \quad x_\ell = \begin{bmatrix} \sin \frac{\pi\ell}{J} \\ \vdots \\ \sin \frac{\pi\ell(J-1)}{J} \end{bmatrix} \quad \ell = 1, \dots, J-1 \quad (7.16)$$

Hence the eigenvalues of the matrix A are


$$v_\ell = \frac{1 - 4\mu(1 - \theta) \sin^2 \frac{\pi\ell}{2J}}{1 + 4\mu\theta \sin^2 \frac{\pi\ell}{2J}} \quad \ell = 1, \dots, J-1 \quad (7.17)$$

Their module must be smaller than 1 for the system to be Lyapunov stable (for all $\ell = 1, \dots, J-1$). This is equivalent to the condition

$$\frac{1 - 4\mu(1 - \theta) \sin^2 \frac{\pi(J-1)}{2J}}{1 + 4\mu\theta \sin^2 \frac{\pi(J-1)}{2J}} \geq -1 \quad (7.18)$$

7.2.6 Dufort-Frankel scheme

$$U_j^{n+1} = U_j^{n-1} + 2\mu \left(U_{j-1}^n + U_{j+1}^n - U_j^{n+1} - U_j^{n-1} \right) \quad (7.19)$$



Let us analyse the stability, given a solution of the form $U_j^n = \lambda^n e^{ikj\Delta x}$, which gives us the values

$$\lambda_{\pm} = \frac{2\mu \cos(k\Delta x) \pm \sqrt{1 - 4\mu^2 \sin^2(k\Delta x)}}{1 + 2\mu} \quad (7.20)$$

We can show through the analysis of the λ that this method is unconditionally stable, but not unconditionally consistent.

→ Note: a scheme taking Dufort-Frankel with the additional point (t_n, x_j) is unconditionally unstable.

7.3 Finite volume methods

Let us study the Poisson equation, written in the following form

$$\nabla \cdot (\kappa(x) \nabla u) = f \quad \text{in } \Omega \subseteq \mathbb{R}^n \quad (7.21)$$

7.3.1 Voronoi cells

The idea of finite volumes consists in creating cells given some vertices $\{x_i\}_i \subset \Omega$. The Voronoi cells are defined as

$$V_i = \{x \in \Omega : \|x - x_i\| \leq \|x - x_j\|, \forall j \neq i\} \quad (7.22)$$




Figure 7.5: Voronoi cells.

The method is the following: by integrating over each cell, we can then use the divergence theorem to approximate using finite differences.

$$\begin{aligned}
 \int_{V_i} \nabla \cdot (\kappa(x) \nabla u) dx &= \int_{V_i} f dx \\
 \int_{\partial V_i} \kappa(x) \nabla u \cdot n ds &\approx f_i Vol(V_i) \\
 \sum_{j \sim i} K_{ij} \underbrace{\frac{u_j - u_i}{\|x_j - x_i\|}}_{=: h_{ij}} \ell_{ij} &\approx f_i Vol(V_i)
 \end{aligned} \tag{7.23}$$

where the notation $j \sim i$ denotes the neighbours j of point i , $K_{ij} = \kappa\left(\frac{x_i + x_j}{2}\right)$, ℓ_{ij} is the length of the interface between cells i and j . This gives the finite volume scheme:

$$\sum_{j \sim i} K_{ij} \frac{U_j - U_i}{h_{ij}} \ell_{ij} = Vol(V_i) f_i \quad \forall i \tag{7.24}$$

7.3.2 Boundary conditions

- Dirichlet: if the condition is $u(x) = g(x) \forall x \in \partial\Omega$, we write for points x_k on the boundary $U_k = g(x_k)$;
- Neumann: the condition is $\nabla u \cdot n = g$ on $\partial\Omega$ and we use it in the form

$$\int_{\partial V_i} \kappa(x) \nabla u \cdot n ds \approx \sum_j K_{ij} \frac{u_j - u_i}{h_{ij}} \ell_{ij} + \int_p \kappa(x) \nabla u \cdot n ds,$$

where p is the boundary of cell V_i , and the integral can be approximated by quadrature.

7.3.3 Analysis of principles

The analysis of principles is complicated using finite volumes. However, here are the results:

- Consistency: finite volume schemes are not consistent in general;
- Convergence: yes;

7.4 Summary

	+	-
Finite differences	Easy to understand and program	Cumbersome for non-rectangular domains or non-Dirichlet boundary conditions
Finite volumes	Works for arbitrary geometries and meshes	Higher order methods are difficult to obtain
Finite elements	Works for arbitrary geometries and meshes; Higher order methods exist	More complicated to implement

Table 7.1: Comparison of numerical methods.

7.5 Hyperbolic equations in 1 space dimension

7.5.1 Linear advection equation

$$u_t + au_x = 0 \quad u(x, t) = u^0(x) \quad (7.25)$$

7.5.2 CFL condition

Consider the finite differences scheme:

$$\frac{U_j^{n+1} - U_j^n}{\Delta t} + a \frac{U_j^n - U_{j-1}^n}{\Delta x} = 0 \quad (7.26)$$

which can also be written

$$U_j^{n+1} = (1 - \nu)U_j^n + \nu U_{j-1}^n \quad \nu := \frac{a\Delta t}{\Delta x} \quad (7.27)$$

The CFL condition states that ν must be smaller than 1. If the scheme is convergent, then the condition holds. The meaning of the CFL condition is that the domain of dependence of the PDE, i.e. all the points that depend on U_j^n , is a subset of the domain of dependence of the numerical scheme.