POLARIS Quickstart Guide

Download

Download zip package from the homepage or clone the github repository via:

```
git clone https://github.com/polaris-MCRT/POLARIS.git
```

HINT: It is recommended to clone the git repository into the home directory. If downloaded from the homepage, extract the zip file into the home directory via:

```
unzip -q POLARIS-master-basic.zip -d ~/
```

Requirements

The following packages are required for the installation:

- gcc (preferred), icc, or clang++
- cmake (preferred), or ninja
- python3 (packages: numpy, setuptools)

Installation (Linux)

Open a terminal/console and move into the POLARIS directory:

```
cd /YOUR/POLARIS/PATH/
```

Run the installation script:

```
./compile.sh -f
```

For the first installation, the option -f is required to install the CCfits and cfitsio libraries. Alternatively, these libraries can be installed with a package manager (root permissions are required):

```
sudo apt update
sudo apt install libccfits-dev libcfitsio-dev
```

If these packages are installed on the system, simply install POLARIS via

```
./compile.sh
```

For more information, type:

```
./compile.sh -h
```

POLARIS can now be executed from any newly opened terminal/console. However, to use it in already open terminals/consoles, execute the following command to update the environmental paths:

```
source ~/.bashrc
```

HINT: Please refer to the manual (Sect. 1.2) for installation on **macOS**. An installer to use POLARIS with Windows is not available yet.

Start a simulation

POLARIS simulations are performed by parsing a command file with the simulation parameters. Exemplary . cmd command files for temperature, thermal emission, and scattered stellar emission simulations can be

found in

- projects/disk/example/temp/,
- projects/disk/example/dust/, and
- projects/disk/example/dust_mc/, respectively.

Parameters of the model such as density distribution or magnetic field direction are stored in a separate grid file (for detailed information, see the manual, Sect. 2.3). The simulations use an exemplary (binary) grid file grid.dat of a circumstellar disk which can be found in projects/disk/.

To start the temperature simulation (temp), move into the POLARIS directory and execute polaris followed by the command file:

cd /YOUR/POLARIS/PATH/
polaris projects/disk/example/temp/POLARIS.cmd

The results are stored at projects/disk/example/temp/data/ as .fits.gz files. These files can be opened with, for example, SAOImageDS9, or a python script using astropy.

Simulations are performed similarly for thermal emission (dust) and stellar scattered radiation (dust_mc). Please refer to the command list in the projects folder or the manual (Table 2.4 - 2.10) for available options of the command file.

HINT: For thermal emission simulations, a temperature simulation has to be performed first.

HINT: The previous results will be overwritten, if the same command file is used. Please change <path_out> in the command file to use a new directory for the new results.

HINT: If users write their own command file, before starting the simulation, please check <dust_component>, <path_grid>, and <path_out> in the command file for the correct (absolute) paths.

Create a grid

POLARIS includes PolarisTools, a Python package to create custom grid files for POLARIS. The (binary) grid file can be created with the command polaris-gen.

Predefined models

There are already two models available:

Circumstellar disk with a Shakura & Sunyaev density distribution (Lynden-Bell & Pringle 1974; Hartmann et al. 1998)

$$\rho(r,z) = \rho_0 \left(\frac{r}{r_0}\right)^{-\alpha} \times \exp\left[-\frac{1}{2} \left(\frac{z}{h(r)}\right)^2\right]$$
$$h(r) = h_0 \left(\frac{r}{r_0}\right)^{\beta}$$

Default values: $r_0=100$ au, $h_0=10$ au, $\beta=1.1$, $\alpha=3(\beta-0.5)$, inner disk radius $r_{\rm in}=0.1$ au, outer disk radius $r_{\rm out}=100$ au, and total gas mass $M_{\rm gas}=10^{-3}~{\rm M}_{\odot}$ with a dust to gas mass ratio of 0.01.

Sphere with a constant density distribution

$$\rho(r) = \rho_0$$

Default values: inner radius $r_{\rm in}=0.1$ au, outer radius $r_{\rm out}=100$ au, and total gas mass $M_{\rm gas}=10^{-4}~{\rm M}_{\odot}$ with a dust to gas mass ratio of 0.01. In addition, the sphere model has a magnetic field with a toroidal geometry and a strength of $10^{-10}~{\rm T}$.

By default, the density distribution is normalized to the given total mass, so the value of ρ_0 is calculated accordingly.

To create a grid file, use

polaris-gen model_name grid_filename.dat

where model_name is either disk, or sphere. The (binary) grid file will be stored at projects/model_name/. To modify specific parameters of the model, for instance a total gas mass of 10^{-5} M_{\odot} and an inner radius of 1 au, type:

polaris-gen model_name grid_filename.dat --gas_mass 1e-5M_sun --inner_radius 1AU

For more information, type:

polaris-gen -h

Extra parameter

To modify further model specific parameter values, the user can parse a list of parameter values using the option --extra followed by the keywords and the corresponding value (int, float, or str). By default, the user can parse

- 4 values for the disk model: reference radius ref_radius (r_0 in meter), reference scale height ref_scale_height (h_0 in meter), alpha (α), and beta (β),
- 2 values for the sphere model: the geometry of the magnetic field mag_field_geometry (toroidal, vertical, or radial) and the magnetic field strength mag_field_strength (in tesla).

For example, the disk density profile can be modified to $r_0=50$ au and $\beta=1.25$ with

polaris-gen disk grid_filename.dat --extra ref_radius 50*149597870700 beta 1.25

or the magnetic field of the sphere to a radial geometry with

polaris-gen sphere grid_filename.dat --extra mag_field_geometry radial

Additional parameter values to modify the model can be defined in the function update_parameter in the file tools/polaris_tools_modules/model.py.

Hint: For any changes in the files, the user has to recompile with:

./compile.sh -u

Custom model

For a more complex model modification, it is recommended that users define their own models in tools/polaris_tools_custom/model.py. Therein, each model is defined as a class with a corresponding entry in the dictionary at the top of model.py. Similar, to create a grid file for a custom model, use

polaris-gen model_name grid_filename.dat

where model_name is the name of the model in the dictionary of model.py.

Hint: For any changes in the files, the user has to recompile with:

./compile.sh -u

Convert a grid file

Users can also write and edit their own grid file. For this purpose, the command polaris-gen has an ascii to binary converter (and vice versa) for converting grid files. To convert an existing ascii grid file to a binary grid file, use

polaris-gen model_name grid_filename.txt --convert ascii2binary

To convert an existing binary grid file to an ascii grid file, use

polaris-gen model_name grid_filename.dat --convert binary2ascii

The input grid file has to be located in projects/model_name/ and the new output grid file will be stored at projects/model_name/. For the general structure and available options in the grid file, please read the manual (Sect. 2.3).