Simplemux Readme file

About Simplemux

There are some situations in which multiplexing a number of small packets into a bigger one is desirable. For example, a number of small packets can be sent together between a pair of machines if they share a common network path. Thus, the traffic profile can be shifted from small to larger packets, reducing the network overhead and the number of packets per second to be managed by intermediate routers.

Simplemux is a generic multiplexing protocol, described in <u>draft-saldana-tsvwg-simplemux</u>. It is able to encapsulate a number of packets belonging to different protocols into a single packet. It includes the "Protocol" field on each multiplexing header, thus allowing the inclusion of a number of packets belonging to different protocols in a packet of another protocol (Fig. 1). The size of the multiplexing headers is kept very low (it may be a single byte when multiplexing small packets) in order to reduce the overhead.




Fig. 1. Example of a Simplemux packet including packets of different protocols

Simplemux is designed to optimize together a number of flows sharing a common network path or segment (Fig. 2). Optimization in the end host is (in principle) not useful, since a number of small-packet flows departing from the same host are unusual. The multiplexing is performed between a pair of machines called ingress-optimizer and egress-optimizer.




Fig. 2. Scheme of the optimization

The present code is an implementation of **Simplemux**, using IP/UDP as the *multiplexing protocol*, and IP or ROHC (<u>RFC 3095</u>) as the *multiplexed protocol*, as illustrated in Fig. 3. Thus, it is able to perform traffic optimization, combining multiplexing with header compression. This may result on significant bandwidth savings and pps reductions for small-packet flows (e.g. VoIP, online games).

Simplemux can run in two modes:

- **Network mode**: the multiplexed packet is sent in an IP datagram using Protocol Number 253 (according to IANA, this number can be used for experimentation and testing¹).
- **Transport mode**: the multiplexed packet is sent in an IP/UDP datagram. In this case, the protocol number in the IP header is that of UDP (17) and both ends have to agree on a UDP port.




Fig. 3. Optimization of five RTP packets of VoIP

Simplemux can be used as an option at the multiplexing layer of TCM², a protocol combining **T**unneling, **C**ompressing and **M**ultiplexing for the optimization of small-packet flows. TCM may use of a number of different standard algorithms for header compression, multiplexing and tunneling, combined in a similar way to RFC 4170, as proposed in draft-saldana-tsvwg-tcmtf.

The implementation is written in C for Linux. It compresses headers using an implementation of ROHC by Didier Barvaux (https://rohc-lib.org/).

Simplemux uses Linux TUN virtual interface.

¹ Protocol numbers, http://www.iana.org/assignments/protocol-numbers/protocol-numbers.xhtml

² Jose Saldana *et al*, "<u>Emerging Real-time Services: Optimizing Traffic by Smart Cooperation in the Network," <u>IEEE Communications Magazine</u>, <u>Vol. 51</u>, n. 11, pp 127-136, Nov. 2013. doi 10.1109/MCOM.2013.6658664</u>

Header compression

Simplemux uses an implementation of ROHC by Didier Barvaux (https://rohc-lib.org/). It implements these ROHC modes:

- ROHC unidirectional.
- ROHC bidirectional optimistic
- ROHC bidirectional reliable is not yet implemented.

ROHC cannot be enabled in one of the peers and disabled in the other peer.

ROHC is able to compress this traffic flows:

- IP/UDP/RTP: If the UDP packets have the destination ports 1234, 36780, 33238, 5020, 5002, the compressor assumes that they are RTP.
- IP/UDP
- IP/TCP
- IP/ESP
- IP/UDP-Lite

Tunneling

In this **Simplemux** implementation, tunneling is performed in a very simple way:

- In **network mode**, the external IP header is the tunneling header. It uses Protocol number 253.
- In **transport mode**, an IP/UDP header is added before the first **Mux separator**. By default, the destination UDP port is 55555.

ROHC feedback information (when using ROHC Bidirectional modes) is sent in UDP packets using port 55556 by default.

Multiplexing

The **Mux separator** (see Fig. 4) has two different formats: one for the *First header* (the separator before the first packet included in the multiplexed bundle), and another one for *Non-first headers* (the rest of the separators).




Fig. 4. First and Non-first Simplemux headers (also known as separators)

Format of the First Simplemux header/separator

The format of the First Simplemux separator is illustrated in Fig. 5:




Fig. 5. Fields of the First Simplemux header/separator

- **Single Protocol Bit (SPB, one bit)** only appears in the first Simplemux header. It is set to 1 if all the multiplexed packets belong to the same protocol (in this case, the "protocol" field will only appear in the first Simplemux header). It is set to 0 when each packet MAY belong to a different protocol.
- Length Extension (LXT, one bit) is 0 if the length of the first packet can be expressed in 6 bits, and 1 in other case.
- Length (LEN, 6 or 14 bits): This is the length of the multiplexed packet in bytes not including the length field. If the length of the multiplexed packet is less than 64 bytes (less than or equal to 63 bytes), LXT is set to 0 and the 6 bits of the length field are the length of the multiplexed packet. If the length of the multiplexed packet is greater than 63 bytes, LXT is set to 1 and the 14 bits of the length field are the length of the multiplexed packet. The maximum length of a multiplexed packet is 16,383 bytes. Packets larger than 16,383 bytes will need to be sent in their native form. A Simplemux ingress is not required to multiplex all packets smaller than 16,383 bytes. It may choose to only multiplex packets smaller than a configurable size into a Simplemux multiplexed packet.
- **Protocol (8 bits)** is the Protocol field of the multiplexed packet, according to IANA "Assigned Internet Protocol Numbers".

Format of the Non-first Simplemux header/separator

If the SPB (Single Protocol Bit) of the First Simplemux header is set to 1, it means that all the multiplexed packets belong to the same protocol. In this case, the format is the one presented in Fig. 6:




Fig. 6. Fields of the Non-first Simplemux header/separator, when the SPB bit of the First header is 1

If the SPB of the First Simplemux header is set to 0, then each packet may belong to a different protocol, so the "Protocol" field is also included, as shown in Fig. 7:




Fig. 7. Fields of the Non-first Simplemux header/separator, when the SPB bit of the First header is 0

These are the fields:

- Length Extension (LXT, one bit) is 0 if the length of the first packet can be expressed in 7 bits, and 1 in other case.
- Length (LEN, 7 or 15 bits): This is the length of the multiplexed packet in bytes not including the length field. If the length of the multiplexed packet is less than 128 bytes (less than or equal to 127 bytes), LXT is set to 0 and the 7 bits of the length field represent the length of the multiplexed packet. If the length of the multiplexed packet is greater than 127 bytes, LXT is set to 1 and the 15 bits of the length field are the length of the multiplexed packet. The maximum length of a multiplexed packet is 32,768 bytes.


Packets larger than 32,768 bytes will need to be sent in their native form. However, this will have to be reduced to 16,383 bytes taking into account that the maximum size of the First header is 14 bits. A Simplemux ingress is not required to multiplex all packets smaller than 32,768 bytes. It may choose to only multiplex packets smaller than a configurable size into a Simplemux multiplexed packet.

- **Protocol (8 bits)** is the Protocol field of the multiplexed packet, according to IANA "Assigned Internet Protocol Numbers". It is only included when the SPB of the First Multiplexing header is 0.

Multiplexing policies

Four different conditions can be used and combined for triggering the sending of a multiplexed packet (in the figures, the triggering moment is expressed by red lines):

- number of packets: a number of packets have arrived to the multiplexer.




- size: two different options apply:
 - the size of the multiplexed packet has exceeded the size threshold specified by the user, but not the MTU. In this case, a packet is sent and a new period is started with the buffer empty.
 - the size of the multiplexed packet has exceeded the MTU (and the size threshold consequently). In this case, a packet is sent without the last one. A new period is started, and the last arrived packet is stored for the next period.

If you want to specify an MTU different from the one of the local interface, you can use the '-m' option. You may use other tools for getting the MTU of a network path. For example with the command³:


you will obtain the MTU of the path to 192.168.137.3

³ http://packetlife.net/blog/2008/aug/18/path-mtu-discovery/

- timeout: a packet arrives, and a timeout since the last sending has expired.



- **period**: an active waiting is performed, and a multiplexed packet including all the packets arrived during a period is sent.



More than one condition can be set at the same time. Please note that if (timeout > period), then the timeout has no effect. Note that **only period policy guarantees an upper bound for the multiplexing delay.**

Simplemux is symmetric, i.e. both machines may act as ingress and egress simultaneously. However, different policies can be established at each of the optimizers, e.g. in one side you can send a multiplexed packet every two native ones, and in the other side you can set a timeout.

What will you find in this package

You will find two different source files:

```
simplemux.c The complete version of Simplemux
simplemux_multiplexing_delay.pl A perl script for reading the traces
simplemux_throughput_pps.pl A perl script for reading the traces
driveGnuPlotStreams.pl A perl script for creating real-time graphs
```

Required tools

ROHC (not required for simplemux-no-compress.c)

First, you have to install rohc 1.7.0 from https://rohc-lib.org/. Download and uncompress the ROHC package.

```
cd rohc-1.7.0
./configure --prefix=/usr
make all
make check
make install
```

Compiling simplemux

```
gcc -o simplemux -g -Wall $(pkg-config rohc --cflags) simplemux_vX.Y.c $(pkg-config rohc --libs )
```

Usage of simplemux

```
./simplemux -i <ifacename> -e <ifacename> -c <peerIP> -M <N or T> [-p <port>]
[-d <debug level>] [-r <ROHC option>] [-n <num mux tun>] [-m <MTU>] [-b
<num_bytes_threshold>] [-t <timeout (microsec)>] [-P <period (microsec)>] [-1
<log file name>] [-L]
./simplemux -h
-i <ifacename>: Name of tun interface to use for capturing native packets
(mandatory)
-e <ifacename>: Name of local interface which IP will be used for reception
of muxed packets, i.e., the tunnel local end (mandatory)
-c <peerIP>: specify peer destination IP address, i.e. the tunnel remote end
(mandatory)
-M <mode>: Network(N) or Transport (T) mode (mandatory)
-p <port>: port to listen on, and to connect to (default 55555)
-d: outputs debug information while running. 0:no debug; 1:minimum debug;
2:medium debug; 3:maximum debug (incl. ROHC)
-r: 0:no ROHC; 1:Unidirectional; 2: Bidirectional Optimistic; 3:
Bidirectional Reliable (not available yet)
-n: number of packets received, to be sent to the network at the same time,
default 1, max 100
-m: Maximum Transmission Unit of the network path (by default the one of the
local interface is taken)
-b: size threshold (bytes) to trigger the departure of packets (default MTU-
28 in transport mode and MTU-20 in network mode)
-t: timeout (in usec) to trigger the departure of packets
-P: period (in usec) to trigger the departure of packets. If ( timeout <
period ) then the timeout has no effect
```

- -1: log file name. Use 'stdout' if you want the log data in standard output
- -L: use default log file name (day and hour Y-m-d_H.M.S)
- -h: prints this help text

Format of the Simplemux traces

Using the options $-1 \log file name or -L you can obtain a text file with traces. This is the format of these traces:$

timestamp	event	type	size	sequence number	from/to	IP	port	number of packets	triggering event(s)
%"PRIu64"	text	text	%i	%lu	text	%s	%d	%i	text
microseconds	rec	native muxed	packet size in bytes	sequence number	-	-	- port	-	
		ROHC_feedback			from	ingress IP address	(only in transport mode)		
	sent	muxed			to	egress IP address	port (only in transport mode)	number	numpacket_limit size_limit timeout period MTU
		demuxed			-	-	-	-	-
	forward	native			from	ingress IP address	port	-	-
	error	bad_separator			-	-	-	-	-
		demux_bad_length			-	-	ı	•	-
		decomp_failed			•		ı	•	-
		comp_failed			-	-	-	-	-
	drop	too_long			to	egress IP address	port	number	•
	drop	no_ROHC_mode			-	-	-	-	-

- timestamp: it is in microseconds. It is obtained with the function GetTimeStamp().
- event and type:
 - rec: a packet has been received:
 - native: a native packet has arrived to the ingress optimizer.
 - muxed: a multiplexed packet has arrived to the egress optimizer.

- ROHC_feedback: a ROHC feedback-only packet has been received from the decompressor. It only contains ROHC feedback information, so there is nothing to decompress
- sent: a packet has been sent
 - muxed: the ingress optimizer has sent a multiplexed packet.
 - demuxed: the egress optimizer has demuxed a native packet and sent it to its destination.
- forward: when a packet arrives to the egress with a port different to the one where the optimization is being deployed, it is just forwarded to the network.

- error:

- bad_separator: the Simplemux header before the packet is not well constructed.
- demux_bad_length: the length of the packet expressed in the Simplemux header is excessive (the multiplexed packet would finish after the end of the global packet).
- decomp_failed: ROHC decompression failed.
- comp_failed: ROHC compression failed.

- drop:

- no_ROHC_mode: a ROHC packet has been received, but the decompressor is not in ROHC mode.
- size: it expresses (in bytes) the size of the packet. If it is a muxed one, it is the global size of the packet (including IP header). If it is a native or demuxed one, it is the size of the original (native) packet.
- sequence number: it is a sequence number generated internally by the program. Two different sequences are generated: one for received packets and other one for sent packets.
- IP: it is the IP address of the peer Simplemux optimizer.
- port: it is the destination port of the packet.
- number of packets: it is the number of packets included in a multiplexed bundle.
- triggering event(s): it is the cause (more than one may appear) of the triggering of the multiplexed bundle:
 - numpacket_limit: the limit of the number of packets has been reached.
 - size limit: the maximum size has been reached.
 - timeout: a packet has arrived once the timeout had expired.
 - period: the period has expired.
 - MTU: the MTU has been reached.

Trace examples

In the ingress optimizer you may obtain:

```
63 1505
65 1506
1417693720928101
                          native
                   rec
1417693720931540
                          native
                   rec
                  rec native 52 1507
1417693720931643
1417693720936101 rec native 48 1508
1417693720936210 rec native 53 1509
1417693720936286 rec native 67 1510
                  rec
                   rec native 57 1511 sent muxed 237 1511 to
1417693720937162
1417693720938081
                                                       192.168.137.4 55555 7 period
```

This means that 7 native packets (length 63, 65, ... 57, and sequence numbers 1505 to 1511) have been received, and finally the period has expired, so they have been sent together to the egress Simplemux optimizer at 192.168.137.4, port 55555.

In the egress optimizer you may obtain:

```
    1417693720922848
    rec
    muxed
    237
    210
    from
    192.168.0.5
    55555

    1417693720922983
    sent
    demuxed
    63
    210

    1417693720923108
    sent
    demuxed
    65
    210

    1417693720923186
    sent
    demuxed
    52
    210

    1417693720923254
    sent
    demuxed
    48
    210

    1417693720923330
    sent
    demuxed
    53
    210

    1417693720923425
    sent
    demuxed
    67
    210

    1417693720923545
    sent
    demuxed
    57
    210
```

This means that a multiplexed packet (sequence number 210) has been received from the ingress optimizer 192.168.0.5 with port 55555, and it has been demuxed, resulting into 7 different packets of lengths 63, 65, ... 57.

Scripts for calculating some statistics

This package includes the next Perl scripts:

Calculate throughput and packets per second

```
simplemux throughput pps.pl
```

It is able to calculate the throughput and the packet-per-second rate, from a Simplemux output trace. The result is in three columns:

```
tick_end_time(us) throughput(bps)
                                     packets_per_second
1000000
                  488144
                                     763
2000000
                  4905047
                                     59
3000000
                  475576
                                     749
4000000
                  483672
                                     760
5000000
                  481784
                                     758
                                     762
6000000
                  487112
7000000
                                     760
                 486824
                 488792
8000000
                                     765
9000000
                  483528
                                     761
10000000
                  486360
                                     760
```

Usage:

```
$perl simplemux_throughput_pps.pl <trace file> <tick(us)> <event> <type>
<peer IP> <port>
```

Examples:

```
# $ perl simplemux_throughput_pps.pl tracefile.txt 1000000 rec native all all
# $ perl simplemux throughput pps.pl log simplemux 1000000 rec muxed all all
```

```
# $ perl simplemux_throughput_pps.pl log_simplemux 1000000 rec muxed
192.168.0.5 55555
# $ perl simplemux_throughput_pps.pl log_simplemux 1000000 sent demuxed
```

Calculate the multiplexing delay of each packet

Multiplexing delay is the time each packet is stopped in the multiplexer, i.e. the interval between its arrival as native packet and its departure inside a multiplexed packet.

```
simplemux_multiplexing_delay.pl
```

It is able to calculate the multiplexing delay of each packet, from a Simplemux output trace. The result is an output file in two columns:

```
packet id
             multiplexing delay(us)
      5279
1
2
      1693
3
      1202
4
      507
5
      10036
6
      8471
7
      6974
8
      5588
9
      1143
10
      10435
11
      8935
12
      7522
13
      5981
14
      4520
15
      3011
```

And other results are shown in stdout:

```
total native packets: 6661
Average multiplexing delay: 5222.47680528449 us
stdev of the multiplexing delay: 3425.575192789 us

Usage:
$ perl simplemux_multiplexing_delay.pl <trace file> <output file>
```

Scripts for drawing the instantaneous throughput and pps

You can make Simplemux generate real-time graphs of the throughput and the amount of packets per second. For that aim, you have to use pipes in order to combine two perl scripts.

You will need to install the gnuplot-x11 Linux package.

- Send the log of simplemux to stdout, using -1 stdout option.
- Use the script simplemux_throughput_pps_live.pl to generate a summary every e.g. 10 ms of packets coming from (or going to) 192.168.0.5 using port 55555.

The output is something like this:

```
0:492800
1:532000
2:700
```

3:700 0:492800 1:532000 2:700 3:700

Where each row represents a value of

- 0: native throughput
- 1: multiplexed throughput
- 2: native pps
- 3: multiplexed pps
- Use the script driveGnuPlotStreams.pl, by Andreas Bernauer⁴ to represent different graphs.

Some examples:

The next command presents two windows, each one with two graphs of 300 samples width, titled "native", "muxed", "ppsnat" and "ppsmux"

```
$ ./simplemux-i tun0 -e eth0 -c 192.168.0.5 -M T -d 0 -r 2 -l stdout |
perl simplemux_throughput_pps_live.pl 10000 192.168.0.5 55555 |
perl ./driveGnuPlotStreams.pl 4 2 300 300 0 10000000 0 200 500x300+0+0
500x300+0+0 'native' 'muxed' 'ppsnat' 'ppsmux' 0 0 1 1
```

The next command presents one window with two graphs of 300 samples width, titled "native" and "muxed"


./simplemux_1.6.21 -i tun0 -e eth0 -c 192.168.0.5 -M T -d 0 -r 2 -l stdout | perl simplemux_throughput_pps_live.pl 10000 192.168.0.5 | perl ./driveGnuPlotStreams.pl 2 1 300 0 1000000 500x300+0+0 'native' 'muxed' 0 0

⁴ http://www.lysium.de/blog/index.php?/archives/234-Plotting-data-with-gnuplot-in-real-time.html

Usage example with three machines

This is the setup:

Machine 6 is the source. Machine 5 and Machine 4 are the two optimizers. Server x.y.z.t is the destination.



Create a tun interface in machine 4

```
ip tuntap add dev tun0 mode tun user root<sup>5</sup> (openvpn --mktun --dev tun0 --user root will also work<sup>6</sup>).
```

ip link set tun0 up (or ifconfig tun0 up for e.g. OpenWRT)

If you want to add an IP address to the tun0 interface, use:

```
ip addr add 192.168.100.4/24 dev tun0
```

If you do not need an IP address, you can omit the previous command.

Create a tun interface in machine 5

```
ip tuntap add dev tun0 mode tun user root
(openvpn --mktun --dev tun0 --user root will also work)
ip link set tun0 up
ip addr add 192.168.100.5/24 dev tun0
```

Establish the simplemux tunnel between machine 4 and machine 5

In machine4:

```
# ./simplemux -i tun0 -e eth0 -M N-c 192.168.0.5
```

In machine5:

```
# ./simplemux -i tun0 -e eth0 -M N -c 192.168.137.4
```

Now you can ping from machine 5 or machine 6 to machine 4:

```
$ ping 192.168.100.4
```

⁵ For removing the interface use ip tuntap del dev tun0 mode tun

⁶ Openvpn is used to create and destroy tun/tap devices. In Debian you can install it this way: #apt-get install openvpn

In OpenWRT you will not be able to run ip tuntap, so you should install openvpn with: #opkg install openvpn-nossl. (do opkg update before)

The ping arrives to the tune interface of machine 5, goes to machine 4 through the tunnel and is returned to machine 6 through the tunnel.

How to steer traffic from Machine 6 to server x.y.z.t through the tunnel

The idea of **simplemux** is that it does not run on endpoints, but on some "optimizing" machines in the network. So you have to define policies to steer the flows of interest, in order to make them go through the TUN interface of the ingress (machine 5). This can be done with iprules and iptables.

Following with the example:

In Machine 5, add a rule that makes the kernel route packets marked with "2" through table 3:

```
# ip rule add fwmark 2 table 3
```

In Machine 5, add a new route for table 3:

```
# ip route add default dev tun0 table 3 ^{7} # ip route flush cache
```

If you show the routes of table 3

```
# ip route show table 3
```

Then you should obtain this:

```
default via 192.168.100.5 dev tun0
```

And now you can use iptables in order to mark certain packets as "2" if they have a certain destination IP, or a port number.

Examples:

```
All packets with destination IP address x.y.z.t

iptables -t mangle -A PREROUTING -p udp -d x.y.z.t -j MARK --set-mark 2

All packets with destination UDP port 8999

iptables -t mangle -A PREROUTING -p udp --dport 8999 -j MARK --set-mark 2

All packets with destination TCP port 44172

iptables -t mangle -A PREROUTING -p tcp --dport 44172 -j MARK --set-mark 2

Remove the table rule

iptables -t mangle -D PREROUTING -p tcp --dport 44172 -j MARK --set-mark 2

Show the table

iptables -t mangle -L
```

⁷ If you have set an IP address in the tun0 interface, this command should also work:

[#] ip route add default via 192.168.100.5 table 3

Other examples implementing different policies

```
Set a period of 50 ms
```

./simplemux -i tun0 -e eth0 -M N -c 192.168.0.5 -P 50000

Send a multiplexed packet every 2 packets, use ROHC Bidirectional Optimistic

./simplemux -i tun0 -e eth0 -M N -c 192.168.0.5-n 2 -r 2

Send a multiplexed packet if the size of the multiplexed bundle is 400 bytes

./simplemux -i tun0 -e eth0 -M N -c 192.168.0.5 -b 400

Send a timeout of 50ms, and a period of 100 ms (to set an upper bound on the added delay), use ROHC Unidirectional

./simplemux -i tun0 -e eth0 -M N -c 192.168.0.5 -t 50000 -P 100000 -r 1

Credits

The author of **simplemux** is Jose Saldana (jsaldana at unizar.es). **Simplemux** has been written for research purposes, so if you find it useful, I would appreciate that you send a message sharing your experiences, and your improvement suggestions.

The software is released under the **GNU General Public License**, Version 3, 29 June 2007.

Thanks to Didier Barvaux for his ROHC implementation.

Thanks to Davide Brini for his simpletun program.

If you have some improvement suggestions, do not hesitate to contact me.

http://diec.unizar.es/~jsaldana/