Data Transfer, Addressing and Arithmetic

Computer Organization and Assembly Languages Yung-Yu Chuang 2005/10/20

with slides by Kip Irvine

Data transfer instructions

- Operand Types
- Instruction Operand Notation
- Direct Memory Operands
- MOV Instruction
- Zero & Sign Extension
- XCHG Instruction
- Direct-Offset Instructions

Chapter overview



- Data Transfer Instructions
- Addition and Subtraction
- Data-Related Operators and Directives
- Indirect Addressing
- JMP and LOOP Instructions

Operand types



- Three basic types of operands:
 - Immediate a constant integer (8, 16, or 32 bits)
 - value is encoded within the instruction
 - Register the name of a register
 - register name is converted to a number and encoded within the instruction
 - Memory reference to a location in memory
 - memory address is encoded within the instruction, or a register holds the address of a memory location

Instruction operand notation



Operand	Description	
r8	8-bit general-purpose register: AH, AL, BH, BL, CH, CL, DH, DL	
r16	16-bit general-purpose register: AX, BX, CX, DX, SI, DI, SP, BP	
r32	32-bit general-purpose register: EAX, EBX, ECX, EDX, ESI, EDI, ESP, EBP	
reg	any general-purpose register	
sreg	16-bit segment register: CS, DS, SS, ES, FS, GS	
imm	8-, 16-, or 32-bit immediate value	
imm8	8-bit immediate byte value	
imm16	16-bit immediate word value	
imm32	32-bit immediate doubleword value	
r/m8	8-bit operand which can be an 8-bit general register or memory byte	
r/m16	r/m16 16-bit operand which can be a 16-bit general register or memory word	
r/m32	32-bit operand which can be a 32-bit general register or memory doubleword	
mem	an 8-, 16-, or 32-bit memory operand	

Direct memory operands



- A direct memory operand is a named reference to storage in memory
- The named reference (label) is automatically dereferenced by the assembler

```
.data
var1 BYTE 10h,
.code
mov al,var1 ; AL = 10h
mov al,[var1] ; AL = 10h
alternate format
```

MOV instruction



- Move from source to destination. Syntax:
 Mov destination, source
- Source and destination have the same size
- No more than one memory operand permitted
- CS, EIP, and IP cannot be the destination
- No immediate to segment moves

```
.data
count BYTE 100
wVal WORD 2
.code
mov bl,count
mov ax,wVal
mov count,al

mov al,wVal
mov ax,count
mov ax,count
mov eax,count
; error
```

Your turn . . .



Explain why each of the following **mov** statements are invalid:

```
.data
bVal BYTE
            100
bVal2 BYTE
wVal WORD
dVal DWORD
.code
   mov ds,45
                           ; a.
   mov esi,wVal
   mov eip,dVal
                           ; c.
   mov 25,bVal
                           ; d.
   mov bVal2,bVal
                           ; e.
```

Memory to memory



.data

var1 WORD ?

var2 WORD ?

.code

mov ax, var1

mov var2, ax

Copy smaller to larger



.data

count WORD 1

.code

mov ecx, 0

mov cx, count

.data

signedVal SWORD -16; FFF0h

.code


mov ecx, 0 ; mov ecx, 0FFFFFFFh

mov cx, signedVal

Zero extension



When you copy a smaller value into a larger destination, the MOVZX instruction fills (extends) the upper half of the destination with zeros.




```
mov bl,10001111b
movzx ax,bl ; zero-extension
```

The destination must be a register.

Sign extension



The **MOVSX** instruction fills the upper half of the destination with a copy of the source operand's sign bit.



```
mov bl,10001111b
movsx ax,bl ; sign extension
```

The destination must be a register.

MOVZX MOVSX



From a smaller location to a larger one

mov bx, 0A69Bh

movzx eax, bx ; EAX=0000A69Bh

movzx edx, bl ; EDX=000009Bh

movzx cx, bl ; EAX=009Bh

mov bx, 0A69Bh

movsx eax, bx ; EAX=FFFFA69Bh

movsx edx, bl ; EDX=FFFFFF9Bh

movsx cx, bl ; EAX=FF9Bh

LAHF SAHF



.data

saveflags BYTE ?

.code

lahf

mov saveflags, ah

. . .

mov ah, saveflags

sahf

XCHG Instruction



XCHG exchanges the values of two operands. At least one operand must be a register. No immediate operands are permitted.

Direct-offset operands



A constant offset is added to a data label to produce an effective address (EA). The address is dereferenced to get the value inside its memory location. (no range checking)

```
.data
arrayB BYTE 10h,20h,30h,40h
.code
mov al,arrayB+1 ; AL = 20h
mov al,[arrayB+1] ; alternative notation
```

Q: Why doesn't arrayB+1 produce 11h?

Direct-offset operands (cont)



A constant offset is added to a data label to produce an effective address (EA). The address is dereferenced to get the value inside its memory location.

```
.data
arrayW WORD 1000h,2000h,3000h
arrayD DWORD 1,2,3,4
.code
mov ax,[arrayW+2] ; AX = 2000h
mov ax,[arrayW+4] ; AX = 3000h
mov eax,[arrayD+4] ; EAX = 00000002h
```

```
; Will the following statements assemble and run?
mov ax,[arrayW-2] ; ??
mov eax,[arrayD+16] ; ??
```

Evaluate this . . .



• We want to write a program that adds the following three bytes:

```
.data
myBytes BYTE 80h,66h,0A5h
```

What is your evaluation of the following code?

```
mov al,myBytes
add al,[myBytes+1]
add al,[myBytes+2]
```

What is your evaluation of the following code?

```
mov ax,myBytes
add ax,[myBytes+1]
add ax,[myBytes+2]
```

• Any other possibilities?

Your turn. . .



Write a program that rearranges the values of three doubleword values in the following array as: 3, 1, 2.

```
.data
arrayD DWORD 1,2,3
```

 Step1: copy the first value into EAX and exchange it with the value in the second position.

```
mov eax,arrayD
xchg eax,[arrayD+4]
```

• Step 2: Exchange EAX with the third array value and copy the value in EAX to the first array position.

```
xchg eax,[arrayD+8]
mov arrayD,eax
```

Evaluate this . . . (cont)



```
.data
myBytes BYTE 80h,66h,0A5h
```

How about the following code. Is anything missing?

```
movzx ax,myBytes
mov bl,[myBytes+1]
add ax,bx
mov bl,[myBytes+2]
add ax,bx ; AX = sum
```

Yes: Move zero to BX before the MOVZX instruction.

Addition and Subtraction



- INC and DEC Instructions
- ADD and SUB Instructions
- NEG Instruction
- Implementing Arithmetic Expressions
- Flags Affected by Arithmetic
 - Zero
 - Sign
 - Carry
 - Overflow

INC and DEC Instructions



- Add 1, subtract 1 from destination operand
 - operand may be register or memory
- INC destination
 - Logic: destination ← destination + 1
- DEC destination
 - Logic: *destination* ← *destination* − 1

INC and **DEC** Examples



```
.data
myWord WORD 1000h
myDword DWORD 1000000h
.code
   inc myWord
                           ; 1001h
   dec myWord
                           ; 1000h
   inc myDword
                           ; 1000001h
   mov ax,00FFh
   inc ax
                           ; AX = 0100h
   mov ax,00FFh
   inc al
                           ; AX = 0000h
```

Your turn...



Show the value of the destination operand after each of the following instructions executes:

ADD and SUB Instructions



- ADD destination, source
 - Logic: destination ← destination + source
- SUB destination, source
 - Logic: destination ← destination source
- Same operand rules as for the MOV instruction

ADD and SUB Examples



```
.data
var1 DWORD 10000h
var2 DWORD 20000h
.code ; ---EAX---
mov eax,var1 ; 00010000h
add eax,var2 ; 00030000h
add ax,0FFFFh
add eax,1 ; 00040000h
sub ax,1 ; 0004FFFFh
```

NEG (negate) Instruction



Reverses the sign of an operand. Operand can be a register or memory operand.

Suppose AX contains –32,768 and we apply NEG to it. Will the result be valid?

Implementing Arithmetic Expressions



HLL compilers translate mathematical expressions into assembly language. You can do it also. For example:

```
Rval = -Xval + (Yval - Zval)
```

```
Rval DWORD ?

Xval DWORD 26

Yval DWORD 30

Zval DWORD 40

.code

mov eax, Xval

neg eax

mov ebx, Yval

sub ebx, Zval

add eax, ebx

mov Rval, eax

; -36
```

Your turn...



Translate the following expression into assembly language. Do not permit Xval, Yval, or Zval to be modified:

Assume that all values are signed doublewords.

```
mov ebx, Yval
neg ebx
add ebx, Zval
mov eax, Xval
sub ebx
mov Rval, eax
```


Flags Affected by Arithmetic



- The ALU has a number of status flags that reflect the outcome of arithmetic (and bitwise) operations
 - based on the contents of the destination operand
- Essential flags:
 - Zero flag destination equals zero
 - Sign flag destination is negative
 - Carry flag unsigned value out of range
 - Overflow flag signed value out of range
- The MOV instruction never affects the flags.

Concept Map





You can use diagrams such as these to express the relationships between assembly language concepts.

Zero Flag (ZF)



Whenever the destination operand equals Zero, the Zero flag is set.

```
mov cx,1

sub cx,1 ; CX = 0, ZF = 1

mov ax,0FFFFh

inc ax ; AX = 0, ZF = 1

inc ax ; AX = 1, ZF = 0
```

A flag is set when it equals 1.

A flag is clear when it equals 0.

Sign Flag (SF)



The Sign flag is set when the destination operand is negative. The flag is clear when the destination is positive.

```
mov cx,0
sub cx,1
add cx,2; CX = -1, SF = 1
; CX = 1, SF = 0
```

The sign flag is a copy of the destination's highest bit:

```
mov al,0

sub al,1 ; AL = 111111111b, SF = 1

add al,2 ; AL = 00000001b, SF = 0
```

Your turn . . .



For each of the following marked entries, show the values of the destination operand and the Sign, Zero, and Carry flags:

```
mov ax,00FFh
add ax,1
                     ; AX=0100h SF=0 ZF=0 CF=0
sub ax,1
                     ; AX=00FFh SF=0 ZF=0 CF=0
add al,1
                     ; AL=00h
                                 SF= 0 ZF= 1 CF= 1
mov bh,6Ch
add bh,95h
                     ; BH=01h
                                 SF= 0 ZF= 0 CF= 1
mov al,2
sub al,3
                                 SF=1 ZF=0 CF=1
                     ; AL=FFh
```

Carry Flag (CF)



The Carry flag is set when the result of an operation generates an unsigned value that is out of range (too big or too small for the destination operand).

```
mov al,0FFh
add al,1 ; CF = 1, AL = 00
; Try to go below zero:

mov al,0
sub al,1 ; CF = 1, AL = FF
```

In the second example, we tried to generate a negative value. Unsigned values cannot be negative, so the Carry flag signaled an error condition.

Overflow Flag (OF)



The Overflow flag is set when the signed result of an operation is invalid or out of range.

The two examples are identical at the binary level because 7Fh equals +127. To determine the value of the destination operand, it is often easier to calculate in hexadecimal.

A Rule of Thumb



- When adding two integers, remember that the Overflow flag is only set when . . .
 - Two positive operands are added and their sum is negative
 - Two negative operands are added and their sum is positive

```
What will be the values of the Overflow flag?
   mov al,80h
   add al,92h
                           ; OF =
   mov al,-2
   add al,+127
                           ; OF =
```

Data-Related Operators and Directives



- OFFSET Operator
- PTR Operator
- TYPE Operator
- LENGTHOF Operator
- SIZEOF Operator
- LABEL Directive

Your turn . . .




What will be the values of the Carry and Overflow flags after each operation?

```
mov al,-128
neg al
                               OF = 1
mov ax,8000h
add ax,2
mov ax,0
sub ax,2
mov al,-5
sub al,+125
```

OFFSET Operator



- OFFSET returns the distance in bytes, of a label from the beginning of its enclosing segment
 - Protected mode: 32 bits
 - Real mode: 16 bits



The Protected-mode programs we write only have a single segment (we use the flat memory model).

OFFSET Examples



Let's assume that the data segment begins at 00404000h:

```
.data
bVal BYTE ?
wVal WORD ?
dVal DWORD ?
dVal2 DWORD ?

.code
mov esi,OFFSET bVal ; ESI = 00404000
mov esi,OFFSET wVal ; ESI = 00404001
mov esi,OFFSET dVal ; ESI = 00404003
mov esi,OFFSET dVal ; ESI = 00404007
```

Relating to C/C++



The value returned by OFFSET is a pointer. Compare the following code written for both C++ and assembly language:

```
; C++ version:
char array[1000];
char * p = &array;
```

```
.data
array BYTE 1000 DUP(?)
.code
mov esi,OFFSET myArray ; ESI is p
```

PTR Operator



Overrides the default type of a label (variable). Provides the flexibility to access part of a variable.


```
.data
myDouble DWORD 12345678h
.code
mov ax,myDouble ; error - why?
mov ax,WORD PTR myDouble ; loads 5678h
mov WORD PTR myDouble,4321h ; saves 4321h
```

To understand how this works, we need to know about little endian ordering of data in memory.

Little Endian Order



- Little endian order refers to the way Intel stores integers in memory.
- Multi-byte integers are stored in reverse order, with the least significant byte stored at the lowest address
- For example, the doubleword 12345678h would



When integers are loaded from memory into registers, the bytes are automatically re-reversed into their correct positions.

PTR Operator Examples



```
.data
myDouble DWORD 12345678h
```

word	byte	offset	
5678	78	0000	myDouble
	56	0001	myDouble + 1
1234	34	0002	myDouble + 2
	12	0003	myDouble + 3
	5678	5678 78 56 1234 34	5678 78 0000 56 0001 1234 34 0002

```
mov al,BYTE PTR myDouble ; AL = 78h mov al,BYTE PTR [myDouble+1] ; AL = 56h mov al,BYTE PTR [myDouble+2] ; AL = 34h mov ax,WORD PTR [myDouble] ; AX = 5678h mov ax,WORD PTR [myDouble+2] ; AX = 1234h
```

Your turn . . .

Write down the value of each destination operand:

```
.data
varB BYTE 65h,31h,02h,05h
varW WORD 6543h,1202h
varD DWORD 12345678h

.code
mov ax,WORD PTR [varB+2] ; a. 0502h
mov bl,BYTE PTR varD ; b. 78h
mov bl,BYTE PTR [varW+2] ; c. 02h
mov ax,WORD PTR [varD+2] ; d. 1234h
mov eax,DWORD PTR varW ; e. 12026543h
```

PTR Operator (cont)



PTR can also be used to combine elements of a smaller data type and move them into a larger operand. The CPU will automatically reverse the bytes.

```
.data
myBytes BYTE 12h,34h,56h,78h

.code
mov ax,WORD PTR [myBytes] ; AX = 3412h
mov ax,WORD PTR [myBytes+2] ; AX = 5634h
mov eax,DWORD PTR myBytes ; EAX = 78563412h
```

TYPE Operator



The TYPE operator returns the size, in bytes, of a single element of a data declaration.

```
.data
var1 BYTE ?
var2 WORD ?
var3 DWORD ?
var4 QWORD ?

.code
mov eax,TYPE var1 ; 1
mov eax,TYPE var2 ; 2
mov eax,TYPE var3 ; 4
mov eax,TYPE var4 ; 8
```

LENGTHOF Operator



The LENGTHOF operator counts the number of elements in a single data declaration.

.data	LENGTHOF
byte1 BYTE 10,20,30	; 3
array1 WORD 30 DUP(?),0,0	; 32
array2 WORD 5 DUP(3 DUP(?))	; 15
array3 DWORD 1,2,3,4	; 4
digitStr BYTE "12345678",0	; 9
.code	
mov ecx,LENGTHOF array1	; 32

SIZEOF Operator



The SIZEOF operator returns a value that is equivalent to multiplying LENGTHOF by TYPE.

.data	SIZEOF			
byte1 BYTE 10,20,30	; 3			
array1 WORD 30 DUP(?),0,0	; 64			
array2 WORD 5 DUP(3 DUP(?))	; 30			
array3 DWORD 1,2,3,4	; 16			
digitStr BYTE "12345678",0	; 9			
.code				
mov ecx,SIZEOF array1	; 64			

Spanning Multiple Lines (1 of 2)



A data declaration spans multiple lines if each line (except the last) ends with a comma. The LENGTHOF and SIZEOF operators include all lines belonging to the declaration:

```
.data
array WORD 10,20,
30,40,
50,60

.code
mov eax,LENGTHOF array ; 6
mov ebx,SIZEOF array ; 12
```

Spanning Multiple Lines (2 of 2)



In the following example, array identifies only the first WORD declaration. Compare the values returned by LENGTHOF and SIZEOF here to those in the previous slide:

```
.data
array WORD 10,20
WORD 30,40
WORD 50,60

.code
mov eax,LENGTHOF array ; 2
mov ebx,SIZEOF array ; 4
```

LABEL Directive



- Assigns an alternate label name and type to an existing storage location
- LABEL does not allocate any storage of its own
- Removes the need for the PTR operator

```
.data
dwList LABEL DWORD
wordList LABEL WORD
intList BYTE 00h,10h,00h,20h
.code
mov eax,dwList ; 20001000h
mov cx,wordList ; 1000h
mov dl,intList ; 00h
```

Indirect Operands (1 of 2)



An indirect operand holds the address of a variable, usually an array or string. It can be dereferenced (just like a pointer).

```
.data
val1 BYTE 10h,20h,30h
.code
mov esi,OFFSET val1
mov al,[esi] ; dereference ESI (AL = 10h)

inc esi
mov al,[esi] ; AL = 20h

inc esi
mov al,[esi] ; AL = 30h
```

Indirect Addressing



- Indirect Operands
- Array Sum Example
- Indexed Operands
- Pointers

Indirect Operands (2 of 2)



Use PTR when the size of a memory operand is ambiguous.

```
.data
myCount WORD 0

.code
mov esi,OFFSET myCount
inc [esi] ; error: ambiguous
inc WORD PTR [esi] ; ok
```

Should PTR be used here?

add [esi],20

Array Sum Example



Indirect operands are ideal for traversing an array. Note that the register in brackets must be incremented by a value that matches the array type.

```
.data
arrayW WORD 1000h,2000h,3000h
.code
  mov esi,OFFSET arrayW
  mov ax,[esi]
  add esi,2 ; or: add esi,TYPE arrayW
  add ax,[esi]
  add esi,2 ; increment ESI by 2
  add ax,[esi] ; AX = sum of the array
```

ToDo: Modify this example for an array of doublewords.

Indexed Operands



An indexed operand adds a constant to a register to generate an effective address. There are two notational forms:

```
[label + reg] label[reg]

.data
arrayW WORD 1000h,2000h,3000h
.code
  mov esi,0
  mov ax,[arrayW + esi] ; AX = 1000h
  mov ax,arrayW[esi] ; alternate format
  add esi,2
  add ax,[arrayW + esi]
  etc.
```

ToDo: Modify this example for an array of doublewords.

Pointers



You can declare a pointer variable that contains the offset of another variable.

```
.data
arrayW WORD 1000h,2000h,3000h
ptrW DWORD arrayW
.code
   mov esi,ptrW
   mov ax,[esi] ; AX = 1000h
```

JMP and LOOP Instructions



- JMP Instruction
- LOOP Instruction
- LOOP Example
- Summing an Integer Array
- · Copying a String

JMP Instruction



- JMP is an unconditional jump to a label that is usually within the same procedure.
- Syntax: JMP target
- Logic: EIP ← *target*
- Example:

A jump outside the current procedure must be to a special type of label called a global label (see Section 5.5.2.3 for details).

LOOP Example



The following loop calculates the sum of the integers 5 + 4 + 3 + 2 + 1:

offset	machine code	source code
0000000	66 B8 0000	mov ax,0
00000004	в9 00000005	mov ecx,5
00000009	66 03 C1	L1: add ax,cx
000000C	E2 FB	loop L1
000000E		

When LOOP is assembled, the current location = 0000000E. Looking at the LOOP machine code, we see that –5 (FBh) is added to the current location, causing a jump to location 00000009:

$$00000009 \leftarrow 0000000E + FB$$

LOOP Instruction



- The LOOP instruction creates a counting loop
- Syntax: LOOP target
- Logic:
 - ECX ← ECX 1
 - if ECX > 0, jump to target
- Implementation:
 - The assembler calculates the distance, in bytes, between the current location and the offset of the target label. It is called the relative offset.
 - The relative offset is added to EIP.

Your turn . . .



If the relative offset is encoded in a single byte,

- (a) what is the largest possible backward jump?
- (b) what is the largest possible forward jump?

Your turn . . .



What will be the final value of AX?

```
mov ax,6
mov ecx,4
L1:
inc ax
loop L1
```

How many times will the loop execute? 4,294,967,296

```
mov ecx,0
X2:
inc ax
loop X2
```

Summing an Integer Array



The following code calculates the sum of an array of 16-bit integers.

```
.data
intarray WORD 100h, 200h, 300h, 400h
.code
   mov edi,OFFSET intarray
                                   ; address of intarray
   mov ecx, LENGTHOF intarray
                                   ; loop counter
    mov ax,0
                                   ; zero the accumulator
L1:
    add ax,[edi]
                                   ; add an integer
   add edi, TYPE intarray
                                   ; point to next integer
   loop L1
                                   ; repeat until ECX = 0
```

Nested Loop



If you need to code a loop within a loop, you must save the outer loop counter's ECX value. In the following example, the outer loop executes 100 times, and the inner loop 20 times.

```
.data
count DWORD ?
.code
   mov ecx,100
                        ; set outer loop count
L1:
   mov count,ecx
                        ; save outer loop count
   mov ecx,20
                        ; set inner loop count
L2:.
   loop L2
                        ; repeat the inner loop
   mov ecx, count
                        ; restore outer loop count
   loop L1
                        ; repeat the outer loop
```

Your turn . . .



What changes would you make to the program on the previous slide if you were summing a doubleword array?

Copying a String



The following code copies a string from source to target.

```
.data
source BYTE "This is the source string",0
                                                  good use of
target BYTE SIZEOF source DUP(0),0
                                                  SIZEOF
.code
   mov esi,0
                                 ; index register
   mov ecx, SIZEOF source
                                 ; loop counter
L1:
   mov al,source[esi]
                                 ; get char from source
   mov target[esi],al
                                 ; store it in the target
                                 ; move to next character
   loop L1
                                 ; repeat for entire string
```

Your turn . . .



Rewrite the program shown in the previous slide, using indirect addressing rather than indexed addressing.