## Control Systems

G V V Sharma\*

1

## **CONTENTS**

## 1 Types of Damping

Abstract—This manual is an introduction to control systems based on GATE problems.Links to sample Python codes are available in the text.

Download python codes using

svn co https://github.com/gadepall/school/trunk/control/codes

## 1 Types of Damping

1.1. Match the transfer functions of the secondorder systems with the nature of the systems given below

6	
Transfer function	Systems
P: $\frac{15}{s^2 + 5s + 15}$	1:Overdamped
Q: $\frac{25}{s^2+10s+25}$	2:Criticallydamped
$R: \frac{35}{5^2+185+35}$	3:Underdamped

$$(A)P - 1, Q - 2, R - 3$$
 (1.1.1)

$$(B)P-2, Q-1, R-3$$
 (1.1.2)

$$(C)P - 3, Q - 2, R - 1$$
 (1.1.3)

$$(D)P-3, Q-1, R-2$$
 (1.1.4)

**Solution:** The standard transfer function is  $H(s) = \frac{\omega^2}{s^2 + 2\zeta\omega + \omega^2}$  where

" $\omega$ " is natural frequency and " $\zeta$ " is damping factor

then compare the given functions with this we get

1. For Transfer function  $H(s) = \frac{15}{s^2 + 5s + 15}$ ,

$$\omega^2 = 15$$
 
$$2\zeta\omega = 5$$
 then we get  $\zeta = \sqrt{\frac{5}{12}} < 1$   $ref$ 

1

2. For Transfer function  $H(s) = \frac{25}{s^2 + 10s + 25}$ 

$$\omega^2 = 25$$

$$2\zeta\omega = 10$$
then we get  $\zeta = \sqrt{\frac{5}{5}} = 1$   $ref$ 

3. For Transfer function  $H(s) = \frac{35}{s^2 + 18s + 35}$ 

$$\omega^2 = 35$$

$$2\zeta\omega = 18$$
then we get  $\zeta = \sqrt{\frac{81}{35}} > 1$  ref

The damping of a system can be described as being one of the following:

Overdamped: The system returns to equilibrium without oscillating. For this

$$\zeta > 1.$$
 (1.1.5)

<u>Critically damped</u>: The system returns to equilibrium as quickly as possible without oscillating. For this

$$\zeta = 1 \tag{1.1.6}$$

<u>Underdamped</u>: The system oscillates(at reduced frequency compared to the undamped case) with the amplitude gradually decreasing to zero. For this

$$0 < \zeta < 1 \tag{1.1.7}$$

Undamped: The system oscillates at its natural

<sup>\*</sup>The author is with the Department of Electrical Engineering, Indian Institute of Technology, Hyderabad 502285 India e-mail: gadepall@iith.ac.in. All content in this manual is released under GNU GPL. Free and open source.




Fig. 1.3: Different systems based on  $\zeta$ 

resonant frequency( $\omega 0$ ). Forthis

$$\zeta = 0 \tag{1.1.8}$$

Relation between damping and $\zeta$	
Types of Damping	$\zeta(dampingratio)$
Overdamped	ζ>1
Criticallydamped	$\zeta = 1$
Underdamped	0 < \( < 1 \)
Undamped	$\zeta = 0$

Final Analysis

- As for  $P: \zeta < 1$ It is Underdamped system
- As for Q: ζ = 1
   It is critically damped system.
- As for R: ζ>1
   It is an overdamped system.
   So,P-3,Q-2,R-1. Option (C) is correct.
- 1.2. Python code for the above damping graph:

1.3. Python code for damped output taking unit step function as input:

codes/ee18btech110012/unitstepdamping.py




Fig. 1.3: Damped output for step input