Programming Languages



Chapter 10

ImplementingSubprograms

SAMUEL GINN COLLEGE OF ENGINEERING

Chapter 10 Topics

- The General Semantics of Calls and Returns
- Implementing "Simple" Subprograms
- Implementing Subprograms with Stack-Dynamic Local Variables
- Nested Subprograms
- Blocks
- Implementing Dynamic Scoping



The General Semantics of Calls and Returns

- The subprogram call and return operations of a language are together called its subprogram linkage
- General semantics of calls to a subprogram
 - Parameter passing methods
 - Stack-dynamic allocation of local variables
 - Save the execution status of calling program
 - Transfer of control and arrange for the return
 - If subprogram nesting is supported, access to nonlocal variables must be arranged

The General Semantics of Calls and Returns

- General semantics of subprogram returns:
 - In mode and inout mode parameters must have their values returned
 - Deallocation of stack-dynamic locals
 - Restore the execution status
 - Return control to the caller



Implementing "Simple" Subprograms

- Call Semantics:
 - Save the execution status of the caller
 - Pass the parameters
 - Pass the return address to the called
 - Transfer control to the called



Implementing "Simple" Subprograms (continued)

- Return Semantics:
 - If pass-by-value-result or out mode parameters are used, move the current values of those parameters to their corresponding actual parameters
 - If it is a function, move the functional value to a place the caller can get it
 - Restore the execution status of the caller
 - Transfer control back to the caller
- Required storage:
 - Status information, parameters, return address, return value for functions, temporaries



Implementing "Simple" Subprograms (continued)

- Two separate parts: the actual code and the non-code part (local variables and data that can change)
- The format, or layout, of the non-code part of an executing subprogram is called an activation record
- An activation record instance is a concrete example of an activation record (the collection of data for a particular subprogram activation)

An Activation Record for "Simple" Subprograms


Local variables

Parameters

Return address



Code and Activation Records of a Program with "Simple" Subprograms





Implementing Subprograms with Stack-Dynamic Local Variables

- More complex activation record
 - The compiler must generate code to cause implicit allocation and deallocation of local variables
 - Recursion must be supported (adds the possibility of multiple simultaneous activations of a subprogram)




Typical Activation Record for a Language with Stack-Dynamic Local Variables

Local variables

Parameters

Dynamic link

Return address






Implementing Subprograms with Stack-Dynamic Local Variables: Activation Record

- The activation record format is static, but its size may be dynamic
- The dynamic link points to the top of an instance of the activation record of the caller
- An activation record instance is dynamically created when a subprogram is called
- Activation record instances reside on the run-time stack
- The Environment Pointer (EP) must be maintained by the run-time system. It always points at the base of the activation record instance of the currently executing program unit



An Example: C Function

```
void sub(float total, int part)
{
  int list[5];
  float sum;
  ...
}
```





Revised Semantic Call/Return Actions

Caller Actions:

- Create an activation record instance
- Save the execution status of the current program unit
- Compute and pass the parameters
- Pass the return address to the called
- Transfer control to the called

Prologue actions of the called:

- Save the old EP in the stack as the dynamic link and create the new value
- Allocate local variables



Revised Semantic Call/Return Actions (continued)

Epilogue actions of the called:

- If there are pass-by-value-result or out-mode parameters, the current values of those parameters are moved to the corresponding actual parameters
- If the subprogram is a function, its value is moved to a place accessible to the caller
- Restore the stack pointer by setting it to the value of the current
 EP-1 and set the EP to the old dynamic link
- Restore the execution status of the caller
- Transfer control back to the caller




An Example Without Recursion

```
void fun1(float r) {
   int s, t;
   fun2(s);
void fun2(int x) {
   int y;
   fun3(y);
void fun3(int q) {
void main() {
   float p;
   fun1(p);
```

```
main calls fun1 fun1 calls fun2 calls fun3
```



An Example Without Recursion



Dynamic Chain and Local Offset

- The collection of dynamic links in the stack at a given time is called the dynamic chain, or call chain
- Local variables can be accessed by their offset from the beginning of the activation record, whose address is in the EP. This offset is called the *local_offset*
- The local_offset of a local variable can be determined by the compiler at compile time



An Example With Recursion

 The activation record used in the previous example supports recursion



Activation Record for factorial

Functional value

Parameter


 \mathbf{n}

Dynamic link

Return address




Stacks for calls to factorial





Stacks for returns from factorial





Nested Subprograms

- Some non-C-based static-scoped languages (e.g., Fortran 95+, Ada, Python, JavaScript, Ruby, and Lua) use stack-dynamic local variables and allow subprograms to be nested
- All variables that can be non-locally accessed reside in some activation record instance in the stack
- The process of locating a non-local reference:
 - 1. Find the correct activation record instance
 - Determine the correct offset within that activation record instance



Locating a Non-local Reference

- Finding the offset is easy
- Finding the correct activation record instance
 - Static semantic rules guarantee that all nonlocal variables that can be referenced have been allocated in some activation record instance that is on the stack when the reference is made



Static Scoping

- A static chain is a chain of static links that connects certain activation record instances
- The static link in an activation record instance for subprogram A points to one of the activation record instances of A's static parent
- The static chain from an activation record instance connects it to all of its static ancestors
- Static_depth is an integer associated with a static scope whose value is the depth of nesting of that scope



Static Scoping (continued)

- The chain_offset or nesting_depth of a nonlocal reference is the difference between the static_depth of the reference and that of the scope when it is declared
- A reference to a variable can be represented by the pair: (chain_offset, local_offset), where local_offset is the offset in the activation record of the variable being referenced



Example Ada Program

```
procedure Main 2 is
 X : Integer;
 procedure Bigsub is
   A, B, C : Integer;
   procedure Sub1 is
     A, D : Integer;
     begin -- of Sub1
     A := B + C; <-----1
   end; -- of Sub1
   procedure Sub2(X : Integer) is
     B, E : Integer;
     procedure Sub3 is
       C, E : Integer;
       begin -- of Sub3
       Sub1:
       E := B + A: <-----2
       end; -- of Sub3
     begin -- of Sub2
     Sub3;
     A := D + E; < -----3
     end; -- of Sub2 }
   begin -- of Bigsub
   Sub2 (7);
   end; -- of Bigsub
 begin
 Biqsub;
end; of Main 2 }
                              1-27
```




Example Ada Program (continued)

Call sequence for Main_2

```
Main_2 calls Bigsub
Bigsub calls Sub2
Sub2 calls Sub3
Sub3 calls Sub1
```



Stack Contents at Position 1



Static Chain Maintenance

- At the call,
 - The activation record instance must be built
 - The dynamic link is just the old stack top pointer
 - The static link must point to the most recent ari of the static parent
 - Two methods:
 - 1. Search the dynamic chain
 - 2. Treat subprogram calls and definitions like variable references and definitions



Evaluation of Static Chains

- Problems:
 - 1. A nonlocal areference is slow if the nesting depth is large
 - 2. Time-critical code is difficult:
 - a. Costs of nonlocal references are difficult to determine
 - b. Code changes can change the nesting depth, and therefore the cost



Blocks

- Blocks are user-specified local scopes for variables
- An example in C

```
{int temp;
  temp = list [upper];
  list [upper] = list [lower];
  list [lower] = temp
}
```

- The lifetime of temp in the above example begins when control enters the block
- An advantage of using a local variable like temp is that it cannot interfere with any other variable with the same name



Implementing Blocks

- Two Methods:
 - 1. Treat blocks as parameter-less subprograms that are always called from the same location
 - Every block has an activation record; an instance is created every time the block is executed
 - 2. Since the maximum storage required for a block can be statically determined, this amount of space can be allocated after the local variables in the activation record




Implementing Dynamic Scoping

- Deep Access: non-local references are found by searching the activation record instances on the dynamic chain
 - Length of the chain cannot be statically determined
 - Every activation record instance must have variable names
- Shallow Access: put locals in a central place
 - One stack for each variable name
 - Central table with an entry for each variable NIVERSITY name

Using Shallow Access to Implement Dynamic Scoping

```
void sub3() {
  int x, z;
  x = u + v;
void sub2() {
  int w, x;
void sub1() {
  int v, w;
void main() {
  int v, u;
```



(The names in the stack cells indicate the program units of the variable declaration.)

Summary

- Subprogram linkage semantics requires many action by the implementation
- Simple subprograms have relatively basic actions
- Stack-dynamic languages are more complex
- Subprograms with stack-dynamic local variables and nested subprograms have two components
 - actual code
 - activation record



Summary (continued)

- Activation record instances contain formal parameters and local variables among other things
- Static chains are the primary method of implementing accesses to non-local variables in static-scoped languages with nested subprograms
- Access to non-local variables in dynamic-scoped languages can be implemented by use of the dynamic chain or thru some central variable table method