SnailVM Specification

June 11, 2025

Contents

1	Overview	2
2	Bytecode File Format 2.1 Header Format 2.2 Constant Pool Format 2.3 Global Variables Format 2.4 Function Table Format 2.5 Function Call and Local Variable Pool 2.5.1 Control Flow 2.6 Global Bytecode	2 2 2 3 3 3 3
3	Bytecode Generation Architecture 3.1 General Approach	3 3 4 4 4 4
4	Instruction Set 4.1 Stack and Memory Operations	4 5 6 7 7 8 8
5	Type System 5.1 Type Identifiers	8
6	Error Diagnostics	8
7	Compilation Example 7.1 Source Code	10 10 10 13
8	Compilation Process	14
9	Conclusion	14

1 Overview

SnailVM is a stack-based virtual machine designed to execute programs written in the Snail programming language, a statically-typed language supporting functions, loops, conditionals, and arrays. The virtual machine processes a compact bytecode format that represents Snail programs efficiently. This specification details the bytecode file structure, instruction set, type system, error handling, and includes examples of compilation from Snail source code to bytecode.

2 Bytecode File Format

The SnailVM bytecode file is a binary format organized into distinct sections to facilitate program execution. Each section is described below with its specific format.

2.1 Header Format

Field	Size	Description
Magic Number	4 bytes	Fixed value 0x534E4131 (ASCII:
		SNA1) to identify the file.
Version	2 bytes	Bytecode format version in big-
		endian (e.g., 0x0001 for version
		1).
Main Function Index	2 bytes	Index of the main function in the
		function table (big-endian). If
		main is absent, set to 0xFFFF (-
		1).

Table 1: Header Format

2.2 Constant Pool Format

Type ID	Type	Binary Format
0x01	i32	4-byte signed integer (big-
		endian).
0x02	usize	4-byte unsigned integer (big-
		endian).
0x03	string	2-byte length (unsigned, big-
		endian), followed by UTF-8
		bytes.

Table 2: Constant Pool Entry Format

The pool starts with a 2-byte (big-endian) number indicating the number of entries.

2.3 Global Variables Format

Field	Description
Number of Variables	2 bytes (big-endian), number of variables.
Name Length	1 byte, length of the variable name (n).
Name	n bytes, UTF-8 encoded variable name.
Type ID	1 byte, type of the variable (see Table 11).
(Array only)	If Type $ID = 0x04$ (array): 1 byte for element type
	ID, 4 bytes (big-endian) for array size.

Table 3: Global Variable Entry Format

2.4 Function Table Format

Field	Description
Number of Functions	2 bytes (big-endian), number of functions.
Name Length	1 byte, length of the function name (n).
Name	n bytes, UTF-8 encoded function name.
Number of Parameters	1 byte, count of function parameters.
Return Type	1 byte, type ID (see Table 11).
Number of Local Variables	2 bytes (big-endian), count of local variables (in-
	cluding parameters).
Bytecode Length	4 bytes (big-endian), length of the function's byte-
	code (t).
Bytecode	t bytes, the function's executable bytecode.

Table 4: Function Table Entry Format

2.5 Function Call and Local Variable Pool

When a function is called, the caller pushes all arguments onto the stack in left-to-right order. Upon entering the function, the callee pops the arguments from the stack in reverse order (last argument first), assigning them to local variable slots 0..N-1, where N is the number of parameters. The local variable pool for a function thus starts with its parameters, followed by other local variables declared in the function body. All accesses to parameters and local variables use their respective indices in this pool.

Instruction PUSH_LOCAL is used to read values from local variable pool by their index, while STORE_LOCAL is used to write values to local variable pool. Both instructions take a 2-byte index (big-endian) that points to the variable's position in the local variable pool.

2.5.1 Control Flow

Control flow statements (conditionals, loops) evaluate conditions first. For if statements, if the condition is true, the body is executed, otherwise the else branch (if present). For loops, as long as the condition is true, the body is executed repeatedly.

For logical operators && (AND) and || (OR), short-circuit evaluation is implemented. In the case of AND, if the first operand evaluates to false, the second operand is not evaluated, and false is immediately returned. For OR, if the first operand evaluates to true, the second operand is not evaluated, and true is immediately returned. This behavior is implemented using conditional jumps in the bytecode.

2.6 Global Bytecode

This section contains bytecode executed before the main function, typically for initializing global variables. It starts with a 4-byte (big-endian) length, followed by the bytecode.

3 Bytecode Generation Architecture

3.1 General Approach

Bytecode generation in SnailVM is based on object-oriented design principles. Each node of the abstract syntax tree (AST) implements the emitBytecode method, which is responsible for generating its own bytecode. The central facade, BytecodeEmitter, only assembles the final file, delegating all instruction generation logic to the nodes themselves.

Instructions that control program flow, such as JMP, JMP_IF_FALSE, and JMP_IF_TRUE, use signed 16-bit offsets measured in bytes relative to the current position after the jump instruction itself. This allows for forward and backward jumps within code sections.

3.2 Variable Pools

Global variable pool is formed from all variables declared at the top level of the program. Each variable receives a unique index in the pool, which is used for generating PUSH_GLOBAL, STORE_GLOBAL, etc.

Local variable pool is formed separately for each function. It includes:

- Function parameters (indices 0..N-1)
- All variables declared inside the function body (indices continue after parameters)

Access to local variables is performed via PUSH_LOCAL, STORE_LOCAL instructions with the corresponding index.

3.3 Bytecode Generation Context

The BytecodeContext class stores tables of constants, global variables, functions, and local variables. It provides methods for obtaining indices and adding new elements. Each AST node uses this context for correct addressing during bytecode generation.

3.4 Example: Bytecode Generation for a Number Literal

```
public class NumberLiteral extends PrimaryExpression {
   private final long value;
   // ...
   @Override
   public void emitBytecode(ByteArrayOutputStream out, BytecodeContext
        context) throws IOException {
   int constIndex = context.addConstant(value);
   out.write(BytecodeConstants.Opcode.PUSH_CONST);
   BytecodeUtils.writeU16(out, constIndex);
   }
}
```

3.5 Advantages

- Easy to extend: adding new constructs only requires implementing the emitBytecode method in the new node.
- Clean architecture: the facade contains no instruction generation logic.
- Simplified maintenance and testing.

4 Instruction Set

SnailVM employs a stack-based architecture with single-byte opcodes.

4.1 Stack and Memory Operations

Opcode	Name	Description	Arguments	Stack Effect
0x01	PUSH_CONST	Pushes a constant	2-byte index (big-endian)	$[] \rightarrow [value]$
		from the constant		
		pool.		
0x02	PUSH_LOCAL	Pushes a local vari-	2-byte index (big-endian)	$[] \rightarrow [value]$
		able's value onto the		
		stack.		
0x03	PUSH_GLOBAL	Pushes a global vari-	2-byte index (big-endian)	$[] \rightarrow [value]$
	!	able's value onto the		
		stack.		
0x04	STORE_LOCAL	Stores the top stack	2-byte index (big-endian)	$[value] \rightarrow []$
	!	value into a local vari-		
		able.		
0x05	STORE_GLOBAL	Stores the top stack	2-byte index (big-endian)	$[value] \rightarrow []$
	!	value into a global		
		variable.		
0x06	POP	Removes the top value	None	$[value] \rightarrow []$
		from the stack.		
0x07	DUP	Duplicates the top	None	$[value] \rightarrow [value, value]$
		value on the stack.		

Table 5: Stack and Memory Operations

4.2 Arithmetic and Logic Operations

Opcode	Name	Description	Arguments	Stack Effect
0x10	ADD	Adds the top two integers	None	$[a, b] \rightarrow [a+b]$
		on the stack.		
0x11	SUB	Subtracts the top integer	None	$[a, b] \rightarrow [a-b]$
		from the second-top integer.		
0x12	MUL	Multiplies the top two inte-	None	$[a, b] \rightarrow [a*b]$
		gers on the stack.		
0x13	DIV	Divides the second-top inte-	None	$[a, b] \rightarrow [a/b]$
		ger by the top integer.		
0x14	MOD	Computes the remainder of	None	$[a, b] \rightarrow [a \% b]$
		the division of the second-		
		top integer by the top inte-		
0.00	T.O.	ger.	2.7	[1] [1 1]
0x20	EQ	Checks if the top two values	None	$[a, b] \rightarrow [bool]$
0.01	NEO	are equal.	NT	[1] . [1 1]
0x21	NEQ	Checks if the top two values	None	$[a, b] \rightarrow [bool]$
0x22	LT	are not equal.	None	[. 1] . [11]
UXZZ	$\Gamma \Gamma$	Checks if the second-top in- teger is less than the top in-	None	$[a, b] \rightarrow [bool]$
		teger is less than the top in-		
0x23	LE	Checks if the second-top in-	None	$[a, b] \rightarrow [bool]$
0.3.2.5		teger is less than or equal to	None	
		the top integer.		
0x24	GT	Checks if the second-top in-	None	$[a, b] \rightarrow [bool]$
01121		teger is greater than the top	Trone	
		integer.		
0x25	GTE	Checks if the second-top	None	$[a, b] \rightarrow [bool]$
		integer is greater than or		
		equal to the top integer.		
0x26	AND	Performs a logical AND on	None	$[a, b] \rightarrow [a \&\& b]$
		the top two booleans.		
0x27	OR	Performs a logical OR on	None	$[a, b] \rightarrow [a \mid\mid b]$
		the top two booleans.		
0x28	NOT	Negates the top boolean	None	$[a] \rightarrow [!a]$
		value.		

Table 6: Arithmetic and Logic Operations

4.3 Control Flow Operations

Opcode	Name	Description	Arguments	Stack Effect
0x30	JMP	Unconditional jump	2-byte signed offset (big-endian)	$[] \to []$
		to the specified offset		
		in bytes relative to		
		the current position		
		after this instruction.		
0x31	JMP_IF_FALSE	Jump if the top value	2-byte signed offset (big-endian)	$[bool] \rightarrow []$
		is 0 (false) to the spec-		
		ified offset in bytes rel-		
		ative to the current		
		position after this in-		
		struction.		
0x35	JMP_IF_TRUE	Jump if the top value	2-byte signed offset (big-endian)	$[bool] \rightarrow []$
		is not 0 (true) to		
		the specified offset in		
		bytes relative to the		
		current position after		
		this instruction.		
0x32	CALL	Calls a function at the	2-byte function index (big-endian)	$[args] \rightarrow [ret]$
		specified index, pass-		
		ing arguments from		
		the stack.		
0x33	RET	Returns from a func-	None	$[value] \rightarrow []$
		tion with the top stack		
		value as the return		
		value.		
0x34	HALT	Stops the execution of	None	$[] \rightarrow []$
		the virtual machine.		

Table 7: Control Flow Operations

4.4 Array Operations

Opcode	Name	Description	Arguments	Stack Effect
0x40	NEW_ARRAY	Creates a new	2-byte size, 1-byte type ID	$[] \rightarrow [array]$
		array of the		
		specified size		
		and type.		
0x41	GET_ARRAY	Retrieves the	None	$[array, index] \rightarrow [value]$
		element at		
		the specified		
		index from		
		the array.		
0x42	SET_ARRAY	Sets the	None	[array, index, value] \rightarrow []
		element at		
		the specified		
		index in the		
		array.		

Table 8: Array Operations

4.5 Intrinsic Instructions

Opcode	Name	Description	Arguments	Stack Effect
0x50	INTRINSIC_CALL	Calls a built-in intrin-	2-byte index (big-endian)	$[args] \rightarrow [ret]$
		sic function identified		
		by its index in the In-		
		trinsic Table.		

Table 9: Intrinsic Instructions

4.6 Intrinsic Functions

Name	Parameters	Return Type	Description	Stack Effect
println	1 (any type convertible to string)	void (0x00)	Outputs the argument	$[value] \rightarrow []$
			to the console followed	
			by a newline and dis-	
			cards the top stack	
			value.	

Table 10: Intrinsic Functions

Note: The Intrinsic Table can be extended with more built-in functions as needed. Each intrinsic is identified by its index in the table.

5 Type System

SnailVM supports i32, usize, string, void, and array types.

5.1 Type Identifiers

Type ID	Type
0x00	void
0x01	i32 (also used for bool)
0x02	usize
0x03	string
0x04	array

Table 11: Type Identifiers

Note: The type bool is represented as i32 (0 for false, 1 for true) in the bytecode and type tables.

6 Error Diagnostics

The SnailL compiler, upon encountering an error, outputs a detailed message including:

- The relevant fragment of the source code
- A pointer line with the characterundertheerrorlocationTheerrortype
- A human-readable error description

Example: Type mismatch

Source Code let x: i32 = "abc";

```
ERROR:
let x: i32 = "abc";
TYPE_MISMATCH
_____
Type mismatch: cannot assign string to i32
_____
Example: Unknown variable
```

```
y = 5;
ERROR:
y = 5;
UNKNOWN VARIABLE
______
Unknown variable: y
_____
```

Example: Unknown operator

```
let x: i32 = 1 \% 2;
ERROR:
let x: i32 = 1 \%\% 2;
UNKNOWN OPERATOR
_____
Unknown operator: %%
```

Example: Dead code

```
fn f() {
  return 1;
  let x = 2; // dead code
```

```
ERROR:
return 1;
let x = 2;
DEAD CODE
_____
Code after return is unreachable
______
```

Note: All errors always include the source line and the error position using the *character*.

bool type

The bool type is represented as i32 (0 - false, 1 - true) in all type tables and in bytecode.

7 Compilation Example

7.1 Source Code

```
let counter: i32 = 0;
  let data: [i32; 5] = [10, 20, 30, 40, 50];
  fn computeSum(a: i32, b: i32) -> i32 {
  let sum: i32 = a + b;
  let offset: i32 = 5;
  return sum + offset;
  fn main() -> void {
  let i: i32 = 0;
  while (i < 5) {
  let value: i32 = data[i];
  if (value > 25) {
  data[i] = value * 2;
  } else {
  data[i] = value - 5;
  i = i + 1;
  let sum: i32 = computeSum(data[0], data[1]);
  if (sum >= 100) {
  counter = sum / 2;
  } else {
  counter = sum;
  let flag: i32 = 0;
  if (counter < 50 \&\& data[2] > 50) {
  flag = 1;
  println(sum); // Example usage of println
```

7.2 Bytecode Output

```
=== HEADER SECTION ===
[HEADER] Magic: SNA1
[HEADER] Version: 1
[HEADER] Main function index: 1
=== CONSTANTS SECTION ===
[CONSTANTS] Count: 11
[CONST] i32: 0
[CONST] i32: 10
```

```
[CONST] i32: 20
 [CONST] i32: 30
 [CONST] i32: 40
 [CONST] i32: 50
 [CONST] i32: 5
 [CONST] i32: 25
 [CONST] i32: 2
 [CONST] i32: 1
 [CONST] i32: 100
=== GLOBALS SECTION ===
[GLOBALS] Count: 2
 [GLOBAL] counter: i32
 [GLOBAL] data : array (elemType: i32, size: 5)
=== FUNCTIONS SECTION ===
[FUNCTIONS] Count: 2
 [FUNC] computeSum (params: 2, return: i32, locals: 4, code length: 30 bytes, offset: 0x0000006C)
    0000: STORE LOCAL 1 (параметр \#1)
    0003: STORE LOCAL 0 (параметр \#0)
    0006: PUSH LOCAL 0 (параметр \#0)
    0009: PUSH LOCAL 1 (параметр #1)
    000C: ADD
    000D: STORE_LOCAL 2 (локальная переменная \#0)
    0010: PUSH CONST 6 (i32: 5)
    0013: STORE LOCAL 3 (локальная переменная #1)
    0016: PUSH LOCAL 2 (локальная переменная \#0)
    0019: PUSH LOCAL 3 (локальная переменная \#1)
    001C: ADD
    001D: RET
 [FUNC] main [main] (params: 0, return: void, locals: 4, code length: 181 bytes, offset: 0x00000097)
    0000: PUSH CONST 0 (i32: 0)
    0003: STORE_LOCAL 0 (локальная переменная #0)
    0006: PUSH LOCAL 0 (локальная переменная #0)
    0009: PUSH CONST 6 (i32: 5)
    000C: LT
    000D: JMP IF FALSE 65 [to 0x0051]
    0010: PUSH GLOBAL 1 (data, array of i32[5])
    0013: PUSH LOCAL 0 (локальная переменная \#0)
    0016: GET ARRAY
    0017: STORE LOCAL 1 (локальная переменная #1)
    001A: PUSH LOCAL 1 (локальная переменная #1)
    001D: PUSH CONST 7 (i32: 25)
    0020: GT
    0021: JMP IF FALSE 17 [to 0x0035]
    0024: PUSH LOCAL 1 (локальная переменная #1)
    0027: PUSH CONST 8 (i32: 2)
    002A: MUL
    002B: PUSH GLOBAL 1 (data, array of i32[5])
    002E: PUSH LOCAL 0 (локальная переменная \#0)
    0031: SET ARRAY
    0032: JMP 14 [to 0x0043]
    0035: PUSH LOCAL 1 (локальная переменная #1)
```

```
0038: PUSH CONST 6 (i32: 5)
003B: SUB
003C: PUSH GLOBAL 1 (data, array of i32[5])
003F: PUSH LOCAL 0 (локальная переменная \#0)
0042: SET ARRAY
0043: PUSH LOCAL 0 (локальная переменная #0)
0046: PUSH CONST 9 (i32: 1)
0049: ADD
004A: STORE LOCAL 0 (локальная переменная #0)
004D: POP
004E: JMP -75 [to 0x0006]
0051: PUSH GLOBAL 1 (data, array of i32[5])
0054: PUSH CONST 0 (i32: 0)
0057: GET ARRAY
0058: PUSH GLOBAL 1 (data, array of i32[5])
005B: PUSH CONST 9 (i32: 1)
005E: GET ARRAY
005F: CALL 0 (computeSum, 2 параметра)
0062: STORE LOCAL 2 (локальная переменная #2)
0065: PUSH LOCAL 2 (локальная переменная #2)
0068: PUSH CONST 10 (i32: 100)
006B: GTE
006C: JMP_IF FALSE 14 [to 0x007D]
006F: PUSH LOCAL 2 (локальная переменная #2)
0072: PUSH CONST 8 (i32: 2)
0075: DIV
0076: STORE GLOBAL 0 (counter, i32)
0079: POP
007A: JMP 7 [to 0x0084]
007D: PUSH LOCAL 2 (локальная переменная \#2)
0080: STORE GLOBAL 0 (counter, i32)
0083: POP
0084: PUSH CONST 0 (i32: 0)
0087: STORE LOCAL 3 (локальная переменная #3)
008A: PUSH GLOBAL 0 (counter, i32)
008D: PUSH CONST 5 (i32: 50)
0090: LT
0091: JMP IF FALSE 12 [to 0x00A0]
0094: POP
0095: PUSH GLOBAL 1 (data, array of i32[5])
0098: PUSH CONST 8 (i32: 2)
009B: GET ARRAY
009C: PUSH CONST 5 (i32: 50)
009F: GT
00A0: JMP IF FALSE 7 [to 0x00AA]
00A3: PUSH CONST 9 (i32: 1)
00A6: STORE LOCAL 3 (локальная переменная #3)
00A9: POP
00AA: PUSH LOCAL 3 (локальная переменная #3)
00AD: INTRINSIC CALL 0
00B0: POP
00B1: PUSH CONST 0 (i32: 0)
00B4: RET
```

```
=== INTRINSICS SECTION ===
[INTRINSICS] Count: 1
 [INTRINSIC] println (params: 1, return: string)
=== GLOBAL CODE SECTION ===
[GLOBAL CODE] Length: 72
 [Найден вызов main в глобальном коде на смещении 0х0045]
 0000: PUSH CONST 0 (i32: 0)
 0003: STORE GLOBAL 0 (counter, i32)
 0006: NEW ARRAY 5 i32
 000A: STORE GLOBAL 2
 000D: PUSH GLOBAL 2
 0010: PUSH CONST 0 (i32: 0)
 0013: PUSH CONST 1 (i32: 10)
 0016: SET ARRAY
 0017: PUSH GLOBAL 2
 001A: PUSH CONST 9 (i32: 1)
 001D: PUSH CONST 2 (i32: 20)
 0020: SET ARRAY
 0021: PUSH GLOBAL 2
 0024: PUSH CONST 8 (i32: 2)
 0027: PUSH CONST 3 (i32: 30)
 002A: SET_ARRAY
 002B: PUSH GLOBAL 2
 002E: PUSH CONST 11
 0031: PUSH CONST 4 (i32: 40)
 0034: SET ARRAY
 0035: PUSH GLOBAL 2
 0038: PUSH CONST 12
 003B: PUSH CONST 5 (i32: 50)
 003E: SET ARRAY
 003F: PUSH GLOBAL 2
 0042: STORE GLOBAL 1 (data, array of i32[5])
 0045: CALL 1 (main)
=== BYTECODE STATISTICS ===
 [Общий размер] 420 байт (0x1A4)
[Секции] Заголовок: 8 байт, Константы: 2 байт (11 записей), Функции: 211 байт кода (2 функций),
Глобальный код: 199 байт
 [Глобальные переменные] 2 переменных
```

7.3 Execution Flow

- Header: Points to main (index 1).
- Constant Pool: Contains 0, 5, 10, 20, 30, 40, 50, 25, 2, 1, 100.
- Function Table: computeSum: Computes and returns a + b + 5. main: Executes loop, calls computeSum, updates counter, sets flag, and prints sum with println.
- Intrinsic Table: Contains println with 1 parameter and void return type.
- Global Variables: counter and data.

• Global Bytecode: Initializes counter and data, calls main.

8 Compilation Process

The Snail compiler parses the source code, generates an abstract syntax tree (AST), and emits bytecode based on the instruction set.

9 Conclusion

SnailVM provides an efficient and robust bytecode format for executing Snail programs.