SysAdmin Notes for RHCSA

Somenath Sinha

August 2017

Contents

I	Ins	talling RHEL Server	8
1	Usir	ng Essential Tools	9
	1.1	Man Command	9
	1.2	Understanding Globbing and Wildcards	10
	1.3	Understanding Globbing and Wildcards	10
	1.4	Understanding I/O Redirection and Pipes	11
		1.4.1 I/O Redirection	11
		1.4.2 Piping	11
	1.5	Using I/O Redireciton and Piping	11
2	Ess	ential File Management Tools	13
	2.1	Understanding Linux File System Layout	13
	2.2	Finding Files	13
	2.3	Understanding Links	14
	2.4	Working with Links	14
	2.5	Working with tar	15
3	Wor	king with Text Files	17
	3.1	Understanding Regular Expressions	17
	3.2	Using common text tools	17
		3.2.1 cat	17
		3.2.2 less	17
		3.2.3 Head and Tail	18
		3.2.4 cut	18
		3.2.5 sort	18
		3.2.6 tr	19

	3.3	grep	19
		3.3.1 wc	20
		3.3.2 grep -l	20
		3.3.3 grep -i	20
		3.3.4 grep -R	21
		3.3.5 grep -v	21
	3.4	sed and awk basics	21
		3.4.1 sed	21
		3.4.2 awk	22
4	Con	necting to a RHEL Server	24
	4.1	Connecting to a Server with SSH	24
	4.2	RSA Key fingerprint and known hosts	24
	4.3	sshd_config	24
	4.4	Understanding SSH keys	25
		4.4.1 Client authentication without password	25
	4.5	Using SSH Keys	26
		4.5.1 Copying SSH keys	26
		4.5.2 Copying files to a server securely using SSH	27
5	Man	aging Users and Groups	28
	5.1	Understanding the need for Users	28
	5.2	User Properties	28
		5.2.1 Username	28
		5.2.2 UID	29
		5.2.3 GID	29
		5.2.4 GECOS or comment field	29
		5.2.5 Home Directory	29
		5.2.6 Default Shell	29
	5.3	Creating and Managing Users	29
		5.3.1 Adding users	29
	5.4	Understanding Group Membership	30
	5.5	Creating and Managing Groups	30

		5.5.1	groupadd	30
		5.5.2	Adding users to a group	30
	5.6	User a	and Group configuration files	31
	5.7	Manag	ging Password properties	31
		5.7.1	passwd	31
		5.7.2	chage	32
6	Con	necting	g to a LDAP Server	33
	6.1	Under	standing LDAP	33
		6.1.1	/bin/login	33
		6.1.2	$Idd \ \ldots \ldots$	33
		6.1.3	PAM config file syntax	34
	6.2	Telling	your server where to find the LDAP Server	35
		6.2.1	nscd	35
		6.2.2	nss-pam-ldapd	35
		6.2.3	pam_ldap	35
		6.2.4	authconfig-gtk	36
		6.2.5	Switching to an LDAP user	36
	6.3	Under	standing Automount	36
		6.3.1	Server selection for auto-mounting	37
		6.3.2	Samba server's CIFS protocol to automount	37
	6.4	Config	juring Automount	38
		6.4.1	NFS Server Automounting	39
	6.5	Config	juring NFS and Automount	39
		6.5.1	yum search	39
		6.5.2	Creating an NFS Server	39
		6.5.3	Starting the NFS server	40
		6.5.4	Automounting NFS	40
	6.6	Modify	ring nslcd Configuration	41
		6.6.1	Naming Services LDAP Client Daemon	41
		6.6.2	/etc/nslcd.conf	42
7	Man	aging l	Permissions	43

7.1	Understanding Ownership: Users, Groups and Others	 43
	7.1.1 Permissions	 43
	7.1.2 Ownership	 44
7.2	Changing file ownership	 44
	7.2.1 chgrp	 44
	7.2.2 chown	 44
7.3	Understanding Basic Permissions	 45
7.4	Managing Basic Permissions	 45
	7.4.1 chmod	 45
7.5	Understanding Special Permissions	 46
7.6	Managing Special Permissions	 47
	7.6.1 Finding a file with a particular set of permissions	 47
	7.6.2 Setting Group ID for a directory	 48
	7.6.3 Sticky Bit	 49
	7.6.4 Lowercase 's' or 't' vs Uppercase in permissions	 50
7.7	Understanding ACLs	 50
	7.7.1 Mount options	 50
	7.7.2 Commands	 51
7.8	Managing ACLs	 51
	7.8.1 history	 53
Con	nfiguring Networking	54
8.1	Understanding NIC Naming	 54
	8.1.1 Network Device Naming Schemes	 54
8.2	Managing NIC Configuration with ip Command	 54
	8.2.1 show commands	 55
	8.2.2 ip addr add	 55
	8.2.3 ip route add	 56
8.3	Storing Network Configuration persistently	 56
	8.3.1 Hostname	 57
8.4	Understanding Network Manager	 57
8.5	Using Network Manager utilities (nmcli_nmtui)	58

		8.5.1 nmcII	58
		8.5.2 nmtui	59
	8.6	Understanding Routing and DNS	59
		8.6.1 Default route	59
		8.6.2 DNS	60
	8.7	Configuring Routing and DNS	60
	8.8	Understanding Network Analysis Tools	61
	8.9	Using Network Analysis Tools	61
		8.9.1 ping	62
		8.9.2 traceroute	62
		8.9.3 host	62
		8.9.4 dig	63
		8.9.5 Physical network problems	64
II	Op	erating RHEL Servers	66
9	Man	aging Processes	67
	9.1	Understanding Jobs and Processes	67
		9.1.1 jobs	67
	9.2	Managing Shell Jobs	67
	9.3	Getting process information with ps	69
		9.3.1 Getting PID of a process	70
		9.3.2 Seeing Parent and Child process relation	70
	9.4	Understanding Memory Usage	70
	9.5	Understanding Performance Load	71
		9.5.1 uptime Command	71
	9.6	Monitoring System Activity with top	72
	9.7	Sending Signals to processes	73
		9.7.1 kill command	73
	9.8	Understanding Drievities and Nicenses	74
	9.0	Understanding Priorities and Niceness	74
	9.9	Changing Process Nice values	74 74

		9.9.2	Changing Niceness from command line		•	•	•	•	74
10	Man	aging S	Software						76
	10.1	Unders	standing Meta Package Handlers						76
	10.2	Setting	up Yum repositories						76
		10.2.1	yum repolist						76
		10.2.2	Custom Repository						76
	10.3	Using t	the yum command						77
		10.3.1	yum search						77
		10.3.2	yum install						78
		10.3.3	yum list						79
		10.3.4	yum provides						79
		10.3.5	yum remove						80
	10.4	Using i	rpm queries						81
		10.4.1	Installing a local rpm file						83
		10.4.2	repoquery						84
		10.4.3	Displaying information about a package						84
11	Worl	kina wi	th Virtual Machines						86
			cing KVM Virtualization						86
			CPU Virtualization Support						86
	11.2		ing Libvirt and KVM						87
			virsh						88
		Ū	Virsh commands						88
	11.4		virt-manager						89
		· · · · · ·							
12	Sche	eduling	Tasks						90
	12.1	Cron v	s at						90
		12.1.1	Cron						90
		12.1.2	at						90
	12.2	Unders	standing Cron Configuration files and Execution times						90
		12.2.1	crontab -e						91
		12.2.2	Other cron config files						91
		1223	cron d						92

12.3 Scheduling with cron	92
12.4 Using at	93
12.4.1 Scheduling using at	93
12.4.2 atq	94
12.4.3 Removing jobs from atq	94

Part I Installing RHEL Server

Chapter 1

Using Essential Tools

1.1 Man Command

man followed by keyword yields the manual page of that command.

\$ man ls

man followed by option **-k** (for keyword) and then followed by a *keyword* yields a list of all the commands containing that keywork and a brief description of that command.

```
$ man -k day
   daylight (3)
                        - initialize time conversion information
   dysize (3)
                       - get number of days for a given year
   daylight (3p)
                       - set timezone conversion information
   gettimeofday (2)
                       - get / set time
   gettimeofday (3p)
                        - get the date and time
   motd (5)
                        - message of the day
   Net::Time (3pm)
                        - time and daytime network client interface
   settimeofday (2)
                       - get / set time
10 Time::HiRes (3pm)
                      - High resolution alarm, sleep, gettimeofday, interval timers
```

The numbers next to the commands indicate which seciton of the man pages the command belongs to (based on their functionality). The actual section that the commands belong to can be determined by the use of

\$ man man-pages

The relevant sections for SysAdmins are Section 1, 5 & 8. The sections are:

Section Number	Deals with	Description
1	Commands (Programs)	Those commands that can be executed by the user from within a shell.
2	System calls	Those functions which must be performed by the kernel.
3	Library calls	Most of the libc functions.
4	Special files (devices)	Files found in /dev.
5	File formats and conventions	The format for /etc/passwd and other human-readable files.
6	Games	
7	Overview, conventions, and miscellaneous	Overviews of various topics, conventions and proto- cols, character set standards, and miscellaneous other things.
8	System management commands	Commands like mount(8), many of which only root can execute.

To filter down the output of the **man -k** command, we can use **grep** to obtain only the relevant parts of the result on the basis of the appropriate section number in the man-pages.

This can be achieved using the pipe which feeds the output of the first command to the input of the second command.

```
$ man -k day | grep 3
daylight (3) - initialize time conversion information
dysize (3) - get number of days for a given year
daylight (3p) - set timezone conversion information
gettimeofday (3p) - get the date and time
Net::Time (3pm) - time and daytime network client interface
Time::HiRes (3pm) - High resolution alarm, sleep, gettimeofday, interval timers
```

1.2 Understanding Globbing and Wildcards

* - Indicates any string.

? - Indicates any single character.

 $\boldsymbol{[\cdot\cdot\cdot]}$ - Indicates any character provided within brackets.

[!···] - Indicates any character *NOT* provided within brackets.

[a-f] - Indicates any character provided within the range of a to f.

1.3 Understanding Globbing and Wildcards

\$ Is a*

Lists all files and folders (including contents of each folder) that start with "a"
\$ Is *a*

Lists all files and folders that contain the string "a".

\$ Is -d a*

Shows all files and folders that start with "a" but excludes the contents of each individual folder.

\$ Is ??st*

Lists all files and folders that have "st" as the 3rd and the 4th character in their name.

\$ [a-f]

Indicates any character provided within the range of a to f.

1.4 Understanding I/O Redirection and Pipes

1.4.1 I/O Redirection

File Descriptors:

STDIN - 0 - Standard Input - Represents the "file" for the Standard Input Device (generally Keyboard).

STDOUT - 1 - Standard Output - Represents the "file" for the Standard Output Device (generally the Monitor).

STDERR - 2 - Standard Error - Represents the "file" for the Standard Output Device (also, generally the Monitor).

Redirection:

STDERR

2 >

STDIN - < - Feeds the file to the right of the "<" as input to the command on the left.

STDOUT - > - Stores the output of the command to the left of the ">" to the file indicated on the right. *OVERWRITES* the mentioned file.

STDOUT - >> - Stores the output of the command to the left of the ">>" to the

file indicated on the right. APPENDS the mentioned file.

Redirects the errors from the command mentioned on the left to

the file on the right. *OVERWRITES* the mentioned file.

- 1 *mail* is a simple command used to send messages. The command expects the message to terminate with a ".", so we feed it directly to the command, instead of providing any input.
- 4 The STDERR is redirected to tty6 (a virtual terminal connected to the host). Can also be diverted to a file if needed, such as an errorLog.

1.4.2 Piping

The command \$ ps aux shows us the overview of all the running processes on the host. However, it's too long to view all at once. In such situations, or wherever we need to feed the output of the first command to the input of the second command, we use the pipe operator. The command would then be \$ ps aux | less.

The difference in the usage of the piping and redirection operators is that Pipe is used to pass output to another program or utility, while Redirect is used to pass output to either a file or stream.

1.5 Using I/O Redirection and Piping

```
$ ps aux | awk '{print $2}'

$ ps aux | awk '{print $2}' | sort

$ ps aux | awk '{print $2}' | sort -n
```

The second column (\$2) of the \$ ps aux command contains the Process ID (PID), and if we only want to filter the output such that only the PID is shown, we simply use the **awk** filtering utility.

If we want to sort the output of the command, we use the **sort** utility, but it generally sorts as a string. To sort the output as a number, we use the option **sort -n**.

If you expect lots of errors for a particular command, but want to discard all errors and only see the output when successful, then simply redirect the STDERR to /dev/null, which is a special device that discards all data written to it, i.e., a dustbin for data.

```
1    $ find / -name "*.rpm"
2    $ find / -name "*.rpm" 2> /dev/null
```

The first command shows all output including errors, but the second command discards all errors and shows the rest.

```
some_command > /dev/null 2> &1
```

The above code redirects STDOUT to /dev/null thus destroying the output, and also redirects the STDERR (2>) to STDOUT (&1). Essentially, it discards all output - useful when we don't need the output but only need the command to execute.

```
1  $ ls / > file_list.txt
2  $ sort < file_list.txt > file_list_sorted.txt
```

The above command stores the contents of the root directory in *file_list.txt*. Then, the second command uses both input and output redirection! The input of the sort command is fed from *file_list.txt* and the corresponding output sent to *file_list_sorted.txt*.

Chapter 2

Essential File Management Tools

2.1 Understanding Linux File System Layout

-	Contains all other directories.
-	Contains everything the system needs to start up Contains program files Contains configuration files Contains a user's files Used to manually mount devices
-	Devices like optical discs get auto-mounted on the media directory

Unlike other OSs, the linux files system is designed as such that multiple devices can be mounted on the same file system hierarchy. Thus, it's possible to mount devices remotely as well!

2.2 Finding Files

The **find** command is used to find a file within a folder and its subdirectories. When the starting point of the search is the root directory (/) then find will search the entire file system. While the utility is extremely thorough, this may cause delays due to remote devices on the network mounted on the file system.

```
find / -name "passwd"
```

If you're trying to find the location of a binary file, a better command would be **which** command, as it directly shows the location of the binary, but be careful as it only works with binaries.

```
$ which passwd /usr/bin/passwd
```

Contrastingly, the command **whereis** not only gives us the locaiton of the binary, but the location of the complete environment of the binary!

```
1 $ whereis passwd
2 passwd: /usr/bin/passwd /etc/passwd /usr/share/man/man1/passwd.1.gz

→ /usr/share/man/man5/passwd.5.gz
```

Another similar utility is called **locate** which shows all files that have the string provided to it in its name. Note, however, that locate operates on a database, that must be updated (especially after the creation of a new file) to show relevant results.

```
# touch sinha
# touch sinha

# locate sinha

# locate sinha

# wydatedb

# locate sinha

# locate sinha

# locate sinha

# updatedb

# locate sinha

# wydatedb

# locate sinha

# wydatedb

# locate sinha

# locate sinha

# wydatedb

# locate sinha

# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# locate sinha
# loca
```

2.3 Understanding Links

inode - An inode is a datastructure that describes a file system object such as a file or a directory, containing both the disc block locations as well as the attributes of the file system object. The inodes are identified by their inode number.

Consequently, for us to access the files/directories, we need to be able to provide a name to the inodes, which are called hardlinks. A file may have more than one hardlink. Note that each hardlink is simply a different name provided tot he same inode. Ths, all hardlinks to the same file/directory have the same inode number. Hardlinks are one-directional only, i.e., the hardlink itself knows which inode it points to, but the inodes only know the total number of hardlinks that are associated with it, and not which exact ones are pointing to it. Since hardlinks point to some inode, they always need to stay on the same partition as the inode.

A symbolic link on the other hand, points to a hardlink instead of an inode. As such, it has a different inode number than the one that the hardlink points to. Thus, the hardlink and symbolic link can be on different partitions as well. It can even exist across servers. Whenever a hardlink is deleted, however, all the symbolic links pointing to it are rendered invalid.

2.4 Working with Links

The \ln command is used to create both hardlinks and symbolic links. To create a symbolic link, we need only add the -s option. The -i option of the \ln command shows us the inode number.

```
# ln /etc/hosts computers
# ls -il /etc/hosts computers
```

```
3 8388733 -rw-r--r-. 2 root root 158 Jun 7 2013 computers
4 8388733 -rw-r--r-. 2 root root 158 Jun 7 2013 /etc/hosts
   # ln -s computers newcomputers
   # ls -il /etc/hosts computers newcomputers
   8388733 -rw-r--r-. 2 root root 158 Jun 7 2013 computers
   8388733 -rw-r--r--. 2 root root 158 Jun 7 2013 /etc/hosts
   27604468 lrwxrwxrwx. 1 root root 9 Sep 7 19:26 newcomputers -> computers
10 # rm -f computers
# 1s -il /etc/hosts newcomputers
12 8388733 -rw-r--r-. 1 root root 158 Jun 7 2013 /etc/hosts
13 27604468 lrwxrwxrwx. 1 root root 9 Sep 7 19:26 newcomputers -> computers
15 exit
16 $ ln /etc/shadow mydata
17 ln: failed to create hard link 'mydata' => '/etc/shadow': Operation not permitted
18 $ ls -l /etc/shadow
    ----- 1 root root 1375 Sep 5 21:04 /etc/shadow
```

When the hardlink *computers* to the inode associated with /etc/hosts is deleted, the associated symbolic link of *newcomputers* becomes invalid.

Finally, RHEL 7 onwards, a user may only create a link to a file/directory that it at least has a read permission to. Thus, any user won't be able to create a link to /etc/shadow as it has no permissions for anybody.

2.5 Working with tar

tar stands for Tape Archive. The command is most commonly used to make backups of files by storing them in archives. Some of the options of tar are:

```
create
                            typically has an extension of .tar
-C
                            show contents of the archive.
-t
        show contents -
-X
        extract
                            compress the archive using gzip. Typically has an extension of .tgz
-Z -
        file
        verbose
-V -

    tell us what the utility is doing.

                            option to indicate the name of the archive file.
-f
        file
                        - indicates where the archive is to be extracted.
-C
        location
```

```
$ tar -cvf /root/etc.tar /etc
```

The above command creates the etc.tar archive in the /root directory and puts the contents of /etc in that archive. Note that the file etc.tar has a .tar extension only because we provided it, and not because Linux mandates it (unlike windows). Thus, sometimes we may run across tar archives that don't have an extension and are hard to detect. So, in that case we use the file command, which tells us the type of a particular file.

```
$ file /root/etc.tar
/root/etc.tar: POSIX tar archive (GNU)
```

Note that the .tar archive only puts all the files of teh /etc directory in the file tar.etc, but doesn't actually compress anything. To enable compression the -z option of the tar command must be used.

```
$ tar -czf /root/etc2.tgz /etc
```

Before extracting the contents of a tar file, we might want to see its contents, which can be done using the -t option of the tar command. NOTE: Some older versions of tar may require the -z option to enable working with gzip archives, even when simply using the archive and not creating it.

```
$ tar -tvf /root/etc2.tgz
```

To actually extract the archive, we use -x option. To indicate the location where we want the extracted files to reside, we include the -C option. If this option is not present then the files will be extracted in the present directory.

```
$ tar -xvf /root/etc2.tgz -C /tmp
```

To extract only one file from the archive, we can simply provide the name of the file at the very end.

```
$ tar -xvf /root/etc2.tgz -C / etc/wgetrc
```

NOTE that in the above command, we use the relative path etc/wgetrc because of the fact that the archive stores a relative file path for easy extraction in any folder.

Chapter 3

Working with Text Files

3.1 Understanding Regular Expressions

Character	Definition	Example	Result
^	Start of a string	^abc	abc, abcdef, abc123
\$	End of a string	abc\$	abc, blahabc, 456abc
	Any character except newline	a.c	abc, aac, a2c
	Alteration	1 8	1,8
{}	Explicit quantity of preceding character	$ab\{2\}c$	abbc
[]	Explicit set of characters to match	a[bB]c	abc, aBc
()	Group of characters	(123){3}	123123123
*	Null or more of the preceding character	ab*c	ac, abc, abbbbbc
+	One or more of the preceding character	ab+c	abc, abbbbc
?	Null or one of the preceding character	ab?c	ac, abc
EARSON T CERTIFICA	ATION		livelessons@ @2015 Pearson, Inc

Figure 3.1: RegEx Cheat Sheet

3.2 Using common text tools

3.2.1 cat

The cat command prints the entire content of a file on to the terminal.

3.2.2 less

Sometimes the cat command is unsuitable, like in the case of extremely large files. In such cases, like the /var/log/messages, the default system log file, using cat won't work as the majority of the messages would scroll past fast. For such cases, less is a better utility. Search functionality is exactly the same as in the case of vim.

3.2.3 Head and Tail

Head

The head command by default shows us the first 10 lines of a text file. To see more or less lines, the -n option can be used.

```
1 $ head -n 20 file.txt
```

Tail

The tail command by default shows us the last 10 lines of a text file. To see more or less lines, the -n option can be used.

```
$ tail -n 5 file.txt
```

Combination of head and tail

The combination of these two commands can enable the viewing of text in between specific line numbers. The command below shows lines 16-20 of file.txt

```
$ head -n 20 file.txt | tail -n 5
```

3.2.4 cut

With the cut utility, we can print out a specific column form a text file. It assumes the columns are separated by Tabs. Which specific column is to be printed is set by using the -f option. For example, to only print the first column of a text file, we say:

```
1 $ cut -f 1 cities
```

To provide a different delimiter, such as ":" we use the -d option followed by the delimiter of our choice.

```
$ cut -f 1 -d : /etc/passwd
```

3.2.5 sort

This command sorts the input provided in the order of the ASCII table. That means numbers first, captial letters next and finally the lower case letters.

```
1 $ cut -f 1 -d : /etc/passwd | sort
```

To sort on the basis of a specific criteria:

- Sort on the basis of actual numberical value, instead of treating a number as a string.
- -f Sort in a case insensitive manner.

3.2.6 tr

The tr command replaces certain characters with certain other characters. Thus, it's frequently used in conjunction with pipes to modify the output of a command.

```
$ echo hello | tr a-z A-Z

HELLO

$ echo hello | tr [:lower:] [:upper:]

HELLO
```

3.3 grep

grep is a filtering utility that only prints those lines that contain a certain expression matching the pattern provided by a *RegEx*.

```
$ ps aux | grep tracker
1
                                     SN1 10:06
  somu 10450 0.0 0.4 469796 9000 ?
                                                 0:00
  somu 10465 0.0 0.6 536856 12012 ? Sl 10:06
                                                 0:00
  somu 10611 0.0 0.7 779816 13108 ? SN1 10:06
                                                 0:00
  \hookrightarrow /usr/libexec/tracker-extract
  somu 10614 0.0 0.5 469800 9632 ? SN1 10:06
                                                 0.00
  → /usr/libexec/tracker-miner-apps
  somu 10615 0.0 0.7 710160 13204 ?
                                      SN1 10:06
                                                 0:00
  → /usr/libexec/tracker-miner-fs
  root 17396 0.0 0.0 112644 968 pts/0
                                       R+ 13:49 0:00 grep --color=auto
  \hookrightarrow tracker
```

Another use for grep is searching files. The syntax is grep <filename-pattern> <search-directory>.

To avoid errors notifying "is a directory", simply redirect errors to /dev/null.

```
$ grep lisa * 2> /dev/null
group:lisa:x:1001:
gshadow:lisa:!::

passwd:lisa:x:1001:1001::/home/lisa:/bin/bash
passwd-:lisa:x:1001:1001::/home/lisa:/bin/bash
```

```
6 services:na-localise 5062/tcp # Localisation access
7 services:na-localise 5062/udp # Localisation access
8 shadow:lisa:$6$01/zSJkh$xjJNYNnj1rPs7Fq0hDWt8VucSOnLL82XrMYpmBnLF2DrzB2npFvCwxM9MJEHgCHCwvabCgEA17LK2aU0h9FIT/:1741
9 shadow-:lisa:password:17414:0:999999:7:::
```

3.3.1 wc

Counts the number of words, lines and characters.

-I - Counts the number of lines
 -w - Counts the number of words
 -m - Counts the number of characters

-c - Counts the number of bytes-L - Counts the length of the longest line

To see the number of matched lines using grep, simply use:

3.3.2 grep -I

Grep by default returns the name of the matching file followed by the matching lines. This output can be made more readable by grep -1 which lists all the files in the directory that matches the criteria.

3.3.3 grep -i

The -i flag turns the grep command case-insensitive!

```
$ grep lisa * 2> /dev/null

2 group:lisa:x:1001:
3 passwd:lisa:x:1001:1001::/home/lisa:/bin/bash

4 services:na-localise 5062/tcp # Localisation access

5 services:na-localise 5062/udp # Localisation access

6 $ grep -i lisa * 2> /dev/null

7 group:lisa:x:1001:
```

```
s passwd:lisa:x:1001:1001::/home/lisa:/bin/bash
services:ltctcp 3487/tcp # LISA TCP Transfer Channel
services:ltcudp 3487/udp # LISA UDP Transfer Channel
services:na-localise 5062/tcp # Localisation access
services:na-localise 5062/udp # Localisation access
```

3.3.4 grep -R

The usage of the -R flag puts grep in recursive mode, where the utility searches for the file in each subfolder as well.

3.3.5 grep -v

Grep with a -v flag excludes the matching results. Here we can exclude the lines containing "Binary" using:

```
$ grep -iR lisa * 2> /dev/null | grep -v Binary
   alternatives/jre_openjdk/lib/security/nss.cfg:handleStartupErrors =
    \hookrightarrow ignoreMultipleInitialisation
   alternatives/jre_openjdk_exports/lib/security/nss.cfg:handleStartupErrors =
    brltty/fr-abrege.ctb:word civilisation
                                              14-1236-16
   brltty/fr-abrege.ctb:word civilisations 14-1236-16-234
brltty/fr-abrege.ctb:word généralisation 1245-1345-16
   brltty/latex-access.ctb: brailleTranslator.capitalisation = "6dot"
   brltty/latex-access.ctb:
9 passwd:lisa:x:1001:1001::/home/lisa:/bin/bash
sane.d/canon_pp.conf:# Set a default initialisation mode for each port. Valid modes are:
11 services:1tctcp 3487/tcp # LISA TCP Transfer Channel
12 services:ltcudp
                          3487/udp
                                                   # LISA UDP Transfer Channel
```

3.4 sed and awk basics

3.4.1 sed

sed is an old utility that's used to process text. Many of it's functionalities can now be done using grep itself.

sed q

To see the first two lines of a file using sed we use:

```
$ sed 2q /etc/passwd
coot:x:0:0:root:/bin/bash
bin:x:1:1:bin:/bin:/sbin/nologin
```

sed -n

The -n flag makes sed print no output unless the p flag is also provided. Here, we use a Regular Expression " $\hat{r}oot$ " to match only a certain part of the text and then the p flag to print only if that criteria is matched.

```
$ sed -n /^root/p /etc/passwd
root:x:0:0:root:/root:/bin/bash
```

The above result could also be obtained with grep "^root" /etc/passwd.

Substitution with sed

Sed can be used to substitute text within a file using the s parameter. It's used as :

```
$ cat names

Somu
Arpi
Debu

sed -i 's/Santy/Dickwad/g' names

cat names

Somu
Arpi
Neha
Dickwad
Dickwad
Dickwad
Dickwad
Dickwad
Debu
```

The -i flag asks the modifications to be made in place. Otherwise the output (changed text) would've simply been displayed to the screen and then need to be redirected to a file for storage.

3.4.2 awk

awk is another utility that is especially useful when working with text files. It excels at operations like cutting out information.

Cutting out information using awk

For certain operations, the awk command is a lot more powerful than the cut utility. In the example below cut has a hard time recognizing the second field, while awk has no problem whatsoever!

```
$ ps aux | grep 'gdm'
   root 1117 0.0 0.1 480248 4688 ? Ssl 09:20 0:00 /usr/sbin/gdm
2
            1333 0.8 1.2 328524 47220 tty1 Ssl+ 09:20 0:43 /usr/bin/X :0
    \,\hookrightarrow\, -background none -noreset -audit 4 -verbose -auth
    \  \, \hookrightarrow \  \, /\text{run/gdm/auth-for-gdm-bgrBZH/database -seat seat0 -nolisten tcp vt1}
   root 1718 0.0 0.1 528944 5848 ? S1 09:20
                                                         0:00 gdm-session-worker
    gdm 1737 0.0 0.1 458088 4152 ? S1 09:20
                                                         0:00 ibus-daemon --xim
    \hookrightarrow --panel disable
   gdm 1741 0.0 0.1 373560 5424 ? S1 09:20
                                                         0:00 /usr/libexec/ibus-dconf
            1745 0.0 0.2 438152 7772 ?
                                            Sl 09:20
                                                         0:00 /usr/libexec/ibus-x11
   \hookrightarrow --kill-daemon
   somu 12218 0.0 0.0 112664 972 pts/0 R+ 10:47
                                                         0:00 grep --color=auto gdm
   $ ps aux | grep 'gdm' | cut -f 2
   root 1117 0.0 0.1 480248 4688 ? Ssl 09:20
                                                         0:00 /usr/sbin/gdm
10
            1333 0.8 1.2 328524 47220 tty1 Ssl+ 09:20 0:43 /usr/bin/X :0
11 root
    \hookrightarrow -background none -noreset -audit 4 -verbose -auth
    → /run/gdm/auth-for-gdm-bgrBZH/database -seat seat0 -nolisten tcp vt1
   root 1718 0.0 0.1 528944 5848 ? Sl 09:20 0:00 gdm-session-worker
    gdm 1737 0.0 0.1 458088 4152 ?
                                            Sl 09:20
                                                         0:00 ibus-daemon --xim
13
    \hookrightarrow --panel disable
        1741 0.0 0.1 373560 5424 ? S1 09:20
                                                         0:00 /usr/libexec/ibus-dconf
14
   gdm
            1745 0.0 0.2 438152 7772 ?
                                            Sl 09:20
                                                         0:00 /usr/libexec/ibus-x11

→ --kill-daemon

   somu 12226 0.0 0.0 112664 968 pts/0 R+ 10:48 0:00 grep --color=auto gdm
   $ ps aux | grep 'gdm' | awk '{ print $2 }'
   1333
   1718
   1737
22
   1741
23
   1745
   12248
```

Chapter 4

Connecting to a RHEL Server

4.1 Connecting to a Server with SSH

To connect to a server we use the ssh command. The Syntax is: ssh <server-ip>.

```
1 $ ssh 192.168.152.129
2 somu@192.168.152.129's password:
3 Last login: Mon Nov 13 12:37:26 2017 from 192.168.152.128
```

The default SSH port is **22**. To connect to SSH on a different port (common when server is exposed to the internet), is ssh -p <port-number> <server-ip>. Note that *if root login is disabled on the server*, we must also provide the username to login as. The syntax then becomes: ssh -p <port-number> <username>@<server-ip>.

```
$ ssh -p 2022 sander@ldap.rhatcertification.com
```

4.2 RSA Key fingerprint and known hosts

Upon each new connection the ssh daemon shows us the RSA key fingerprint of the host to verify if we're connecting to the right computer. If so, the host is added to a list of known hosts permanently, in $^{\sim}/.ssh/known_hosts$.

When the key fingerprint of the server doesn't match the Key fingerprint on record, the system warns us from connecting! This may occur when the server has been reinstalled on the same IP address. Thus, the new key fingerprint won't match the old one. To fix this, simply remove the old entry from ~/.ssh/known_hosts.

4.3 sshd_config

The details of the method of connection to a server is stored in the **sshd_config** file, located in /etc/ssh/sshd_config.

Some of the options are:

Option	Description	Default Value
Port	The port number which is used for SSH on that server	22
PermitRootLogin	Whether an user is allowed to login as root user via SSH	yes

If the root login on the server via SSH is disabled, it generally makes the server a little bit more secure!

4.4 Understanding SSH keys

To initiate the ssh connection, the **SSHD** service on the server is contacted by the client. In order to confirm it's identity, the server responds with it's own $/etc/ssh/ssh_host.pub$ public key to the client. When the client's user has verified the key of the server, the public key fingerprint gets stored in the clients $^{\sim}/.ssh/known_hosts$ file. Finally, the user is asked for the password to log on to the server.




Figure 4.1: Server Authentication procedure

4.4.1 Client authentication without password

The client can also prove it's identity without a password by the use of a public key that it provides to the server. The private key of the user is stored in the home directory of the user ~/.ssh/id_rsa. A packet encrypted with the private key is sent to the server which knows the user's public key. Some complex calculations based on this is performed on the authentication token sent from the client and if the identity is confirmed, then the user is logged in without needing a password.




Figure 4.2: Public Key Client Authentication without password.

4.5 Using SSH Keys

SSH keys can be used to authenticate an user instead of a password. The private-public key pair can be generated using the ssh-keygen utility.

```
$ ssh-keygen
   Generating public/private rsa key pair.
   Enter file in which to save the key (/home/somu/.ssh/id_rsa):
4 Enter passphrase (empty for no passphrase):
5 Enter same passphrase again:
6 Your identification has been saved in /home/somu/.ssh/id_rsa.
7 Your public key has been saved in /home/somu/.ssh/id_rsa.pub.
   The key fingerprint is:
   SHA256:0C5uEHnAgJvzFEcOulfL1YSygT/YF5UtL9lweTfPDAc somu@vmPrime.somusysadmin.com
   The key's randomart image is:
10
    +---[RSA 2048]----+
11
    ..==. ooo .E.
12
    . ..++0.00+ + 0.0
13
    | o.oo+++o..B . *o|
    + ...===. 0 0
15
    +. o +oS .
18
19
20
    +----[SHA256]----+
```

4.5.1 Copying SSH keys

The SSH keys generated on the client now have to be copied to the server which requires authentication. This can be done using ssh-copy-id.

While previous versions of ssh-copy-id didn't support specifying a port number, RHEL 7 onwards this feature is supported.

```
$ ssh-copy-id -p 2022 sander@ldap.rhatcertification.com
```

In case the public key is not recognized, it is possible to specify the public key using the ssh-copy-id -i <publicKeyFile.pub> flag.

4.5.2 Copying files to a server securely using SSH

Files can be copied to a server using SSH connection using the scp (secure copy) utility.

```
1 $ scp -P 22 names 192.168.152.129:~
2 names 100% 28 8.1KB/s 00:00
```

NOTE that the directory on which the file has to be copied to on the server, (in this case the directory) has to be specified for the copy to be successful. Otherwise, scp just creates a local copy of the file with the name of the server as the filename.

Also, if the port has to be specified, the flag is -P which is in capital unlike ssh and ssh-copy-id.

Chapter 5

Managing Users and Groups

5.1 Understanding the need for Users

User accounts are not just to ensure that different people use resources with accountability and resource management. Several processes also have to execute with permissions given to them by their respective user accounts.

For example, the apache web server's processes and services execute under the permissions given to the apache account. This account doesn't have root privileges, which ensures that in case of security breaches of the apache user account, the culprit doesn't gain access to any critical resources that only an administrator or the root account should have access to.

5.2 User Properties

5.2.1 Username

A typical user info in the /etc/passwd file consists of the login information of several users, each with the following details:-somu:x:1000:1000:Somu:/home/somu:/bin/bash. Here, Somu is the username, the x in the second field references that a password has been stored for that username in the /etc/shadow file. The file contains the (one-way) encrypted password as well as several password related information such as password expiration dates, etc. Since the /etc/shadow file is only readable by the root user, it minimizes the security risk. Generally, only real user accounts need a password and system users (accounts used by processes to execute) don't.

/etc/shadow

While the /etc/shadow file contains the password of an user in an encrypted format, if the user account is new and doesn't yet have any password assigned to it, then the entry for it in /etc/shadow looks like:

```
$ cat /etc/shadow | grep lisa
```

lisa:!!:17485:0:99999:7:::

The second entry (!!) is where the encrypted password is usually stored. The double exclamation indicates that the *lisa* account hasn't set up a password yet.

5.2.2 UID

Each user on the system is setup with a unique UserID (UID). The root has a UID of 0, and normal users start with an UID of 1000 onwards. There are a total of 64,000 UIDs available for 2.4 kernels, and 4 billion for 2.6 kernels.

5.2.3 GID

On Linux, every user must be the member of at least one group, which is known as the **primary group** of the user, stored in the /etc/passwd file. On RHEL, that primary group has the same name as the username and the user is the only member of that group by default (i.e., private group). The list of Groups is stored in a file called /etc/group.

5.2.4 GECOS or comment field

This is a comment field that can contain anything the admin deems necessary. It generally contains information that makes the identification of each user easier.

5.2.5 Home Directory

The home directory refers to the location where the user is allowed to store files. For services, this folder is important because it defines the directory where the service can read and write files. While for regular users the home directory is typically inside $/ \mathtt{home}$, for services, they can be anywhere.

5.2.6 Default Shell

This is the shell (or command) that is executed on login of the user. The default value is /bin/bash.

5.3 Creating and Managing Users

5.3.1 Adding users

The default command for adding users on RHEL is useradd.

Option	Description
-е	Expiration date in the format YYYY-MM-DD. Sets the date on which the user account will be disabled.
-c	Comment that sets the contents of the GECOS field.
-s	Sets the default shell of the user. For example, a C programmer can use a shell such as TCSH.

```
$ sudo useradd -c "New Test User" -s /bin/tcsh -e 2017-12-31 laura
[sudo] password for somu:

$ # To verify the addition of the new user

$ tail -n 1 /etc/passwd

$ laura:x:1001:1001:New Test User:/home/laura:/bin/tcsh
```

id command

The id command prints the real and effective user information.

5.4 Understanding Group Membership

Groups are especially useful to enable users to share files with one another. These groups may be additional groups known as secondary groups.

The /etc/passwd file doesn't contain any reference to the secondary groups that the user is a part of, even though the /etc/group file lists that user as a member. Thus, the best way to obtain the groups the user is a part of is by using the id command.

5.5 Creating and Managing Groups

5.5.1 groupadd

The groupadd command is used to add a new group.

Option	Description
-g	Specify the GID of the group.

5.5.2 Adding users to a group

A user can be added to a group by directly editing the /etc/group file, or by| using the moduser command.

usermod

Option	Description
-g	Force assign the GID as the new default group of the user.
-G	Erase older list of supplementary groups and assign the given groups as the supplementary group of he user.
-a	Add the given group to the list of groups for the user.

Adding a user to a group using the usermod command is shown below.

```
$ sudo usermod -aG account laura

$ sudo usermod -aG 5010 lisa

$ tail -n 1 /etc/group

4 account:x:5010:laura,lisa
```

5.6 User and Group configuration files

Some of the important configuration files are:

Option	Description
/etc/passwd	Contains several details of the user, other than the password.
/etc/shadow	Contains the password hash and password properties for the user.
/etc/group	Contains the names of all the groups along with a list of all users in them.
/etc/login.defs	Contains the values (definitions) of several parameters used to create the user, such as password max days, min days, etc.
/etc/default/useradd	Contains the default values for several useradd parameters.
/etc/skel	When a user's home directory is created, the contents of /etc/skel is copied there, with the appropriate group of the user.

5.7 Managing Password properties

The user *root* can manage the password properties using two commands:

5.7.1 passwd

Option	Description
-d	Delete the current password.
-I	Lock the current password.
-u	Unlock the current password.
-е	Expire the current password - force user to change password during next login.
-x	Set the maximum lifetime of the password.
-n	Set the maximum lifetime of the password.
-w	Set days before expiration the user is warned.
i	Set days after expiration the user account becomes inactive.

Locking and Unlocking passwords

```
$ sudo passwd -1 laura
2 Locking password for user laura.
3 passwd: Success
4 $ su - laura
5 Password:
   su: Authentication failure
   $ sudo cat /etc/shadow | grep laura
s \quad \texttt{laura:!!\$6\$0zDhsJet\$q2...KRVKv8D2.:17486:0:99999:7::17531:}
   $ sudo passwd -u laura
10 Unlocking password for user laura.
   passwd: Success
$ sudo cat /etc/shadow | grep laura
   laura:$6$0zDhsJet$q2...KRVKv8D2.:17486:0:99999:7::17531:
   $ su - laura
   Password:
   Last login: Thu Nov 16 13:40:45 IST 2017 on pts/0
   $ whoami
   laura
```

When an account is locked, the password hash for that user in the /etc/shadow file is prefixed with a !! to render it invalid and prevent authentication from succeeding (unless the root logs in as that user, which requires no password prompt).

5.7.2 chage

Option	Description
-1	List all password aging information.
-E	Set the account expiration date.
-m	Set the maximum lifetime of the password.
-M	Set the maximum lifetime of the password.
-W	Set days before expiration the user is warned.
-I	Set days after expiration the user account becomes inactive.

Setting the account expiration date

```
sudo chage -E 2017-12-31 laura

[sudo] password for somu:

[somu@cliServer ~]$ sudo cat /etc/shadow | grep laura

laura:$6$0zDhsJet$q2...KRVKv8D2::17486:0:99999:7::17531:

sudo chage -l laura

Last password change : Nov 16, 2017

Password expires : never

Password inactive : never

Account expires : Dec 31, 2017

Minimum number of days between password change : 0

Maximum number of days between password change : 99999

Number of days of warning before password expires : 7
```

The string 17531 represents the account expiration date in epoch time (seconds since Jan 1 1970).

Chapter 6

Connecting to a LDAP Server

6.1 Understanding LDAP

LDAP is an easy way to provide centralized authentication from a server. This way, many computers can be connected to a single LDAP server and the user accounts (and permissions) have to be set up only once!

LDAP stands for *Lightweight Directory Access Protocol*. It connects us to a hierarchical directory server. In the hierarchy (e.g., server.rhatcertification.com), there are top level domains such as *.com*, subdomain (rhatcertification) and leaf objects (lisa). Even though the structure is similar to DNS, the notation of LDAP is different. For every container object, we write $dc=\langle objectName \rangle$ ($dc \rightarrow Domain Component$) and for leaf objects, it becomes $cn=\langle objectName \rangle$ ($cn \rightarrow Common Name$). The complete format then becomes cn=lisa, dc=rhatcertificaton, dc=com.

An important part of connecting to an LDAP server is the **base context**. The base context, like the search domain of DNS, is the starting point where our client should look for objects. In this case, the base context is dc=rhatcertification,dc=com. Thus, for logging in to a server, the *cn*(lisa) is searched for within the base context.

6.1.1 /bin/login

The login service is used whenever the user requires authentication to connect to anything.

6.1.2 Idd

The 1dd command (List Dynamic Dependencies) prints all the shared libraries required by a program.

```
$ ldd /bin/login
linux-vdso.so.1 => (0x00007ffc333e3000)
libpam.so.0 => /lib64/libpam.so.0 (0x00007f85cad8a000)
libpam_misc.so.0 => /lib64/libpam_misc.so.0 (0x00007f85cab86000)
libaudit.so.1 => /lib64/libaudit.so.1 (0x00007f85ca95d000)
libselinux.so.1 => /lib64/libselinux.so.1 (0x00007f85ca736000)
libc.so.6 => /lib64/libc.so.6 (0x00007f85ca73000)
```

- 8 libdl.so.2 => /lib64/libdl.so.2 (0x00007f85ca16e000)
- 9 libcap-ng.so.0 => /lib64/libcap-ng.so.0 (0x00007f85c9f68000)
- libpcre.so.1 => /lib64/libpcre.so.1 (0x00007f85c9d06000)
- 11 /lib64/ld-linux-x86-64.so.2 (0x0000558e5f0bd000)
- 12 libpthread.so.0 => /lib64/libpthread.so.0 (0x00007f85c9ae9000)

The PAM library shown above (libpam) is akin to a plugin that adds additional functionality to the login utility (as well as several others). PAM stands for *Plugable Authentication Modules*. The configuration files for the authentication module is stored in /etc/pam.d directory. The /etc/pam.d/login is the configuration file for login utility.

6.1.3 PAM config file syntax

The PAM config files are each named after the services that require the usage of PAM. For example, the config file for the *login* service is called /etc/pam.d/login. Each file lists a bunch of rules in the syntax: <service-type> <control> <module-path> <arugments>.

Service Type

Service Type	Description
auth	Deals with user authentication via password (or other means like keys).
account	Non-authentication based account management.
password	Updating the authentication token of the user.
session	Modules listed here are used for setup/cleanup of a service for the user.

PAM Module Controls

Control	Description
requisite required	Immediately causes failure when the module returns a status that isn't 'success'. If the service returns a non-success status, then the operation fails ultimately, but only after the modules below it are invoked. This is to prevent a person with malicious intent from gaining knowledge of which module failed.
sufficient optional	If a <i>sufficient</i> module returns a 'success' status, the other modules below it that are also a part of 'sufficient' management group will not be invoked. In case of failure, another module listed 'sufficient' in the stack below it must succeed for the operation to succeed. Only causes failure if the rule stack contains only optional modules and all fail.
include substack	For the given service type, include all lines of that type from the provided configuration file. Same as <i>include</i> but when <i>done</i> and <i>die</i> actions are evaluated, they only cause skipping of the substack.

The login config file in /etc/pam.d contains the line:

auth substack system-auth

NOTE: the entry for pam_Idap requires that the host should be able to use LDAP, which requires pam_ldap to be installed, and authconfig-tui to be executed.

The system-auth file has rules for the common login procedure for any any process that deals with user authentication. This file in turn contains the lines:

```
1authsufficientpam_unix.so nullok try_first_pass2...3authsufficientpam_ldap.so use_first_pass
```

The line auth sufficient pam_unix.so tells the system to look at the System login local authentication mechanism (pam_unix.so). If that is not successful, the system is instructed to use the LDAP PAM mechanism (in pam_ldap.so). Thus, the login process is contacting an LDAP server and trying to verify if the user account exists on that server.



Figure 6.1: LDAP Authentication

Next, the LDAP configuration file (/etc/nslcd.conf) is read, which contains the URI of the LDAP Server (ldap://server.rhatcert.com). Finally, the client is able to connect to the LDAP server where is a LDAP hierarchy that it can log into.

6.2 Telling your server where to find the LDAP Server

6.2.1 nscd

The Naming Service Cache Daemon needs to be installed to configure the connection of a server to an external LDAP server. It is the part of the OS that caches the information from external authentication mechanisms on the local machine.

6.2.2 nss-pam-ldapd

This sets up the local name resolution and local authentication and connects it to LDAP services.

6.2.3 pam_ldap

The libraries needed to make the local authentication aware of LDAP services.

6.2.4 authconfig-gtk

authconfig is an utility used to setup the server for external authentication. There are several variations of it, such as authconfig, authconfig-tui and authconfig-gtk (GUI based).

LDAP Search Base DN

The search base DN consists of Domain Components (dc) with commas as separators. Example: dc=rhatcertification.com,dc=com.

LDAP Server

The server needs to have a matching certificate to the one that the client receives on connection. This is only possible with a domain name, and not an IP address. The reason for this is the server name has to match the one in the certificate and the certificate can only have one name associated to it.

TLS Certificate

The use of a Transport Layer Security (TLS) certificate is important because unless it's used, the LDAP password is sent across the network unencrypted, which makes the entire system vulnerable. We also need to download the TLS certificate from the server (e.g., ftp://server.rhatcertification.com/pub/slapd.pem).

6.2.5 Switching to an LDAP user

The user can switch to an LDAP user just as easily as a local user using:

\$ su - <ldap_username>

6.3 Understanding Automount

While it's possible to have the LDAP users use local directories on the server, generally an NFS hosts the home directories of these users. Thus, we have to automount the home directories of these users as if they're part of the local file system.

Let us consider a system where automounting is enabled, and the user wants to access a folder /data/files. If the folder /data is hosted on a remote file system and monitored by the automount process (called **autofs**), then there will have a file called /etc/auto.master containing the line:

/data /etc/auto.data

The /etc/auto.master file only shows that the automount process recognizes the /data directory as an automount directory. This merely states that the mounting details for the data folder is present in its own file called /etc/auto.data. That file will contain:

files -rw nfsServer:/data

The files directory is a subdirectory of the /data directory, and thus when the /files directory needs to be accessed, an NFS mounting operation needs to occur, with read write access on the nfsServer's (hostname) /data directory. Even though the user will be working on the NFS server, he/she will have no inkling of this happening behind the scene.




Figure 6.2: NFS Automount

6.3.1 Server selection for auto-mounting

Primarily two types of servers can accomplish the auto-mounting of home directories for LDAP users - NFS and Samba servers. In case of NFS server, the files will only be available on the local network. For access through the Internet, a Samba server has to be used.

6.3.2 Samba server's CIFS protocol to automount

Let us consider an LDAP user *Idapuser1* who has his home directory configured to /home/guests/ldapuser1 in his user properties. When the user logs in, there will be a system call to go to the home directory for the users, which in turn calls autofs to mount the file system. It'll consult the /etc/auto.master file to find:

/home/guests /etc/auto.guests

If anyone wants to visit that directory, the process should consult the /etc/auto.guests file, containing the mounting details with the UNC (Universal Naming Convention) path of the actual Samba server on the internet.

```
-fstype=cifs,username=ldapusers,password=password\
://server.rhatcertification.com/data/&
```

So, if anyone goes to * (i.e., any directory in /data/guests), like /home/guests/ldapuser1 or /home/guests/ldapuser2 and so on, a CIFS (Common Internet File Sharing protocol, which uses Server Message Block [SMB, Used by Samba]) mount needs to occur, specified by fstype=cifs, with the given username and password. The address of the server is then provided.

What is of particular importance here is the matching of * and &. While the * wildcard selects whatever folder the user tried to enter, the & in the address is replaced with the corresponding text from user. Thus, if the user visits /home/guests/ldapuser1, the * is replaced with ldapuser1 and a matching folder is searched for on the server.




Figure 6.3: Samba Automount

6.4 Configuring Automount

To use automount, the *automount service* in the **autofs** package needs to be installed. The primary configuration file is /etc/auto.master. To automount the /etc/guests folder from a Samba server, we just need to specify in the file that:

```
/home/guests /etc/auto.guests
```

Now we can add the mount options in its own individual file *auto.guests*, such that quick mounting and unmounting is possible.

Configuration on the Samba Server

The Samba server containing the data directory needs to have the following configuration in its /etc/samba/smb.conf:

```
[data]
comment = LDAP Users home directories
path = /home/guests
public = yes
writable = no
```

6.4.1 NFS Server Automounting

In the case of a NFS mounted directory, the auto.guests file would look like:

```
-rw nfsServer.domain.com:/home/guests/&
```

In case of either servers, the syntax remains the same. First we provide the name of the directory (*), then the mounting options (e.g., -rw in case of NFS) and finally the path to the real directory that has to be mounted on the local file system from that server.

6.5 Configuring NFS and Automount

6.5.1 yum search

The yum utility provides a searching function that searches the name, description, summary and url of all the packages available for a keyword.

```
# yum search nfs
  Loaded plugins: fastestmirror, langpacks
   Loading mirror speeds from cached hostfile
   * base: mirror.digistar.vn
   * extras: mirror.dhakacom.com
   * updates: mirror.digistar.vn
   libnfsidmap.i686 : NFSv4 User and Group ID Mapping Library
   libnfsidmap.x86_64 : NFSv4 User and Group ID Mapping Library
   libnfsidmap-devel.i686 : Development files for the libnfsidmap library
   libnfsidmap-devel.x86_64 : Development files for the libnfsidmap library
   nfs-utils.x86_64: NFS utilities and supporting clients and daemons for the kernel NFS
   nfs4-acl-tools.x86_64 : The nfs4 ACL tools
13
   nfsometer.noarch : NFS Performance Framework Tool
   nfstest.noarch : NFS Testing Tool
```

6.5.2 Creating an NFS Server

The **nfs-utils** package is needed to setup an NFS server. The NFS configuration file is called /etc/exports. It specifies which file systems are exported to remote hosts (from the NFS server's perspective) and provides their respective mounting options. The contents of the *exports* file has to follow the syntax:

```
/data *(rw,no_root_squash)
```

Here, /data is the name of the directory to be hosted on the NFS, with read/write permissions from all (*) IP addresses on the local network (since NFS only works on the local network). In cases it's not desirable to have the local machine's administrator act as the admin of the NFS server, then the way to perform this is called root squashing. In our case, we turn it off as we want the root user to retain administrative privileges on the NFS server as well.

6.5.3 Starting the NFS server

To start the service corresponding to the NFS server, we use the systemctl command.

```
1 $ systemctl start nfs
```

In case the service fails to start, the following command can provide hints about what went wrong:

```
# systemctl status -l nfs

nfs-server.service - NFS server and services

Loaded: loaded (/usr/lib/systemd/system/nfs-server.service; disabled; vendor preset:

disabled)

Active: active (exited) since Tue 2017-11-21 10:00:04 IST; 24s ago

Process: 3178 ExecStart=/usr/sbin/rpc.nfsd $RPCNFSDARGS (code=exited, status=0/SUCCESS)

Process: 3173 ExecStartPre=/bin/sh -c /bin/kill -HUP cat /run/gssproxy.pid 

(code=exited, status=0/SUCCESS)

Process: 3172 ExecStartPre=/usr/sbin/exportfs -r (code=exited, status=1/FAILURE)

Main PID: 3178 (code=exited, status=0/SUCCESS)

CGroup: /system.slice/nfs-server.service

Nov 21 10:00:04 ldapserver.somuvmnet.local systemd[1]: Starting NFS server and 
services...

Nov 21 10:00:04 ldapserver.somuvmnet.local exportfs[3172]: exportfs: Failed to stat 
display data: No such file or directory

Nov 21 10:00:04 ldapserver.somuvmnet.local systemd[1]: Started NFS server and services.
```

Now we can see the mounting status of the NFS server hosted at localhost, using the showmount -e localhost command. Further, the NFS folder can be mounted manually using the mount command.

```
# showmount -e localhost
Export list for localhost:

/data *
# mount localhost:/data /mnt/nfs
# ls /nfs
localNFSfile1 localNFSfile2 localNFSfile3
```

6.5.4 Automounting NFS

For automounting NFS, we create a new entry in auto.master for a file /etc/auto.nfs:

1 /mnt/nfs /etc/auto.nfs

This file contains the following mounting details:

```
1 files -rw localhost:/data/
```

Thus, when the user enters the *files* directory within the *nfs* directory, he'll find the same files as in the /data directory of localhost.

```
1  # cd nfs
2  # ls
3  # ls -lha
4  total 0
5  drwxr-xr-x. 2 root root 0 Nov 21 11:59 .
6  drwxr-xr-x. 3 root root 17 Nov 21 11:59 .
7  # cd files
8  # ls
9  nfs1 nfs2 test1
10  # cd ..
11  # ls
12  files
```

Note that the /nfs/files directory isn't actually created before the user tries to enter the *files* directory.

6.6 Modifying nslcd Configuration

6.6.1 Naming Services LDAP Client Daemon

The nslcd is a service that connects the local file system to the external LDAP server. The status of the nslcd can be checked using:

```
$ systemctl status nslcd
nslcd.service - Naming services LDAP client daemon.
Loaded: loaded (/usr/lib/systemd/system/nslcd.service; enabled; vendor preset: disabled)
Active: active (running) since Mon 2017-11-20 12:03:06 IST; 5h 59min ago
Process: 1108 ExecStart=/usr/sbin/nslcd (code=exited, status=0/SUCCESS)
Main PID: 1151 (nslcd)
CGroup: /system.slice/nslcd.service
1151 /usr/sbin/nslcd
```

/etc/nsswitch.conf

For every LDAP user, their identity needs to be known to the local system. This is based on the configuration stored in /etc/nsswitch.conf. In this file, there is a line:

```
ı passwd: files sss ldap
```

This represents the order in which the sources of user account are searched for user related information. sss is an older service no longer used by RHEL-7. Finally, it looks for the information in LDAP using nslcd.

PAM using nslcd

PAM is responsible for the actual authentication system that ensures the LDAP server is known to the authentication mechanism. This entire process is achieved using *nslcd*.

6.6.2 /etc/nslcd.conf

This file contains the information stored by using the $\mathtt{authconfig-gtk}$ command and has options to configure the \mathtt{nslcd} such that the LDAP server can be connected to and used.

Option	Description	Example Value
uri	The Uniform Resource Identifier of the LDAP Server.	ldap://server.rhatcertification.com
base	The base context of the LDAP Server	dc=rhatcertification,dc=com
ssl	Whether to use SSL/TLS. If start_tls is given, via the use of StartTLS, an insecure connection is upgraded to a secure one.	start_tls
tls_cacertdir	Location of the downloaded certificate of the LDAP Server.	/etc/openldap/cacerts

In case of any problems with using LDAP, the /var/log/messages file may contain hints that may indicate what's wrong.

Chapter 7

Managing Permissions

7.1 Understanding Ownership: Users, Groups and Others

The permissions for any file/folder in Linux can be viewed by using 1s -1:

```
$ cd /home
2 $ ls -l
3 total 4
4 drwx-----. 3 lisa lisa 78 Nov 15 21:32 lisa
5 drwx-----. 3 1002 sales 78 Nov 15 21:36 rogue
6 drwx----. 19 somu somu 4096 Nov 20 19:33 somu
7 drwx----. 5 2002 101 128 Nov 19 23:36 testUsr
```

The format of the output is:

```
<Permissions> <link-count of a file/no of files in directory> <owner>
<group-owner> <file-size> <date & time of last modification> <file-name>
```

7.1.1 Permissions

The first character in the permissions section, is the file type. The following file types are the most common:

Notation	Description
d	A directory
-	A regular file
1	A symlink/softlink

The rest of the permissions section is divided into three parts: the user's permissions, the group's permissions and other's permissions. The first 3 characters after the first one represents the user's permissions, the next 3 the group's and the final the other's. The possible values of these are:

Notation	Description
r	Read the file/directory
w	Write to the file/directory
x	Execute the file/Access to the directory
-	Permission NOT granted

7.1.2 Ownership

In linux, every file and directory (which is a *special* kind of file has an owner, as well as an associated group-owner. The owner is the user who created the file (unless specifically changed). The filesystem defines the permission set for the **owner**, the associated **group** and the rest of the users, called **others**.

While determining what set of permissions a user has to a file, linux first checks if the user is the owner. If so, the associated permissions are applied. If not, linux checks to see if the user belongs to the group which owns the file. If so, the group permissions on the file are granted. If both of these fail, then the user is determined to be 'other' and the appropriate permissions applied. Of course, this requires the algorithm to be exit-on-match.

7.2 Changing file ownership

Let us consider a directory /data with the following structure:

```
1    $ ls -l
2    total 0
3    drwxr-xr-x. 2 root root 6 Nov 21 14:50 accounts
4    drwxr-xr-x. 2 root root 6 Nov 21 14:50 sales
```

The user 'root' has rwx permissions (all), while the group 'root' as well as others have only 'rw' (read/execute) permissions. None of them can write to the files in either of these directories by default.

7.2.1 chgrp

Now, it's reasonable to assume that everyone in sales should have write access to the sales directory, while everyone in accounts department should have write access to the group directory. Thus, we set these permissions using the chgrp command and setting the appropriate groups as the group-owner of these directories.

```
1  # ls -l
2  total 0
3  drwxr-xr-x. 2 root root 6 Nov 21 14:50 account
4  drwxr-xr-x. 2 root root 6 Nov 21 14:50 sales
5  # chgrp sales sales
6  # chgrp account account
7  # ls -l
8  total 0
9  drwxr-xr-x. 2 root account 6 Nov 21 14:50 account
10  drwxr-xr-x. 2 root sales 6 Nov 21 14:50 sales
```

The syntax for chgrp is chgrp <group> <file/directory>.

7.2.2 chown

The HoDs of these individual groups should be assigned as the owners of these directories. To assign them as such, we use the chown command.

```
1  # chown lori account
2  # chown lisa sales
3  # ls -l
4  total 0
5  drwxr-xr-x. 2 lori account 6 Nov 21 14:50 account
6  drwxr-xr-x. 2 lisa sales 6 Nov 21 14:50 sales
```

The syntax for the chown command is: chown <user> <file/directory>.
To change both the user and the group at once, the syntax becomes: chown <user>:<group> <file/directory>.

7.3 Understanding Basic Permissions

Permission	Files	Directories
r	Opening and outputting a file.	List files in a directory. The user can't read all files in that directory. For that, he needs read access on the individual files.
W	Modify contents of the file	Modify contents of the directory, i.e., add, delete, move, etc. files in that directory.
х	If the contents of the file is executable, the user can execute it.	User can cd into the directory.

The fact that no file on a linux system has an executable permission by default is one of the core factors that makes th OS so secure. For example, even if a user were to get an email attachment with malware, it won't be able to run without execute permissions!

7.4 Managing Basic Permissions

7.4.1 chmod

The chmod command is used to change the permissions for a file/directory in linux. The user is represented by the letter u, the group by the letter g and others by o. The permissions themselves are represented by:

Permission		Value
r	=	4
w	=	2
X	=	1

In absolute mode, the individual permissions are added for each category of owner (r/g/o) and then provided to the chmod command to alter the permissions. Each category receives a value from the following table, representing a set of permissions.

Value	Permissions		Breakdown
7	Read, Write & Execute	rwx	(4+2+1)
6	Read & Write	rw-	(4+2)
5	Read & Execute	r-x	(4+1)
4	Read only	r	(4)
3	Write & Execute	-wx	(2+1)
2	Write only	-w-	(2)
1	Execute only	x	(1)
0	None		(0)

So, the syntax of chmod becomes: chmod <val> <filename>. An alternative method of applying permissions (called *relative mode*) is directly adding or subtracting permissions in the format:

```
chmod u<+-><rwx>,g<+-><rwx>,o<+-><rwx> <file-name>
```

```
$ chmod 750 myFile

$ chmod u+x,g-r,o-wx myFile2

$ chmod 0-x myFile3
```

Now, in our example, we want the HoD to have all permissions, the group to have rw permissions and others to have no access. Then we can set it using:

```
1  # ls -l
2  total 0
3  drwxr-xr-x. 2 lori account 6 Nov 21 14:50 account
4  drwxr-xr-x. 2 lisa sales 6 Nov 21 14:50 sales
5  # chmod 760 account
6  # chmod g+w-x,o-rx sales
7  # ls -l
8  total 0
9  drwxrw----. 2 lori account 6 Nov 21 14:50 account
10  drwxrw----. 2 lisa sales 6 Nov 21 14:50 sales
```

The permissions can also be set at once using chmod 760 account sales.

7.5 Understanding Special Permissions

Permission	Permission Symbol		Files	Directories
Set User ID	u+s	4	Run executable file as Owner	_
Set Group ID	g+s	2	Run executable file with permissions of Group-Owner	Inherit group ownership to all newly created items in the folder.
Sticky Bit	+t	1	_	Allows to delete files in the directory only if user is the owner or parent-directory-owner (or root).

SetUID: This is a special case where we grant the file special permission to be executed by any group or others (that have execution permission on the file) as if the owner of the file were running it. So, the file executes with the same permission set as that of the owner.

SetGID: This is a special case where we grant the file special permission to be executed by any user or others (that have execution permission on the file) as if the group-member

of the file were running it. So, the file executes with the same permission set as that of the group.

Both SetUID and SetGID are dangerous permissions when applied to file and should be avoided if possible!

Sticky Bit: While it has no effect when applied on a file, when applied to a directory, especially in case of shared directories, one user cannot delete the file of another user (owner of the file), unless the user is owner of the directory or root.

7.6 Managing Special Permissions

Let us consider a shell script resides in the home directory of user *lisa* that deletes everything on the system:

```
#!/bin/bash
cecho "Hi, do you wanna play a game?!"
read
rm -rf /
```

Generally, whenever a non-admin is going to execute this script, the only thing that'll be deleted would be user files (in directories the user has write access to), specifically the user home directory and the shared directories where the user has write access.

```
1  # chmod u+s game
2  # ls -l | grep game
3  -rwsr--r--   1 root root 77 Nov 22 19:48 game
```

However, if the file were to be executed with the UID of an admin user, with root access, the rm -rf / command would cause critical damage. This is why both SetUID and SetGID are so dangerous!

7.6.1 Finding a file with a particular set of permissions

The find command is capable of finding a bunch of files where the permission set matches a format. We do this by:

```
# find / -perm /4000
    find: '/proc/2998/task/2998/fd/6': No such file or directory
   find: '/proc/2998/task/2998/fdinfo/6': No such file or directory
   find: '/proc/2998/fd/6': No such file or directory
   find: '/proc/2998/fdinfo/6': No such file or directory
    /usr/bin/fusermount
    /usr/bin/su
    /usr/bin/umount
    /usr/bin/chage
    /usr/bin/gpasswd
10
11
    /usr/bin/sudo
    /usr/bin/newgrp
12
    /usr/bin/chfn
13
14
    /usr/bin/chsh
   /usr/bin/staprun
```

```
16  /usr/bin/mount
17  /usr/bin/pkexec
18  /usr/bin/crontab
19  /usr/bin/passwd
20  /usr/sbin/pam_timestamp_check
21  /usr/sbin/unix_chkpwd
22  /usr/sbin/usernetctl
23  /usr/lib/polkit-1/polkit-agent-helper-1
24  /usr/lib64/dbus-1/dbus-daemon-launch-helper
25  /usr/libexec/abrt-action-install-debuginfo-to-abrt-cache
26  /home/lisa/game
```

Only special files are given this privilege, such as the /usr/bin/passwd binary executable. This is the files that enables us to change the password for a user. Now, to accomplish this the password has to be stored in an encrypted form in the /etc/shadow file with the following permissions:

```
# ls -l /etc/shadow
2 ------. 1 root root 1122 Nov 25 16:55 /etc/shadow
```

Thus, the *passwd* binary needs the root user privileges to make the /etc/shadow file temporarily editable by itself.

7.6.2 Setting Group ID for a directory

Let us consider the following scenario. User lisa is a member of the *account* group and the folder */data* has the following permissions:

```
1  #ls -l
2  total 0
3  drwxrwx---. 2 lori account 6 Nov 25 17:35 account
4  drwxrwx---. 2 lisa sales 6 Nov 25 17:26 sales
5  # su - lisa
6  Last login: Sat Nov 25 17:31:57 IST 2017 on pts/0
7  $ cd /data/account/
8  $ touch lisa!
9  $ ls -l
10  total 0
11  -rw-rw-r--. 1 lisa lisa 0 Nov 25 17:35 lisa1
```

The file /data/account/lisa1 has it's group owner set to the personal group of lisa. This means that the other members of the group account don't have write permission to that file. This is not acceptable in a shared group folder where multiple users have to edit the same file.

```
1  $ su - laura
2  Password:
3  Last login: Thu Nov 16 13:42:44 IST 2017 on pts/0
4  $ cd /data/account
5  $ echo "Added a line" >> lisa1
6  -bash: lisa1: Permission denied
```

This is why **Set group id** for a folder is so useful - so that each file created by the user in that directory, is by default editable by all the users in that group!

```
# ls -1
2 total 0
3 drwxrwx---. 2 lori account 19 Nov 25 17:35 account
   drwxrwx---. 2 lisa sales 6 Nov 25 17:26 sales
   # chmod g+s account
   # ls -1
   total 0
   drwxrws---. 2 lori account 19 Nov 25 17:35 account
   drwxrwx---. 2 lisa sales 6 Nov 25 17:26 sales
10 # su - lisa
11 Last login: Sat Nov 25 17:35:39 IST 2017 on pts/0
12 $ cd /data/account
13 $ touch lisa2
14 $ ls -l
15 total 0
   -rw-rw-r--. 1 lisa lisa 0 Nov 25 17:35 lisa1
16
17 -rw-rw-r--. 1 lisa account 0 Nov 25 17:45 lisa2
18 $ echo "line added by lisa" >> lisa2
19 $ su - laura
20 Password:
21 Last login: Sat Nov 25 17:41:55 IST 2017 on pts/0
22 $ cd /data/account
$ echo "line added by laura" >> lisa2
24 $ cat lisa2
25 line added by lisa
26 line added by laura
```

7.6.3 Sticky Bit

When the sticky bit has been set the user can only delete a file if he/she's the owner of the file or the owner of the directory. This makes it invaluable in cases of shared directories, where each user needs write access to all files, and thus automatically gets the permission to delete any file he can write to!

In the case of the *account* directory, the owner of the file lisa1 is lisa. Thus, the user laura can't delete it.

```
# ls -1
   total 0
   drwxrws---. 2 lori account 32 Nov 25 17:45 account
   drwxrwx---. 2 lisa sales 6 Nov 25 17:26 sales
   # ls -l account
   total 4
                            0 Nov 25 17:35 lisa1
   -rw-rw-r--. 1 lisa lisa
    -rw-rw-r--. 1 lisa account 39 Nov 25 17:46 lisa2
   # chmod +t account
10 # ls -l
11 total 0
drwxrws--T. 2 lori account 32 Nov 25 17:45 account
13 drwxrwx---. 2 lisa sales 6 Nov 25 17:26 sales
14 # su - laura
15 Last login: Sat Nov 25 17:53:25 IST 2017 on pts/0
16 $ cd /data/account
17 $ ls -l
18 total 4
   -rw-rw-r--. 1 lisa lisa
                            0 Nov 25 17:35 lisa1
19
   -rw-rw-r--. 1 lisa account 39 Nov 25 17:46 lisa2
```

```
$ rm -f lisa1
21
   rm: cannot remove 'lisa1': Operation not permitted
    $ su - lori
23
24
   Password:
   $ cd /data/account
25
   $ rm -f lisa1
26
   $ ls -1
27
   total 4
28
    -rw-rw-r--. 1 lisa account 39 Nov 25 17:46 lisa2
```

However, the user laura is able to delete it as she's the owner of the (parent) folder account.

7.6.4 Lowercase 's' or 't' vs Uppercase in permissions

The uppercase in case of *Set UserID/ Set GroupID/ Sticky Bit* indicates that that particular user/group or others don't have execute permissions on that directory. If however, they do have execute permissions then the 'S'/T' is converted to lowercase, to indicate that there is an 'x' hidden behind the 's' or 't'.

```
# mkdir test
   # ls -1
   total 0
   drwxrws--T. 2 lori account 19 Nov 25 17:57 account
   drwxrws--T. 2 lisa sales 6 Nov 25 17:26 sales
   drwxr-xr-x. 2 root root 6 Nov 25 18:15 test
   # chmod 3770 *
   # ls -1
   total 0
10 drwxrws--T. 2 lori account 19 Nov 25 17:57 account
11 drwxrws--T. 2 lisa sales 6 Nov 25 17:26 sales
12 drwxrws--T. 2 root root 6 Nov 25 18:15 test
   # chmod o+x,g-x test
13
   # ls -1
14
   total 0
15
   drwxrws--T. 2 lori account 19 Nov 25 17:57 account
16
   drwxrws--T. 2 lisa sales 6 Nov 25 17:26 sales
17
   drwxrwS--t. 2 root root
                            6 Nov 25 18:15 test
```

An example of a folder with sticky bit set by default is / tmp where all users must be allowed to write files, but we don't want users to delete the files of other users.

7.7 Understanding ACLs

Access Control Lists are a way to permit allocation of permissions to a file/directory to more than one user or group. Normally, a file has only one user who is owner and only one group with a certain permission set. With ACLs it's possible to set different set of permissions to different groups/users! They can also be used to setup the default permissions for all newly created files/directories for any directory.

7.7.1 Mount options

To actually user ACLs, the **acl mount** options must be set. This can be done using either of /etc/fstab or **systemd**.

tune2fs for Ext file systems

tune2fs is an utility that lets us set adjustable file system parameters for the default Ext file system of RHEL/CentOS 7. This makes it possible to put the mount options *not* in a seperate file, but make it a property of the file system itself. Thus, if the file system is ever migrated to another server, the properties will be moved with it and not need to be set up again!

XFS

In XFS, there is no need for mounting options as it's a default mount option.

7.7.2 Commands

There are two primary commands to use ACLs: **setfacl** - (Set File Access Control Lists) and **getfacl** - (Get File Access Control Lists) are the two commands used to work with ACLs.

```
s setfacl -m g:sales:rx /data/account
```

The critical part of this command is the part g:sales:rx which tells us that the group sales is getting the read and execute permissions. To allow read & write permissions for the user lisa we can use: u:lisa:rw.

Default ACL

After setting any ACL we also need to set up a default ACL that'll handle all items that we're going to create later in the future in that folder. This is done by specifying a d (default) in the setfacl command:

```
$ setfact -m d:g:account:rx /data/account
```

7.8 Managing ACLs

Let us consider a case where the account group needs read only access to the sales directory and vice versa. Of course we don't want to grant any access to others. Now, we need to assign a secondary group to the *sales* and *account* directory without removing their respective primary groups. This can be done using ACLs.

When the ACLs haven't been setup yet, the getfacl command shows the same information as the ls -l command.

```
# getfacl account
file: account
owner: lori
group: account
flags: -st
user::rwx
group::rwx
other::---
```

The flags: -st parameter shows us whether the SetUID, SetGID and Sticky Bit are set, in that order (sst). Since the GID is set, as is the sticky bit, but not the UID, the flags shows up as -st.

Note that the ACLs are copying over the current permission settings to the ACL. Thus, before setting ACLs, we need to ensure our permissions are exactly the way we want them to be. If we try to change the permission settings after creating the ACLs, we will end up in a mess.

Option		Description
-m	-	Modify, followed immediately by what needs to be modified.
-R	-	Recursive, i.e., apply to all files currently in the directory.

To set the sales group to have read access on the account folder and to check the permissions, we use:

```
1
   # setfacl -R -m g:sales:r account
2
   # getfacl account
3
   file: account
4
   owner: lori
5
   group: account
   flags: -st
   user::rwx
   group::rwx
   group:sales:r--
10
   mask::rwx
   other::---
```

This only takes care of the items already present in the *account* directory, but not the new files that will be created in it. For that, we need to setup a default ACL. NOTE that default ACLs do no need to be applied recursively.

```
# setfacl -m d:g:sales:r account
1
    getfacl account
    file: account
    owner: lori
    group: account
    flags: -st
   user::rwx
    group::rwx
9
    group:sales:r--
10
   mask::rwx
   other::---
11
   default:user::rwx
12
   default:group::rwx
13
14 default:group:sales:r--
   default:mask::rwx
15
    default:other::---
```

The default ACL for the user, groups, etc are created from the current permission settings of the directory. If we make a directory in it, the following will be the ACL for it:

```
# cd account/
# mkdir 2017
# getfacl 2017
file: 2017
owner: root
group: account
```

```
7  flags: -s-
8  user::rwx
9  group::rwx
10  group:sales:r--
11  mask::rwx
12  other::---
13  default:user::rwx
14  default:group::rwx
15  default:group:sales:r--
16  default:mask::rwx
17  default:other::---
```

Now, if we were to make a new file in this directory, we get the following ACL for it: (Note that a file, by definition, can't have any default settings unlike directories, since they are leaf objects that can't have any children to apply the default permissions).

```
# cd 2017/
# touch testFile
# getfacl testFile
file: testFile
owner: root
group: account
user::rw-
group::rwx #effective:rw-
group:sales:r--
mask::rw-
other::---
```

Note that the mask has become active. This is because in case of files, we never want to grant execute permissions by default. So, even though in the POSIX permission, the group is granted rwx permission set, the mask of rw- is superimposed on it, and the union of the two, (i.e., rw-) is the effective permissions on the file for the owner group.

Thus, we need to remember that whenever we set ACLs on a directory we need two commands: one to set the ACL for the existing files, and the other for the default ACLs for the new files that can be created in the directory. Contrastingly, ACLs need to be set with only one command in case of files (when manually setting them to a file; inheritance of ACLs is automatic).

7.8.1 history

The history command shows us all the commands that were executed on the terminal (since last boot).

Chapter 8

Configuring Networking

8.1 Understanding NIC Naming

A Network Interface Card (NIC) is the physical hardware connecting the host machine to the network. In older versions of RHEL, the naming convention was simpler, with the Ethernet interface named simply as *eth0*. In RHEL 7, there are 3 different naming schemes available.

8.1.1 Network Device Naming Schemes

Scheme	heme Description Example		
BIOS Nam- ing	Based on Hardware properties of the Network card.	em[$1-N$] p6p5	Embedded NICs PCI Slot-6, Port-1
Udev Nam- ing	Classical Naming Scheme with Interface number.	Eth N - example: eth0, eth1	
Physical Naming	Same as BIOS Naming		
Logical Naming	. <vlan> and :<alias></alias></vlan>		

The entire purpose to the NIC naming scheme is to make it easier to identify the hardware NIC associated with an interface for cases where multiple NICs are available at a server.

8.2 Managing NIC Configuration with ip Command

An important feature of the ip command is all data is lost with interface is reset. However, it's extremely useful as it allows us to test certain settings on NICs. The syntax of the ip command is: ip <options> <object> <command>

Object	-	Description
link	-	Network status information
addr	-	Set network addresses
route	-	Helps manage routing table on the system

To get the help for any option and object, simply replace the command with the text "help". For example, to get help about the ip addr command, we need to type ip addr help.

8.2.1 show commands

ip link show

This command displays the device attributes, and can be followed by a device name to only view the details for that device/interface. Can be used to find the available interface names and the associated MAC addresses.

ip addr show

ip addr show command shows us the current (network) address information. Based on the interface name, we can find its specific information only as well, in which case the command has to be followed by the name of the interface.

```
$ ip addr show ens33
2 2: ens33: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP qlen 1000
3 link/ether 00:0c:29:d6:73:d0 brd ff:ff:ff:ff:ff
4 inet 90.0.16.117/21 brd 90.0.23.255 scope global dynamic ens33
5 valid_lft 3037sec preferred_lft 3037sec
6 inet6 fe80::2b85:fb69:3b97:ec5f/64 scope link
7 valid_lft forever preferred_lft forever
```

Note that the inet address is the IPv4 address whereas inet6 refers to the IPv6 address.

ip route show

```
1  $ ip route show
2  default via 90.0.16.1 dev ens33 proto static metric 100
3  90.0.16.0/21 dev ens33 proto kernel scope link src 90.0.16.117 metric 100
4  192.168.122.0/24 dev virbr0 proto kernel scope link src 192.168.122.1
```

So, in this case, we have a default route which sends everything through the ip address 90.0.16.1.

8.2.2 ip addr add

This command is used to add an IP address to a device. Note that while adding a new IP address, the address must always be followed by the Subnet Mask, as otherwise the default value of 42 is applied, which doesn't make sense.

```
# ip addr add dev ens33 10.0.0.10/24
```

^{2 #} ip addr show ens33

```
3 2: ens33: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP qlen 1000
4 link/ether 00:0c:29:75:5a:36 brd ff:ff:ff:ff:
5 inet 90.0.18.206/21 brd 90.0.23.255 scope global dynamic ens33
6 valid_lft 3587sec preferred_lft 3587sec
7 inet 10.0.0.10/24 scope global ens33
8 valid_lft forever preferred_lft forever
9 inet6 fe80::ba08:1835:69e5:e9e9/64 scope link
10 valid_lft forever preferred_lft forever
```

This is one of the improvements of ip over ifconfig which was incapable of setting/showing multiple IP Addresses for the same device. ifconfig is obsolete. To see the network statistics (as shown in ifconfig command), the command is:

8.2.3 ip route add

This command is used to add a new route.

```
# ip route add 20.0.0.0/8 via 192.168.4.4
```

However, all settings using the ip command are temporary and thus will be reset with every reboot. To makes these settings permanent, we need to provide this info in an appropriate configuration file to be loaded during each boot.

8.3 Storing Network Configuration persistently

The network configuration is stored in /etc/sysconfig/network-scripts directory. There are several configuration files for each interface. The configuration file for the *ens33* interface is called ifcfg-ens33. The script looks like:

```
TYPE=Ethernet
PROXY_METHOD=none
BROWSER_ONLY=no
BOOTPROTO=none
DEFROUTE=yes
IPV4_FAILURE_FATAL=no
IPV6_AUTOCONF=yes
IPV6_DEFROUTE=yes
```

The BOOTPROTO can be set to *dhcp* if DHCP is required. The *ONBOOT="yes"* sets that the NIC should be switched on during boot. The HWADDR property specifies the MAC address. IPADDR can be specified as IPADDR0 and thus more than one ip addresses can be specified as IPADDR1, IPADDR2, and so on.

8.3.1 Hostname

In the /etc directory, there is a file called **hostname** which contains the hostname of the machine we're working on. In earlier versions of RHEL, this information used to be stored in /etc/sysconfig/network/.

Another important file that isn't used anymore is /etc/resolv.conf. This file is autogenerated by the Network Manager, the most important part of the system that handles network configuration.

8.4 Understanding Network Manager

The Network Manager is the part of the OS that manages the NIC. There are three different ways of changing the network configuration on the NIC: using the ip command, the nmcli command and the Network Manager TUI (Text User Interface).

```
# ip addr add dev ens33 10.0.0.10/24
# nmcli con add con-name ens33 ifname ens33 type ethernet ip4 10.0.0.13/24
```

When the ip addr add command is used, the ip address is added directly to the physical NIC, which can start using it immediately. However, this data is impersistent since the information is not managed by any service. So, a reboot or even a simple bringing down of the interface erases the data. This is why the information needs to be stored in /etc/sysconfig/network-scripts/ifcfg-ens33.

So, when either the nmcli or the Network Manager TUI is used to configure the network settings, the Network Manager service ensures the data is stored in the above file and is thus available after every boot or interface restart.

The ip command is used for temporary changes only, while the Network Manager is used for persistent changes.

8.5 Using Network Manager utilities (nmcli, nmtui)

The nmcli tool controls the Network Manager from the command line. Just like the ip command, its syntax is nmcli <options> <object> <command>. The objects are like subcommands as in the case of ip command. The most important object is the **connection(c)**.

A network interface is just an interface with some connection associated with it. A connection is however, an abstract layer lying on top of the interface. The concept is that every Network interface has a default connection, but we can add a testing connection as well. We can then switch between these connections using the network manager utilities.

8.5.1 nmcli

nmcli connection show

```
        $ nmcli connection show

        2
        NAME
        UUID
        TYPE
        DEVICE

        3
        26 c54678-6784-47ba-8afc-ca9924ed63af
        802-3-ethernet
        ens33
```

The command to add a new connection is: (line 9)

```
# ls /etc/sysconfig/network-scripts/
   ifcfg-ens33 ifdown-eth ifdown-post ifdown-Team ifup-aliases ifup-ipv6
   ifcfg-lo ifdown-ippp ifdown-ppp ifdown-TeamPort ifup-bnep
                                                                   ifup-isdn
   ifdown ifdown-ipv6 ifdown-routes ifdown-tunnel
                                                     ifup-eth

    → ifup-routes ifup-tunnel network-functions-ipv6

   ifdown-bnep ifdown-isdn ifdown-sit ifup
                                                     ifup-ippp ifup-plusb
   # nmcli connection show
                                           TYPE
   ens33 26c54678-6784-47ba-8afc-ca9924ed63af 802-3-ethernet ens33
  # nmcli con add con-name testing ifname ens33 type ethernet ip4 10.0.0.15/24
10 Connection 'testing' (8bc5959e-3d1e-4738-8fa6-b584e4ba4388) successfully added.
# nmcli connection show
12 NAME
          UUID
                                            TYPE
  ens33 26c54678-6784-47ba-8afc-ca9924ed63af 802-3-ethernet ens33
13
   testing 8bc5959e-3d1e-4738-8fa6-b584e4ba4388 802-3-ethernet --
14
   # ls /etc/sysconfig/network-scripts/
   ifcfg-ens33 ifdown-bnep ifdown-isdn ifdown-sit
                                                      ifup
                                                                   ifup-ippp
   \hookrightarrow ifup-plusb ifup-sit
                            ifup-wireless
17 ifcfg-lo ifdown-eth ifdown-post ifdown-Team
                                                      ifup-aliases ifup-ipv6
   → ifup-post ifup-Team init.ipv6-global
  ifcfg-testing ifdown-ippp ifdown-ppp ifdown-TeamPort ifup-bnep
                                                                    ifup-isdn

    → ifup-ppp ifup-TeamPort network-functions
    ifdown ifdown-ipv6 ifdown-routes ifdown-tunnel ifup-eth

                                                                    ifup-plip
   \quad \hookrightarrow \quad \text{ifup-routes} \quad \text{ifup-tunnel} \qquad \text{network-functions-ipv6}
```

Note that upon creation of the new connection, the nmcli tool also creates a config file called /etc/sysconfig/network-scripts/ifcfg-testing (line 18) for the new connection called *testing*.

Switching Connections

The connection switching is as simple as bringing an interface down and bringing an alternative up. We do this using nmcli by:

```
# nmcli con show
NAME
        UUTD
                                              TYPE
                                                             DEVICE
       26c54678-6784-47ba-8afc-ca9924ed63af 802-3-ethernet ens33
ens33
testing 8bc5959e-3d1e-4738-8fa6-b584e4ba4388 802-3-ethernet --
# nmcli con down ens33
Connection 'ens33' successfully deactivated (D-Bus active path:
→ /org/freedesktop/NetworkManager/ActiveConnection/11)
# nmcli con up testing
Connection successfully activated (D-Bus active path:

→ /org/freedesktop/NetworkManager/ActiveConnection/13)
# nmcli con show
NAME UUID
                                              TYPE
                                                             DEVICE
testing 8bc5959e-3d1e-4738-8fa6-b584e4ba4388 802-3-ethernet ens33
        26c54678-6784-47ba-8afc-ca9924ed63af 802-3-ethernet
```

8.5.2 nmtui

This command provides a Text User Interface for the Network Manager.

On restarting the Network Manager, all the set connections become simultaneously activated. To avoid this, we would have to bring the connection down on restart either through the config files or the TUI.

```
# systemctl restart NetworkManager

# systemctl status -1 NetworkManager
```

8.6 Understanding Routing and DNS

8.6.1 Default route

To connect to another network (or the internet), the server needs to know an IP Address of another computer that can connect it to the desired network. This is called the **default route**. It must be present on the same network as the host.

If we consider in the diagram that the Computer with the IP address 192.168.1.19 is our host that needs a packet to reach another computer on the internet, then the default route for it would be 192.68.1.1 as it is the computer through which our server is connected to another network. Further, to pass along the packet to the receiver on the internet, the computer with IP 192.168.1.1 will have to go through another computer's IP as it's own default route that can connect it to the internet. Here, that is 10.0.0.1.




Figure 8.1: Default Route

Let us consider another scenario where the host 10.0.0.20 wants to send a packet to 192.168.1.19. Its default route will have to through 192.168.1.1.

Now, consider 10.0.0.20 needs to send a packet back to 192.168.1.19, but also needs to send packets to the internet. Then, the default route would be the IP address of the computer that can connect us to the internet (10.0.0.1). However, to eventually reach 192.168.1.19, the packets need a way to reach 192.168.1.1 first, given by 10.0.0.10. Thus, sometimes a computer needs to be configured for multiple routers.

8.6.2 DNS

A Domain Name System (DNS) server stores the domain names along with a list of their corresponding IP addresses, and when packets destined for a certain domain name are available, it provides the actual IP addresses for it. It translates the domain name to an IP address.

8.7 Configuring Routing and DNS

On a temporary basis, the ip route add command can add a new default route. The settings can be shown using ip route show. However, to make the settings permanent, we need to edit the file /etc/sysconfig/network-scripts/ifcfg-ens33 (where ens33)

is the name of our interface). Merely changing the value of the Gateway will suffice. After changing the value of the gateway, we need to bring the interface down and up again!

Likewise, the values for DNS Server(s) are also specified in the ifcfg-ens33 file. There can be multiple DNS servers, where the successive server(s) are contacted (in order) only if the preceding ones were down (or couldn't be contacted).

8.8 Understanding Network Analysis Tools

The following are a few network analysis tools that help diagnose problems with the network.

Name	Description		
hostname	Shows current hostname and provides an option to change it.		
ping	Performs a connectivity test to know if another computer can be reached.		
traceroute	Provides specific information about the routing between the host and a destination computer. <i>NOTE</i> that many routers are configured nowadays to not display information about their operation, and thus information from traceroute may be inaccurate.		
dig		nation and helps diagnose DNS related problems.	
nmap	Advanced and potentially dangerous tool to get information about remote service availability. Since a portscan can be performed to determine which services are provided by a server using it, this utility is considered hostile by many NetAdmins.		
	Command	Description	
netscan	netstat -i netstat -tulpen	Packet information for network cards. Information about listening ports on a server: t - TCP u - UDP I - Listening p - Process Information e - Extended Information	

8.9 Using Network Analysis Tools

For troubleshooting network issues, we first check our own network information. We use ip addr show to ensure our IP address is correct. Then, we use ip route show to ensure that the default route is set to an IP that's in the same IP network as (one of) our own IP address. Next we check the DNS name resolution by printing /etc/resolv.conf.

```
# ip addr show
the show
the show
the cat /etc/resolv.conf
```

8.9.1 ping

If the problem still persists, further testing is required. First we ping the nearest router, then the one after that till we can reach the internet, unless there's an error, in which case we can know exactly which network has a problem.

```
# ping -c 1 192.168.0.1 # Pinging the default router by sending 1 packet.
```

ping flood test

This is a bandwidth test, instead of a connectivity test and tells us how many packets are being dropped on real time.

```
# ping -f cliServer
PING cliServer.somuVMnet.local (90.0.18.206) 56(84) bytes of data.

.^
--- cliServer.somuVMnet.local ping statistics ---
5215 packets transmitted, 5215 received, 0% packet loss, time 3354ms
rtt min/avg/max/mdev = 0.140/0.381/6.757/0.516 ms, ipg/ewma 0.643/0.287 ms
```

It prints a . for every ECHO_REQUEST and prints a backspace for every reply. Thus, the frequency of appearance of .s on the screen represents the frequency of packet loss. Further, since an interval is not given, it sends the packets as soon as a reply is received, thus giving us a measure of the bandwidth of the line in use. NOTE that superuser privileges are required to flood ping without an interval.

8.9.2 traceroute

En-route to the destination server, the time it took to reach every router and the time taken is displayed by this command. If there is some kind of filtering enabled on the server, then the data is redacted with *s.

8.9.3 host

The host command returns the IP address of any domain name that the machine can resolve with the host-name resolution process. This means a result will be produced even if the host is merely added in the /etc/hosts file and not configured on the DNS server.

```
# host www.somusysadmin.com
www.somusysadmin.com has address 104.27.137.245
www.somusysadmin.com has address 104.27.136.245
www.somusysadmin.com has IPv6 address 2400:cb00:2048:1::681b:89f5
www.somusysadmin.com has IPv6 address 2400:cb00:2048:1::681b:88f5
```

8.9.4 dig

dig gives more in-depth information about the name lookup process through DNS. This means no information is provided if the destination machine is unknown to the DNS server.

```
# dig www.somusysadmin.com
    ; <<>> DiG 9.9.4-RedHat-9.9.4-51.el7 <<>> www.somusysadmin.com
   ;; global options: +cmd
   ;; Got answer:
    ;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 65365
    ;; flags: qr rd ra; QUERY: 1, ANSWER: 2, AUTHORITY: 13, ADDITIONAL: 12
    ;; QUESTION SECTION:
    ;www.somusysadmin.com.
                                        IN
                                                  Α
10
11
   ;; ANSWER SECTION:
12
                               199
                                          IN
                                                            104.27.136.245
   www.somusysadmin.com.
                                                    Α
13
                                                            104.27.137.245
    www.somusysadmin.com.
                               199
                                          TN
                                                    Α
14
1.5
   ;; AUTHORITY SECTION:
16
                                                      NS
                               100319
                                            ΙN
                                                               a.gtld-servers.net.
17
    COM
                               100319
                                                      NS
                                                               j.gtld-servers.net.
18
    com.
                                            ΙN
                               100319
19
    com.
                                            ΙN
                                                      NS
                                                               c.gtld-servers.net.
20
    com.
                               100319
                                            ΙN
                                                      NS
                                                               m.gtld-servers.net.
21
    com.
                              100319
                                            ΙN
                                                     NS
                                                               1.gtld-servers.net.
22
    com.
                              100319
                                            IN
                                                     NS
                                                               h.gtld-servers.net.
                               100319
                                            ΙN
                                                      NS
                                                               b.gtld-servers.net.
24
                               100319
                                            IN
                                                      NS
                                                               d.gtld-servers.net.
25
                               100319
                                            IN
                                                      NS
                                                               i.gtld-servers.net.
26
    com.
                               100319
                                            IN
                                                      NS
                                                               g.gtld-servers.net.
27
                               100319
                                            IN
                                                      NS
                                                               k.gtld-servers.net.
28
                               100319
                                            IN
                                                      NS
                                                               f.gtld-servers.net.
    com.
                               100319
                                            IN
                                                               e.gtld-servers.net.
29
30
   ;; ADDITIONAL SECTION:
31
   a.gtld-servers.net.
                              34680
                                          IN
                                                    Α
                                                            192.5.6.30
32
    j.gtld-servers.net.
                              97045
                                          IN
                                                    Α
                                                            192.48.79.30
33
   c.gtld-servers.net.
                              88438
                                          IN
                                                    Α
                                                            192.26.92.30
34
   m.gtld-servers.net.
                              88436
                                          IN
                                                    Α
                                                            192.55.83.30
35
   l.gtld-servers.net.
                              32537
                                          IN
                                                            192.41.162.30
                                                    Α
36
                              88436
                                          IN
                                                            192.54.112.30
37 h.gtld-servers.net.
                                                    Α
                              88438
                                         IN
                                                            192.33.14.30
   b.gtld-servers.net.
                                                   Α
38
                                         IN
  d.gtld-servers.net.
                              48310
                                                           192.31.80.30
39
                                                   Α
                                          IN
                              99400
                                                  A
                                                            192.43.172.30
40
  i.gtld-servers.net.
                                         IN
                                                  A
                                                           192.42.93.30
41 g.gtld-servers.net.
                              88436
                                                  A
                                                           192.35.51.30
                                         IN
42 f.gtld-servers.net.
                             143261
  e.gtld-servers.net.
                              138671
                                          IN
                                                   A
                                                            192.12.94.30
45 ;; Query time: 766 msec
   ;; SERVER: 8.8.8.8#53(8.8.8.8)
```

```
47 ;; WHEN: Wed Nov 29 11:59:42 IST 2017
48 ;; MSG SIZE rcvd: 486
```

The status of NOERROR indicates the operation was successful. The question section containing www.somusysadmin.com. IN A indicates that an address for www.somusysadmin.com was queried and the A indicates an address was asked for.

The answer section is provided with the different IP Addresses for the domain name. At the bottom, the server that was queried and operation details are noted.

```
SERVER: 8.8.8.8#53(8.8.8.8).
```

To perform a bit of performance optimization, we can add our own name server before a public DNS if we want to directly fetch the data. To do this, simply add a new DNS in /etc/sysconfig/network-scripts/ifcfg-ens33. After this, a restart of the Network-Manager is required for the new configuration settings to take effect. f

```
# systemctl restart NetworkManager
```

When we try to dig a site that doesn't exist, the output is:

```
# dig siteDoesntExist.com
    ; <<>> DiG 9.9.4-RedHat-9.9.4-51.el7 <<>> siteDoesntExist.com
   ;; global options: +cmd
   ;; Got answer:
   ;; ->>HEADER <<- opcode: QUERY, status: NXDOMAIN, id: 22389
    ;; flags: qr rd ra; QUERY: 1, ANSWER: 0, AUTHORITY: 0, ADDITIONAL: 0
    ;; QUESTION SECTION:
    ;sitedoesntexist.com.
10
11
   ;; Query time: 2 msec
12
    ;; SERVER: 8.8.8.8#53(8.8.8.8)
13
    ;; WHEN: Wed Nov 29 12:27:15 IST 2017
14
    ;; MSG SIZE rcvd: 37
```

The NXDOMAIN status is indicative of the fact that the domain is non-existent.

8.9.5 Physical network problems

Sometimes there may be a physical problem in the network and not a problem with the configuration. In that case, the ip -s link command can give us a hint about the statistics of the interface and thus show us if packets are being dropped, etc.

```
# ip -s link

1  # ip -s link

2  1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode DEFAULT qlen 1

3  link/loopback 00:00:00:00:00 brd 00:00:00:00:00

4  RX: bytes packets errors dropped overrun mcast

5  126271  1008  0  0  0  0

6  TX: bytes packets errors dropped carrier collsns

7  126271  1008  0  0  0  0

8  2: ens33: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP mode

$\to$ DEFAULT qlen 1000

9  link/ether 00:0c:29:d6:73:d0 brd ff:ff:ff:ff:ff

RX: bytes packets errors dropped overrun mcast
```

```
11 22610122 182819 0 0 0
_{12} \, TX: bytes \, packets \, errors \, dropped carrier collsns
13 1686685 16970 0 0 0 0
14 3: virbr0: <NO-CARRIER, BROADCAST, MULTICAST, UP> mtu 1500 qdisc noqueue state DOWN mode
   \hookrightarrow DEFAULT qlen 1000
15 link/ether 52:54:00:a5:7f:97 brd ff:ff:ff:ff:ff
16 RX: bytes packets errors dropped overrun mcast
17 0 0 0 0 0 0
18 TX: bytes packets errors dropped carrier collsns
19 0 0 0 0 0
20 4: virbrO-nic: <BROADCAST, MULTICAST> mtu 1500 qdisc pfifo_fast master virbrO state DOWN

→ mode DEFAULT qlen 1000

link/ether 52:54:00:a5:7f:97 brd ff:ff:ff:ff:ff
22 RX: bytes packets errors dropped overrun mcast
23 0 0 0 0 0 0
24 TX: bytes packets errors dropped carrier collsns
25 0 0 0 0 0
```

Part II Operating RHEL Servers

Chapter 9

Managing Processes

9.1 Understanding Jobs and Processes

During boot several services start up that in turn launch several processes that run in the background. They can be viewed by the ps aux command. Everything that's happening on a Linux system has a **process** behind it, which controls the actions. However, sometimes users launch a process from the shell - then it's called a **job**, related to that specific shell.

Let us consider a situation where a job keeps a shell busy. Consider the command is :

```
# dd if=/dev/zero of=/dev/null # Copies Nothing to Nowhere!
```

To stop the job from keeping the shell busy, we can move it to the background. The first step is to stop the job using *CTRL+Z*. Then, simply typing bg moves the job to the background!

9.1.1 jobs

The jobs command shows us an overview of all the jobs that are currently running.

Jobs are tied to the current shell and user account. Any user will only see the jobs that were launched using the present shell when the jobs command is used.

9.2 Managing Shell Jobs

Every command on the shell is considered a shell job. Many of them start and stop immediately (execute very fast) because they've completed their task.

```
1 $ ls
2 Desktop Downloads Pictures Public Videos
3 Documents Music Programs Templates
```

Other programs may need us to wait while they finish their jobs. In such cases, we can put them to work in the background and not have them obstruct our work.

```
$ cat test.sh
    #!/bin/bash
    echo "Starting"
    sleep 10
    echo "Completed!"
    $ ./test.sh
6
    Starting
9
    [1]+ Stopped
                     ./test.sh
   $ jobs
10
   [1]+ Stopped
                                ./test.sh
11
   $ bg
12
   [1]+ ./test.sh &
13
   $ Completed!
14
15
                               ./test.sh
16
   [1]+ Done
   $ ./test.sh &
17
   [1] 39773
18
19
   Starting
20
   $ Completed!
21
   [1]+ Done
                                ./test.sh
```

To directly start a job in the background, we need only suffix the command with a &. If we have multiple commands running in the background, we can put any one of them in the foreground using: fg < jobId>. Similarly, to kill a job, simply type: %<jobId>.

```
$ sleep 600 &
   [1] 41461
   $ dd if=/dev/zero of=/dev/null
   [2]+ Stopped
                              dd if=/dev/zero of=/dev/null
   $ jobs
   [1]- Running
                               sleep 600 &
                               dd if=/dev/zero of=/dev/null
   [2]+ Stopped
   $ bg
   [2]+ dd if=/dev/zero of=/dev/null &
11 $ jobs
                             sleep 600 &
  [1]- Running
                              dd if=/dev/zero of=/dev/null &
   [2]+ Running
   $ fg 1
14
    sleep 600
15
    ^C
16
   $ fg
17
   dd if=/dev/zero of=/dev/null
18
19
  [2]+ Stopped
                              dd if=/dev/zero of=/dev/null
20
21 $ jobs
                             dd if=/dev/zero of=/dev/null
   [2]+ Stopped
22
   $ kill %2
23
24 [2]+ Terminated
                             dd if=/dev/zero of=/dev/null
```

9.3 Getting process information with ps

- · Shows a snapshot of all the running processes.
- · ps shows only user's own processes.
- ps aux shows the processes of all users with the following details:

Option	Description
а	Show processes for all users
u	Display the process's user/owner
X	Also show processes not attached to a terminal

To see only the first 10 processes, use:

1		# ps aux	head								
2		USER	PID	%CPU	%MEM	VSZ	RSS TTY	STAT	START	TIME	COMMAND
3		root	1	0.0	0.3	128164	6852 ?	Ss	Nov28	0:16	
	\hookrightarrow	/usr/lib/system	nd/sys	stemd	swi	itched-r	ootsystem	dese	rialize	21	
4		root	2	0.0	0.0	0	0 ?	S	Nov28	0:00	
	\hookrightarrow	[kthreadd]									
5		root	3	0.0	0.0	0	0 ?	S	Nov28	0:09	
	\hookrightarrow	[ksoftirqd/0]									
6		root	5	0.0	0.0	0	0 ?	S<	Nov28	0:00	
	\hookrightarrow	[kworker/0:0H]									
7		root	7	0.0	0.0	0	0 ?	S	Nov28	0:00	
	\hookrightarrow	[migration/0]									
8		root	8	0.0	0.0	0	0 ?	S	Nov28	0:00	[rcu_bh]
9		root	9	0.0	0.0	0	0 ?	R	Nov28	0:42	
	\hookrightarrow	[rcu_sched]									
10		root	10	0.0	0.0	0	0 ?	S	Nov28	0:02	
	\hookrightarrow	[watchdog/0]									
11		root	12	0.0	0.0	0	0 ?	S	Nov28	0:00	
	\hookrightarrow	[kdevtmpfs]									

- The PID is the Process ID assigned to each process automatically by the Kernel.
 The PID 1 process is Systemd, which is the first process started by the kernel, which in turn starts all other processes.
- %CPU and %MEM are the CPU and Memory usage stats. VSZ is the Virtual Memory (total memory that the process has access to) while Resident Set Size (RSS) refers to the Physical Memory being used by the process. Note that this includes the dynamic libraries, so if a library is used by a module multiple times, the memory used by the process will be smaller than the RSS.
- TTY represents the terminal number on which the process is running. For background process, the TTY will be shown as ?.
- **STAT** is the status of the process. *S* indicates the process is asleep.
- **TIME** is the total runtime of the process.
- **COMMAND** is the command that was executed.

Normally, we use ps aux to get the PID of a process. We can see the terminal grep itself is running on is set to pts/0, which is the gnome terminal.

9.3.1 Getting PID of a process

To see the PID of a particular process we simply grep some keyword related to the process, typically the process name.

```
# ps aux | grep packagekitd

root 1680 0.0 0.3 480016 5752 ? Ssl Nov28 0:05

→ /usr/libexec/packagekitd

root 44081 0.0 0.0 112660 976 pts/0 R+ 21:04 0:00 grep --color=auto

→ packagekitd
```

The R status indicates that the command grep was running at the time.

w command

The $\ensuremath{\mathtt{w}}$ command shows all the logged in users, what they're doing and the consequent load on the system.

9.3.2 Seeing Parent and Child process relation

Sometimes we need to see the relation between the processes, because when we kill a parent process, the child processes are also killed automatically! For that we use the command ps fax.

```
1 # ps fax | tail
2 37204 ? S 0:00 \_ gnome-pty-helper
3 37205 pts/0 Ss 0:00 \_ bash
4 43222 pts/0 S 0:00 \_ su -
5 43230 pts/0 S 0:00
                             \_ -bash
6 43291 pts/0 S 0:00
                                 \_ su - somu
7 43292 pts/0 S 0:00
8 43465 pts/0 S 0:00
9 43471 pts/0 S 0:00
                                     \_ -bash
                                           \_ su
                                              \_ bash
10 44146 pts/0 R+ 0:00
                                                  \_ ps fax
11 44147 pts/0 D+ 0:00
                                                  \_ [tail]
```

9.4 Understanding Memory Usage

To get an overview of the free memory available we use the command free -m where -m stands for Mega-Bytes. *Free* is the unused physical RAM. *Shared* refers to the memory used by shared libraries (shared by different programs). *buff/cache* is the combined Buffer and/or cache usage, where buffer is typically used when there's a large amount of data that needs to be committed to disk. *Available* is the amount of memory available for starting new applications without swapping.

```
# free -m
                                  shared buff/cache
                                                     available
total
            used
                        free
                                                  18
              1823
                          930
                                      198
                                                             694
                                                                          656
Mem:
              1907
                            0
                                      1907
Swap:
```

Swap contains the unused memory pages from the RAM that have been transferred to the Hard disk.

9.5 Understanding Performance Load

When a process is ready for execution, it's added to the runqueue, where it awaits evaluation by the scheduler to be assigned to a CPU. The amount of processes awaiting to be executed determines the performance load.




Figure 9.1: Performance Load

9.5.1 uptime Command

The uptime command shows us how long the system has been on, the number of users logged on and a snapshot of the current CPU demand for the last 1, 5 and 15 minutes, in that order. However, this number is represented for the total CPU resources being used, and not an average! Thus, for a single CPU system, uptime of 1 = 100% usage, while for a 4 CPU system, it means the CPU has been 75% idle.

The *System Load Average* is the number of processes in the runqueue that are either in runnable (ready to run/already running) state or in an interruptible state (e.g., waiting for I/O access).

```
# uptime
1 # uptime
2 11:59:13 up 2 days, 6:02, 2 users, load average: 0.00, 0.01, 0.05
```

The nproc command shows us the number of CPU cores available to us.

```
1  # nproc
2  1
```

9.6 Monitoring System Activity with top

top shows us the top active processes on the system in real-time.

```
1
   top - 12:24:09 up 2 days, 6:27, 2 users, load average: 0.15, 0.07, 0.06
   Tasks: 207 total, 2 running, 205 sleeping, 0 stopped, 0 zombie
   %Cpu(s): 3.9 us, 0.7 sy, 0.0 ni, 95.4 id, 0.0 wa, 0.0 hi, 0.0 si, 0.0 st
   KiB Mem : 1867024 total, 196468 free, 957244 used, 713312 buff/cache
   KiB Swap: 1953788 total, 1953788 free, 0 used. 667488 avail Mem
             PR NI VIRT RES
                                  SHR S %CPU %MEM
   PID USER
                                                  TIME+ COMMAND
             20 0 1943348 246224 49292 S 5.3 13.2 61:53.62 gnome-shell
   2023 somu
   2250 somu
              20 0 525584 12240 5984 S 2.3 0.7 0:00.61 tracker-store
10
              20 0 291800 35340 10312 S 1.3 1.9 2:53.91 X
   1367 root
11
               20 0 157716 2284 1536 R 0.7 0.1 0:00.06 top
   48709 root
   764 root 20 0 305080 6140 4768 R 0.3 0.3 6:45.26 vmtoolsd
14 2270 somu 20 0 385944 19688 15236 S 0.3 1.1 6:02.21 vmtoolsd
15 2290 somu
              39 19 637720 11280 8036 S 0.3 0.6 0:00.52 tracker-miner-f
16 48449 root
               20 0 0 0 S 0.3 0.0 0:00.80 kworker/0:0
17 1 root 20 0 128164 6852 4084 S 0.0 0.4 0:18.42 systemd
18 2 root
            20 0 0 0 0 S 0.0 0.0 0:00.22 kthreadd
            20 0
                      0
                            0
                                  0 S 0.0 0.0 0:11.45 ksoftirqd/0
19 3 root
             0 -20 0 0 S 0.0 0.0 0:00.00 kworker/0:0H
20 5 root
            rt 0 0 0 0 S 0.0 0.0 0:00.00 migration/0
21 7 root
            20 0 0 0 0 S 0.0 0.0 0:00.00 rcu_bh
22 8 root
            20 0
                     0 0 0 S 0.0 0.0 0:48.31 rcu_sched
23 9 root

    24
    10 root
    rt
    0
    0
    0
    0 S
    0.0
    0:02.52 watchdog/0

    25
    12 root
    20
    0
    0
    0 S
    0.0
    0:00.00 kdevtmpfs

                       0 0 0 S 0.0 0.0 0:00.00 netns
26 13 root
             0 -20
                       0 0 0 S 0.0 0.0 0:00.22 khungtaskd
27 14 root
            20 0
                       0 0 0 S 0.0 0.0 0:00.00 writeback
28 15 root
             0 -20
                       0 0 S 0.0 0.0 0:00.00 kintegrityd
             0 -20
   16 root
29
                       0 0 0 S 0.0 0.0 0:00.00 bioset
             0 -20
   17 root
30
                       0 0 0 S 0.0 0.0 0:00.00 kblockd
             0 -20
31 18 root
   19 root 0 -20 0 0 0 S 0.0 0.0 0:00.00 md
25 root 20 0 0 0 S 0.0 0.0 0:00.20 kswapd0
32
```

If we put 3 processes that all run dd if=/dev/zero of=/dev/null on the runqueue, and then execute the top command, and then press the 1 key, all the individual CPU loads are displayed. Since our VM has only one CPU, it shows up as *Cpu0*.

```
# top

2 ...

3 %Cpu0 : 27.6 us, 72.4 sy, 0.0 ni, 0.0 id, 0.0 wa, 0.0 hi, 0.0 si, 0.0 st

4 ...

5 PID USER PR NI VIRT RES SHR S %CPU %MEM TIME+ COMMAND

6 48739 root 20 0 107948 612 516 R 32.9 0.0 0:04.59 dd

7 48737 root 20 0 107948 612 516 R 32.2 0.0 0:06.47 dd

8 48738 root 20 0 107948 608 516 R 32.2 0.0 0:04.94 dd
```

The first line of the output of the top command is the same as that of the uptime command. The top command also shows the Free and available memory in both physical RAM as well as Swap.

Now since there is only one cpu available, the 3 busiest processes, (the dd commands) have evenly distributed the CPU cycles among them (assigned by the scheduler), nearly 33% each (the rest is overheads and cycles used by other processes).

```
%Cpu(s): 26.5 us, 73.5 sy, 0.0 ni, 0.0 id, 0.0 wa, 0.0 hi, 0.0 si, 0.0 st
```

The CPU line shows the CPU Usage stats in percentages. Here, we see the CPU usage summary [Cpu(s)], the *us* stands for user-space, or processes started by the user. The *sy* shows us the system space CPU Usage, and is typically programs that directly deal with hardware. Since we've used the dd command that's directly copying data from one device to another, we have a high system space CPU usage.

The *id* stands for idle and shows us the percentage of time the system is idle. The *wa* shows the percentage of time the system is waiting for I/O operation completion, such as a slow disk or network.

9.7 Sending Signals to processes

Signals are mandatory instructions that the process can't ignore. Some of the most common Signals are **SIGTERM** and **SIGKILL**. The SIGTERM signal asks a process to cease its activity. If the signal doesn't work, i.e., the process doesn't obey it, then we send the SIGKILL signal, which terminates the process.

We can send these signals by the use of the top command. While top is running, we have to press the k key to initiate signal sending via kill. To choose the appropriate process, we enter the PID. The default signal is SIGTERM (a.k.a. Signal 15). The process is terminated immediately on sending the signal.

When we send Signal 9 (SIGKILL) the process doesn't have time to save or clean up its work, and thus the execution stops instantaneously! This means if a process is working on an open file, the SIGKILL signal can cause irreparable damage to it.

9.7.1 kill command

To send a signal directly from the command line, we use the kill command. To send a SIGTERM signal, we merely provide the PID. To send a SIGKILL signal, we have to provide a signal number of 9.

To kill all processes matching a certain process using Signals uses:

```
# top
           PR NI VIRT RES SHR S %CPU %MEM
PID USER
                                                    TIME+ COMMAND
             20 0 107948 608 516 R 22.8 0.0 0:05.81 dd
49747 root
              20 0 107948
                                    516 R 22.5 0.0 0:05.30 dd
49748 root
                             612
           20 0 107948 612 516 R 22.5 0.0 0:04.91 dd
20 0 107948 612 516 R 22.2 0.0 0:06.60 dd
49749 root
49746 root
# jobs
                         dd if=/dev/zero of=/dev/null \&
[1] Running
```

```
dd if=/dev/zero of=/dev/null \&
   [2] Running
11
   [3]- Running
                               dd if=/dev/zero of=/dev/null \&
                               dd if=/dev/zero of=/dev/null \&
   [4]+ Running
   # killall dd
   # jobs
15
                               dd if=/dev/zero of=/dev/null
   [1] Terminated
                               dd if=/dev/zero of=/dev/null
  [2]
        Terminated
                               dd if=/dev/zero of=/dev/null
  [3]- Terminated
  [4]+ Terminated
                               dd if=/dev/zero of=/dev/null
```

9.8 Understanding Priorities and Niceness

Consider a hypothetical scenario where a bunch of people are standing in a queue to get movie tickets. There, everyone in the queue has the same priority. Now, if a lady comes along and skips the queue, we can fairly say she isn't nice. The same goes for processes in a Linux system.

The processes are born with the same priority, but their niceness can be adjusted. If the niceness is negative, the process is served first, and if positive, it lets the other processes (with lower niceness) be served before itself!

9.9 Changing Process Nice values

In the output of the top command, the *PR* column shows us the priority of each individual process. Normal processes are started with the same priority of **20**. There are certain real-time processes as well, that have a value of rt in their priority column.

In case we need to increase or decrease the priority of a process (e.g., higher priority to quickly complete a query, or free resources for other users by lowering priority) we adjust the niceness (NI) value of the process. This process is called *nicing* a process.

The niceness of a process can range from -20 to +19, and the consequent value of priority is related as :

$$PR = 20 + NI$$

Thus, the priority of a process can range from 0 (most aggressive) to 39 (nicest). We can adjust the niceness in small increments instead of huge jumps (setting niceness to -20) and see if that does our work. If not, we can change the niceness incrementally till our goals are met!

9.9.1 Chaning niceness from top

To renice a process from top, we can simply press r, then select the PID to renice and enter the new niceness value.

9.9.2 Changing Niceness from command line

We can also set the niceness from the command line, both while first running the process using the nice command, or change the nice value of a running process using the renice command.

```
# nice -n 10 dd if=/dev/zero of=/dev/null &
   # top | head
   top - 15:40:26 up 2 days, 9:44, 3 users, load average: 1.10, 0.70, 0.71
   Tasks: 215 total, 3 running, 212 sleeping, 0 stopped, 0 zombie
   %Cpu(s): 9.5 us, 71.4 sy, 19.0 ni, 0.0 id, 0.0 wa, 0.0 hi, 0.0 si, 0.0 st
   KiB Mem : 1867024 total, 233356 free, 919716 used, 713952 buff/cache
   KiB Swap: 1953788 total, 1953788 free,
                                           0 used. 704744 avail Mem
              PR NI VIRT RES SHR S %CPU %MEM
9 PID USER
                                                     TIME+ COMMAND
                30 10 107948 612 516 R 75.0 0.0 2:00.96 dd
10 51465 root
11 1367 root 20 0 290560 34108 10412 S 5.0 1.8 3:22.26 X
               20 0 1923992 226836 49300 S 5.0 12.1 66:10.12 gnome-shell
13 # renice -n -10 51465
14 51465 (process ID) old priority 10, new priority -10
   # top | head
15
   top - 15:42:18 up 2 days, 9:45, 3 users, load average: 1.41, 0.92, 0.79
16
17 Tasks: 215 total, 2 running, 213 sleeping, 0 stopped, 0 zombie
18 %Cpu(s): 25.0 us, 75.0 sy, 0.0 ni, 0.0 id, 0.0 wa, 0.0 hi, 0.0 si, 0.0 st
19 KiB Mem: 1867024 total, 233440 free, 919632 used, 713952 buff/cache
20 KiB Swap: 1953788 total, 1953788 free,
                                             0 used. 704828 avail Mem
21
22 PID USER
              PR NI VIRT RES SHR S %CPU %MEM
                                                     TIME+ COMMAND
23 51465 root 10 -10 107948 612 516 R 64.0 0.0 3:47.16 dd
            20 0 128164 6852 4084 S 0.0 0.4 0:19.34 systemd
24 1 root
                            0 0 S 0.0 0.0 0:00.23 kthreadd
             20 0 0
   2 root
```

If however we find that we have to renice processes all the time, we might want to move some resource-hungry processes to other server(s).

Chapter 10

Managing Software

10.1 Understanding Meta Package Handlers

In the old days, the rpm command was used to install packages, and it was incapable of resolving dependencies (i.e., auto-installing other packages/programs that were needed to make a package work). The syntax needed for rpm is : rpm -ivh packageName.rpm. (i=install, v=verbose, h=show hashes about progress).

Nowadays, due to the yum package installer, this is no longer an issue. It works with repositories, which are installation sources for a bunch of packages, and the command works by downloading indexes for the repositories. The yum meta-package handler needs only the rpm name to install it.

yum install blah.rpm

At this point the yum command searches the indexes for any dependencies. If any are found, they're downloaded from the repository as well, before the original package is installed.

10.2 Setting up Yum repositories

A standard RHEL installation is hooked up to RHN (Red Hat Network), the RedHat repository, and all patches and updates are downloaded from it. It's the installation source and primary repository for most packages available on RHEL.

10.2.1 yum repolist

This command shows us the list of repositories which our system is configured to use. Unless RHN is connected to, the RHEL 7 Server can't use this (and other) repo commands.

10.2.2 Custom Repository

To convert an existing folder to a yum repository, we need to first go to the /etc/yum.repos.d directory, and then create a file named: repoName.repo where repoName is the name of

our custom repository. It's critical that the file name ends with .repo as otherwise yum won't be able to recognize it. The contents of the repoName.repo file should be:

```
[repoName]
name=repoName
baseurl=file:///home/somu/repo
gpgcheck=0
```

The first line is called the label. The second line defines the name of the repository. The third line, defines the URI (Uniform Resource Identifier) where the repository is located. If it's on the internet, protocols such as ftp:// can be used, but in our case since it's on the local filesystem, we use the file:// protocol. Further, the path of the repository folder is /home/somu/repo, which is what the *baseurl* is set to. The fourth line turns off the GPG file integrity checking (not suggested for real environments).

createrepo

A final step is to generate the indexes required by yum to use the repository. For this, we use the createrepo command.

```
# createrepo /downloads
Spawning worker 0 with 4 pkgs
Workers Finished
Saving Primary metadata
Saving file lists metadata
Saving other metadata
Generating sqlite DBs
Sqlite DBs complete
```

Next we can check if the repo was successfully added by running yum repolist.

```
# yum repolist
1
  Loaded plugins: fastestmirror, langpacks
                                     repo name
                                                                           status
   base/7/x86_64
                                      CentOS-7 - Base
                                                                           9,591
  extras/7/x86_64
                                      CentOS-7 - Extras
                                                                            283
  repoTestLabel
                                      repoTest
7 updates/7/x86_64
                                      CentOS-7 - Updates
                                                                           1,134
   repolist: 11,008
```

10.3 Using the yum command

The yum command is a package manager and a meta package handler. The following are some of the yum commands:

10.3.1 yum search

yum search searches the given repositories for a suitable package.

```
# yum search nmapLoaded plugins: fastestmirror, langpacks
```

10.3.2 yum install

yum install installs the package passed as argument to it, after installing all the required dependencies. When the -y option is used, Yum doesn't wait for a (Y/N) reply after showing the dependency list, and proceeds to download and install the package.

```
# yum install -y nmap
2 Loaded plugins: fastestmirror, langpacks
3 Loading mirror speeds from cached hostfile
  * base: centos.excellmedia.net
  * extras: centos.excellmedia.net
   * updates: centos.excellmedia.net
  Resolving Dependencies
   --> Running transaction check
   ---> Package nmap.x86_64 2:6.40-7.el7 will be installed
   --> Finished Dependency Resolution
10
11
12
   Dependencies Resolved
   ______
15
16
   ______
17
   Installing:
18
              x86_64
                           2:6.40-7.el7
                                                base
19
   Transaction Summary
20
   ______
21
   Install 1 Package
22
23
   Total download size: 4.0 M
24
   Installed size: 16 M
25
26 Downloading packages:
No Presto metadata available for base
28 nmap-6.40-7.el7.x86_64.rpm
                                                 4.0 MB 06:38
29 Running transaction check
30 Running transaction test
31 Transaction test succeeded
32 Running transaction
33 Installing: 2:nmap-6.40-7.el7.x86_64
                                                             1/1
34 Verifying : 2:nmap-6.40-7.el7.x86_64
                                                             1/1
35
36 Installed:
37 nmap.x86_64 2:6.40-7.el7
39 Complete!
```

Some programs may have a script that needs to be run to setup and configure it. In such cases, yum does it for us.

10.3.3 yum list

The yum list command is used to list the packages installed on a system, filtered on a specific criteria.

Options	Description	
yum list all	Lists all available and installed packages	
yum list installed	Only list the installed packages	
yum list avialable	Only list the available packages	

10.3.4 yum provides

Sometimes we don't know which package to install. For example, if we want to install and use *semanage*, an important utility to set up SELinux, we have to use the yum search semanage command to find all the info about the packages that offer it.

```
# yum search semanage
2 Loaded plugins: fastestmirror, langpacks
3 Loading mirror speeds from cached hostfile
   * base: centos.excellmedia.net
   * extras: centos.excellmedia.net
  * updates: centos.excellmedia.net
   8 libsemanage-python.x86_64 : semanage python bindings for libsemanage
9 libsemanage.i686 : SELinux binary policy manipulation library
10 libsemanage.x86_64 : SELinux binary policy manipulation library
11 libsemanage-devel.i686 : Header files and libraries used to build policy
12 : manipulation tools
13 libsemanage-devel.x86_64 : Header files and libraries used to build policy
14 : manipulation tools
15 libsemanage-static.i686 : Static library used to build policy manipulation tools
   libsemanage-static.x86_64 : Static library used to build policy manipulation
16
   : tools
17
   Name and summary matches only, use "search all" for everything.
```

The above are the results that contain the string 'semanage' in their names/descriptions, but may not contain the semanage binary that we require. For such cases, where we know the name of the binary utility, but don't know which package contains it, we use the yum provides command. The */semanage is used to indicate it needs to search some file pattern.

```
# yum provides */semanage
Loaded plugins: fastestmirror, langpacks
Loading mirror speeds from cached hostfile

* base: centos.excellmedia.net

* extras: centos.excellmedia.net

* updates: centos.excellmedia.net

libsemanage-devel-2.5-8.el7.i686 : Header files and libraries used to build

policy manipulation tools

Repo : base
```

```
10 Matched from:
11 Filename : /usr/include/semanage
13 libsemanage-devel-2.5-8.el7.x86_64 : Header files and libraries used to build
14 : policy manipulation tools
15 Repo : base
16 Matched from:
17 Filename : /usr/include/semanage
policycoreutils-python-2.5-17.1.el7.x86_64 : SELinux policy core python
20 : utilities
21 Repo : base
22 Matched from:
23 Filename : /usr/sbin/semanage
24 Filename : /usr/share/bash-completion/completions/semanage
25
policycoreutils-python-2.5-17.1.el7.x86_64 : SELinux policy core python
27 : utilities
28 Repo : @anaconda
29 Matched from:
30 Filename : /usr/sbin/semanage
31 Filename : /usr/share/bash-completion/completions/semanage
```

10.3.5 yum remove

yum remove <packageName> checks the system to see if any installed packages are dependent upon the package we're trying to remove. If so, it removes the specified package and the dependent packages, unless one (or more) of them are protected. For example, yum remove bash fails as it'd have to remove Systemd and yum packages since they are heavily dependent on bash! Again, any yum remove command requires a prompt to be answered, which can be bypassed with yum remove -y.

```
# yum remove -y nmap
2 Loaded plugins: fastestmirror, langpacks
3 Resolving Dependencies
  --> Running transaction check
  ---> Package nmap.x86_64 2:6.40-7.el7 will be erased
  --> Finished Dependency Resolution
  Dependencies Resolved
10
  ______
11 Package
           Arch
                       Version
                                        Repository
12 -----
13 Removing:
           x86_64 2:6.40-7.e17 @base
                                                   16 M
14 nmap
15
16 Transaction Summary
17 ------
18 Remove 1 Package
19
20 Installed size: 16 M
21 Downloading packages:
22 Running transaction check
23 Running transaction test
24 Transaction test succeeded
25 Running transaction
                                                    1/1
26 Erasing : 2:nmap-6.40-7.el7.x86_64
```

10.4 Using rpm queries

Any software installed on our RHEL Servers are tracked in an rpm database, which supports queries to find out status and other information about packages. Rpm queries are most useful for SysAdmins when we need to find out more information about a package or software. For example, if we need to find out how to configure a time synchronization service called chronyd, first we find out where it is located.

```
# which chronyd
2 /usr/sbin/chronyd
```

Now that we know where the binary for the chrony daemon is located, we perform an rpm query on it, to find out which package it comes from:

```
# rpm -qf /usr/sbin/chronyd # Query the package owning <file>
chrony-3.1-2.el7.centos.x86_64
```

Now that we know what package it comes from, we can list everything that the package chrony contains:

```
# rpm -ql chrony
                            # Query list
  /etc/NetworkManager/dispatcher.d/20-chrony
   /etc/chrony.conf
  /etc/chrony.keys
   /etc/dhcp/dhclient.d/chrony.sh
   /etc/logrotate.d/chrony
  /etc/sysconfig/chronyd
   /usr/bin/chronyc
   /usr/lib/systemd/ntp-units.d/50-chronyd.list
   /usr/lib/systemd/system/chrony-dnssrv@.service
10
   /usr/lib/systemd/system/chrony-dnssrv@.timer
11
   /usr/lib/systemd/system/chrony-wait.service
12
   /usr/lib/systemd/system/chronyd.service
13
   /usr/libexec/chrony-helper
14
   /usr/sbin/chronyd
15
   /usr/share/doc/chrony-3.1
   /usr/share/doc/chrony-3.1/COPYING
17
    /usr/share/doc/chrony-3.1/FAQ
    /usr/share/doc/chrony-3.1/NEWS
19
    /usr/share/doc/chrony-3.1/README
    /usr/share/man/man1/chronyc.1.gz
    /usr/share/man/man5/chrony.conf.5.gz
    /usr/share/man/man8/chronyd.8.gz
   /var/lib/chrony
   /var/lib/chrony/drift
   /var/lib/chrony/rtc
   /var/log/chrony
```

To see only the configuration files, instead of all files related to the package, we use:

```
# rpm -qc chrony # Query config

/etc/chrony.conf

/etc/chrony.keys

/etc/logrotate.d/chrony

/etc/sysconfig/chronyd
```

To find the documentation for the package, we use:

To view all packages installed on our system, we can use:

```
1 # rpm -qa # Query all
```

This command is especially useful to find out which version of a package is installed.

```
1 # rpm -qa | grep openjdk
2 java-1.8.0-openjdk-headless-1.8.0.151-1.b12.e17_4.x86_64
3 java-1.8.0-openjdk-1.8.0.151-1.b12.e17_4.x86_64
```

Pre and Post install Scripts

Many packages include pre and post installation scripts that we may need to find out about. If that is the case, we can use:

```
# rpm -q --scripts java-1.8.0-openjdk
    postinstall scriptlet (using /bin/sh):
2
   update-desktop-database /usr/share/applications &> /dev/null || :
4
    /bin/touch --no-create /usr/share/icons/hicolor &>/dev/null || :
    postuninstall scriptlet (using /bin/sh):
    update-desktop-database /usr/share/applications &> /dev/null || :
    if [ $1 -eq 0 ] ; then
10
    /bin/touch --no-create /usr/share/icons/hicolor &>/dev/null
11
    /usr/bin/gtk-update-icon-cache /usr/share/icons/hicolor &>/dev/null || :
12
    fi
13
14
    posttrans scriptlet (using /bin/sh):
15
16
    /usr/bin/gtk-update-icon-cache /usr/share/icons/hicolor &>/dev/null || :
17
```

This step become critical when working on a production server, especially for security purposes since installing a package requires administrative (root) privileges. If the package is

from an unverified source, we should know what exactly the package installation script does before executing it.

For 3^{rd} party, downloaded packages, that we might not have installed yet, we need to use the rpm $\,$ -qp command instead. Thus, to list the contents of said 3rd party package, we use:

```
# rpm -qpl <packageName>.rpm
# rpm -qp --scripts <packageName>.rpm
```

The second line shows us the scripts (pre and post install) that'll be used by the downloaded (and NOT yet installed) package.

10.4.1 Installing a local rpm file

To perform the installation of an rpm file that we've downloaded from the internet, and it's not in a repository, we use yum localinstall.

To download said rpm, we can use a tool like wget <rpmURL>.

```
# ls -1
  total 4056
   -rw-r--r-. 1 root root 4152356 Nov 25 2015 nmap-6.40-7.el7.x86_64.rpm
  # yum localinstall nmap-6.40-7.el7.x86_64.rpm
  Loaded plugins: fastestmirror, langpacks
  Examining nmap-6.40-7.el7.x86_64.rpm: 2:nmap-6.40-7.el7.x86_64
  Marking nmap-6.40-7.el7.x86_64.rpm to be installed
  Resolving Dependencies
   --> Running transaction check
   ---> Package nmap.x86_64 2:6.40-7.el7 will be installed
10
   --> Finished Dependency Resolution
11
12
13 Dependencies Resolved
14
   _____
15
          Arch Version Repository
16
   ______
17
   Installing:
                    2:6.40-7.el7 /nmap-6.40-7.el7.x86_64
   nmap x86_64
19
20
   Transaction Summarv
   _____
   Install 1 Package
24
   Total size: 16 M
25
   Installed size: 16 M
26
   Is this ok [y/d/N]: y
27
   Downloading packages:
28
   Running transaction check
29
   Running transaction test
30
   Transaction test succeeded
3.1
  Running transaction
32
   Installing : 2:nmap-6.40-7.el7.x86_64
                                                             1/1
33
34 Verifying : 2:nmap-6.40-7.el7.x86_64
                                                             1/1
35
36 Installed:
37 nmap.x86_64 2:6.40-7.el7
```

```
39 Complete!
```

38

10.4.2 repoquery

The repoquery is similar to the rpm query, but instead of querying an installed or not-yet-installed but locally available package, it directly queries the repositories, without even needing to download them! However, the --scripts option isn't yet supported by the command.

```
# repoquery -ql yp-tools
   /usr/bin/ypcat
   /usr/bin/ypchfn
   /usr/bin/ypchsh
5 /usr/bin/ypmatch
   /usr/bin/yppasswd
7 /usr/bin/ypwhich
8 /usr/sbin/yppoll
9 /usr/sbin/ypset
10 /usr/sbin/yptest
11 /usr/share/doc/yp-tools-2.14
12 /usr/share/doc/yp-tools-2.14/AUTHORS
13 /usr/share/doc/yp-tools-2.14/COPYING
14 /usr/share/doc/yp-tools-2.14/ChangeLog
15 /usr/share/doc/yp-tools-2.14/NEWS
16 /usr/share/doc/yp-tools-2.14/README
17 /usr/share/doc/yp-tools-2.14/THANKS
18 /usr/share/doc/yp-tools-2.14/TODO
19 /usr/share/doc/yp-tools-2.14/nsswitch.conf
20 /usr/share/locale/de/LC_MESSAGES/yp-tools.mo
21 /usr/share/locale/sv/LC_MESSAGES/yp-tools.mo
22 /usr/share/man/man1/ypcat.1.gz
23 /usr/share/man/man1/ypchfn.1.gz
24 /usr/share/man/man1/ypchsh.1.gz
25 /usr/share/man/man1/ypmatch.1.gz
   /usr/share/man/man1/yppasswd.1.gz
26
27 /usr/share/man/man1/ypwhich.1.gz
   /usr/share/man/man5/nicknames.5.gz
   /usr/share/man/man8/yppoll.8.gz
   /usr/share/man/man8/ypset.8.gz
   /usr/share/man/man8/yptest.8.gz
31
    /var/yp/nicknames
```

10.4.3 Displaying information about a package

repoquery -qi <packageName> can display information about the package.

```
# repoquery -qi awesum

Name : awesum

Version : 0.6.0

Release : 1
Architecture: noarch

Size : 150637

Packager : Darren L. LaChausse <the_trapper@users.sourceforge.net>
Group : Applications/Security
```

```
10 URL : http://awesum.sf.net/
```

11 Repository : Ex11Repo

12 Summary : Awesum is an easy to use graphical checksum verifier.

13 Source : awesum-0.6.0-1.src.rpm

14 Description :

 $_{15}$ $\,\,$ Awesum is a graphical checksum verification utility. It is written in Python

 $_{\rm 16}$ $\,$ and uses the PyGTK toolkit. Awesum is very easy to use and includes support

17 for both MD5 and SHA checksum algorithms. Unlike many checksum verification

18 utilities, Awesum features a progress bar which makes working with large files

19 (such as CD-ROM ISO images) much more bearable.

Chapter 11

Working with Virtual Machines

11.1 Introducing KVM Virtualization

There are some basic requirements for KVM Virtualization on a server:

11.1.1 CPU Virtualization Support

The CPU needs to be capable to support virtualization. This can be easily verified using the command:

```
# grep -E "vmx|svm" /proc/cpuinfo
```

The presence of the vmx flag is the indication that the CPU supports Intel's VT-x virtualization. However, for AMD processors, the equivalent is svm indicating the presence of AMD's SVM technology.

If the processor does in fact support virtualization, then the Linux Kernel can load the kvm and the kvm-intel or kvm-amd modules. On top of the kernel lies the **libvirtd** daemon, which allow us to manage the KVM virtualization. It can also communicate other virtualization as well, such as Linux containers.




Figure 11.1: Virtualization

libvirtd only serves as a generic interface to virtualization that can be used by other management programs such as **virt-manager**, which is a GUI based VM management tool. There's also **virsh**, a shell-based VM manager, that is extremely useful to manage multiple VMs in an automated way!

There is also vert-install, a small installation interface that allow us to install VMs.

11.2 Managing Libvirt and KVM

First we need to verify that the required kernel modules for KVM are available. This can be done with:

```
# lsmod | grep kvm
kvm_intel 200704 0
kvm 585728 1 kvm_intel
irqbypass 16384 1 kvm
```

The lsmod command shows us the status of the Linux Kernel modules. The kvm module is the generic KVM support module, while the kvm-intel module provides platform specific support for KVM virtualization.

Finally, we check if the libvirtd daemon is up and running using:

```
# systemctl status libvirtd
libvirtd.service - Virtualization daemon
Loaded: loaded (/usr/lib/systemd/system/libvirtd.service; enabled; vendor pre
Active: active (running) since Sat 2017-12-02 16:08:39 IST; 2h 43min ago
Docs: man:libvirtd(8)
http://libvirt.org
Main PID: 945 (libvirtd)
Tasks: 18 (limit: 32768)
CGroup: /system.slice/libvirtd.service
945 /usr/sbin/libvirtd
1210 /usr/sbin/dnsmasq --conf-file=/var/lib/libvirt/dnsmasq/default
1211 /usr/sbin/dnsmasq --conf-file=/var/lib/libvirt/dnsmasq/default
Dec 02 16:08:55 lappyPrime dnsmasq[1210]: compile time options: IPv6 GNU-getopt
Dec 02 16:08:55 lappyPrime dnsmasq-dhcp[1210]: DHCP, IP range 192.168.124.2 -- 1
Dec 02 16:08:55 lappyPrime dnsmasq-dhcp[1210]: DHCP, sockets bound exclusively t
Dec 02 16:08:55 lappyPrime dnsmasq[1210]: no servers found in /etc/resolv.conf,
Dec 02 16:08:55 lappyPrime dnsmasq[1210]: read /etc/hosts - 2 addresses
Dec 02 16:08:55 lappyPrime dnsmasq[1210]: read /var/lib/libvirt/dnsmasq/default.
Dec 02 16:08:55 lappyPrime dnsmasq-dhcp[1210]: read /var/lib/libvirt/dnsmasq/def
Dec 02 16:09:37 lappyPrime dnsmasq[1210]: reading /etc/resolv.conf
Dec 02 16:09:37 lappyPrime dnsmasq[1210]: using nameserver 8.8.8.8#53
Dec 02 16:09:37 lappyPrime dnsmasq[1210]: using nameserver 202.38.180.7#53
```

Thus, this machine is completely ready for virtualization! If we run the ip link show command, we can also find a virtual bridge called virbr0, which is provided courtesy of KVM. This network acts as if it's connected to a virtual switch and provides inter-VM bridged networking support.

```
4 2: enp1s0: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc fq_codel state DOWN mode

→ DEFAULT group default qlen 1000

5 link/ether 3c:52:82:b9:05:5f brd ff:ff:ff:ff:ff

6 3: wlo1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP mode DORMANT group

→ default qlen 1000

7 link/ether 3c:95:09:de:4e:8d brd ff:ff:ff:ff:ff

8 4: virbr0: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc noqueue state DOWN mode

→ DEFAULT group default qlen 1000

9 link/ether 52:54:00:62:77:f7 brd ff:ff:ff:ff:ff

10 5: virbr0-nic: <BROADCAST,MULTICAST> mtu 1500 qdisc fq_codel master virbr0 state DOWN

→ mode DEFAULT group default qlen 1000

11 link/ether 52:54:00:62:77:f7 brd ff:ff:ff:ff:ff:
```

11.3 Using virsh

KVM requires a 64-bit architecture host. This can be verified by using:

```
1 # arch
2 x86_64
```

The x86_64 output tells us that the installed OS is 64-bit. The Virtualization shell is opened by simply typing virsh which in turn supports a lot of commands.

```
# virsh
Welcome to virsh, the virtualization interactive terminal.

Type: 'help' for help with commands
'quit' to quit

virsh #
```

11.3.1 Virsh commands

virsh list

The following are the virsh list commands. They need to be run from the CLI directly. If the commands are being run from within the sub-shell provided by virsh then only the second command onward suffices (i.e., virsh need not be retyped).

Command	Description	
virsh list	Shows all the virtual machines that are currently running	
virsh list all	Shows all virtual machines that exist	
virsh destroy <vmname></vmname>	Merely pulls the plug on the VM, i.e., immediately terminates the running VM.	
virsh start <vmname></vmname>	Starts the VM.	

Each virtual machine on the system has a configuration file that defines what the VM consists of. The /etc/libvirt/ folder is related to the configuration of the libvirtd daemon that acts as a common interface for all KVM managers. Inside it is a directory called qemu. qemu is an old emulator that has been adapted for use in the KVM environment. The qemu configuration files are stored in this /etc/libvirt/qemu directory in XML format. This file is auto-generated by virsh, and thus should only be edited with virsh edit <vmName>. This has the benefit of ensuring nothing else is concurrently editing the file.

11.4 Using virt-manager

The virt-manager is a GUI interface for the control of VMs. It can be started by:

virt-manager

Note that to control VMs made using virt-manager from within virsh, we need to be logged in under the same user when starting these utilities. They use the same libvirt database of VMs, but the user context can cause the VMs to be unavailable to some users!

Chapter 12

Scheduling Tasks

12.1 Cron vs at

Both cron and at enable us to perform a task in the future. However, cron lets us perform a job on a regular basis, while if we only need to perform a task once in the future, we use at.

12.1.1 Cron

Cron uses the crond service which is started by default and in turn used by many services. The configuration files for cron reside in various locations, and this allows RPMs to drop shell scripts in cron without any interruption or change of config. It also allows users to create their own cron jobs.

12.1.2 at

at which uses the atd daemon runs tasks only once in the future at a pre-scheduled time. The at command is used to add jobs.

12.2 Understanding Cron Configuration files and Execution times

The main configuration file for cron is located at /etc/crontab. The default contents of the file is:

```
SHELL=/bin/bash
PATH=/sbin:/bin:/usr/sbin:/usr/bin

MAILTO=root

# For details see man 4 crontabs

# Example of job definition:
# # .----- minute (0 - 59)
# | .----- hour (0 - 23)
# | / .---- day of month (1 - 31)
```

```
11 # | | | .----- month (1 - 12) OR jan, feb, mar, apr ...
12 # | | | | .---- day of week (0 - 6) (Sunday=0 or 7) OR sun, mon, tue, wed, thu, fri, sat
13 # | | | | |
14 # * * * * * user-name command to be executed
```

This config file lists the meaning of the time specifications for setting up a cronjob. We shouldn't modify this file as it'll be over-written every time the software is updated.

12.2.1 crontab -e

One of the recommended ways to create a new cronjob is to use the command crontab -e. Each user has his own *crontab* that contains instructions to the cron daemon to execute certain tasks at a certain time. The crontab -e command opens the user's crontab in editor mode and creates a cron config file for the present user.

12.2.2 Other cron config files

Many other cron config files are located in the /etc directory.

```
1 $ ls -ld cron*
2 drwxr-xr-x. 2 root root 54 Nov 25 08:59 cron.d
3 drwxr-xr-x. 2 root root 57 Nov 25 08:59 cron.daily
4 -rw-----. 1 root root 0 Aug 3 21:03 cron.deny
5 drwxr-xr-x. 2 root root 41 Nov 25 08:59 cron.hourly
6 drwxr-xr-x. 2 root root 6 Jun 10 2014 cron.monthly
7 -rw-r----. 1 root root 451 Jun 10 2014 cron.weekly
```

Each of the folders named *cron.hourly*, *cron.daily*, *cron.weekly* and *cron.monthly* are used by RPMs to drop shell scripts that the cron daemon automatically executes on an appropriate schedule.

For example, the /etc/cron.daily has a file called man-db.cron. The mandb command (executed appropriately by this file) has to be executed periodically to rebuild the index that the man pages that we search using man - k. The file contains:

```
$ cat man-db.cron
    #!/bin/bash
   if [ -e /etc/sysconfig/man-db ]; then
   . /etc/sysconfig/man-db
   if [ "$CRON" = "no" ]; then
   exit 0
10
11
   renice +19 -p $$ >/dev/null 2>&1
12
   ionice -c3 -p $$ >/dev/null 2>&1
13
14
   LOCKFILE=/var/lock/man-db.lock
1.5
16
   # the lockfile is not meant to be perfect, it's just in case the
17
    # two man-db cron scripts get run close to each other to keep
18
    # them from stepping on each other's toes. The worst that will
```

```
# happen is that they will temporarily corrupt the database
[[ -f $LOCKFILE ]] && exit 0

trap "{ rm -f $LOCKFILE ; exit 0; }" EXIT

touch $LOCKFILE

# create/update the mandb database
mandb $OPTS

exit 0
```

The file is *not* a typical cronjob since we don't need to tell the cron daemon when to execute it. It knows that the given shell script has to be executed once daily. There is no fixed time for the cron job to run, and thus, even if the system goes down during a certain period of time, the cron daemon will execute the job at a later time.

12.2.3 cron.d

The files in this directory look a lot more like the crontab files. Some of the contents of this directory are:

```
$ ls -l /etc/cron.d

2 total 12

3 -rw-r--r-. 1 root root 128 Aug 3 21:03 Ohourly

4 -rw-r--r-. 1 root root 108 Jun 13 19:38 raid-check

5 -rw-----. 1 root root 235 Aug 3 15:00 sysstat
```

The contents of the sysstat file is:

```
$ sudo cat sysstat

2  # Run system activity accounting tool every 10 minutes

3  */10 * * * * root /usr/lib64/sa/sa1 1 1

4  # 0 * * * root /usr/lib64/sa/sa1 600 6 8

5  # Generate a daily summary of process accounting at 23:53

6  53 23 * * * root /usr/lib64/sa/sa2 -A
```

The format followed is: time specification, name of the user under which the command has to be executed, followed by the command to be executed.

Thus, if a cronjob has to be run as an administrator, we should put it in a cron file in the /etc/cron.d directory. If however, a user-specific cron file has to be executed, then it's better to use the crontab -e command to generate and store the cronjobs for that user.

12.3 Scheduling with cron

One of the best ways to run cronjobs is to become the user that we want to run the cronjob as and then open their crontab, using the crontab -e command.

Let us consider a hypothetical scenario where we want to run a specific set of commands at 2.30PM everyday. Now, we first write the minutes(30) followed by the hour in 24-hour format [military time](2PM=14). Next, we want the script to run everyday, so we mark the day of the month, the month and the day of the week with *s (everyday of the month, every month and everyday of the week). Let us consider we want the cronjob to write something to the syslog using the logger command. Then the entry in the crontab will look like:

```
1 30 14 * * * logger Hello
```

Typically, the anacron utility takes care of executing the shell scripts in the *cron.hourly, cron.daily, cron.weekly and cron.monthly* directories. It ensures that the commands will be executed at appropriate times (that cannot be controlled by the user) if the machine is down on the originally scheduled time.

12.4 Using at

Before using at, we need to ensure that the atd daemon is running:

```
$ systemctl status atd -l
atd.service - Job spooling tools
Loaded: loaded (/usr/lib/systemd/system/atd.service; enabled; vendor preset: enabled)
Active: active (running) since Sat 2017-12-02 15:26:18 IST; 1 day 8h ago
Main PID: 1224 (atd)
CGroup: /system.slice/atd.service
1224 /usr/sbin/atd -f

Dec 02 15:26:18 vmPrime.somuVMnet.local systemd[1]: Started Job spooling tools.
Dec 02 15:26:18 vmPrime.somuVMnet.local systemd[1]: Starting Job spooling tools.
```

12.4.1 Scheduling using at

The syntax for using at is simple: at <time>. This will open up the at prompt which takes as input the commands to be performed. We can escape the at prompt by sending an EOF signal using CTRL+D. We can schedule a message to be logged at 2:30PM using:

```
1 # at 1:17
2 at> logger Hello @ 02:30PM!
3 at> <EOT>
4 job 1 at Mon Dec 4 14:30:00 2017
```

Alternatively, the output of another command (or a shell script) can be piped to at.

12.4.2 atq

The atq command is used to see how many at jobs are waiting to be run.

```
$ echo 'echo "2mins after 1AM" >> time.log' | at 01:02
job 9 at Mon Dec 4 01:02:00 2017
3  $ echo 'echo "3mins after 1AM" >> time.log' | at 01:03
   job 10 at Mon Dec 4 01:03:00 2017
   $ ls -1
   total 0
   $ atq
            Mon Dec 4 01:02:00 2017 a somu
            Mon Dec 4 01:03:00 2017 a somu
10
11 Mon Dec 4 01:01:54 IST 2017
12 $ ls -l
13 total 0
14 $ date
15 Mon Dec 4 01:02:04 IST 2017
16 $ ls -l
17 total 4
   -rw-rw-r--. 1 somu somu 16 Dec 4 01:02 time.log
18
19 $ cat time.log
20 2mins after 1AM
21
   $ date
22
   Mon Dec 4 01:03:01 IST 2017
   $ cat time.log
   2mins after 1AM
   3mins after 1AM
```

12.4.3 Removing jobs from atq

The jobs scheduled by at can be removed by passing their job number to atrm command.

The at jobs are stored in a file in the /var/spool/at directory in a file with a system generated name.

The output of the logger command can be checked by using tail -f /var/log/messages.

```
1  # at 1:17
2  at> logger Hello @ 12:17AM!
3  at> <EOT>
4  job 15 at Mon Dec  4 01:17:00 2017
5  [root@vmPrime at]# atq
6  15  Mon Dec  4 01:17:00 2017 a root
```

7 # tail -f /var/log/messages

- 8~ Dec $\ 4~01:12:03~vmPrime~dbus[702]:$ [system] Successfully activated service
 - → 'org.freedesktop.problems'
- 9 Dec 4 01:12:03 vmPrime dbus-daemon: dbus[702]: [system] Successfully activated service
 - → 'org.freedesktop.problems'
- Dec 4 01:12:28 vmPrime journal: No devices in use, exit
- 11 Dec 4 01:17:00 vmPrime root: Hello @ 12:17AM!

Chapter 13

Configuring Logging

13.1 Understanding rsyslogd and journald logging

On RHEL 7 there are two systems responsible for logging : **rsyslogd** and **journald**. These two services together to handle logging system information.

It is up to the services (containing the logging information) to decide how and where the log files will be written to. It is possible to write directly to a log file anywhere (e.g., /somewhere/my.log). The service may also choose to pass over the information to systemctl as well. The systemctl utility is used to start the service and keep track of the actions of the service while it's starting. Anything that goes through systemd will be writing to journald, which is the systemd way of logging.




Figure 13.1: Logging Options

The classic way of logging is through the rsyslogd daemon, which typically writes information to the /var/log/ directory. Alternative locations can also be used.

Given the various ways to log information, it may also become challenging for a user to get that logged information. It can be through **journalctl** or rsyslog. It is possible to tie these two systems together.

13.1.1 Sharing logging information

To ensure that journalctl information is automatically logged to rsyslog, we need to add a couple of lines to /etc/rsyslog.conf and /etc/rsyslog.d/listend.conf:

In /etc/rsyslog.conf:	In /etc/rsyslog.d/listend.conf:
<pre>\$ModLoad imuxsock \$OmitLocalLogging off</pre>	\$SystemLogSocketName → /run/systemd/journal/syslog

The above lines enable rsyslog to receive information logged by journald. To enable the logging of rsyslog information in journald, we only need to add in the /etc/rsyslog.conf:

```
$Modload omjournal *.* :omjournal:
```

The above lines specify that any information being logged should be sent to omjournal which is a part of journald. The information from there is available from journalctl.




Figure 13.2: Sharing logging information between rsyslog and journald

13.2 Integrating rsyslogd and journald

Rsyslog is the old process of logging system information, and journald is the new process that's trying to do the same. Both of them are built to log process information.

13.2.1 rsyslog

Let us consider a process that's trying to write what it's doing in log files. It has two options: rsyslog and journald. If it writes to rsyslog, the advantage is that rsyslog is the system process that can handle logging for all processes. Some processes, however, just have some internal logging option (direct writes) thus bypassing rsyslog. A well known example of such a process is the *apache web server*. This is a disadvantage as if every process is doing its own logging, it's harder to manage the whole thing in a centralized way. These processes can however, be configured to write to rsyslog anyway!

13.2.2 journald

Journald is controlled by **systemd**, which takes care of starting services while booting. Systemd writes its own information to journald, and thus, if something goes wrong while starting a service, the information is available from *journald*.

For RHEL 7 in general, *journald* generally takes care of loggin the startup information logging while *rsyslog* takes care of logging current activity of processes.

13.3 Configuring rsyslog logging

[VIDEO TUTORIAL MISSING]

13.4 Working with journald

Everything that *journald* is doing is written to a binary file. The file can be explored using two methods: by using **systemctl** and **journalctl**. Journald integrates very well with systemctl and thus, systemctl commands can get information from journald and vice versa. Using systemctl status <serviceName> gives us the log information that systemctl receives from the journald environment.

13.4.1 journalctl

The journalctl command opens up the binary file that journald is writing to. Since it's a large file, there are several filtering options:

journalctl -b

The journal -b command only shows us the boot log.

```
# journalctl -b

-- Logs begin at Sat 2017-12-02 15:25:40 IST, end at Mon 2017-12-04 13:23:04 IST. --

Dec 02 15:25:40 vmPrime.somuVMnet.com systemd-journal[86]: Runtime journal is using 8.0M

→ (max allowed 289.5M, trying to leave 434.3M free of 2.

Dec 02 15:25:40 vmPrime.somuVMnet.com kernel: Initializing cgroup subsys cpuset

Dec 02 15:25:40 vmPrime.somuVMnet.com kernel: Initializing cgroup subsys cpu

Dec 02 15:25:40 vmPrime.somuVMnet.com kernel: Initializing cgroup subsys cpuacct

Dec 02 15:25:40 vmPrime.somuVMnet.com kernel: Linux version 3.10.0-693.5.2.el7.x86_64

→ (builder@kbuilder.dev.centos.org) (gcc version 4.8.5 2015

Dec 02 15:25:40 vmPrime.somuVMnet.com kernel: Command line:

→ BOOT_IMAGE=/vmlinuz-3.10.0-693.5.2.el7.x86_64 root=/dev/mapper/centos-root ro crash

Dec 02 15:25:40 vmPrime.somuVMnet.com kernel: Disabled fast string operations

...
```

One of the best features of journald is that systemd initiates it immediately during boot and thus logs about what happens even during the very first stages of RHEL boot is available.

journalctl -since=<time>

The journalctl has a method to filter all results to show us what has happened since a specified period where only the logs written after a certain period are show.

```
# journalctl --since=yesterday
-- Logs begin at Sat 2017-12-02 15:25:40 IST, end at Mon 2017-12-04 13:28:03 IST. --
Dec 03 23:04:36 vmPrime.somuVMnet.local systemd[1]: Time has been changed
Dec 03 23:04:36 vmPrime.somuVMnet.local NetworkManager[834]: <info> [1512322476.5889]
-- audit: op="sleep-control" arg="off" pid=3311 uid=0 resul
Dec 03 23:04:36 vmPrime.somuVMnet.local systemd[1]: Stopping LSB: Bring up/down
-- networking...
```

journald -u

The journal -u command shows us all the logs corresponding to a certain process.

```
# systemctl status atd -l
atd.service - Job spooling tools
Loaded: loaded (/usr/lib/systemd/system/atd.service; enabled; vendor preset: enabled)
Active: active (running) since Sat 2017-12-02 15:26:18 IST; 1 day 22h ago
Main PID: 1224 (atd)
CGroup: /system.slice/atd.service
1224 /usr/sbin/atd -f

Dec 02 15:26:18 vmPrime.somuVMnet.local systemd[1]: Started Job spooling tools.
Dec 02 15:26:18 vmPrime.somuVMnet.local systemd[1]: Starting Job spooling tools...
# journalctl -u atd
-- Logs begin at Sat 2017-12-02 15:25:40 IST, end at Mon 2017-12-04 13:37:28 IST. --
Dec 02 15:26:18 vmPrime.somuVMnet.local systemd[1]: Started Job spooling tools...
Dec 02 15:26:18 vmPrime.somuVMnet.local systemd[1]: Started Job spooling tools...
Dec 02 15:26:18 vmPrime.somuVMnet.local systemd[1]: Starting Job spooling tools...
```

Both systemctl and journald are intimately interconnected. Journald receives it's original logging information from systemctl, while the information displayed by the systemctl status command is derived from the information stored by journald. To see the information in even more detail, we use the command journalctl -u processName> -o verbose.

The above command gives us complete information about the environment of the process.

13.5 Understanding logrotate

Logrotate is a system that's used to ensure that logging doesn't fill the hard disk of the server. Logrotate ensures that after a specified amount of time, log files will be closed and new ones opened, and a backlog of a couple of log files will be kept. This is all done

based on the assumption that old logs are useless beyond a certain age. This has a stark disadvantage of erasing logging data that may become useful at a later date.

A solution to this problem is the use of a log server, with sufficient hard disk space to keep about a year's worth of logs. The client machines can have logrotate setup to keep only a couple of week's data since there will be a backup available on the log server.

13.6 Configuring logrotate

The configuration files for logrotate reside in the /etc directory. The generic logrotate configuration is stored in /etc/logrotate.conf while the directory /etc/logrotate.d contains include files that RPMs dump in it for package specific log rotation. Anything in the logrotate.d directory will always overwrite the settings in logrotate.conf. Typical contents of the logrotate.conf file is:

```
# see "man logrotate" for details
    # rotate log files weekly
    weekly
    # keep 4 weeks worth of backlogs
    # create new (empty) log files after rotating old ones
 9
10
    # use date as a suffix of the rotated file
1.1
12
13
    # uncomment this if you want your log files compressed
14
    #compress
15
16
    # RPM packages drop log rotation information into this directory
17
    include /etc/logrotate.d
18
19
    # no packages own wtmp and btmp -- we'll rotate them here
20
21 /var/log/wtmp {
22 monthly
   create 0664 root utmp
23
24 minsize 1M
  rotate 1
25
26
27
  /var/log/btmp {
28
29 missingok
30 monthly
31 create 0600 root utmp
    rotate 1
32
    }
33
```

The last two settings demonstrate how specific logrotation instructions can be given for specific files. For example, the /var/log/wtmp file has to be rotated monthly, and only 1 copy of the backlog is maintained.

Since logrotate doesn't need to run all the time, it doesn't itself run as a service, but as a cron job! The config file for logrotate cron job is /etc/cron.daily/logrotate.

13.6.1 Checking avialable hard disk space

The available hard disk space and the disk space occupied by a certain directory can be checked using these two commands:

```
# df -h
2 Filesystem
             Size Used Avail Use% Mounted on
3 /dev/mapper/centos-root 3.8G 3.4G 412M 90% /
4 devtmpfs 2.9G 0 2.9G 0%/dev
5 tmpfs
                  2.9G 0 2.9G 0% /dev/shm
6 tmpfs
                  2.9G 9.2M 2.9G 1% /run
                  2.9G 0 2.9G 0% /sys/fs/cgroup
7 tmpfs
s /dev/mapper/centos-home 7.5G 65M 7.4G 1%/home
9 /dev/mapper/centos-var 1.9G 327M 1.6G 18% /var
580M 0 580M 0% /run/user/0
14 tmpfs
# du -hs /var/log
  13M /var/log
```