# **Chapter 1**

# **Managing Partitions**

## 1.1 Understanding Disk Layout

There are two basic ways of organizing data on a hard disk: Partitions and LVM (Logical Volume Management). Some parts of a hard disk need to be configured with a fixed amount of storage. In such cases we use partitions. This is applicable for /boot and / in the figure. However, certain directories contain dynamic user data, and thus need to be able to grow to any size. In such cases, the partitions don't work and we need to use Logical Volumes. In the image below, sda1, sda2 & sda3 are all Physical Volume(PV)s or partitions. In linux, each partition needs to be connected to one or more directories in order to be used.




Figure 1.1: Disk Layout

In the case of Logical Volumes (LVs), just like partitions, there needs to be a Physical Volume (PV). This PV is then put in a Volume Group (Vg), represented by the red boundary

lines in the image above. From this volume group, we can create Logical Volumes (represented by the blue lines). The advantage of this method is the unused space between different LVs can be added to any of the LVs, and thus no disk space is wasted and no directory in the LV is going to be full while another is barely filled. In LVM it's very easy to grow a logical volume later!

# 1.2 Creating Partitions

To add a new disk to our OS, first we need to verify the storage disks that are available. For this we use the **proc** filesystem in /proc/. It acts as an interface to everything that's happening in the kernel. The /proc/partitions file contains a listing of all the disks and partitions that are currently existing.

```
$ cat /proc/partitions
   major minor #blocks name
           0 20971520 sda
           1
              2048 sda1
           2
                499712 sda2
           3 15634432 sda3
          16 10485760 sdb
   11
            0 8491008 sr0
            0 3903488 dm-0
10
  253
                1953792 dm-1
11
            1
             2 1953792 dm-2
12
  253
                 7815168 dm-3
```

While *sda* is the first hard disk, the device *sdb* is a newly added one - the second hard disk avaiable in the computer. The partitions are marked by a number after the device name - *sda1*, *sda2* and *sda3*. The second hard disk doesn't have any partitions yet.

### 1.2.1 fdisk

**fdisk** is an old partitioning tool that has been revised for RHEL 7. Running the fdisk utility on /dev/sdb, the location which the OS uses to designate the second hard disk yeilds:

```
# fdisk /dev/sdb
Welcome to fdisk (util-linux 2.23.2).

Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table
Building a new DOS disklabel with disk identifier Oxf11ab429.
```

It tells us that the disk doesn't contain any partitions (since it's brand new). The fdisk utility offers us a bunch of commands, among which we'll use:

Options	Description
р	Print partition table
n	Add a new partition
W	Write the table to disk and exit

### p command

The p option gives us the current disk layout:

```
Command (m for help): p

Disk /dev/sdb: 10.7 GB, 10737418240 bytes, 20971520 sectors

Units = sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk label type: dos

Disk identifier: 0xf11ab429

Device Boot Start End Blocks Id System

Command (m for help):
```

The device name is *sdb* and its size is 10.7GB. This gives it 20 Million sectors, since the size of each sector is 512B. Now we add a new partition on the disk:

```
Command (m for help): n

Partition type:

primary (0 primary, 0 extended, 4 free)

e extended

Select (default p): p

Partition number (1-4, default 1):

First sector (2048-20971519, default 2048):

Using default value 2048

Last sector, +sectors or +size{K,M,G} (2048-20971519, default 20971519): +100M

Partition 1 of type Linux and of size 100 MiB is set

Command (m for help):
```

The default option at the prompt can be selected by simply pressing the enter key. Since there are no physical partitions already available, and since we should always choose the option to add physical partitions whenever possible, we add a new physical partition. It asks us for the starting sector, the default of which is 2048. The first 2MBs are used to store metadata. Next, we mark the end of the partition using a relative size: in this case, of 100MiB  $(1024^2\text{B})$ . The size has to be specified with uppercase K/M/G to not be misconstrued to any other unit. Printing the partition table now shows:

```
        1
        Device Boot
        Start
        End
        Blocks
        Id
        System

        2
        /dev/sdb1
        2048
        206847
        102400
        83
        Linux
```

This new partition can then be written to the disk using  $\ensuremath{\mathtt{w}}$ .

```
Command (m for help): w
The partition table has been altered!

Calling ioctl() to re-read partition table.
Syncing disks.
```

Now when we view the partitions in /proc/partitions we see:

```
# cat /proc/partitions
major minor #blocks name
```

```
0 20971520 sda
        1 2048 sda1
         2 499712 sda2
         3 15634432 sda3
  8
        16 10485760 sdb
  8
        17 102400 sdb1
        0 8491008 sr0
  11
         0 3903488 dm-0
11 253
12 253
          1 1953792 dm-1
13 253
          2 1953792 dm-2
14 253
          3 7815168 dm-3
```

The disk now has a sdb1 partition of size 100MiB. This indicates that the disk is now ready to accept a filesystem. In case an error is show along the lines of "the device is busy", the system probably needs a restart.

# 1.3 Understanding File System Differences

For a RHEL 7 installation, there are several file system choices:

File System	Description
XFS	The default file system for RHEL 7 and many others, built with scalability in mind. Based on a B-Tree database, which specializes in disk space allocation with high speed and makes looking up files really easy. It also has different tuning options for varying workloads.
Ext4	This was the default filesystem till RHEL 6. It was based on 1993's Ext2 file system which was built to handle much smaller disks than our current needs. It uses H-Tree indexing, which is use of basic index files - suitable for thousands of files, but not practical or economical (in terms of time) for millions of files, which our systems demand. While it is not as scalable as XFS, it does provide backwards compatibility. Thus, for best performance, it shouldn't be used as a default file system.
Btrfs	This is a Copy-on-Write(CoW) file system, which means that before writing to a file, that file is copied somewhere else, thus making journaling unnecessary! Journalling is the system where the filesystem keeps track of the changes being made to the file to make rolling back possible. This also makes undelete operations unnecessary (which have never worked on Linux anyway). It even has added features like subvolumes. It wasn't however included in RHEL 7 First Customer Shipment (FCS).
vfat	Primarily for compatibility with other OSs, such as Windows. It is particularly useful for removable media such as USB sticks. This filesystem is not needed to be installed on the hard disk of the server however, even in cases where Samba provides access to files on the server (Samba handles the file system differences and translation itself).
GFS2	For Active/Active High Availability (HA) Clustering Environments. Only needed when multiple nodes need to write to the same file system concurrently. For Active/Passive File HA Clusters, XFS/Ext4/etc. suffice.
Gluster	Gluster is a distributed file system. Thus, even though represented under the same hierarchy, it can reside on multiple servers. Storage is configured to be done in <i>bricks</i> that are spread over servers. Each brick uses XFS as their back-end file system. This is an important file system for cloud environments.

## 1.4 Making the File System

Just after being created, a partition contains no file system, and thus no files can yet be stored on it. We have to create an appropriate file system using:

#### 1.4.1 mkfs

This is actually a whole bunch of different utilities that are grouped together under the same command. They are:

```
mkfs \qquad mkfs.btrfs \qquad mkfs.cramfs \qquad mkfs.ext2 \qquad mkfs.ext3 \qquad mkfs.ext4 \qquad mkfs.fat \\ \hookrightarrow \qquad mkfs.minix \qquad mkfs.msdos \qquad mkfs.vfat \qquad mkfs.xfs
```

Since the default file system is XFS, mkfs.xfs is the default file system utility.

```
# mkfs.xfs --help
2 mkfs.xfs: invalid option -- '-'
3 unknown option --
4 Usage: mkfs.xfs
5 /* blocksize */
                                 [-b log=n|size=num]
6 /* metadata */
                                [-m crc=0|1,finobt=0|1,uuid=xxx]
7 /* data subvol */ [-d agcount=n,agsize=n,file,name=xxx,size=num,
   (sunit=value, swidth=value|su=num, sw=num|noalign),
   sectlog=n|sectsize=num
10 /* force overwrite */
                               [-f]
11 /* inode size */
                          [-i log=n|perblock=n|size=num,maxpct=n,attr=0|1|2,
12 projid32bit=0|1]
13 /* no discard */
                          [-K]
13 /* no discard */ L-NJ
14 /* log subvol */ [-l agnum=n,internal,size=num,logdev=xxx,version=n
   sunit=value|su=num,sectlog=n|sectsize=num,
15
16 lazy-count=0|1]
17 /* label */
                             [-L label (maximum 12 characters)]
                          [-n log=n|size=num,version=2|ci,ftype=0|1]

[-N]
[-p fname]
18 /* naming */
19 /* no-op info only */
20 /* prototype file */
   /* quiet */
                              [-q]
   /* realtime subvol */ [-r extsize=num,size=num,rtdev=xxx]
   /* sectorsize */ [-s log=n|size=num]
23
   /* version */
                               \Gamma - \nabla \Gamma
24
   devicename
    <devicename> is required unless -d name=xxx is given.
    <num> is xxx (bytes), xxxs (sectors), xxxb (fs blocks), xxxk (xxx KiB),
    xxxm (xxx MiB), xxxg (xxx GiB), xxxt (xxx TiB) or xxxp (xxx PiB).
28
    <value> is xxx (512 byte blocks).
```

The **block size (-b)** should be larger when primarily dealing with large files. This way, lesser blocks are used, and the administration of large files becomes easier. The **inode size (-i)** should be larger if it is known beforehand that lots of advanced stuff that stores metadata in inodes will be used. The *label (-L)* sets the name for that filesystem. To actually create the file system, we use the command:

```
meta-data=/dev/sdb1 isize=512 agcount=4, agsize=65536 blks

2 = sectsz=512 attr=2, projid32bit=1

3 = crc=1 finobt=0, sparse=0

4 data = bsize=4096 blocks=262144, imaxpct=25
```

```
sunit=0 swidth=0 blks
naming =version 2 bsize=4096 ascii-ci=0 ftype=1
log =internal log bsize=4096 blocks=2560, version=2
s = sectsz=512 sunit=0 blks, lazy-count=1
realtime =none extsz=4096 blocks=0, rtextents=0
```

# 1.5 Mounting the Partition Manually

The new partition is mounted using the mount command. For recurring mounting, it's advisable to create a permanent mounting directory. For temporary mounts, we can use /mnt. The mounting operation can be verified by typing the mount command. The command to mount the new partition sdb1 on the /mnt directory is:

```
# mount /dev/sdb1 /mnt

# mount | tail -n 5

tmpfs on /run/user/1000 type tmpfs

(rw,nosuid,nodev,relatime,seclabel,size=592968k,mode=700,uid=1000,gid=1000)

fusectl on /sys/fs/fuse/connections type fusectl (rw,relatime)

gvfsd-fuse on /run/user/1000/gvfs type fuse.gvfsd-fuse

(rw,nosuid,nodev,relatime,user_id=1000,group_id=1000)

/dev/sr0 on /run/media/somu/CentOS 7 x86_64 type iso9660

(ro,nosuid,nodev,relatime,uid=1000,gid=1000,iocharset=utf8,mode=0400,dmode=0500,uhelper=udisks2)

/dev/sdb1 on /mnt type xfs (rw,relatime,seclabel,attr2,inode64,noquota)
```

**Mounting** means connecting some device or functionality to a particular directory. This not only includes removable media and peripheral device directories, but also many system settings (such as the /proc file system or the /sys file system).

To view only the devices that have been mounted, we can use:

```
# mount | grep '/dev

/dev/mapper/centos-root on / type xfs
/ (rw,relatime,seclabel,attr2,inode64,noquota)

/dev/mapper/centos-home on /home type xfs
/ (rw,relatime,seclabel,attr2,inode64,noquota)

/dev/sda2 on /boot type xfs (rw,relatime,seclabel,attr2,inode64,noquota)

/dev/mapper/centos-var on /var type xfs
/ (rw,relatime,seclabel,attr2,inode64,noquota)

/dev/sr0 on /run/media/somu/CentOS 7 x86_64 type iso9660
/ (ro,nosuid,nodev,relatime,uid=1000,gid=1000,iocharset=utf8,mode=0400,dmode=0500,uhelper=udisks2)

/dev/sdb1 on /mnt type xfs (rw,relatime,seclabel,attr2,inode64,noquota)
```

### 1.5.1 umount

The umount command is used to unmount a mounted directory. This is to ensure that no files are open and cannot be damaged by the sudden removal of the file system. The umount command takes as parameter either the device name or the directory where it is mounted. So, both /dev/sdb1 and /mnt are valid parameters to unmount the new partition.

```
# umount /dev/sdb1
# mount | grep ^/dev

/dev/mapper/centos-root on / type xfs
(rw,relatime,seclabel,attr2,inode64,noquota)
```

The device /dev/sdb1 is no longer mounted, as can be seen from the output. A major challenge that may be presented by this is the fact that the device names may change at any time! Today the device that's called /dev/sdb1 may change to /dev/sdc1 if the OS detects the devices (and names them) in another order, thus making our references to them useless. For this reason the *Universally Unique ID (UUID)* of a device can be used to refer to it. The UUID of all existing devices can be displayed using:

```
# blkid

/dev/sda2: UUID="1c55e935-8099-49c4-8c72-0bc1ff7c396a" TYPE="xfs"

/dev/sda3: UUID="DfepDW-igyh-eI6D-SgBB-3HV5-QTQT-EI3Pc2" TYPE="LVM2_member"

/dev/sdb1: LABEL="myfs" UUID="00a8c244-8781-492c-a6ad-85624780e1e8" TYPE="xfs"

/dev/sr0: UUID="2017-09-06-10-53-42-00" LABEL="Cent0S 7 x86_64" TYPE="iso9660"

PTTYPE="dos"

/dev/mapper/centos-root: UUID="d2fe3168-4eef-431b-9a8e-eb59dae10bcb" TYPE="xfs"

/dev/mapper/centos-swap: UUID="24b0103c-d574-4623-bc85-9255076e3b7d" TYPE="xfs"

/dev/mapper/centos-var: UUID="ed13b5f3-1b26-48f7-81cb-03a2bad5fc61" TYPE="xfs"

/dev/mapper/centos-home: UUID="710a33e6-7e52-4c06-830d-e53ae0d58fed" TYPE="xfs"
```

As can be seen, the label for the file system is also shown using the blkid command. Both the UUID and the label for the file system can be used to reference the device while using the mount command:

```
# mount LABEL=myfs /mnt

# mount | tail -n 3

gvfsd-fuse on /run/user/1000/gvfs type fuse.gvfsd-fuse

(rw,nosuid,nodev,relatime,user_id=1000,group_id=1000)

/dev/sr0 on /run/media/somu/CentOS 7 x86_64 type iso9660

(ro,nosuid,nodev,relatime,uid=1000,gid=1000,iocharset=utf8,mode=0400,dmode=0500,uhelper=udisks2)

/dev/sdb1 on /mnt type xfs (rw,relatime,seclabel,attr2,inode64,noquota)
```