
# Operating Systems: Processes CIS\*3110: Operating Systems

Dr. A. Hamilton-Wright

School of Computer Science University of Guelph


2025-01-19

# Parts of a Computer



**RAM** 


I/O Devices



#### Tools at the Hardware Architecture Level

- program counter (PC)
- stack pointer/frame pointer
- processor status register
- general purpose registers
- memory management unit (mapping, protection)
- kernel/user mode
- interrupts and interrupt vector


## Interrupt vector links devices with service routines



- basic instruction cycle of the ALU of the CPU:
  - 1. fetch instruction pointed to by the PC )
  - 2. increment PC
  - 3. execute instruction

over and over again

- processor status (usually a special register on each CPU)
   user mode can execute most instructions (but no I/O)
   kernel mode can execute all user instructions,
   PLUS access special instructions and
   registers that control I/O, memory access
   (also called supervisor mode)
- interrupt vector (special range of locations in RAM)
  - used to link hardware interrupts with ...interrupt service routines




# Program on an Example Machine

	Assem	bler	Mach Code	Virt Addr				
	load	R1, OxA2	0x11A2	0x10				
	incr	R1	0x3100	0x12				
	store	R1, 0xA2	0x21A2	0x14				
	jmp	XX	0x5026	0x16				
yy:	decr	R2	0x4200	0x18				
	rsb		0x7000	0x24				
xx:	zero	R2	0x8200	0x26				
	incr	R2	0x3200	0x28				
	store	R2, 0xA0	0x22A0	0x2A				
	jsr	уу	0x6018	0x2C				
	incr	R2	0x3200	0x2E				
	store	R2, 0xA2	0x22A0	0x30				
Registers: R0, R1, R2, R3, SP, PC								

Op Codes							
load	0x1						
store	0x2						
incr decr	0x3 0x4						
jmp jsr	0x5 0x6						
rsb	0x7						
zero	8x0						

#### **Context Switch**

- change from one running program to another "on the fly"
- need to be able to change back later
- to do this, we must save the "program state"
  - program counter
  - general purpose registers
  - status register
  - stack pointer
- each program must be resident in different parts of memory



#### **Interrupts**

- a hardware generated jump to subroutine (JSR) requested by an external hardware device (not the CPU)
- defined through the interrupt vector
  - resides somewhere in physical memory
  - is effectively an array of function pointers
- may be delayed (i.e.; disabled, possibly temporarily) by masking off

## **Interrupt Steps**

#### $\textbf{Interrupt} \rightarrow$

- save PC on stack
- switch CPU to kernel (supervisor) mode
- load PC from vector using hardware id (vector contains the start address of the interrupt service routine)
- save all registers
- continue execution

#### **Return from Interrupt (RTI)**

 $\leftarrow$ 

- restore registers
- restore saved PC value
- set CPU to previous mode

#### **Critical Sections**

- a critical section contains reference(s) to data shared between two or more "threads of control"
  - one may be an interrupt
  - this may be two or more processes
  - this may be two or more threads
- must manage the data so all parties can rely on its value
  - if we fail to do this, data may be wrong for one party, or even corrupted for all

```
load R1, #i
i++; ←→ incr R1
store R1, #i
```

## A Critical Example

```
c = 'A';
for (i = 0; i < MAX; i++) {
    a[i] = c++;
    if (c > 'E')
        c = 'B';
Interrupt Service Routine
set_to_a() {
    c = 'A':
```

# Modern (UNIX-type) systems: 3 types of device drivers

- BLOCK devices that read/write blocks (disc, tapes, SD-cards, CD-ROM/DVD, ...)
- NETWORK local area network (Ethernet, token ring), remote connection network interface (PPP, ISDN, ...)
- CHARACTER everything that does not fit the above two cases (serial ports, display/keyboard, mouse, joystick, touchscreen,...)

#### **Device Driver Functions**

```
Top Half: communicate with user, kernel
        check for hardware at boot time
 probe
        called when a process does an open of a device file
  open
         (e.g., /dev/mouse, /dev/disk0, /dev/null etc.)

    mostly initializes variables and maybe hardware

    generates a file descriptor in user space

 close
        called when a process does a close() of the file de-
         scriptor created from open (usually just marks the de-
         vice closed)
  read
         called when a process does a read(fd) — transfers
         data from device to process
 write
         called when a process does a write(fd) — queues data
         for device to output
Bottom Half: event handling
 interrupt service routine
```

I/O on the hardware

called when device generates an interrupt and does the

```
char get_keyb()
    while (???) {
    return ???:
void keyb_intr()
        /* "magic" addresses for memory mapped I/O */
    char *keyb_reg = (char *) 0x2ff4200;
    char *keyb_status = (char *) 0x2ff4201;
    while (*keyb_status)
    ??? = *keyb_reg;
```

# Circular Queue (Ring Buffer)

```
char Q[QSIZE];
     int numQ, startQpos, endQpos;
     numQ = startQpos = endQpos = 0;
Add into queue
     Q[endQpos] = value;
     endQpos = (endQpos + 1) % QSIZE;
     numQ++;
Remove from queue
     value = Q[startQpos];
     startQpos = (startQpos + 1) % QSIZE;
     numQ-;
```

#### Critical Sections in Device Driver

interrupts can be masked off:

process can be "put to sleep" until there is space in a buffer:

#### Device Driver Skeleton - read

```
static char Q[QSIZE];
static int numQ = 0, startQpos = 0, endQpos = 0;
devread(char *ubuf) { /** read one character */
   int s;
   s = spltty();
   while (numQ == 0) {
       splx(s); /** can't sleep inside critical section */
       tsleep(devread, ...); /* sleep */
       s = spltty();
    *ubuf = Q[ startQpos ];
    startQpos = (startQpos + 1) % QSIZE;
   numQ-;
   splx(s);
```

#### Device Driver Skeleton - intr


```
devintr() {
    int s;
    s = spltty();
    if (QSIZE == numQ) {
        /* queue is full . . . */
        splx(s); /* leave crit section before return */
        return;
    Q[ endQpos ] = GET_CHAR_FROM_DEVICE();
    endQpos = (endQpos + 1) % QSIZE;
    numQ++;
    splx(s);
    wakeup(devread);
```

## **Running Programs**

The **execution** of a **program** (an "image") is a **process**. The environment that the O/S provides for the execution of a program (*i.e.*; a process) is that of a **simplified** pseudo-computer.

UNIX/Mach process environment:

- virtual (simplified) address space
- process context
- no direct access to I/O ports



## Process Table Entry (Process Context)

- the process table contains an entry for each current process
  - if a process has more than one thread there is usually one process table entry per thread (ps(1) may or may not show it this way)
- each entry holds all the information about a process:
  - process (thread) context
    - program counter
    - registers (general and special purpose)
    - stack pointer
    - virtual address space reference
  - scheduling information
    - BLOCKED -vs-RUNNABLE -vs-RUNNING
    - priority
    - time used

# **Process Status Listing**

% ps au	1XW									
USER	PID	%CPU	%MEM	VSZ	RSS	TTY	STAT	START	TIME	COMMAND
root	1	0.0	0.0	1368	84	?	S	Jan11	0:04	init [3]
root	2	0.0	0.0	0	0	?	SW	Jan11	0:00	[keventd]
root	4	0.0	0.0	0	0	?	SWN	Jan11	0:00	[ksoftirqd_CPU0]
root	9	0.0	0.0	0	0	?	SW	Jan11	0:00	[bdflush]
root	5	0.0	0.0	0	0	?	SW	Jan11	0:00	[kswapd]
root	1609	0.0	0.0	1368	144	?	S	Jan11	0:00	klogd -x
root	1761	0.0	0.0	3508	480	?	S	Jan11	0:00	/usr/sbin/sshd
root	1920	0.0	0.2	2320	1380	?	S	Jan11	0:00	[login]
root	1921	0.0	0.0	1352	60	tty2	S	Jan11	0:00	/sbin/mingetty
andrew	8506	0.0	0.2	4692	1448	tty1	S	09:33	0:00	-csh
andrew	9373	0.0	0.5	8196	2980	pts/7	S	10:43	0:03	vim Processes.t
andrew	9795	0.0	0.2	4680	1428	pts/8	S	11:20	0:00	-bin/csh
andrew	10154	0.0	0.1	2728	780	pts/7	R	11:36	0:00	ps auxw

## **Synchronization Primitives**

Shared data can also be used between **processes/threads**  $\rightarrow$  we need to manage critical sections at this level.

The two most popular synchronization primitives are:

**mutex**: bracket critical section so only 1 process allowed at a time:

```
critical_begin();
... code in critical section ...
critical_end();
```

semaphores: allow N-at-a-time

Co-operating sequential processes can be envisioned as a separate, dedicated processor for each – with no guarantee which runs first/faster *etc*.

## **Mutex Synchronization: Producer**

```
void add_queue(char aNewChar) {
    int oldsize;
    do { /** wait until not full */
       critical_begin();
        oldsize = numQ;
        critical_end():
   } while (oldsize == QSIZE);
    critical_begin();
    Q[ endQpos ] = aNewChar;
    endQpos = (endQpos + 1) % QSIZE;
   numQ++;
    critical_end();
```

## **Mutex Synchronization: Consumer**

```
void del_queue(char aNewChar) {
   int oldsize, tmpBuf;
   do { /** wait until not empty */
       critical_begin();
       oldsize = numQ;
       critical_end():
   } while (oldsize == 0);
   critical_begin();
   tmpBuf = Q[ startQpos ];
   startQpos = (startQpos + 1) % QSIZE;
   numQ-;
   critical_end();
   return tmpBuf;
```

## Implementing Mutual Exclusion (in Hardware)

```
static mutexFlag = 0;
critical_begin() {
    int oldFlag;
   do {
        /** does oldflag = flag, flag = 1 */
        TEST_AND_SET(&oldFlag, &mutexFlag);
        /** as one indivisible operation */
    } while (oldFlag);
critical_end() {
   mutexFlag = 0:
```

# Dekker's Algorithm (2 processes)

```
int need[2] = \{0, 0\};
int turn;
critical_begin(int who) {
    need[who] = 1;
    turn = !who;
    while (need[ !who ] && turn != who)
critical_end(int who) {
    need[ who ] = 0;
}
```

#### **Semaphores**

A **semaphore** is a synchronization primitive which has an internal integer counter supporting the following operations:

**signal** increments the internal counter

wait until the internal counter > 0 ...only then decrement the counter

# Semaphore Implementation - Using Mutexes

```
SEM_WAIT(semaphore_t *s) {
                                 SEM_SIGNAL(semaphore_t *s) {
   semaphore_t oldsem;
                                     critical_begin():
                                     *s = *s + 1;
                                     critical_end():
   /** wait until sem > 0 */
   do {
       critical_begin();
       oldsem = *s:
       if (*s > 0)
           *s = *s - 1;
       critical_end();
   } while (oldsem == 0);
```

• commercial/professional implementations use tsleep() to block the process instead of a busy-loop

#### Semaphore Producer/Consumer

```
available_sem = QSIZE;
used sem = 0:
critical_sem = 1;
void add_queue(char aNewChar) {
  SEM_WAIT( &available_sem ):
  SEM_WAIT( &critical_sem ):
  Q[ endQpos ] = aNewChar;
  endQpos = (endQpos + 1) % QSIZE;
  SEM_SIGNAL( &critical_sem );
  SEM_SIGNAL( &used_sem );
```

```
void del_queue(char aNewChar) {
  int tmpBuf;
  SEM_WAIT( &used_sem );
  SEM_WAIT( &critical_sem );
  tmpBuf = Q[ startQpos ];
  startQpos = (startQpos + 1)
       % QSIZE;
  SEM_SIGNAL( &critical_sem );
  SEM_SIGNAL( &available_sem ):
  return tmpBuf;
```

## Co-Operating Sequential Processes - Examples

```
semaphore_t U = 1; semaphore_t D = 0; int sharedch = 'a';
up() {
                                  down() {
  while (1) {
                                    while (1) {
     printf("U-%c ", sharedch);
                                       printf("D-%c ", sharedch);
     if(++sharedch > 'z')
                                       if(--sharedch < 'a')</pre>
       sharedch = 'a';
                                         sharedch = 'a';
```

## Co-Operating Sequential Processes - Example #1

```
semaphore_t U = 1; semaphore_t D = 0; int sharedch = 'a';
                                  down() {
up() {
  while (1) {
                                    while (1) {
    SEM_WAIT( &U );
                                       SEM_WAIT( &D );
    printf("U-%c ", sharedch);
                                       printf("D-%c ", sharedch);
     if(++sharedch > 'z')
                                       if(--sharedch < 'a')</pre>
       sharedch = 'a';
                                         sharedch = 'a';
     SEM_SIGNAL( &D );
                                       SEM_SIGNAL( &U );
    Output: U-a D-b U-a D-b U-a ...
```

# Co-Operating Sequential Processes - Example #2

```
semaphore_t U = 2; semaphore_t D = 0; int sharedch = 'a';
                                  down() {
up() {
  while (1) {
                                    while (1) {
    SEM_WAIT( &U );
                                       SEM_WAIT( &D );
                                       SEM_WAIT( &D );
    printf("U-%c ", sharedch);
                                       printf("D-%c ", sharedch);
     if(++sharedch > 'z')
                                       if(--sharedch < 'a')</pre>
       sharedch = 'a';
                                         sharedch = 'a';
     SEM_SIGNAL( &D ):
                                       SEM_SIGNAL( &U );
                                       SEM_SIGNAL( &U );
    Output: U-a U-b D-c U-c U-d D-e U-d U-e D-f U-e U-f D-g U-f ...
```

# Co-Operating Sequential Processes - Example #3


```
semaphore_t U = 0; semaphore_t D = 2; int sharedch = 'a';
                                  down() {
up() {
  while (1) {
                                    while (1) {
    SEM_WAIT( &U );
                                       SEM_WAIT( &D );
    printf("U-%c ", sharedch);
                                       SEM_WAIT( &D );
     if(++sharedch > 'z')
                                       printf("D-%c ", sharedch);
       sharedch = 'a';
                                      if(--sharedch < 'a')</pre>
     SEM_SIGNAL( &D ):
                                         sharedch = 'a';
                                       SEM_SIGNAL( &U );
                                       SEM_SIGNAL( &U );
```

Output: D-a U-a U-b D-c U-c U-d D-e U-d U-e D-f U-e U-f D-g ...


## **Semaphore Hints:**

- all semaphores must be properly initialized
- always work from the definition of wait\_sem() and signal\_sem()
- normally, there will be a wait\_sem with a corresponding signal\_sem() on the same semaphore
- the order of wait\_sem() operations is quite important; the order of signal less so


- deadlock occurs when processes hold resources and they require resources that other processes already hold
- shown by the presence of a cycle in the request allocation graph




- deadlock occurs when processes hold resources and they require resources that other processes already hold
- shown by the presence of a cycle in the request allocation graph




- deadlock occurs when processes hold resources and they require resources that other processes already hold
- shown by the presence of a cycle in the request allocation graph




- deadlock occurs when processes hold resources and they require resources that other processes already hold
- shown by the presence of a cycle in the request allocation graph



- deadlock occurs when processes hold resources and they require resources that other processes already hold
- shown by the presence of a cycle in the request allocation graph



- deadlock occurs when processes hold resources and they require resources that other processes already hold
- shown by the presence of a cycle in the request allocation graph



## Java synchronized keyword

- The synchronized keyword can be used on a whole method or a block to provide a critical section
- method locking:

```
public class SyncCount {
   private int count = 0;
   public synchronized void increment() { count++; };
   public synchronized int getValue() { return count; };
}
```

• block locking:

```
public void someMethod() {
    while(keepGoing()) {
        synchronized(someObject) {
            count++;
        }
    }
}
```

## **IPC** in General

Shared Memory blocks of shared process image
Semaphores/Mutexes integer data values for flow control
Signals a software "interrupt"
Pipes an imitation file shared by two processes

# **Signals**

- used to indicate that some important event has happened
- sequence of events
  - process A is running and performing some task
  - process B sends a signal to process A
  - process A interrupts whatever it is doing ...
  - call a signal handler (a function) ...
  - returns to whatever it was doing before
- there is no direct notification to process B that anything has been done

# Signal Values

Signals are simply integer valued actions, similar to interrupts. Some common signals are:


1	HUP	hangup	BUS	bus error
2	INT	interrupt	SEGV	segmentation violation
3	QUIT	quit	PWR	power failure
4	ILL	illegal instruction	TERM	terminate process
5	TRAP	trace trap	USR1	user defined #1
9	KILL	kill process	USR2	user defined #2

# Signal Example

```
#include <signal.h>
void signalHandler(int code)
{
    fprintf(stderr.
            "Interrupt caught — cleaning up\n");
    performCleanup():
    exit(1);
void main()
    signal(SIGINT, signalHandler);
```

## **Pipes**

A **pipe** is a file descriptor pair shared between processes, attached to a buffer common to both processes. The buffer is not stored anywhere in a filesystem, only in memory.



## Scheduling

#### Basic process scheduler loop:

- when a process can no longer run (exits, waiting for I/O or time-slice used up)
  - mark process RUNNABLE or blocked (and why blocked status)
  - save process context in process table entry
- search process table for another RUNNABLE process
  - · mark this process running
  - restore process context for this process
- the system now runs this process, picking up where it left off (just as with a hardware interrupt)

# Scheduling Algorithm or "Queuing Discipline"

#### **FIFO**

- if jobs/processes/...repeatedly join the queue this is typically called "round robin."
- typically, round robin is preemptive

#### **SJF**

- shortest job first
- allow the job with the shortest running time to go next (jump to the head of the queue)
- not preemptive

A preemptive discipline permits a job to be preempted before it completes

# Scheduling Algorithms/Queuing Disciplines

- FIFO and round robin are generally considered to be fair, as jobs cannot be stuck waiting forever
- SJF is optimal w.r.t. throughput:
  - iff you always run the job that will finish in the shortest time.
  - will always finish more jobs in a given elapsed time than any other ordering
  - it is unfair, and impractical for processes (can be approximated)

# Scheduling Algorithms/Queuing Disciplines

#### In general:

- preemptive schedulers will perform better (i.e.; smoother response) than non-preemptive schedulers and are required for interactive systems
- schedulers will normally bias towards short jobs, such as updating an editor after a keystroke
- operators/users will be able to set/adjust priorities for jobs, see nice(1)
  - dynamic priority is updated during context switch based on last run time
- there will always be a trade-off between coarse -vs-fine granularity of the time-slices:

coarse: low overhead/poor interactive response fine: higher overhead/better interactive response

# Scheduling Algorithms/Queuing Disciplines

 if preemption occurs extremely frequently such that each job gets an infinitesimally small time each time it runs, the discipline is called "processor sharing"

 whereas, if the preemption time is infinitely large, the discipline is called FIFO

## Scheduling Algorithms/Types of Tasks


batch insensitive to gaps in runtime; get overall task done

interactive sensitive to runtime gaps; typically lots of I/O

real-time critically sensitive to runtime gaps

demand fixed fraction of CPU/unit time

# Priority Queues (VMS/Windows)



Some systems vary the priority dynamically, others do not