Programming Parallel Computers

```
Intro Chapter 1 Chapter 2 Chapter 3 Chapter 4 Lectures Links About Index
```

Chapter 2: Case study

```
        Intro
        V0
        Asm
        OpenMP
        V1
        Asm
        V2
        Asm
        V3
        Asm
        V4
        Asm
        V5
        Asm
        V6
        V7
```

Version 2: Assembly code [advanced]

Let us now see that the compiler really does the right job here. By looking at the assembly code produced by the compiler, we see that the innermost loops

```
for (int ka = 0; ka < na; ++ka) {
    for (int kb = 0; kb < nb; ++kb) {
        float x = d[nab*i + ka * nb + kb];
        float y = t[nab*j + ka * nb + kb];
        float z = x + y;
        vv[kb] = std::min(vv[kb], z);
    }
}</pre>
```

get translated into this assembly code:

```
LOOP:
                      (%rax), %xmm0
           VMOVSS
          addq
                      $16, %rax
                      $16, %rdx
           addq
           vaddss
                      -16(%rdx), %xmm0, %xmm0
                      %xmm1, %xmm0, %xmm1
           vminss
                      -12(%rax), %xmm0
           vmovss
           vaddss
                      -12(%rdx), %xmm0, %xmm0
                      %xmm4, %xmm0, %xmm4
           vminss
                      -8(%rax), %xmm0
           VMOVSS
           vaddss
                      -8(%rdx), %xmm0, %xmm0
                      %xmm3, %xmm0, %xmm3
           vminss
                      -4(%rax), %xmm0
           VMOVSS
           vaddss
                      -4(%rdx), %xmm0, %xmm0
                      %rsi, %rax
           cmpq
                      %xmm2, %xmm0, %xmm2
           vminss
                      L00P
           jne
```

```
Modified C++ code
                             Assembly code
x = d[... + 0];
                             vmovss ..., %xmm0
                            vaddss ..., %xmm0, %xmm0
x = t[... + 0] + x;
vv[0] = std::min(vv[0], x); vminss %xmm1, %xmm0, %xmm1
x = d[... + 1];
                            vmovss ..., %xmm0
x = t[... + 1] + x;
                            vaddss ..., %xmm0, %xmm0
vv[1] = std::min(vv[1], x); vminss %xmm4, %xmm0, %xmm4
x = d[... + 2];
                            vmovss ..., %xmm0
x = t[... + 2] + x; vaddss ..., %xmm0, %xmm0
vv[2] = std::min(vv[2], x); vminss %xmm3, %xmm0, %xmm3
x = d[... + 3];
                            vmovss ..., %xmm0
x = t[... + 3] + x;
                            vaddss ..., %xmm0, %xmm0
vv[3] = std::min(vv[3], x); vminss %xmm2, %xmm0, %xmm2
                            %xmm0
X
vv[0]
                             %xmm1
vv[1]
                            %xmm4
vv[2]
                            %xmm3
vv[3]
                            %xmm2
```

Most importantly, we can see that the compiler did not do anything special related to instruction-level parallelism. There is no special annotation in the machine code that instructs the CPU which operations can be executed in parallel. The CPU does the job by itself, and it automatically realizes that all of these instructions can be safely executed in parallel (as soon as the other operand is available):

```
vminss %xmm1, ..., %xmm1
vminss %xmm4, ..., %xmm4
vminss %xmm3, ..., %xmm3
vminss %xmm2, ..., %xmm2
....
```

But what about vaddss and %xmm0?

At first it might look like the register %xmm0 would be a bottleneck here. Every vaddss operation needs it, every vaddss operation modifies it, and finally every vminss needs it. Doesn't this make the code inherently sequential, and prevent the processor from executing instructions efficiently?

The short answer is: no, this is not a problem, thanks to **register renaming**. The names such as <code>%xmm0</code> do not really refer to physical registers in the processor, but they are just some labels that the programmer can use – a lot like the names of the local variables in C++ code, except that there is a limited number of those.

Internally, the processor is free to assign these labels into physical registers, as long as it does not change the result. Let us use fictitious names such as %xmm0a for the physical registers. The processor might rename the registers e.g. as follows:

```
Original registers
                            Physical registers
vmovss ..., %xmm0
                            vmovss ..., %xmm0a
vaddss ..., %xmm0, %xmm0
                            vaddss ..., %xmm0a, %xmm0a
vminss %xmm1, %xmm0, %xmm1 vminss %xmm1, %xmm0a, %xmm1
vmovss ..., %xmm0
                            vmovss ..., %xmm0b
vaddss ..., %xmm0, %xmm0
                            vaddss ..., %xmm0b, %xmm0b
vminss %xmm4, %xmm0, %xmm4 vminss %xmm4, %xmm0b, %xmm4
vmovss ..., %xmm0
                           vmovss ..., %xmm0c
vaddss ..., %xmm0, %xmm0
                           vaddss ..., %xmm0c, %xmm0c
vminss %xmm3, %xmm0, %xmm3 vminss %xmm3, %xmm0c, %xmm3
vmovss ..., %xmm0
                            vmovss ..., %xmm0d
                           vaddss ..., %xmm0d, %xmm0d
vaddss ..., %xmm0, %xmm0
vminss %xmm2, %xmm0, %xmm2 vminss %xmm2, %xmm0d, %xmm2
```

separate local variables in the C++ code, instead of reusing the same variable |x|:

Clearly, the new code is equivalent to the old code. What we achieved is the same thing as if we had used

```
Original C++ code

x = d[... + 0];
x = t[... + 0] + x;
vv[0] = std::min(vv[0], x);
x = d[... + 1];
x = t[... + 1] + x;
vv[1] = std::min(vv[1], x);
x = d[... + 2];
x = t[... + 2] + x;
vv[2] = std::min(vv[2], x);
x = d[... + 3];
x = t[... + 3] + x;
vv[3] = std::min(vv[3], x);
Renamed variables

xa = d[... + 0];
xa = t[... + 0] + xa;
vv[0] = std::min(vv[0], xa);
xb = d[... + 1];
xb = d[... + 1];
xb = t[... + 1] + xb;
vv[1] = std::min(vv[1], xb);
xc = d[... + 2];
xc = t[... + 2] + xc;
vv[2] = std::min(vv[2], xc);
xd = d[... + 3];
xd = t[... + 3] + xd;
vv[3] = std::min(vv[3], xd);
```

the following memory lookup instructions in parallel:

vmovss ..., %xmm0a

After renaming, it is much easier to see that there is lots of potential for parallelism. For example, we can execute

```
vmovss ..., %xmm0a
vmovss ..., %xmm0b
vmovss ..., %xmm0c
vmovss ..., %xmm0d
```

vaddss ..., %xmm0a, %xmm0a
vaddss ..., %xmm0b, %xmm0b

And we can do the following additions in parallel:

```
      vaddss ..., %xmm0b, %xmm0b

      vaddss ..., %xmm0c, %xmm0c

      vaddss ..., %xmm0d, %xmm0d

And finally we can also do the following minimum operations in parallel:
```

vminss %xmm1, %xmm0a, %xmm1
vminss %xmm4, %xmm0b, %xmm4
vminss %xmm2, %xmm0a, %xmm2

```
vminss %xmm3, %xmm0c, %xmm3
vminss %xmm2, %xmm0d, %xmm2

This is not the whole truth. The CPU looks at the instruction stream much further than just one iteration of the loop, and does register allocation and instruction scheduling for a code segment that spans several iterations of the innermost loop. Hence, it might well happen that the CPU is executing simultaneously e.g.
```

• vminss related to iteration ka,

memory lookups related to iteration ka + 2,
vaddss operations related to iteration ka + 1, and

```
Hence, e.g., the results of vaddss will be conveniently available when vminss needs them.
```

Analysis

are 2 execution ports ("port 0" and "port 1") in the CPU core that are able to run vaddss and vminss operations. In each clock cycle, we can start either one vaddss or one vminss operation in port 0, and simultaneously we can also start either one vaddss or one vminss operation in port 1.

2 operations per clock cycle per CPU core.
And it turns out that we are now pretty close to the theoretical limits. For n = 4000, we now manage to do approx.
1.6 operations per clock cycle per CPU core, so there is not much room for improvement unless we manage to write code that does something substantially different from vaddss and vminss.

operations per clock cycles. In addition to these operations, we also do memory lookups, manipulations of the

Hence if we have any sequence of vaddss and/or vminss operations, we can at best hope to complete

Note that the number 1.6 is the number of "useful" operations, i.e., the number of vaddss and vminss

Recall that vaddss and vminss have a throughput of 2 instructions per clock cycle. A bit more precisely, there

loop counters, comparisons, and conditional jumps. The grand total is approx. 3.3 machine language instructions per clock cycle per core (we can easily find these statistics with the help of the perf tool — just run the program under perf stat and see the output). This is a relatively high number. It is reasonable to expect the CPU cores to execute some 3–4 instructions per clock cycle, but much more than that is going to be difficult to achieve in practice. Hence, for further speedups we will need to do more useful work per instruction. This is exactly what we can achieve with vector instructions, which is our next topic.

Interactive assembly

As before, a simplified version of this code is provided on Compiler Explorer. You can experiment with this, e.g.,

see what happens if you change the nb variable. Here are some suggestions to investigate:

V1 Asm

What happens if you increase nb a bit?
 What happens if you remove the constexpr specifier? Also try this with less aggressive optimization, i.e.,

OpenMP

-02 .

Intro

V0 Asm

- What happens if you remove the constexpr specifier, but move the declaration of nb inside step?
 What happens if you increase nb a lot, e.g., to 20?

V2 Asm

[V3 | Asm]

(V5 | Asm)

V6

V4 Asm