Amazon Kinesis Video Streams Developer Guide



Amazon Kinesis Video Streams: Developer Guide

Copyright © 2019 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

What Is Amazon Kinesis Video Streams?	
Are You a First-Time User of Kinesis Video Streams?	2
System Requirements	
Camera Requirements	3
Tested Cameras	
Tested Operating Systems	4
SDK Storage Requirements	4
How It Works	5
API and Producer Libraries	6
Kinesis Video Streams API	6
Producer Libraries	8
Video Playback Using HLS	9
Example: Using HLS in HTML and JavaScript	9
Using Streaming Metadata	
Adding Metadata to a Kinesis Video Stream	
Consuming Metadata Embedded in a Kinesis Video Stream	
Streaming Metadata Limitations	
Controlling Access	
Policy Syntax	
Actions for Kinesis Video Streams	
Amazon Resource Names (ARNs) for Kinesis Video Streams	
Granting Other IAM Accounts Access to a Kinesis Video Stream	
Example Policies	
Using Server-Side Encryption	
What Is Server-Side Encryption for Kinesis Video Streams?	
Costs, Regions, and Performance Considerations	
How Do I Get Started with Server-Side Encryption?	
Creating and Using User-Generated AWS KMS Master Keys	
Permissions to Use User-Generated AWS KMS Master Keys	
Data Model	
Stream Header Elements	
Stream Track Data	
Frame Header Elements	
MKV Frame Data	
Getting Started	
Step 1: Set Up an Account	
Sign Up for AWS	
Create an Administrator IAM User	
Create an AWS Account Key	
Next Step	
Step 2: Create a Kinesis Video Stream	
Create a Video Stream Using the Console	
Create a Video Stream Using the AWS CLI	
Next Step	
Step 3: Send Data to a Kinesis Video Stream	
Download the C++ Producer SDK	
Compile the GStreamer Example	
Run the GStreamer Example	
Next Step	
What's Next?	
Producer Libraries	
	3 ²
Kinesis Video Streams Producer Library	

Related Topics	35
Java Producer Library	35
Procedure: Using the Java Producer SDK	36
Step 1: Download and Configure the Code	36
Step 2: Write and Examine the Code	
Step 3: Run and Verify the Code	
Android Producer Library	
Procedure: Using the Android Producer SDK	
Step 1: Download and Configure the Code	
Step 2: Examine the Code	
Step 3: Run and Verify the Code	
C++ Producer Library	
Object Model	
Putting Media into the Stream	
Callback Interfaces	
Procedure: Using the C++ Producer SDK	
Step 1: Download and Configure the Code	
Step 2: Write and Examine the Code	
Step 3: Run and Verify the Code	
Using the C++ Producer SDK as a GStreamer Plugin	
Using the C++ Producer SDK as a GStreamer Plugin in a Docker Container	
Using the C++ Producer SDK on Windows	53
Using the C++ Producer SDK on Raspberry Pi	57
Using Logging	62
Reference	63
Producer SDK Limits	
Error Code Reference	65
NAL Adaptation Flags	
Producer Structures	
Stream Structures	
Callbacks	
Stream Parser Library	
Procedure: Using the Kinesis Video Stream Parser Library	
Prerequisites	
Step 1: Download and Configure the Code	
Next Step	
Step 2: Write and Examine the Code	
StreamingMkvReader	
FragmentMetadataVisitor	
OutputSegmentMerger	
KinesisVideoExample	
Next Step	
Step 3: Run and Verify the Code	113
Examples	114
Examples: Sending Data to Kinesis Video Streams	114
Examples: Retrieving Data from Kinesis Video Streams	
Examples: Playing Back Video Data	114
Prerequisites	
GStreamer	
Download, Build, and Configure the GStreamer Element	
Run the GStreamer Element	
Launch Commands	
Run the GStreamer Element in a Docker Container	
Parameter Reference	
PutMedia API	
Step 1: Download and Configure the Code	
Step 2: Write and Examine the Code	125

Step 3: Run and Verify the Code	126
RTSP and Docker	. 127
Prerequisites	127
Build the Docker Image	. 127
Run the RTSP Example Application	
Renderer	
Prerequisites	
Running the Renderer Example	
How It Works	
Amazon SageMaker	
Prerequisites	
Creating the Application	
Monitoring the Application	
Extending the Application	
Cleaning up the Application	
Monitoring	
Monitoring Metrics with CloudWatch	
CloudWatch Metrics Guidance	
Logging API Calls with CloudTrail	
Kinesis Video Streams and CloudTrail	
Example: Amazon Kinesis Video Streams Log File Entries	145
_imits	. 148
Control Plane API limits	148
Media and Archived Media API limits	
Troubleshooting	
Troubleshooting General Issues	
Latency too high	
Troubleshooting API Issues	
Error: "Unknown options"	
Error: "Unable to determine service/operation name to be authorized"	
Error: "Failed to put a frame in the stream"	
Error: "Service closed connection before final AckEvent was received"	
Error: "STATUS_STORE_OUT_OF_MEMORY"	
Troubleshooting HLS Issues	
Retrieving HLS streaming session URL succeeds, but playback fails in video player	153
Latency too high between producer and player	154
Troubleshooting Java Issues	154
Enabling Java logs	
Troubleshooting Producer Library Issues	
Cannot compile the Producer SDK	
Video stream does not appear in the console	
Error: "Security token included in the request is invalid" when streaming data using the	
GStreamer demo application	156
Error: "Failed to submit frame to Kinesis Video client"	
	150
GStreamer application stops with "streaming stopped, reason not-negotiated" message on OS	457
X	15/
Error: "Failed to allocate heap" when creating Kinesis Video Client in GStreamer demo on	
Raspberry Pi	157
Error: "Illegal Instruction" when running GStreamer demo on Raspberry Pi	
Camera fails to load on Raspberry Pi	
Camera can't be found on macOS High Sierra	
jni.h file not found when compiling on macOS High Sierra	
Curl errors when running the GStreamer demo application	
Timestamp/range assertion at runtime on Raspberry Pi	
Assertion on qst_value_set_fraction_range_full on Raspberry Pi	
STATUS_MKV_INVALID_ANNEXB_NALU_IN_FRAME_DATA (0x3200000d) error on Android	
Maximum Fragment Duration Was Reached Error	159

Amazon Kinesis Video Streams Developer Guide

Troubleshooting Stream Parser Library Issues	159
Cannot access a single frame from the stream	160
Fragment decoding error	
Document History	161
API Reference	164
Actions	164
Amazon Kinesis Video Streams	
Amazon Kinesis Video Streams Media	195
Amazon Kinesis Video Streams Archived Media	
Data Types	218
Amazon Kinesis Video Streams	219
Amazon Kinesis Video Streams Media	222
Amazon Kinesis Video Streams Archived Media	224
Common Errors	229
Common Parameters	231

What Is Amazon Kinesis Video Streams?

Amazon Kinesis Video Streams is a fully managed AWS service that you can use to stream live video from devices to the AWS Cloud, or build applications for real-time video processing or batch-oriented video analytics.

Kinesis Video Streams isn't just storage for video data. You can use it to watch your video streams in real time as they are received in the cloud. You can either monitor your live streams in the AWS Management Console, or develop your own monitoring application that uses the Kinesis Video Streams API library to display live video.

You can use Kinesis Video Streams to capture massive amounts of live video data from millions of sources, including smartphones, security cameras, webcams, cameras embedded in cars, drones, and other sources. You can also send non-video time-serialized data such as audio data, thermal imagery, depth data, RADAR data, and more. As live video streams from these sources into a Kinesis video stream, you can build applications that can access the data, frame-by-frame, in real time for low-latency processing. Kinesis Video Streams is source-agnostic; you can stream video from a computer's webcam using the GStreamer (p. 115) library, or from a camera on your network using RTSP.

You can also configure your Kinesis video stream to durably store media data for the specified retention period. Kinesis Video Streams automatically stores this data and encrypts it at rest. Additionally, Kinesis Video Streams time-indexes stored data based on both the producer time stamps and ingestion time stamps. You can build applications that periodically batch-process the video data, or you can create applications that require ad hoc access to historical data for different use cases.

Your custom applications, real-time or batch-oriented, can run on Amazon EC2 instances. These applications might process data using open source deep-learning algorithms, or use third-party applications that integrate with Kinesis Video Streams.

Benefits of using Kinesis Video Streams include the following:

- Connect and stream from millions of devices Kinesis Video Streams enables you to connect and stream video, audio, and other data from millions of devices ranging from consumer smartphones, drones, dash cams, and more. You can use the Kinesis Video Streams producer libraries to configure your devices and reliably stream in real time, or as after-the-fact media uploads.
- **Durably store, encrypt, and index data** You can configure your Kinesis video stream to durably store media data for custom retention periods. Kinesis Video Streams also generates an index over the stored data based on producer-generated or service-side time stamps. Your applications can easily retrieve specified data in a stream using the time-index.
- Focus on managing applications instead of infrastructure Kinesis Video Streams is serverless, so there is no infrastructure to set up or manage. You don't need to worry about the deployment, configuration, or elastic scaling of the underlying infrastructure as your data streams and number of consuming applications grow and shrink. Kinesis Video Streams automatically does all the administration and maintenance required to manage streams, so you can focus on the applications, not the infrastructure.
- Build real-time and batch applications on data streams You can use Kinesis Video Streams to build custom real-time applications that operate on live data streams, and create batch or ad hoc applications that operate on durably persisted data without strict latency requirements. You can build, deploy, and manage custom applications: open source (Apache MXNet, OpenCV), homegrown, or third-party solutions via the AWS Marketplace to process and analyze your streams. Kinesis Video Streams

Get APIs enable you to build multiple concurrent applications processing data in a real-time or batchoriented basis.

- Stream data more securely Kinesis Video Streams encrypts all data as it flows through the service and when it persists the data. Kinesis Video Streams enforces Transport Layer Security (TLS)-based encryption on data streaming from devices, and encrypts all data at rest using AWS Key Management Service (AWS KMS). Additionally, you can manage access to your data using AWS Identity and Access Management (IAM).
- Pay as you go For more information, see AWS Pricing.

Are You a First-Time User of Kinesis Video Streams?

If you're a first-time user of Kinesis Video Streams, we recommend that you read the following sections in order:

- Amazon Kinesis Video Streams: How It Works (p. 5) To learn about Kinesis Video Streams concepts.
- Getting Started with Kinesis Video Streams (p. 27) To set up your account and test Kinesis Video Streams.
- 3. Kinesis Video Streams Producer Libraries (p. 34) To learn about creating a Kinesis Video Streams producer application.
- 4. Kinesis Video Stream Parser Library (p. 107) To learn about processing incoming data frames in a Kinesis Video Streams consumer application.
- Amazon Kinesis Video Streams Examples (p. 114) To see more examples of what you can do with Kinesis Video Streams.

Kinesis Video Streams System Requirements

The following sections contain hardware, software, and storage requirements for Amazon Kinesis Video Streams.

Topics

- Camera Requirements (p. 3)
- SDK Storage Requirements (p. 4)

Camera Requirements

Cameras that are used for running the Kinesis Video Streams Producer SDK and samples have the following memory requirements:

- · The SDK content view requires 16 MB of memory.
- The sample application default configuration is 512 MB. This value is appropriate for producers that have good network connectivity and no requirements for additional buffering. If the network connectivity is poor and more buffering is required, you can calculate the memory requirement per second of buffering by multiplying the frame rate per second by the frame memory size. For more information about allocating memory, see StorageInfo (p. 88).

We recommend using USB or RTSP (Real Time Streaming Protocol) cameras that encode data using H.264 because this removes the encoding workload from the CPU.

Currently, the demo application does not support the User Datagram Protocol (UDP) for RTSP streaming. This capability will be added in the future.

The Producer SDK supports the following types of cameras:

- · Web cameras.
- · USB cameras.
- Cameras with H.264 encoding (preferred).
- · Cameras without H.264 encoding.
- Raspberry Pi camera module. This is preferred for Raspberry Pi devices because it connects to the GPU for video data transfer, so there is no overhead for CPU processing.
- RTSP (network) cameras. These cameras are preferred because the video streams are already encoded with H.264.

Tested Cameras

We have tested the following USB cameras with Kinesis Video Streams:

- Logitech 1080p
- · Logitech C930
- Logitech C920 (H.264)

Amazon Kinesis Video Streams Developer Guide Tested Operating Systems

- Logitech Brio (4K)
- SVPRO USB Camera 170degree Fisheye Lens Wide Angle 1080P 2mp Sony IMX322 HD H.264 30fps Mini Aluminum USB Webcam Camera

We have tested the following IP cameras with Kinesis Video Streams:

- Vivotek FD9371 HTV/EHTV
- Vivotek IB9371 HT
- Hikvision 3MP IP Camera DS-2CD2035FWD-I
- Sricam SP012 IP
- VStarcam 720P WiFi IP Camera (TCP)
- Ipccam Security Surveillance IP Camera 1080P
- AXIS P3354 Fixed Dome Network Camera

Of the cameras that were tested with Kinesis Video Streams, the Vivotek cameras have the most consistent RTSP stream. The Sricam camera has the least consistent RTSP stream.

Tested Operating Systems

We have tested web cameras and RTSP cameras with the following devices and operating systems:

- · Mac mini
 - · High Sierra
- · MacBook Pro laptops
 - Sierra (10.12)
 - El Capitan (10.11)
- HP laptops running Ubuntu 16.04
- Ubuntu 17.10 (Docker container)
- Raspberry Pi 3

SDK Storage Requirements

Installing the Kinesis Video Streams Producer Libraries (p. 34) has a minimum storage requirement of 170 MB and a recommended storage requirement of 512 MB.


Amazon Kinesis Video Streams: How It Works

Topics

- Kinesis Video Streams API and Producer Libraries Support (p. 6)
- Kinesis Video Streams Playback with HLS (p. 9)
- Using Streaming Metadata with Kinesis Video Streams (p. 12)
- Controlling Access to Kinesis Video Streams Resources Using IAM (p. 15)
- Using Server-Side Encryption with Kinesis Video Streams (p. 18)
- Kinesis Video Streams Data Model (p. 22)

Amazon Kinesis Video Streams is a fully managed AWS service that enables you to stream live video from devices to the AWS Cloud and durably store it. You can then build your own applications for real-time video processing or perform batch-oriented video analytics.

The following diagram provides an overview of how Kinesis Video Streams works.



Amazon Kinesis Video Streams Developer Guide API and Producer Libraries

The diagram demonstrates the interaction among the following components:

 Producer – Any source that puts data into a Kinesis video stream. A producer can be any videogenerating device, such as a security camera, a body-worn camera, a smartphone camera, or a dashboard camera. A producer can also send non-video data, such as audio feeds, images, or RADAR data.

A single producer can generate one or more video streams. For example, a video camera can push video data to one Kinesis video stream and audio data to another.

- Kinesis Video Streams Producer libraries A set of easy-to-use software and libraries that you can install and configure on your devices. These libraries make it easy to securely connect and reliably stream video in different ways, including in real time, after buffering it for a few seconds, or as after-the-fact media uploads.
- **Kinesis video stream** A resource that enables you to transport live video data, optionally store it, and make the data available for consumption both in real time and on a batch or ad hoc basis. In a typical configuration, a Kinesis video stream has only one producer publishing data into it.

The stream can carry audio, video, and similar time-encoded data streams, such as depth sensing feeds, RADAR feeds, and more. You create a Kinesis video stream using the AWS Management Console or programmatically using the AWS SDKs.

Multiple independent applications can consume a Kinesis video stream in parallel.

- Consumer Gets data, such as fragments and frames, from a Kinesis video stream to view, process, or analyze it. Generally these consumers are called Kinesis Video Streams applications. You can write applications that consume and process data in Kinesis video streams in real time, or after the data is durably stored and time-indexed when low latency processing is not required. You can create these consumer applications to run on Amazon EC2 instances.
 - Kinesis Video Stream Parser Library (p. 107) Enables Kinesis Video Streams applications to reliably get media from Kinesis video streams in a low-latency manner. Additionally, it parses the frame boundaries in the media so that applications can focus on processing and analyzing the frames themselves.

Kinesis Video Streams API and Producer Libraries Support

Kinesis Video Streams provides APIs for you to create and manage streams and read or write media data to and from a stream. The Kinesis Video Streams console, in addition to administration functionality, also supports live and video-on-demand playback. Kinesis Video Streams also provides a set of producer libraries that you can use in your application code to extract data from your media sources and upload to your Kinesis video stream.

Topics

- Kinesis Video Streams API (p. 6)
- Producer Libraries (p. 8)

Kinesis Video Streams API

Kinesis Video Streams provides APIs for creating and managing Kinesis video streams. It also provides APIs for reading and writing media data to a stream, as follows:

 Producer API – Kinesis Video Streams provides a PutMedia API to write media data to a Kinesis video stream. In a PutMedia request, the producer sends a stream of media fragments. A fragment is a self-

Amazon Kinesis Video Streams Developer Guide Kinesis Video Streams API

contained sequence of frames. The frames belonging to a fragment should have no dependency on any frames from other fragments. For more information, see PutMedia (p. 200).

As fragments arrive, Kinesis Video Streams assigns a unique fragment number, in increasing order. It also stores producer-side and server-side time stamps for each fragment, as Kinesis Video Streams-specific metadata.

- Consumer APIs –The following APIs enable consumers to get data from a stream:
 - GetMedia When using this API, consumers must identify the starting fragment. The API then returns fragments in the order in which they were added to the stream (in increasing order by fragment number). The media data in the fragments is packed into a structured format such as Matroska (MKV). For more information, see GetMedia (p. 196).

Note

GetMedia knows where the fragments are (archived in the data store or available in real time). For example, if GetMedia determines that the starting fragment is archived, it starts returning fragments from the data store. When it needs to return newer fragments that are not archived yet, GetMedia switches to reading fragments from an in-memory stream buffer.

This is an example of a continuous consumer, which processes fragments in the order that they are ingested by the stream.


GetMedia enables video-processing applications to fail or fall behind, and then catch up with no additional effort. Using GetMedia, applications can process data that's archived in the data store, and as the application catches up, GetMedia continues to feed media data in real time as it arrives.

• GetMediaFromFragmentList (and ListFragments) - Batch processing applications are considered offline consumers. Offline consumers might choose to explicitly fetch particular media fragments or ranges of video by combining the ListFragments and GetMediaFromFragmentList APIs. ListFragments and GetMediaFromFragmentList enable an application to identify segments of video for a particular time range or fragment range, and then fetch those fragments either sequentially or in parallel for processing. This approach is suitable for MapReduce application suites, which must quickly process large amounts of data in parallel.

For example, suppose that a consumer wants to process one day's worth of video fragments. The consumer would do the following:

- 1. Get a list of fragments by calling the ListFragments API and specifying a time range to select the desired collection of fragments.
 - The API returns metadata from all the fragments in the specified time range. The metadata provides information such as fragment number, producer-side/server-side time stamps, and so on.
- 2. Take the fragment metadata list and retrieve fragments, in any order. For example, to process all the fragments for the day, the consumer might choose to split the list into sub-lists and have workers (for example, multiple Amazon EC2 instances) fetch the fragments in parallel using the GetMediaFromFragmentList, and process them in parallel.

The following diagram shows the data flow for fragments and chunks during these API calls.



When a producer sends a PutMedia request, it sends media metadata in the payload, and then sends a sequence of media data fragments. Upon receiving the data, Kinesis Video Streams stores incoming media data as Kinesis Video Streams chunks. Each chunk consists of the following:

- · A copy of the media metadata
- A fragment
- Kinesis Video Streams-specific metadata; for example, the fragment number and server-side and producer-side time stamps

When a consumer requests media metadata, Kinesis Video Streams returns a stream of chunks, starting with the fragment number that you specify in the request.

If you enable data persistence for the stream, after receiving a fragment on the stream, Kinesis Video Streams also saves a copy of the fragment to the data store.

Producer Libraries

After you create a Kinesis video stream, you can start sending data to the stream. In your application code, you can use these libraries to extract data from your media sources and upload to your Kinesis video stream. For more information about the available producer libraries, see Kinesis Video Streams Producer Libraries (p. 34).

Kinesis Video Streams Playback with HLS

HTTP Live Streaming (HLS) is an industry-standard HTTP-based media streaming communications protocol. You can use HLS to view an Amazon Kinesis video stream, either for live playback or to view archived video.

You can view a Kinesis video stream using either HLS or the GetMedia API. The differences between these methods are as follows:

- **GetMedia**: You use the GetMedia API to build your own applications to process Kinesis video streams. GetMedia is a real-time API with low latency. If you want to create a player that uses GetMedia, you have to build it yourself. For information about how to develop an application that displays a Kinesis video stream using GetMedia, see Stream Parser Library (p. 107).
- HLS: You can use HLS for live playback. Latency is typically between 3 and 5 seconds, but it can be
 between 1 and 10 seconds, depending on the use case, player, and network conditions. You can use a
 third-party player (such as Video.js or Google Shaka Player) to display the video stream by providing
 the HLS streaming session URL, either programmatically or manually. You can also play back video
 by typing the HLS streaming session URL in the Location bar of the Apple Safari or Microsoft Edge
 browsers.

To view a Kinesis video stream using HLS, you first create a streaming session using GetHLSStreamingSessionURL. This action returns a URL (containing a session token) for accessing the HLS session. You can then use the URL in a media player or a standalone application to display the stream.

An Amazon Kinesis video stream has the following requirements for providing video through HLS:

- Data retention must be greater than 0.
- Track 1 of the stream must have a codec ID of V_MPEG/ISO/AVC and contain H.264 encoded media. If
 there is an audio track (optional), it must be track number 2 and have a codec ID of A_AAC and contain
 AAC encoded audio.
- The fragments must contain codec private data in the Advanced Video Coding (AVC) for H.264 format (MPEG-4 specification ISO/IEC 14496-15) for the video media. They must also contain codec private data for ACC (AAC specification ISO/IEC 13818-7) for the audio media (if present). For information about adapting stream data to a given format, see NAL Adaptation Flags (p. 87).

Example: Using HLS in HTML and JavaScript

The following example shows how to retrieve an HLS streaming session for a Kinesis video stream and play it back in a webpage. The example shows how to play back video in the following players:

- · Video.js
- Google Shaka Player
- hls.js

Topics

- Set Up the Kinesis Video Streams Client (p. 10)
- Retrieve the Kinesis Video Streams Archived Content Endpoint (p. 10)
- Retrieve the HLS Streaming Session URL (p. 10)
- Display the Streaming Video (p. 11)
- Troubleshooting (p. 12)

• Completed Example (p. 12)

Set Up the Kinesis Video Streams Client

To access streaming video with HLS, first create and configure the Kinesis Video Streams client (to retrieve the service endpoint) and archived media client (to retrieve the HLS streaming session). The application retrieves the necessary values from input boxes on the HTML page.

```
<script src="https://cdnjs.cloudflare.com/ajax/libs/aws-sdk/2.278.1/aws-sdk.min.js"></
script>
...

var streamName = 'STREAM_NAME';

// Step 1: Configure SDK Clients
var options = {
    accessKeyId: 'ACCESS_KEY_ID',
    secretAccessKey: 'SECRET_KEY',
    region: 'REGION'
}

var kinesisVideo = new AWS.KinesisVideo(options);
var kinesisVideoArchivedContent = new AWS.KinesisVideoArchivedMedia(options);
```

Retrieve the Kinesis Video Streams Archived Content Endpoint

After the clients are initiated, retrieve the Kinesis Video Streams archived content endpoint to retrieve the HLS streaming session URL:

```
// Step 2: Get a data endpoint for the stream
kinesisVideo.getDataEndpoint({
    StreamName: streamName,
    APIName: "GET_HLS_STREAMING_SESSION_URL"
}, function(err, response) {
    if (err) { return console.error(err); }
    console.log('Data endpoint: ' + response.DataEndpoint);
    kinesisVideoArchivedContent.endpoint = new AWS.Endpoint(response.DataEndpoint);
});
```

Retrieve the HLS Streaming Session URL

When you have the archived content endpoint, call the GetHLSStreamingSessionURL API to retrieve the HLS streaming session URL:

```
// Step 3: Get an HLS Streaming Session URL
console.log('Fetching HLS Streaming Session URL');
var playbackMode = 'PLAYBACK_MODE'; // 'LIVE' or 'ON_DEMAND'
var startTimestamp = new Date('START_TIMESTAMP'); // For ON_DEMAND only
var endTimestamp = new Date('END_TIMESTAMP'); // For ON_DEMAND only
var fragmentSelectorType = 'FRAGMENT_SELECTOR_TYPE'; // 'SERVER_TIMESTAMP' or
'PRODUCER_TIMESTAMP'
kinesisVideoArchivedContent.getHLSStreamingSessionURL({
    StreamName: streamName,
    PlaybackMode: playbackMode,
    HLSFragmentSelector: {
        FragmentSelectorType: fragmentSelectorType,
        TimestampRange: playbackMode === 'LIVE' ? undefined : {
            StartTimestamp: startTimestamp,
            EndTimestamp: endTimestamp
```

```
}
},
Expires: parseInt(SESSION_EXPIRATION_SECONDS)
}, function(err, response) {
  if (err) { return console.error(err); }
  console.log('HLS Streaming Session URL: ' + response.HLSStreamingSessionURL);
```

Display the Streaming Video

When you have the HLS streaming session URL, provide it to the video player. The method for providing the URL to the video player is specific to the player used.

The following code example shows how to provide the streaming session URL to a Video.js player:

```
<!-- VideoJS elements -->
<video id="videojs" class="video-js vjs-default-skin" controls autoplay></video>
<script src="https://vjs.zencdn.net/6.6.3/video.js"></script>
<script src="https://cdnjs.cloudflare.com/ajax/libs/videojs-contrib-hls/5.14.1/videojs-</pre>
contrib-hls.js"></script>
var playerElement = $('#videojs');
playerElement.show();
var player = videojs('videojs');
console.log('Created VideoJS Player');
player.src({
    src: response.HLSStreamingSessionURL,
    type: 'application/x-mpegURL'
});
console.log('Set player source');
player.play();
console.log('Starting playback');
```

The following code example shows how to provide the streaming session URL to a Google Shaka player:

```
<!-- Shaka Player elements -->
<video id="shaka" controls autoplay></video>
<script src="https://cdnjs.cloudflare.com/ajax/libs/shaka-player/2.4.1/shaka-player.compiled.js"></script>
...

var playerElement = $('#shaka');
playerElement.show();
var player = new shaka.Player(playerElement[0]);
console.log('Created Shaka Player');
player.load(response.HLSStreamingSessionURL).then(function() {
    console.log('Starting playback');
});
console.log('Set player source');
```

The following code example shows how to provide the streaming session URL to an hls.js player:

```
<!-- hls.js Player elements -->
<video id="hlsjs" class="player" controls autoplay></video>
<script src="https://cdn.jsdelivr.net/npm/hls.js@latest"></script>
```

Amazon Kinesis Video Streams Developer Guide Using Streaming Metadata

```
var playerElement = $('#hlsjs');
playerElement.show();
var player = new Hls();
console.log('Created HLS.js Player');

player.loadSource(response.HLSStreamingSessionURL);
player.attachMedia(playerElement[0]);
console.log('Set player source');

player.on(Hls.Events.MANIFEST_PARSED, function() {
    video.play();
    console.log('Starting playback');
});
```

Troubleshooting

If the video stream does not play back correctly, see Troubleshooting HLS Issues (p. 153).

Completed Example

You can download or view the completed example code.

Using Streaming Metadata with Kinesis Video Streams

You can use the Amazon Kinesis Video Streams Producer SDK to embed metadata at the individual fragment level in a Kinesis video stream. Metadata in Kinesis Video Streams is a mutable key-value pair. You can use it to describe the content of the fragment, embed associated sensor readings that need to be transferred along with the actual fragment, or meet other custom needs. The metadata is made available as part of the the section called "GetMedia" (p. 196) or the section called "GetMediaForFragmentList" (p. 213) API operations. It is stored along with the fragments for the entire duration of the stream's retention period. Your consuming applications can read, process, and take action based on the metadata using the Kinesis Video Stream Parser Library (p. 107).

There are two modes in which the metadata can be embedded with fragments in a stream:

- Nonpersistent: You can affix metadata on an ad hoc basis to fragments in a stream, based on business-specific criteria that have occurred. An example is a smart camera that detects motion and adds metadata to the corresponding fragments that contain the motion before sending the fragments to its Kinesis video stream. You might apply metadata to the fragment in the following format:

 Motion = true.
- Persistent: You can affix metadata to successive, consecutive fragments in a stream based on
 a continuing need. An example is a smart camera that sends the current latitude and longitude
 coordinates associated with all fragments that it sends to its Kinesis video stream. You might
 apply metadata to all the fragments in the following format: Lat = 47.608013N , Long =
 -122.335167W

You can affix metadata in both of these modes to the same fragment simultaneously, based on your application's needs. The embedded metadata might include objects detected, activity tracked, GPS coordinates, or any other custom data that you want to associate with the fragments in the stream. Metadata is encoded as key-value string pairs.

Topics

- Adding Metadata to a Kinesis Video Stream (p. 13)
- Consuming Metadata Embedded in a Kinesis Video Stream (p. 14)
- Streaming Metadata Limitations (p. 15)

Adding Metadata to a Kinesis Video Stream

Metadata that you add to a Kinesis video stream is modeled as MKV tags, which are implemented as key-value pairs.

Metadata can either be *transient*, such as to mark an event within the stream, or *persistent*, such as to identify fragments where a given event is taking place. A persistent metadata item remains, and is applied to each consecutive fragment, until it is canceled.

Note

The metadata items added using the Producer Libraries (p. 34) are distinct from the stream-level tagging APIs implemented with the section called "TagStream" (p. 185), the section called "UntagStream" (p. 188), and the section called "ListTagsForStream" (p. 182).

Streaming Metadata API

You can use the following operations in the Producer SDK to implement streaming metadata.

PIC

```
PUBLIC_API STATUS putKinesisVideoFragmentMetadata(STREAM_HANDLE streamHandle,
PCHAR name,
PCHAR value,
BOOL persistent);
```

C++ Producer SDK

```
/**
  * Appends a "tag" or metadata - a key/value string pair into the stream.
  */
bool putFragmentMetadata(const std::string& name, const std::string& value, bool persistent
  = true);
```

Java Producer SDK

Using the Java Producer SDK, you add metadata to a MediaSource using MediaSourceSink.onCodecPrivateData:

```
void onFragmentMetadata(final @Nonnull String metadataName, final @Nonnull String
  metadataValue, final boolean persistent)
throws KinesisVideoException;
```

Persistent and Nonpersistent Metadata

For nonpersistent metadata, you can add multiple metadata items with the same *name*. The Producer SDK collects the metadata items in the metadata queue until they are prepended to the next fragment. The metadata queue is cleared as the metadata items are applied to the stream. To repeat the metadata, call putKinesisVideoFragmentMetadata or putFragmentMetadata again.

For persistent metadata, the Producer SDK collects the metadata items in the metadata queue in the same way as for nonpersistent metadata. However, the metadata items are not removed from the queue when they are prepended to the next fragment.

Calling putKinesisVideoFragmentMetadata or putFragmentMetadata with persistent set to true has the following behavior:

- Calling the API puts the metadata item in the queue. The metadata is added as an MKV tag to every fragment while the item is in the queue.
- Calling the API with the same *name* and a different *value* as a previously added metadata item overwrites the item.
- Calling the API with an empty value removes (cancels) the metadata item from the metadata queue.

Consuming Metadata Embedded in a Kinesis Video Stream

To consume the metadata in a Kinesis video stream, use an implementation of MkvTagProcessor:

This interface is found in the FragmentMetadataVisitor (p. 109) class in the Kinesis Video Stream Parser Library (p. 107).

The FragmentMetadataVisitor class contains an implementation of MkvTagProcessor:

```
public static final class BasicMkvTagProcessor implements
FragmentMetadataVisitor.MkvTagProcessor {
    @Getter
    private List<MkvTag> tags = new ArrayList<>();

    @Override
    public void process(MkvTag mkvTag, Optional<FragmentMetadata> currentFragmentMetadata)
{
      tags.add(mkvTag);
    }

    @Override
    public void clear() {
      tags.clear();
    }
}
```

The KinesisVideoRendererExample class contains an example of how to use a BasicMkvTagProcessor. In the following example, a BasicMkvTagProcessor is added to the MediaProcessingArguments of an application:

```
if (renderFragmentMetadata) {
    getMediaProcessingArguments =
KinesisVideoRendererExample.GetMediaProcessingArguments.create(
          Optional.of(new FragmentMetadataVisitor.BasicMkvTagProcessor()));
```

The BasicMkvTagProcessor.process method is called when fragment metadata arrives. You can retrieve the accumulated metadata with GetTags. If you want to retrieve a single metadata item, first call clear to clear the collected metadata, and then retrieve the metadata items again.

Streaming Metadata Limitations

The following limitations apply to adding streaming metadata to a Kinesis video stream:

- You can prepend up to 10 metadata items to a fragment.
- A fragment metadata name can be up to 128 bytes in length.
- A fragment metadata value can be up to 256 bytes in length.
- A fragment metadata name cannot begin with the string "AWS". If such a metadata item is added, the putFragmentMetadata method in the PIC returns a STATUS_INVALID_METADATA_NAME error (error code 0x52000077). Your application can then either ignore the error (the PIC doesn't add the metadata item), or respond to the error.

Controlling Access to Kinesis Video Streams Resources Using IAM

By using AWS Identity and Access Management (IAM) with Amazon Kinesis Video Streams, you can control whether users in your organization can perform a task using specific Kinesis Video Streams API operations and whether they can use specific AWS resources.

For more information about IAM, see the following:

- AWS Identity and Access Management (IAM)
- · Getting Started
- IAM User Guide

Contents

- Policy Syntax (p. 15)
- Actions for Kinesis Video Streams (p. 16)
- Amazon Resource Names (ARNs) for Kinesis Video Streams (p. 16)
- Granting Other IAM Accounts Access to a Kinesis Video Stream (p. 17)
- Example Policies for Kinesis Video Streams (p. 17)

Policy Syntax

An IAM policy is a JSON document that consists of one or more statements. Each statement is structured as follows:

Amazon Kinesis Video Streams Developer Guide Actions for Kinesis Video Streams

There are various elements that make up a statement:

- Effect: The effect can be Allow or Deny. By default, IAM users don't have permission to use resources and API actions, so all requests are denied. An explicit allow overrides the default. An explicit deny overrides any allows.
- Action: The action is the specific API action for which you are granting or denying permission.
- **Resource**: The resource that's affected by the action. To specify a resource in the statement, you need to use its Amazon Resource Name (ARN).
- Condition: Conditions are optional. They can be used to control when your policy is in effect.

As you create and manage IAM policies, you might want to use the IAM Policy Generator and the IAM Policy Simulator.

Actions for Kinesis Video Streams

In an IAM policy statement, you can specify any API action from any service that supports IAM. For Kinesis Video Streams, use the following prefix with the name of the API action: kinesisvideo: For example: kinesisvideo: CreateStream, kinesisvideo: ListStreams, and kinesisvideo: DescribeStream.

To specify multiple actions in a single statement, separate them with commas as follows:

```
"Action": ["kinesisvideo:action1", "kinesisvideo:action2"]
```

You can also specify multiple actions using wildcards. For example, you can specify all actions whose name begins with the word "Get" as follows:

```
"Action": "kinesisvideo:Get*"
```

To specify all Kinesis Video Streams operations, use the asterisk (*) wildcard as follows:

```
"Action": "kinesisvideo:*"
```

For the complete list of Kinesis Video Streams API actions, see the Kinesis Video Streams API reference.

Amazon Resource Names (ARNs) for Kinesis Video Streams

Each IAM policy statement applies to the resources that you specify using their ARNs.

Use the following ARN resource format for Kinesis Video Streams:

```
arn:aws:kinesisvideo:region:account-id:stream/stream-name/code
```

For example:

```
"Resource": arn:aws:kinesisvideo::*:111122223333:stream/my-stream/0123456789012
```

You can get the ARN of a stream using DescribeStream.

Granting Other IAM Accounts Access to a Kinesis Video Stream

You might need to grant permission to other IAM accounts to perform operations on Kinesis video streams. The following overview describes the general steps to grant access to video streams across accounts:

- 1. Get the 12-digit account ID of the account that you want to grant permissions to perform operations on your stream (for example, 111111111111).
- 2. Create a managed policy on the account that owns the stream that allows the level of access that you want to grant. For example policies for Kinesis Video Streams resources, see Example Policies (p. 17) in the next section.
- 3. Create a role, specifying the account to which you are granting permissions, and attach the policy that you created in the previous step.
- 4. Create a managed policy that allows the AssumeRole action on the role you created in the previous step. For example, the role might look like the following:

```
{
  "Version": "2012-10-17",
  "Statement": {
    "Effect": "Allow",
    "Action": "sts:AssumeRole",
    "Resource": "arn:aws:iam::123456789012:role/CustomRole"
  }
}
```

For step-by-step instructions on granting cross-account access, see Delegate Access Across AWS Accounts Using IAM Roles.

Example Policies for Kinesis Video Streams

The following example policies demonstrate how you can control user access to your Kinesis video streams.

Example 1: Allow users to get data from any Kinesis video stream

This policy allows a user or group to perform the DescribeStream, GetDataEndpoint, GetMedia, ListStreams, and ListTagsForStream operations on any Kinesis video stream. This policy is appropriate for users who can get data from any video stream.

Example 2: Allow a user to create a Kinesis video stream and write data to it

This policy allows a user or group to perform the CreateStream and PutMedia operations. This policy is appropriate for a security camera that can create a video stream and send data to it.

Example 3: Allow a user full access to all Kinesis Video Streams resources

This policy allows a user or group to perform any Kinesis Video Streams operation on any resource. This policy is appropriate for administrators.

Example 4: Allow a user to write data to a specific Kinesis video stream

This policy allows a user or group to write data to a specific video stream. This policy is appropriate for a device that can send data to a single stream.

Using Server-Side Encryption with Kinesis Video Streams

Server-side encryption using AWS Key Management Service (AWS KMS) keys makes it easier for you to meet strict data management requirements by encrypting your data at rest in Amazon Kinesis Video Streams.

Topics

- What Is Server-Side Encryption for Kinesis Video Streams? (p. 19)
- Costs, Regions, and Performance Considerations (p. 19)
- How Do I Get Started with Server-Side Encryption? (p. 20)
- Creating and Using User-Generated AWS KMS Master Keys (p. 20)
- Permissions to Use User-Generated AWS KMS Master Keys (p. 20)

What Is Server-Side Encryption for Kinesis Video Streams?

Server-side encryption is a feature in Kinesis Video Streams that automatically encrypts data before it's at rest by using an AWS KMS customer master key (CMK) that you specify. Data is encrypted before it is written to the Kinesis Video Streams stream storage layer, and it is decrypted after it is retrieved from storage. As a result, your data is always encrypted at rest within the Kinesis Video Streams service.

With server-side encryption, your Kinesis video stream producers and consumers don't need to manage master keys or cryptographic operations. If data retention is enabled, your data is automatically encrypted as it enters and leaves Kinesis Video Streams, so your data at rest is encrypted. AWS KMS provides all the master keys that are used by the server-side encryption feature. AWS KMS makes it easier to use a CMK for Kinesis Video Streams that is managed by AWS, a user-specified AWS KMS CMK, or a master key imported into the AWS KMS service.

Costs, Regions, and Performance Considerations

When you apply server-side encryption, you are subject to AWS KMS API usage and key costs. Unlike custom AWS KMS master keys, the (Default) aws/kinesis-video customer master key (CMK) is offered free of charge. However, you still must pay for the API usage costs that Kinesis Video Streams incurs on your behalf.

API usage costs apply for every CMK, including custom ones. The KMS costs scale with the number of user credentials that you use on your data producers and consumers because each user credential requires a unique API call to AWS KMS.

The following describes the costs by resource:

Keys

- The CMK for Kinesis Video Streams that's managed by AWS (alias = aws/kinesis-video) is free.
- User-generated AWS KMS keys are subject to AWS KMS key costs. For more information, see AWS Key Management Service Pricing.

AWS KMS API Usage

API requests to generate new data encryption keys or to retrieve existing encryption keys increase as traffic increases, and are subject to AWS KMS usage costs. For more information, see AWS Key Management Service Pricing: Usage.

Kinesis Video Streams generates key requests even when retention is set to 0 (no retention).

Availability of Server-Side Encryption by Region

Server-side encryption of Kinesis video streams is available in all the AWS Regions where Kinesis Video Streams is available.

How Do I Get Started with Server-Side Encryption?

Server-side encryption is always enabled on Kinesis video streams. If a user-provided key is not specified when the stream is created, the default key (provided by Kinesis Video Streams) is used.

A user-provided AWS KMS master key must be assigned to a Kinesis video stream when it is created. You can't later assign a different key to a stream using the UpdateStream API.

You can assign a user-provided AWS KMS master key to a Kinesis video stream in two ways:

- When creating a Kinesis video stream in the AWS Management Console, specify the AWS KMS master key in the Encryption section on the Create new Kinesis Video stream page.
- When creating a Kinesis video stream using the CreateStream API, specify the key ID in the KmsKeyId parameter.

Creating and Using User-Generated AWS KMS Master Keys

This section describes how to create and use your own AWS KMS master keys instead of using the master key administered by Amazon Kinesis Video Streams.

Creating User-Generated AWS KMS Master Keys

For information about how to create your own master keys, see <u>Creating Keys</u> in the <u>AWS Key Management Service Developer Guide</u>. After you create keys for your account, the Kinesis Video Streams service returns these keys in the <u>KMS master key</u> list.

Using User-Generated AWS KMS Master Keys

After the correct permissions are applied to your consumers, producers, and administrators, you can use custom AWS KMS master keys in your own AWS account or another AWS account. All AWS KMS master keys in your account appear in the **KMS Master Key** list on the console.

To use custom AWS KMS master keys that are located in another account, you must have permissions to use those keys. You must also create the stream using the CreateStream API. You can't use AWS KMS master keys from different accounts in streams created in the console.

Note

The AWS KMS key is not accessed until the PutMedia or GetMedia operation is executed. This has the following results:

- If the key you specify doesn't exist, the CreateStream operation succeeds, but PutMedia and GetMedia operations on the stream fail.
- If you use the provided master key (aws/kinesis-video), the key is not present in your account until the first PutMedia or GetMedia operation is performed.

Permissions to Use User-Generated AWS KMS Master Keys

Before you can use server-side encryption with a user-generated AWS KMS master key, you must configure AWS KMS key policies to allow encryption of streams and encryption and decryption of stream

records. For examples and more information about AWS KMS permissions, see AWS KMS API Permissions: Actions and Resources Reference.

Note

The use of the default service key for encryption does not require application of custom IAM permissions.

Before you use user-generated AWS KMS master keys, ensure that your Kinesis video stream producers and consumers (IAM principals) are users in the AWS KMS master key policy. Otherwise, writes and reads from a stream will fail, which could ultimately result in data loss, delayed processing, or hung applications. You can manage permissions for AWS KMS keys using IAM policies. For more information, see Using IAM Policies with AWS KMS.

Example Producer Permissions

Your Kinesis video stream producers must have the kms: GenerateDataKey permission:

Example Consumer Permissions

Your Kinesis video stream consumers must have the kms: Decrypt permission:

```
"Version": "2012-10-17",
  "Statement": [
   {
        "Effect": "Allow",
        "Action": [
            "kms:Decrypt"
        "Resource": "arn:aws:kms:us-
west-2:123456789012:key/1234abcd-12ab-34cd-56ef-1234567890ab"
   },
    {
        "Effect": "Allow",
        "Action": [
            "kinesis-video:GetMedia",
        "Resource": "arn:aws:kinesis-video:*:123456789012:MyStream"
  ]
}
```

Kinesis Video Streams Data Model

The Producer Libraries (p. 34) and Stream Parser Library (p. 107) send and receive video data in a format that supports embedding information alongside video data. This format is based on the Matroska (MKV) specification.

The MKV format is an open specification for media data. All the libraries and code examples in the *Amazon Kinesis Video Streams Developer Guide* send or receive data in the MKV format.

The Kinesis Video Streams Producer Libraries (p. 34) use the StreamDefinition and Frame types to produce MKV stream headers, frame headers, and frame data.

For information about the full MKV specification, see Matroska Specifications.

The following sections describe the components of MKV-formatted data produced by the C++ Producer Library (p. 44).

Topics

- Stream Header Elements (p. 22)
- Stream Track Data (p. 25)
- Frame Header Elements (p. 26)
- MKV Frame Data (p. 26)

Stream Header Elements

The following MKV header elements are used by StreamDefinition (defined in StreamDefinition.h).

Element	Description	Typical Values
stream_name	Corresponds to the name of the Kinesis video stream.	my-stream
retention_period	The duration that stream data is persisted by Kinesis Video Streams. Specify 0 for a stream that does not retain data.	24
tags	A key-value collection of user data. This data is displayed in the AWS Management Console and can be read by client applications to filter or get information about a stream.	
kms_key_id	If present, the user-defined AWS KMS master key that is used to encrypt data on the stream. If it is absent, the data is encrypted by the Kinesis-supplied master key (aws/kinesis-video).	01234567-89ab- cdef-0123-456789ab
streaming_type	Currently, the only valid streaming type is STREAMING_TYPE_REALTIME.	STREAMING_TYPE_REALTIME

Amazon Kinesis Video Streams Developer Guide Stream Header Elements

Element	Description	Typical Values
content_type	The user-defined content type. For streaming video data to play in the console, the content type must be video/h264.	video/h264
max_latency	This value is not currently used and should be set to 0.	0
fragment_duration	The estimate of how long your fragments should be, which is used for optimization. The actual fragment duration is determined by the streaming data.	2
timecode_scale	Indicates the scale used by frame time stamps. The default is 1 millisecond. Specifying 0 also assigns the default value of 1 millisecond. This value can be between 100 nanoseconds and 1 second. For more information, see TimecodeScale in the Matroska documentation.	
key_frame_fragmentation	If true, the stream starts a new cluster when a keyframe is received.	true
frame_timecodes	If true, Kinesis Video Streams stamps the frames when they are received. If false, Kinesis Video Streams uses the decode time of the received frames.	true
absolute_fragment_time	If true, the cluster timecodes are interpreted as using absolute time (for example, from the producer's system clock). If false, the cluster timecodes are interpreted as being relative to the start time of the stream.	true
fragment_acks	If true, acknowledgements (ACKs) are sent when Kinesis Video Streams receives the data. The ACKs can be received using the KinesisVideoStreamFragment or KinesisVideoStreamParseFracallbacks.	

Amazon Kinesis Video Streams Developer Guide Stream Header Elements

Element	Description	Typical Values
restart_on_error	Indicates whether the stream should resume transmission after a stream error is raised.	true
nal_adaptation_flags	Indicates whether NAL (Network Abstraction Layer) adaptation or codec private data is present in the content. Valid flags include NAL_ADAPTATION_ANNEXB_NALS and NAL_ADAPTATION_ANNEXB_CPD_	
frame_rate	An estimate of the content frame rate. This value is used for optimization; the actual frame rate is determined by the rate of incoming data. Specifying 0 assigns the default of 24.	24
avg_bandwidth_bps	An estimate of the content bandwidth. This value is used for optimization; the actual rate is determined by the bandwidth of incoming data. For example, for a 720 p resolution video stream running at 25 FPS, you can expect the average bandwidth to be 5 Mbps.	5
buffer_duration	The duration that content is to be buffered on the producer. If there is low network latency, this value can be reduced; if network latency is high, increasing this value prevents frames from being dropped before they can be sent, due to allocation failing to put frames into the smaller buffer.	
replay_duration	The amount of time the video data stream is "rewound" in the case of connection loss. This value can be zero if lost frames due to connection loss are not a concern; the value can be increased if the consuming application can eliminate redundant frames. This value should be less than the buffer duration; otherwise the buffer duration is used.	
connection_staleness	The duration that a connection is maintained when no data is received.	

Amazon Kinesis Video Streams Developer Guide Stream Track Data

Element	Description	Typical Values
codec_id	The codec used by the content. For more information, see CodecID in the Matroska specification.	V_MPEG2
track_name	The user-defined name of the track.	my_track
codecPrivateData	Data provided by the encoder used to decode the frame data, such as the frame width and height in pixels, which is needed by many downstream consumers. In the C++ Producer Library (p. 44), the gMkvTrackVideoBits array in MkvStatics.cpp includes pixel width and height for the frame.	
codecPrivateDataSize	The size of the data in the codecPrivateData parameter.	
track_type	The type of the track for the stream.	MKV_TRACK_INFO_TYPE_AUDIO or MKV_TRACK_INFO_TYPE_VIDEO
segment_uuid	User-defined segment uuid (16 bytes).	
default_track_id	Unique non-zero number for the track.	1

Stream Track Data

The following MKV track elements are used by StreamDefinition (defined in StreamDefinition.h).

Element	Description	Typical Values
track_name	User-defined track name. For example, "audio" for the audio track.	audio
codec_id	Codec id for the track. For example, "A_AAC" for an audio track.	A_AAC
cpd	Data provided by the encoder used to decode the frame data. This data can include frame width and height in pixels, which is needed by many downstream consumers. In the C++ Producer Library, the gMkvTrackVideoBits array in MkvStatics.cpp includes	

Amazon Kinesis Video Streams Developer Guide Frame Header Elements

Element	Description	Typical Values
	pixel width and height for the frame.	
cpd_size	The size of the data in the codecPrivateData parameter.	
track_type	The type of the track. For example, you can use the enum value of MKV_TRACK_INFO_TYPE_AUDIO for audio.	MKV_TRACK_INFO_TYPE_AUDIO

Frame Header Elements

The following MKV header elements are used by Frame (defined in the KinesisVideoPic package, in mkvgen/Include.h):

- Frame Index: A monotonically increasing value.
- Flags: The type of frame. Valid values include the following:
 - FRAME_FLAGS_NONE
 - FRAME_FLAG_KEY_FRAME: If key_frame_fragmentation is set on the stream, key frames start a new fragment.
 - FRAME_FLAG_DISCARDABLE_FRAME: Tells the decoder that it can discard this frame if decoding is slow.
 - FRAME_FLAG_INVISIBLE_FRAME: Duration of this block is 0.
- **Decoding Timestamp:** The time stamp of when this frame was decoded. If previous frames depend on this frame for decoding, this time stamp might be earlier than that of earlier frames. This value is relative to the start of the fragment.
- **Presentation Timestamp:** The time stamp of when this frame is displayed. This value is relative to the start of the fragment.
- Duration: The playback duration of the frame.
- Size: The size of the frame data in bytes

MKV Frame Data

The data in frame.frameData might contain only media data for the frame, or it might contain further nested header information, depending on the encoding schema used. To be displayed in the AWS Management Console, the data must be encoded in the H.264 codec, but Kinesis Video Streams can receive time-serialized data streams in any format.

Getting Started with Kinesis Video Streams

This section describes how to perform the following tasks in Amazon Kinesis Video Streams:

- Set up your AWS account and create an administrator, if you haven't already done so.
- · Create a Kinesis video stream.
- Send data to the Kinesis video stream from your camera and view the media in the console.

If you are new to Amazon Kinesis Video Streams, we recommend that you read Amazon Kinesis Video Streams: How It Works (p. 5) first.

Note

Following the Getting Started sample will not incur any charges to your AWS account. See Amazon Kinesis Video Streams Pricing for data costs in your region.

Topics

- Step 1: Set Up an AWS Account and Create an Administrator (p. 27)
- Step 2: Create a Kinesis Video Stream (p. 29)
- Step 3: Send Data to a Kinesis Video Stream (p. 31)
- What's Next? (p. 33)

Step 1: Set Up an AWS Account and Create an Administrator

Before you use Kinesis Video Streams for the first time, complete the following tasks:

- 1. Sign Up for AWS (p. 27) (unless you already have an account)
- 2. Create an Administrator IAM User (p. 28)
- 3. Create an AWS Account Key (p. 28)

Sign Up for AWS

If you already have an AWS account, you can skip this step.

When you sign up for Amazon Web Services (AWS), your AWS account is automatically signed up for all services in AWS, including Kinesis Video Streams. When you use Kinesis Video Streams, you are charged based on the amount of data ingested into, stored by, and consumed from the service. If you are a new AWS customer, you can get started with Kinesis Video Streams for free. For more information, see AWS Free Usage Tier.

To create an AWS account

1. Open https://aws.amazon.com/, and then choose Create an AWS Account.

Note

If you previously signed in to the AWS Management Console using AWS account root user credentials, choose **Sign in to a different account**. If you previously signed in to the console using IAM credentials, choose **Sign-in using root account credentials**. Then choose **Create a new AWS account**.

2. Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call and entering a verification code using the phone keypad.

Write down your AWS account ID because you need it for the next task.

Create an Administrator IAM User

When you sign up for AWS, you provide an email address and password that is associated with your AWS account. This is your AWS account root user. Its credentials provide complete access to all of your AWS resources.

Note

For security reasons, we recommend that you use the root user only to create an *administrator*, which is an *IAM user* with full permissions to your AWS account. You can then use this administrator to create other IAM users and roles with limited permissions. For more information, see IAM Best Practices and Creating an Admin User and Group in the *IAM User Guide*.

To create an administrator and sign into the console

- 1. Create an administrator in your AWS account. For instructions, see Creating Your First IAM User and Administrators Group in the *IAM User Guide*.
- 2. As an administrator, you can sign in to the console using a special URL. For more information, see How Users Sign in to Your Account in the *IAM User Guide*.

The administrator can create more users in the account. IAM users by default don't have any permissions. The administrator can create users and manage their permissions. For more information, see Creating Your First IAM User and Administrators Group.

For more information about IAM, see the following:

- AWS Identity and Access Management (IAM)
- Getting Started
- IAM User Guide

Create an AWS Account Key

You will need an AWS Account Key to access Kinesis Video Streams programmatically.

To create an AWS Account Key, do the following:

- 1. Sign in to the AWS Management Console and open the IAM console at https://console.aws.amazon.com/iam/.
- 2. Choose **Users** in the navigation bar, and choose the **Admininstrator** user.
- 3. Choose the Security credentials tab, and choose Create access key.
- 4. Record the Access key ID. Choose Show under Secret access key. Record the Secret access key.

Next Step

Step 2: Create a Kinesis Video Stream (p. 29)

Step 2: Create a Kinesis Video Stream

This section describes how to create a Kinesis video stream.

This section contains the following procedures:

- the section called "Create a Video Stream Using the Console" (p. 29)
- the section called "Create a Video Stream Using the AWS CLI" (p. 31)

Create a Video Stream Using the Console

- Sign in to the AWS Management Console and open the Kinesis console at https:// console.aws.amazon.com/kinesis.
- 2. On the **Manage streams** page, choose **Create**.
- 3. On the **Create new KinesisVideo Stream** page, type **ExampleStream** for the stream name. Leave the **Use default settings** check box selected.

Amazon Kinesis

Kinesis Data Streams

Kinesis Data Firehose

Kinesis Data Analytics

Kinesis Video Streams

Streams

Producer SDK

Kinesis video streams > Streams > Create stream

Create new Kinesis video stream

The primary resource of the Kinesis Video Streams service is a video stream. The diagra a Kinesis video stream and its producers and consumers.



Kinesis producers

Producers generate data like video, and send them into Kinesis video streams.

Kinesis video streams

Kinesis Video Streams capture, store, and index the data fragments in a video stream for real-time and batch oriented use cases

Kinesis consumer

Consumers are applications that analyor process fragments Kinesis video streams machine learning, video analytics and other workflows.

Stream configuration

Once this stream is created, you can use the Kinesis Video Streams APIs to put data into stream. Default settings provide the fastest way to get started.

Stream name*

Max length: 128 characters. May include: numbers letters

Use default settings

- Media type is video/h264. H.264 video data pui back in the Kinesis Video Streams management modified later.
- . Data will be archived for 24 hours. Data retention
- . No tags will be added. Tags can be added later.
- Data will be encrypted at rest using the default K settings if you intend to use your own KMS cannot be changed later.

*Required

- 4. Choose Create stream.
- 5. After Kinesis Video Streams creates the stream, review the details on the ExampleStream page.

Create a Video Stream Using the AWS CLI

- Ensure that you have the AWS CLI installed and configured. For more information, see the AWS Command Line Interface documentation.
- 2. Run the following Create-Stream command in the AWS CLI:

```
$ aws kinesisvideo create-stream --stream-name "MyKVStream" --data-retention-in-hours
"24"
```

The response will look similar to the following:

```
{
    "StreamARN": "arn:aws:kinesisvideo:us-west-2:123456789012:stream/
MyKVSStream/123456789012"
}
```

Next Step

Step 3: Send Data to a Kinesis Video Stream (p. 31)

Step 3: Send Data to a Kinesis Video Stream

This section describes how to send media data from a camera to the Kinesis video stream you created in the previous step. This section uses the C++ Producer Library (p. 44) as a GStreamer (p. 115) plugin.

To easily send media from a variety of devices on a variety of operating systems, this tutorial uses GStreamer, an open-source media framework that standardizes access to cameras and other media sources.

The GStreamer example application is supported on the following operating systems:

- Ubuntu
- macOS
- · Microsoft Windows
- Raspbian (Raspberry Pi)

For more information about using the GStreamer plugin to stream video from a file or an RTSP stream from a camera, see Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 115).

Download the C++ Producer SDK

The GStreamer sample is included in the C++ Producer SDK. You can download the C++ Producer SDK from Github using the following Git command:

```
$ git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp
```

For information about SDK prerequisites and downloading, see Step 1: Download and Configure the C++ Producer Library Code (p. 47).

Compile the GStreamer Example

You can compile and install the GStreamer sample in the kinesis-video-native-build directory using the following command:

```
./gstreamer-plugin-install-script
```

Run the GStreamer Example

The GStreamer application sends media from your camera to the Kinesis Video Streams service. You can run the GStreamer example application for your operating system with the following commands. Run the example application from the kinesis-video-native-build/downloads/local/bin directory. Use the following parameters for the command:

- Access key: The AWS access key you recorded in the first step of this tutorial.
- Secret key: The AWS secret key you recorded in the first step of this tutorial.
- AWS Region: A region that supports Kinesis Video Streams. For information on supported regions, see Amazon Kinesis Video Streams Regions.

Run the GStreamer Example on Ubuntu

You can run the GStreamer example application on Ubuntu with the following command. Specify your camera device with the device parameter.

```
$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! h264parse ! video/x-
h264,stream-format=avc,alignment=au ! kvssink stream-name="MyKinesisVideoStream" storage-
size=512 access-key="YourAccessKey" secret-key="YourSecretKey" aws-region="YourAWSRegion"
```

Run the GStreamer Example on macOS

You can run the GStreamer example application on MacOS with the following command:

```
$ gst-launch-1.0 autovideosrc ! videoconvert ! video/x-
raw,format=I420,width=640,height=480,framerate=30/1 ! vtenc_h264_hw allow-frame-
reordering=FALSE realtime=TRUE max-keyframe-interval=45 bitrate=500 ! h264parse ! video/x-
h264,stream-format=avc,alignment=au,width=640,height=480,framerate=30/1 ! kvssink stream-
name=MyKinesisVideoStream storage-size=512
```

Run the GStreamer Example on Windows

You can run the GStreamer example application on Windows with the following command:

```
gst-launch-1.0 ksvideosrc do-timestamp=TRUE ! video/x-
raw,width=640,height=480,framerate=30/1 ! videoconvert ! x264enc bframes=0
key-int-max=45 bitrate=512 ! video/x-h264,profile=baseline,stream-
format=avc,alignment=au,width=640,height=480,framerate=30/1 ! kvssink stream-
name="MyKinesisVideoStream" access-key=your_accesskey_id secret-key=your_secret_access_key
```

Run the GStreamer Example on Raspbian (Raspberry Pi)

You can run the GStreamer example application on Raspbian with the following command. Specify your camera device with the device parameter.

Amazon Kinesis Video Streams Developer Guide Consume Media Data

\$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! videoconvert ! video/x-raw,format=I420,width=640,height=480,framerate=30/1 ! omxh264enc control-rate=1 target-bitrate=5120000 periodicity-idr=45 inline-header=FALSE ! h264parse ! video/x-h264,stream-format=avc,alignment=au,width=640,height=480,framerate=30/1,profile=baseline ! kvssink stream-name="MyKinesisVideoStream" frame-timestamp=dts-only access-key="YourAccessKey" secret-key="YourSecretKey" aws-region="YourAWSRegion"

Consume Media Data

You can consume media data by either viewing it in the console, or by creating an application that reads media data from a stream using HLS.

View Media Data in the Console

To view the media data sent from your camera in the Kinesis Video Streams console, open the Kinesis Video Streams console at https://console.aws.amazon.com/kinesisvideo/, and choose the MyKinesisVideoStream stream on the Manage Streams page. The video plays in the Video Preview pane.

Consume Media Data using HLS

You can create a client application that consumes data from a Kinesis video stream using Hypertext Live Streaming (HLS). For information about creating an application that consumes media data using HLS, see the section called "Video Playback Using HLS" (p. 9).

Next Step

What's Next? (p. 33)

What's Next?

See the following topics for further information about Kinesis Video Streams:

- Producer Libraries (p. 34): Describes the classes and methods used to send media data to the Kinesis Video Streams service.
- Stream Parser Library (p. 107): Describes how to create an application that reads and displays media data from a Kinesis video stream.
- RTSP and Docker (p. 127): Describes how to stream video to the Kinesis Video Streams service from a network (RTSP) camera.

Kinesis Video Streams Producer Libraries

The Amazon Kinesis Video Streams Producer libraries are a set of easy-to-use libraries that are part of the Kinesis Video Streams Producer SDK. The client uses the libraries and SDK to build the on-device application for securely connecting to Kinesis Video Streams and streaming video and other media data that can be viewed in the console or client applications in real time.

Media data can be streamed in the following ways:

- · Streaming media data in real time
- Streaming media data after buffering it for a few seconds
- · Streaming after-the-fact media uploads

After you create a Kinesis Video Streams stream, you can start sending data to the stream. You can use the SDK to create application code that extracts the video data (frames) from the media source and uploads it to Kinesis Video Streams. These applications are also referred to as *producer* applications.

The Producer libraries contain the following components:

- Kinesis Video Streams Producer Client (p. 34)
- Kinesis Video Streams Producer Library (p. 35)

Kinesis Video Streams Producer Client

The Kinesis Video Streams Producer Client includes a single KinesisVideoClient class. This class manages media sources, receives data from the sources, and manages the stream lifecycle as data flows from a media source to Kinesis Video Streams. Furthermore, it provides a MediaSource interface for defining the interaction between Kinesis Video Streams and your proprietary hardware and software.

A media source can be almost anything. For example, you can use a camera media source or a microphone media source. Media sources are not limited to audio and video sources only. For example, data logs might be text files, but they can still be sent as a stream of data. You could also have multiple cameras on your phone that stream data simultaneously.

To get data from any of these sources, you can implement the MediaSource interface. This interface enables additional scenarios for which we don't provide built-in support. For example, you might choose to send the following to Kinesis Video Streams:

- A diagnostic data stream (for example, application logs and events)
- Data from infrared cameras, RADARs, or depth cameras

Kinesis Video Streams does not provide built-in implementations for media-producing devices such as cameras. To extract data from these devices, you must implement code, thus creating your own custom media source implementation. You can then explicitly register your custom media sources with KinesisVideoClient, which uploads the data to Kinesis Video Streams.

The Kinesis Video Streams Producer Client is available for Java and Android applications. For more information, see Using the Java Producer Library (p. 35) and Using the Android Producer Library (p. 39).

Kinesis Video Streams Producer Library

The Kinesis Video Streams Producer Library is contained within the Kinesis Video Streams Producer Client. The library is also available to use directly for those who want a deeper integration with Kinesis Video Streams. It enables integration from devices with proprietary operating systems, network stacks, or limited on-device resources.

The Kinesis Video Streams Producer Library implements the state machine for streaming to Kinesis Video Streams. It provides callback hooks, which require that you provide your own transport implementation and explicitly handle each message going to and from the service.

You might choose to use the Kinesis Video Streams Producer Library directly for the following reasons:

- The device on which you want to run the application doesn't have a Java virtual machine.
- You want to write application code in languages other than Java.
- You might have Java on the device, but you want to reduce the amount of overhead in your code and limit it to the bare minimum level of abstraction, due to limitations such as memory and processing power.

Currently, the Kinesis Video Streams Producer Library is available for C++ applications. For more information, see Using the C++ Producer Library (p. 44).

Related Topics

Using the Java Producer Library (p. 35)

Using the Android Producer Library (p. 39)

Using the C++ Producer Library (p. 44)

Using the Java Producer Library

Amazon Kinesis Video Streams provides the Java Producer Library, which you can use to write application code, with minimal configuration, to send media data from a device to a Kinesis video stream.

You must perform the following steps to integrate your code with Kinesis Video Streams, so that your application can start streaming data to your Kinesis video stream:

- 1. Create an instance of the KinesisVideoClient object.
- Create a MediaSource object by providing media source information. For example, when creating a camera media source, you provide information such as identifying the camera and specifying the encoding the camera uses.

When you want to start streaming, you must create a custom media source.

3. Register the media source with KinesisVideoClient.

After you register the media source with KinesisVideoClient, whenever the data becomes available with the media source, it calls KinesisVideoClient with the data.

Procedure: Using the Java Producer SDK

This procedure demonstrates how to use the Kinesis Video Streams Java Producer Client in your Java application to send data to your Kinesis video stream.

These steps don't require you to have a media source, such as a camera or microphone. Instead, for testing purposes, the code generates sample frames that consist of a series of bytes. You can use the same coding pattern when you send media data from real sources such as cameras and microphones.

The procedure includes the following steps:

- · Download and Configure the Code
- · Write and Examine the Code
- · Run and Verify the Code

Prerequisites

• In the sample code, you provide credentials by specifying a profile that you set up in your AWS credentials profile file. If you haven't already done so, first set up your credentials profile. For more information, see Set up AWS Credentials and Region for Development in the AWS SDK for Java.

Note

The Java example uses a SystemPropertiesCredentialsProvider object to obtain your AWS credentials. The provider retrieves these credentials from the aws.accessKeyId and aws.secretKey Java system properties. You set these system properties in your Java development environment. For information about how to set Java system properties, see the documentation for your particular integrated development environment (IDE).

- Your NativeLibraryPath must contain your KinesisVideoProducerJNI file, available at https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp. The file name extension for this file depends on your operating system:
 - KinesisVideoProducerJNI.so for Linux
 - KinesisVideoProducerJNI.dylib for macOS
 - KinesisVideoProducerJNI.dll for Windows

Note

Pre-built libraries for macOS, Ubuntu, Windows, and Raspbian are available in src/main/resources/lib at https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-java. For other environments, compile the C++ Producer Library (p. 44).

Step 1: Download and Configure the Java Producer Library Code

In this section of the Java Producer Library procedure, you download the Java example code, import the project into your Java IDE, and configure the library locations.

For prerequisites and other details about this example, see Using the Java Producer Library.

1. Create a directory, and then clone the example source code from the GitHub repository.

```
$ git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-java
```

- Open the Java integrated development environment (IDE) that you use (for example, Eclipse or JetBrains IntelliJ IDEA), and import the Apache Maven project that you downloaded:
 - In Intellij IDEA: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.
 - In Eclipse: Choose File, Import, Maven, Existing Maven Projects. Then navigate to the kinesis-video-java-demo directory.

For more information, see the documentation for your IDE.

3. The Java example code uses the current AWS credentials. To use a different credentials profile, locate the following code in DemoAppMain.java:

```
final KinesisVideoClient kinesisVideoClient = KinesisVideoJavaClientFactory
    .createKinesisVideoClient(
    Regions.US_WEST_2,
    AuthHelper.getSystemPropertiesCredentialsProvider());
```

Change the code to the following:

```
final KinesisVideoClient kinesisVideoClient = KinesisVideoJavaClientFactory
   .createKinesisVideoClient(
    Regions.US_WEST_2,
    new ProfileCredentialsProvider("credentials-profile-name"););
```

For more information, see ProfileCredentialsProvider in the AWS SDK for Java reference.

Next Step

the section called "Step 2: Write and Examine the Code" (p. 37)

Step 2: Write and Examine the Code

In this section of the Java Producer Library procedure, you write and examine the Java example code you downloaded in the previous section.

The Java test application (DemoAppMain) shows the following coding pattern:

- Create an instance of KinesisVideoClient.
- Create an instance of MediaSource.
- Register the MediaSource with the client.
- Start streaming. That is, start the MediaSource, and it starts sending data to the client.

The following sections provide details.

Creating an Instance of KinesisVideoClient

You create the KinesisVideoClient object by calling the createKinesisVideoClient operation.

```
final KinesisVideoClient kinesisVideoClient = KinesisVideoJavaClientFactory
    .createKinesisVideoClient(
```

Amazon Kinesis Video Streams Developer Guide Step 3: Run and Verify the Code

```
Regions.US_WEST_2,
AuthHelper.getSystemPropertiesCredentialsProvider());
```

For KinesisVideoClient to make network calls, it needs credentials to authenticate. You pass in an instance of SystemPropertiesCredentialsProvider, which reads AWSCredentials for the default profile in the credentials file:

```
[default]
aws_access_key_id = ABCDEFGHIJKLMOPQRSTU
aws_secret_access_key = AbCd1234EfGh5678IjKl9012MnOp3456QrSt7890
```

Creating an Instance of MediaSource

To send bytes to your Kinesis video stream, you need to produce the data. Amazon Kinesis Video Streams provides the MediaSource interface, which represents the data source.

For example, the Kinesis Video Streams Java library provides the ImageFileMediaSource implementation of the MediaSource interface. This class only reads data from a series of media files rather than a Kinesis video stream, but you can use it for testing the code.

```
final MediaSource bytesMediaSource = createImageFileMediaSource();
```

Registering the MediaSource with the Client

Register the media source that you created with the KinesisVideoClient so that it knows about the client (and can then send data to the client).

```
kinesisVideoClient.registerMediaSource(STREAM_NAME, bytesMediaSource);
```

Starting the Media Source

Start the media source so that it can begin generating data and sending it to the client.

```
bytesMediaSource.start();
```

Next Step

the section called "Step 3: Run and Verify the Code" (p. 38)

Step 3: Run and Verify the Code

To run the Java test harness for the Java Producer library, do the following.

- 1. Choose **DemoAppMain**.
- 2. Choose Run, Run 'DemoAppMain'.
- 3. Add your credentials to the JVM arguments for the application:
 - For non-temporary AWS credentials: "-Daws.accessKeyId={YourAwsAccessKey} Daws.secretKey={YourAwsSecretKey} -Djava.library.path={NativeLibraryPath}"
 - For temporary AWS credentials: "-Daws.accessKeyId={YourAwsAccessKey} Daws.secretKey={YourAwsSecretKey} -Daws.sessionToken={YourAwsSessionToken}
 -Djava.library.path={NativeLibraryPath}"
- 4. Sign in to the AWS Management Console and open the Kinesis Video Streams console.

On the Manage Streams page, choose your stream.

The sample video will play in the embedded player. You might need to wait a short time (up to ten seconds under typical bandwidth and processor conditions) while the frames accumulate before the video appears.

The code example creates a stream. As the MediaSource in the code starts, it begins sending sample frames to the KinesisVideoClient. The client then sends the data to your Kinesis video stream.

Using the Android Producer Library

Amazon Kinesis Video Streams provides the Android Producer Library, which you can use to write application code, with minimal configuration, to send media data from an Android device to a Kinesis video stream.

You must perform the following steps to integrate your code with Kinesis Video Streams so that your application can start streaming data to your Kinesis video stream:

- 1. Create an instance of the KinesisVideoClient object.
- 2. Create a MediaSource object by providing media source information. For example, when creating a camera media source, you provide information such as identifying the camera and specifying the encoding the camera uses.

When you want to start streaming, you must create a custom media source.

Procedure: Using the Android Producer SDK

This procedure demonstrates how to use the Kinesis Video Streams Android Producer Client in your Android application to send data to your Kinesis video stream.

The procedure includes the following steps:

- Download and Configure the Code
- Examine the Code
- Run and Verify the Code

Prerequisites

- We recommend Android Studio for examining, editing, and running the application code. We recommend at least version 3.0.0, released October 2017.
- In the sample code, you provide Amazon Cognito credentials. Follow these procedures to set up an Amazon Cognito user pool and identity pool:

To set up a user pool

- 1. Sign in to the Amazon Cognito console.
- 2. Choose Manage your User Pools.
- 3. Choose Create a user pool.
- 4. Type a value for Pool name; for example, <username>_android_user_pool.
- 5. Choose Review defaults.
- 6. Choose Create pool.

- 7. Copy and save the **Pool Id** value. You will need this value when you configure the example application.
- 8. On the page for your pool, choose **App clients**.
- 9. Choose Add an app client.
- 10. Type a value for App client name; for example, <username>_android_app_client.
- 11. Choose Create app client.
- 12. Choose **Show Details**, and copy and save the **App client ID** and **App client secret**. You will need these values when you configure the example application.

To set up an identity pool

- 1. Open the Amazon Cognito console.
- 2. Choose Manage Identity Pools.
- 3. Choose Create new identity pool.
- 4. Type a value for Identity pool name; for example, <username>_android_identity_pool.
- 5. Expand the **Authentication providers** section. On the **Cognito** tab, add the values for the **User Pool ID** and **App client ID** from the previous procedure.
- 6. Choose Create pool.
- 7. On the next page, expand the **Show Details** section.
- In the section that has a value for Role name that ends in Auth_Role, choose View Policy Document.
- 9. Choose **Edit**, and confirm the **Edit Policy** dialog box that appears. Then copy the following JSON and paste it into the editor:

```
{
    "Version": "2012-10-17",
    "Statement": [
    {
        "Effect": "Allow",
        "Action": [
            "cognito-identity:*",
            "kinesisvideo:*"
        ],
        "Resource": [
            "*"
        ]
    }
}
```

- 10. Choose Allow.
- 11. On the next page, copy and save the **Identity pool ID** value from the **Get AWS Credentials** code snippet. You will need this value when you configure the example application.

Step 1: Download and Configure the Android Producer Library Code

In this section of the Android Producer Library procedure, you download the Android example code and open the project in Android Studio.

For prerequisites and other details about this example, see Using the Android Producer Library.

1. Create a directory, and then clone the AWS Android SDK from the GitHub repository.

```
$ git clone https://github.com/awslabs/aws-sdk-android-samples
```

- 2. Open Android Studio.
- 3. In the opening screen, choose Open an existing Android Studio project.
- Navigate to the aws-sdk-android-samples/AmazonKinesisVideoDemoApp directory, and choose OK.
- 5. Open the AmazonKinesisVideoDemoApp/src/main/res/raw/awsconfiguration.json file.

In the CredentialsProvider node, provide the identity pool ID from the **To set up an identity pool** procedure in the Prerequisites section, and provide your AWS Region (for example, us-west-2).

In the CognitoUserPool node, provide the App client secret, App client ID, and Pool ID from the **To set up a user pool** procedure in the Prerequisites section, and provide your AWS Region (for example, us-west-2).

6. Your awsconfiguration. json file will look similar to the following:

```
"Version": "1.0",
"CredentialsProvider": {
  "CognitoIdentity": {
    "Default": {
      "PoolId": "us-west-2:01234567-89ab-cdef-0123-456789abcdef",
      "Region": "us-west-2"
    }
  }
},
"IdentityManager": {
  "Default": {}
"CognitoUserPool": {
  "Default": {
    "AppClientSecret": "abcdefghijklmnopqrstuvwxyz0123456789abcdefghijklmno",
    "AppClientId": "0123456789abcdefghijklmnop",
    "PoolId": "us-west-2_qRsTuVwXy",
    "Region": "us-west-2"
}
```

7. Update the AmazonKinesisVideoDemoApp/src/main/java/com/amazonaws/kinesisvideo/demoapp/fragment/StreamingFragment.java with your region:

```
try {
    mKinesisVideoClient = KinesisVideoAndroidClientFactory.createKinesisVideoClient(
    getActivity(),
    KinesisVideoDemoApp.KINESIS_VIDEO_REGION,
    KinesisVideoDemoApp.getCredentialsProvider());
```

For AWS region constants, see Regions.

Next Step

the section called "Step 2: Examine the Code" (p. 42)

Step 2: Examine the Code

In this section of the Android Producer Library procedure, you examine the example code.

The Android test application (AmazonKinesisVideoDemoApp) shows the following coding pattern:

- Create an instance of KinesisVideoClient.
- Create an instance of MediaSource.
- Start streaming—that is, start the MediaSource, and it starts sending data to the client.

The following sections provide details.

Creating an Instance of KinesisVideoClient

You create the KinesisVideoClient object by calling the createKinesisVideoClient operation.

For KinesisVideoClient to make network calls, it needs credentials to authenticate. You pass in an instance of AWSCredentialsProvider, which reads your Amazon Cognito credentials from the awsconfiguration.json file that you modified in the previous section.

Creating an Instance of MediaSource

To send bytes to your Kinesis video Stream, you must produce the data. Amazon Kinesis Video Streams provides the MediaSource interface, which represents the data source.

For example, the Kinesis Video Streams Android library provides the AndroidCameraMediaSource implementation of the MediaSource interface. This class reads data from one of the device's cameras.

In the following code example (from the fragment/StreamConfigurationFragment.java file), the configuration for the media source is created:

```
private AndroidCameraMediaSourceConfiguration getCurrentConfiguration() {
return new AndroidCameraMediaSourceConfiguration(
        AndroidCameraMediaSourceConfiguration.builder()
                 .withCameraId(mCamerasDropdown.getSelectedItem().getCameraId())
                 . with {\tt Encoding MimeType} ({\tt mMimeTypeDropdown.getSelectedItem().getMimeType())} \\
                 .withHorizontalResolution(mResolutionDropdown.getSelectedItem().getWidth())
                 .withVerticalResolution(mResolutionDropdown.getSelectedItem().getHeight())
                 .withCameraFacing(mCamerasDropdown.getSelectedItem().getCameraFacing())
                 .withIsEncoderHardwareAccelerated(
                         mCamerasDropdown.getSelectedItem().isEndcoderHardwareAccelerated())
                 .withFrameRate(FRAMERATE_20)
                 .withRetentionPeriodInHours(RETENTION_PERIOD_48_HOURS)
                 .withEncodingBitRate(BITRATE_384_KBPS)
                .withCameraOrientation(-
mCamerasDropdown.getSelectedItem().getCameraOrientation())
 .withNalAdaptationFlags(StreamInfo.NalAdaptationFlags.NAL ADAPTATION ANNEXB CPD AND FRAME NALS)
                 .withIsAbsoluteTimecode(false));
}
```

Amazon Kinesis Video Streams Developer Guide Step 3: Run and Verify the Code

In the following code example (from the fragment/StreamingFragment.java file), the media source is created:

mCameraMediaSource = (AndroidCameraMediaSource) mKinesisVideoClient
 .createMediaSource(mStreamName, mConfiguration);

Starting the Media Source

Start the media source so that it can begin generating data and sending it to the client. The following code example is from the fragment/StreamingFragment.java file:

mCameraMediaSource.start();

Next Step

the section called "Step 3: Run and Verify the Code" (p. 43)

Step 3: Run and Verify the Code

To run the Android example application for the Android Producer Library, do the following.

- 1. Connect to an Android device.
- 2. Choose Run, Run..., and choose Edit configurations....
- Choose +, Android App. In the Name field, enter AmazonKinesisVideoDemoApp. In the Module pulldown, choose AmazonKinesisVideoDemoApp. Choose OK.
- 4. Choose Run, Run.
- 5. In the Select Deployment Target screen, choose your connected device, and choose OK.
- 6. In the AWSKinesisVideoDemoApp application on the device, choose Create new account.
- 7. Enter values for **USERNAME**, **Password**, **Given name**, **Email address**, and **Phone number**, and then choose **Sign up**.

Note

These values have the following constraints:

- Password: Must contain uppercase and lowercase letters, numbers, and special characters. You can change these constraints in your User pool page on the Amazon Cognito console.
- Email address: Must be a valid address so that you can receive a confirmation code.
- Phone number: Must be in the following format: +<Country code><Number>, for example, +12065551212.
- 8. Enter the code you receive by email, and choose **Confirm**. Choose **Ok**.
- 9. On the next page, leave the default values, and choose **Stream**.
- 10. Sign in to the AWS Management Console and open the Kinesis Video Streams console at https://console.aws.amazon.com/kinesisvideo/ in the US West (Oregon) Region.

On the Manage Streams page, choose demo-stream.

11. The streaming video plays in the embedded player. You might need to wait a short time (up to ten seconds under typical bandwidth and processor conditions) while the frames accumulate before the video appears.

Note

If the device's screen rotates (for example, from portrait to landscape), the application stops streaming video.

The code example creates a stream. As the MediaSource in the code starts, it begins sending frames from the camera to the KinesisVideoClient. The client then sends the data to a Kinesis video stream named demo-stream.

Using the C++ Producer Library

Amazon Kinesis Video Streams provides the C++ Producer Library, which you can use to write application code to send media data from a device to a Kinesis video stream.

Object Model

The C++ library provides the following objects to manage sending data to a Kinesis video stream:

- **KinesisVideoProducer:** Contains information about your media source and AWS credentials, and maintains callbacks to report on Kinesis Video Streams events.
- **KinesisVideoStream:** Represents the Kinesis video stream. Contains information about the video stream's parameters, such as name, data retention period, media content type, and so on.

Putting Media into the Stream

The C++ library provides methods (for example, PutFrame) that you can use to put data into the KinesisVideoStream object. The library then manages the internal state of the data, which can include the following tasks:

- Performing authentication.
- Watching for network latency. If the latency is too high, the library might choose to drop frames.
- Tracking status of streaming in progress.

Callback Interfaces

This layer exposes a set of callback interfaces, which enable it to talk to the application layer. These callback interfaces include the following:

- Service callbacks interface (CallbackProvider): The library invokes events obtained through this interface when it creates a stream, obtains a stream description, deletes a stream, and so on.
- Client-ready state or low storage events interface (ClientCallbackProvider): The library invokes
 events on this interface when the client is ready, or when it detects that it might run out of available
 storage or memory.
- Stream events callback interface (StreamCallbackProvider): The library invokes events on this
 interface when stream events occur, such as the stream entering the ready state, dropped frames, or
 stream errors.

Kinesis Video Streams provides default implementations for these interfaces. You can also provide your own custom implementation—for example, if you need custom networking logic or you want to expose a low storage condition to the user interface.

For more information about callbacks in the Producer Libraries, see Producer SDK Callbacks (p. 101).

Procedure: Using the C++ Producer SDK

This procedure demonstrates how to use the Kinesis Video Streams client and media sources in a C++ application to send data to your Kinesis video stream.

Note

The C++ library includes a sample build script for macOS. To use the C++ Producer Library on Microsoft Windows, see Using the C++ Producer SDK on Windows (p. 53). To use the C++ Producer Library on a Raspberry Pi device, see Using the C++ Producer SDK on Raspberry Pi (p. 57).

The procedure includes the following steps:

- Step 1: Download and Configure the Code
- Step 2: Write and Examine the Code
- Step 3: Run and Verify the Code

Prerequisites

• **Credentials:** In the sample code, you provide credentials by specifying a profile that you set up in your AWS credentials profile file. If you haven't already done so, first set up your credentials profile.

For more information, see Set up AWS Credentials and Region for Development.

• Certificate store integration: The Kinesis Video Streams Producer Library must establish trust with the service it calls. This is done through validating the certification authorities (CAs) in the public certificate store. On Linux-based models, this store is located in the /etc/ssl/directory.

Download the certificate from the following location to your certificate store:

https://www.amazontrust.com/repository/SFSRootCAG2.pem

- Install the following build dependencies for macOS:
 - Autoconf 2.69 (License GPLv3+/Autoconf: GNU GPL version 3 or later)
 - CMake 3.7 or 3.8
 - Pkg-Config
 - Flex 2.5.35 Apple (flex-31) or later
 - Bison 2.4 (GNU License)
 - Automake 1.15.1 (GNU License)
 - GNU Libtool (Apple Inc. version cctools-898)
 - xCode (macOS) / clang / gcc (xcode-select version 2347)
 - Java Development Kit (JDK) (for Java JNI compilation)
 - Lib-Pkg
- Install the following build dependencies for Ubuntu (responses to version commands are truncated):
 - Install Git: sudo apt-get install git

```
$ git --version
git version 2.14.1
```

• Install CMake: sudo apt-get install cmake

```
$ cmake --version
cmake version 3.9.1
```

Install Libtool: sudo apt-get install libtool

Amazon Kinesis Video Streams Developer Guide Procedure: Using the C++ Producer SDK

```
2.4.6-2
```

• Install libtool-bin: sudo apt-get install libtool-bin

```
$ libtool --version
libtool (GNU libtool) 2.4.6
Written by Gordon Matzigkeit, 1996
```

• Install GNU Automake: sudo apt-get install automake

```
$ automake --version
automake (GNU automake) 1.15
```

• Install GNU Bison: sudo apt-get install bison

```
$ bison -V
bison (GNU Bison) 3.0.4
```

• Install G++: sudo apt-get install g++

```
g++ --version
g++ (Ubuntu 7.2.0-8ubuntu3) 7.2.0
```

• Install curl: sudo apt-get install curl

```
$ curl --version
curl 7.55.1 (x86_64-pc-linux-gnu) libcurl/7.55.1 OpenSSL/1.0.2g zlib/1.2.11
libidn2/2.0.2 libpsl/0.18.0 (+libidn2/2.0.2) librtmp/2.3
```

• Install pkg-config: sudo apt-get install pkg-config

```
$ pkg-config --version
0.29.1
```

• Install Flex: sudo apt-get install flex

```
$ flex --version
flex 2.6.1
```

• Install OpenJDK: sudo apt-get install openjdk-8-jdk

```
$ java -version
openjdk version "1.8.0_171"
```

- Set the JAVA_HOME environment variable: export JAVA_HOME=/usr/lib/jvm/java-8-openjdk-amd64/
- Run the build script: ./install-script

Next Step

Step 1: Download and Configure the C++ Producer Library Code

Step 1: Download and Configure the C++ Producer Library Code

In this section, you download the low-level libraries and configure the application to use your AWS credentials.

For prerequisites and other details about this example, see Using the C++ Producer Library.

1. Create a directory, and then clone the example source code from the GitHub repository.

```
$ git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp
```

- Open the code in the integrated development environment (IDE) of your choice (for example, Eclipse).
- At the command line, set the ACCESS_KEY_ENV_VAR and SECRET_KEY_ENV_VAR environment variables to your AWS credentials. Alternatively, you can hardcode your AWS credentials in the following lines of ProducerTestFixture.h:

```
if (nullptr == (accessKey = getenv(ACCESS_KEY_ENV_VAR))) {
    accessKey = "AccessKey";
}

if (nullptr == (secretKey = getenv(SECRET_KEY_ENV_VAR))) {
    secretKey = "SecretKey";
}
```

4. In tst/ProducerTestFixture.h, find the call to CreateStream. Change the name of the stream definition from ScaryTestStream2 to a unique name:

```
shared_ptr<KinesisVideoStream> CreateTestStream(int index) {
    char stream_name[MAX_STREAM_NAME_LEN];
    sprintf(stream_name, "ScaryTestStream_%d", index);
```

Next Step

Step 2: Write and Examine the Code (p. 47)

Step 2: Write and Examine the Code

In this section of the C++ Producer Library procedure, you examine the code in the C++ test harness (tst/ProducerTestFixture.h and other files). You downloaded this code in the previous section.

The **Platform Independent** C++ example shows the following coding pattern:

- Create an instance of KinesisVideoProducer to access Kinesis Video Streams.
- Create an instance of KinesisVideoStream. This creates a Kinesis video stream in your AWS account if a stream of the same name doesn't already exist.
- Call putFrame on the KinesisVideoStream for every frame of data, as it becomes available, to send it to the stream.

The following sections provide details:

Creating an Instance of KinesisVideoProducer

You create the KinesisVideoProducer object by calling the KinesisVideoProducer::createSync method. The following example creates the KinesisVideoProducer in the ProducerTestFixture.h file:

```
kinesis_video_producer_ = KinesisVideoProducer::createSync(move(device_provider_),
    move(client_callback_provider_),
    move(stream_callback_provider_),
    move(credential_provider_),
    defaultRegion_);
```

The createSync method takes the following parameters:

• A DeviceInfoProvider object, which returns a DeviceInfo object containing information about the device or storage configuration.

Note

You configure your content store size using the deviceInfo.storageInfo.storageSize parameter. Your content streams share the content store. To determine your storage size requirement, multiply the average frame size by the number of frames stored for the max duration for all the streams. Then multiply by 1.2 to account for defragmentation. For example, suppose that your application has the following configuration:

- Three streams
- 3 minutes of maximum duration
- Each stream is 30 frames per second (FPS)
- Each frame is 10,000 KB in size

The content store requirement for this application is 3 (streams) * 3 (minutes) * 60 (seconds in a minute) * 10000 (kb) * 1.2 (defragmentation allowance) = 194.4 Mb ~ 200Mb.

- A ClientCallbackProvider object, which returns function pointers that report client-specific events.
- A StreamCallbackProvider object, which returns function pointers that are called back when stream-specific events occur.
- A CredentialProvider object, which provides access to AWS credential environment variables.
- The AWS Region ("us-west-2"). The service endpoint is determined from the Region.

Creating an Instance of KinesisVideoStream

You create the KinesisVideoStream object by calling the KinesisVideoProducer::CreateStream method with a StreamDefinition parameter. The example creates the KinesisVideoStream in the ProducerTestFixture.h file with the track type as video, and with track id as 1:

```
return kinesis_video_producer_->createStream(move(stream_definition));
```

The StreamDefinition object has the following fields:

- · Stream name.
- · Data retention period.
- Tags for the stream. These tags can be used by consumer applications to find the correct stream, or to get more information about the stream. The tags can also be viewed in the AWS Management Console.
- AWS KMS encryption key for the stream. For more information, see Using Server-Side Encryption with Kinesis Video Streams.
- Streaming type. Currently, the only valid value is STREAMING TYPE REALTIME.
- · Media content type.
- Media latency. This value is not currently used, and should be set to 0.
- Playback duration of each fragment.
- · Media timecode scale.
- Whether the media uses key frame fragmentation.
- · Whether the media uses timecodes.
- Whether the media uses absolute fragment times.

Adding an audio track to the Kinesis Video Stream

You can add audio track details to a video track stream definition by using the addTrack method of the StreamDefinition:

```
stream_definition->addTrack(DEFAULT_AUDIO_TRACKID, DEFAULT_AUDIO_TRACK_NAME,
    DEFAULT_AUDIO_CODEC_ID, MKV_TRACK_INFO_TYPE_AUDIO);
```

The addTrack method requires the following parameters:

- Track id (as 1 for audio). This should be unique and non-zero value.
- User-defined track name (e.g. "audio" for the audio track).
- Codec id for this track (e.g. for audio track "A_AAC").
- Track type (e.g. use the enum value of MKV_TRACK_INFO_TYPE_AUDIO for audio).

If you have codec private data for the audio track, then you can pass it when calling the addTrack function. You can also send the codec private data after creating the KinesisVideoStream object while calling the start method in KinesisVideoStream.

Putting a Frame into the Kinesis Video Stream

You put media into the Kinesis video stream using KinesisVideoStream::putFrame, passing in a Frame object that contains the header and media data. The example calls putFrame in the ProducerApiTest.cpp file:

```
frame.duration = FRAME_DURATION_IN_MICROS * HUNDREDS_OF_NANOS_IN_A_MICROSECOND;
    frame.size = SIZEOF(frameBuffer_);
    frame.frameData = frameBuffer_;
    MEMSET(frame.frameData, 0x55, frame.size);

while (!stop_producer_) {
    // Produce frames
    timestamp = std::chrono::duration_cast<std::chrono::nanoseconds>(
```

```
std::chrono::system_clock::now().time_since_epoch()).count() /
DEFAULT_TIME_UNIT_IN_NANOS;
    frame.index = index++;
    frame.decodingTs = timestamp;
    frame.presentationTs = timestamp;

    // Key frame every 50th
    frame.flags = (frame.index % 50 == 0) ? FRAME_FLAG_KEY_FRAME : FRAME_FLAG_NONE;
...

EXPECT_TRUE(kinesis_video_stream->putFrame(frame));
```

Note

The preceding C++ Producer example sends a buffer of test data. In a real-world application, you should obtain the frame buffer and size from the frame data from a media source (such as a camera).

The Frame object has the following fields:

- Frame index. This should be a monotonically incrementing value.
- Flags associated with the frame. For example, if the encoder were configured to produce a key frame, this frame would be assigned the FRAME FLAG KEY FRAME flag.
- · Decoding time stamp.
- · Presentation time stamp.
- Duration of the frame (to 100 ns units).
- · Size of the frame in bytes.
- Frame data.

For more information about the format of the frame, see Kinesis Video Streams Data Model.

Putting a KinesisVideoFrame into a specific track of KinesisVideoStream

You can use the PutFrameHelper class to put frame data into a specific track. First, call the getFrameDataBuffer to get a pointer to one of the pre-allocated buffers to fill in the KinesisVideoFrame data. Then, you can call the putFrameMultiTrack to send the KinesisVideoFrame along with the boolean value to indicate the type of frame data. Use true if it's a video data or false if the frame contains audio data. The putFrameMultiTrack method uses a queueing mechanism to ensure that the MKV Fragments maintain monotonically increasing frame time stamps and any two fragments do not overlap. For example, MKV timestamp of the first frame of a fragment should always be greater than the MKV timestamp of the last frame of the previous fragment.

The PutFrameHelper has the following fields:

- Maximum number of audio frames in the queue
- Maximum number of video frames in the queue
- Size to allocate for a single audio frame
- Size to allocate for a single video frame

Metrics and Metric Logging

The C++ Producer SDK includes functionality for metrics and metric logging.

You can use the getKinesisVideoMetrics and getKinesisVideoStreamMetrics API operations to retrieve information about Kinesis Video Streams and your active streams.

The following code is from the kinesis-video-pic/src/client/include/com/amazonaws/kinesis/video/client/Include.h file.

```
/**

* Gets information about the storage availability.

* @param 1 CLIENT_HANDLE - the client object handle.

* @param 2 PKinesisVideoMetrics - OUT - Kinesis Video metrics to be filled.

*

* @return Status of the function call.

*/

PUBLIC_API STATUS getKinesisVideoMetrics(CLIENT_HANDLE, PKinesisVideoMetrics);

/**

* Gets information about the stream content view.

*

* @param 1 STREAM_HANDLE - the stream object handle.

* @param 2 PStreamMetrics - Stream metrics to fill.

*

* @return Status of the function call.

*/

PUBLIC_API STATUS getKinesisVideoStreamMetrics(STREAM_HANDLE, PStreamMetrics);
```

The PClientMetrics object filled by getKinesisVideoMetrics contains the following information:

- contentStoreSize: The overall size in bytes of the content store (the memory used to store streaming data).
- contentStoreAvailableSize: The free memory in the content store, in bytes.
- contentStoreAllocatedSize: The allocated memory in the content store.
- totalContentViewsSize: The total memory used for the content view. (The content view is a series of indices of information in the content store.)
- totalFrameRate: The aggregate number of frames per second across all active streams.
- totalTransferRate: The total bits per second (bps) being sent in all streams.

The PStreamMetrics object filled by getKinesisVideoStreamMetrics contains the following information:

- **currentViewDuration:** The difference in 100 ns units between the head of the content view (when frames are encoded) and the current position (when frame data is being sent to Kinesis Video Streams).
- overallViewDuration: The difference in 100 ns units between the head of the content view (when frames are encoded) to the tail (when frames are flushed from memory, either because the total allocated space for the content view is exceeded, or because a PersistedAck message is received from Kinesis Video Streams, and frames known to be persisted are flushed).
- **currentViewSize:** The size in bytes of the content view from the head (when frames are encoded) to the current position (when frames are sent to Kinesis Video Streams).
- overallViewSize: The total size in bytes of the content view.
- currentFrameRate: The last measured rate of the stream, in frames per second.
- currentTransferRate: The last measured rate of the stream, in bytes per second.

Next Step

the section called "Step 3: Run and Verify the Code" (p. 52)

Step 3: Run and Verify the Code

To run and verify the code for the C++ Producer Library procedure, do the following:

- 1. See Prerequisites for credential, certificate, and build requirements.
- 2. Build the project by using the /kinesis-video-native-build/install-script script. Running the install script installs the following open source dependencies:
 - curl lib
 - · openssl (crypto and ssl)
 - log4cplus
 - jsoncpp

Note

To configure **log4cplus**, set the following value in PlatformUtils.h to point to your logging function:

```
#define __LOG(p1, p2, p3, ...) printf(p3, ##__VA_ARGS___)
```

- 3. The executable is built in kinesis-video-native-build/start. Launch it to run the unit test and kick off dummy frame streaming.
- 4. To enable verbose logs, define the HEAP_DEBUG and LOG_STREAMING C-defines by uncommenting the appropriate lines in CMakeList.txt.

You can monitor the progress of the test suite in the debug output in your IDE. You can also monitor the traffic on your stream by watching the metrics that are associated with your stream in the Amazon CloudWatch console, such as PutMedia.IncomingBytes.

Note

Because the test harness only sends frames of empty bytes, the console doesn't display the data as a video stream.

Using the C++ Producer SDK as a GStreamer Plugin

GStreamer is a popular media framework used by a multitude of cameras and video sources to create custom media pipelines by combining modular plugins. The Kinesis Video Streams GStreamer plugin greatly simplifies the integration of your existing GStreamer media pipeline with Kinesis Video Streams.

For information about using the C++ Producer SDK as a GStreamer plugin, see Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 115).

Using the C++ Producer SDK as a GStreamer Plugin in a Docker Container

GStreamer is a popular media framework used by a multitude of cameras and video sources to create custom media pipelines by combining modular plugins. The Kinesis Video Streams GStreamer plugin greatly simplifies the integration of your existing GStreamer media pipeline with Kinesis Video Streams.

In addition, using Docker to create the GStreamer pipeline standardizes the operating environment for Kinesis Video Streams, which greatly simplifies building and executing the application.

For information about using the C++ Producer SDK as a GStreamer plugin in a Docker container, see Run the GStreamer Element in a Docker Container (p. 119).

Using the C++ Producer SDK on Windows

This tutorial demonstrates how to build and run the Producer Libraries (p. 34) on Microsoft Windows. You can then stream video to Kinesis Video Streams from sources such as webcams, USB cameras, or RTSP (Real Time Streaming Protocol) cameras. When you start streaming from your media source to a Kinesis video stream, you can view the video in the Kinesis Video Streams console. You can also build applications that operate on the streaming video that is available in your Kinesis video stream.

Topics

- · Building and Running the Producer SDK: Minimalist GNU for Windows (MinGW) (p. 53)
- Building and Running the Producer SDK: Microsoft Visual C++ Compiler (MSVC) (p. 55)

Building and Running the Producer SDK: Minimalist GNU for Windows (MinGW)

Minimalist GNU for Windows (MinGW) is an open-source programming toolchain for developing native Windows applications. You can use MinGW to build the Kinesis Video Streams Producer SDK for Windows and then run one of the sample applications to start streaming video.

This section describes prerequisites and steps needed to build the Amazon Kinesis Video Streams Producer SDK using the MinGW compiler.

Prerequisites

Before you start, ensure that you have the following:

 Download and install the MSYS2 version for your specific Windows platform. MSYS2 provides all the tools to build native Windows applications using MinGW toolchains.

Building the Producer SDK Using MinGW

Follow these steps to use the MinGW runtime environment to compile the Kinesis Video StreamsProducer SDK on Windows.

- 1. Launch the MinGW shell (mingw64.exe) from the C:\msys32 or C:\msys64 directory. Make sure that you are opening the mingw64.exe or mingw32.exe based on your platform, and not the MSYS2 application. The MSYS2 application is the default application that is opened after you finish installing MSYS2.
- 2. Install Git by running the following command in the MinGW shell:

```
pacman -S git
```

3. Download the Kinesis Video Streams Producer SDK from GitHub:

```
git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp.git
```

4. Navigate to the amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-native-build directory, and run the following install script to build the Producer SDK:

```
./msys2-install-script -a
```

Note

• Accept all of the prompts when the script runs.

 Log4cplus is compiled from source, but all other components are downloaded as pre-built binaries.

Running the Producer SDK to Send Video to Kinesis Video Streams

After compiling the Kinesis Video Streams Producer SDK using MinGW, follow these steps to run it:

Step 1: Set Environment Variables

• In the MinGW shell, set the following environment variables:

```
export AWS_ACCESS_KEY_ID=<u>YOUR_ACCESS_KEY</u>
export AWS_SECRET_ACCESS_KEY=<u>YOUR_SECRET_ACCESS_KEY</u>
export GST_PLUGIN_PATH=$PWD
```

Note

YOUR_ACCESS_KEY and YOUR_SECRET_ACCESS_KEY are the access keys for your AWS account used for signing programmatic requests that you make to AWS. For more information, see Managing Access Keys for IAM Users.

Step 2: Run the Sample Application for Your Media Source

 To stream video from your PC webcam, run the sample application from the kinesis-videonative-build directory using the following command:

```
kinesis_video_gstreamer_sample_app.exe my-stream-name
```

To stream video from your PC webcam using a custom configuration, such as a specific bitrate
or resolution, run the Kinesis Video Streams Producer SDK GStreamer plugin using the gstlaunch-1.0 command:

```
gst-launch-1.0 ksvideosrc do-timestamp=TRUE ! video/x-
raw,width=640,height=480,framerate=30/1 ! videoconvert ! x264enc bframes=0
key-int-max=45 bitrate=512 ! video/x-h264,profile=baseline,stream-
format=avc,alignment=au,width=640,height=480,framerate=30/1 ! kvssink stream-
name="your-stream-name" access-key=your_accesskey_id secret-key=your_secret_access_key
```

For information about how to determine the parameters for the gst-launch-1.0 command, see GStreamer Element Parameter Reference (p. 121).

Note

If you are using IoT credentials instead of your access key and secret key to authenticate, you can supply IoT credentials as parameters to the gst-launch-1.0 command. The following example demonstrates using IoT parameters to stream video from an RTSP camera:

```
gst-launch-1.0 rtspsrc location=rtsp://YourCameraRtspUrl short-header=TRUE ! rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-name="your-iot-stream" iot-certificate="iot-certificate,endpoint=endpoint,cert-path=/path/to/certificate,key-path=/path/to/private/key,ca-path=/path/to/ca-cert,role-aliases=role-aliases"
```

3. To stream video from an RTSP (network) camera, run the sample application from the kinesis-video-native-build directory using the following command:

```
kinesis_video_gstreamer_sample_rtsp_app.exe RTSP-camera-URL my-test-rtsp-stream
```

Building and Running the Producer SDK: Microsoft Visual C++ Compiler (MSVC)

The Microsoft Visual C++ Compiler (MSVC) is the compiler for Microsoft Visual Studio. The following sections include the prerequisites and steps that are required to build the Kinesis Video Streams Producer SDK using MSVC.

Prerequisites

Before you start, ensure that you have the following:

- · Microsoft Windows version 7 or later.
- Microsoft .NET Framework version 4.6.1 or later.
- Windows PowerShell version 5.1 (included in Windows 10). On Windows 7, update Windows PowerShell.
- Git. In the Adjusting your PATH environment installation step, choose Use Git from the Windows Command Prompt.

Building the Producer SDK Using MSVC

Follow these steps to use MSVC to compile the Producer SDK on Windows.

Note

If you previously installed the Producer SDK for Windows using MinGW, do the following cleanup steps before building the SDK using MSVC:

- Delete the files in the kinesis-video-native-build/downloads directory.
- Remove the CMakeFiles directory and the CMakeCachedList.txt file in the kinesis-video-native-build directory.
- 1. Open a Windows command prompt as an administrator.
- 2. Download the Producer SDK:

```
git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp.git
```

- After the download is complete, change to the kinesis-video-native-build directory within the downloaded project.
- 4. Run the Visual Studio build tools install script:

```
vs-buildtools-install.bat
```

- 5. After the install script completes, if you are using Windows 10 or Windows 7, reboot your computer. Then re-open a Windows command prompt as an administrator.
- In the kinesis-video-native-build directory, run windows-install.bat, specifying your system's bit width (32 or 64):

```
windows-install.bat 32
or
windows-install.bat 64
```

Note

This script builds the following components:

• The C++ Producer Library (p. 44) libraries.

- The C++ Producer SDK GStreamer (p. 115) (kvssink).
- The RTSP and Docker (p. 127) demo, which shows how to stream data from an RTSP (network) camera.

Running the Producer SDK to Send Video to Kinesis Video Streams

After compiling the Kinesis Video Streams Producer SDK using MSVC, follow these steps to run it as a GStreamer plugin.

You have several options for starting the SDK. We recommend that you use the GStreamer (p. 115), which you can run using the example executables available in the kinesis-video-native-build/start directory.

1. Add the following directories to your path (specify the location for the Producer SDK, including the drive):

```
set PATH=%PATH%; install directory\amazon-kinesis-video-streams-producer-sdk-cpp \kinesis-video-native-build\downloads\gstreamer\1.0\x86_64\bin;
```

2. Set the following environment variables (replace *install directory* with the location for the Producer SDK, including the drive):

```
set GST_PLUGIN_PATH=install directory\amazon-kinesis-video-streams-producer-sdk-cpp \kinesis-video-native-build\Release set GST_PLUGIN_SYSTEM_PATH=install directory\amazon-kinesis-video-streams-producer-sdk-cpp\kinesis-video-native-build\downloads\gstreamer\1.0\x86_64\lib\gstreamer-1.0
```

 Stream video from the webcam on the PC to the Kinesis Video Streams service using the gstlaunch-1.0 command:

```
gst-launch-1.0 ksvideosrc do-timestamp=TRUE ! video/x-
raw,width=640,height=480,framerate=30/1 ! videoconvert ! x264enc bframes=0
key-int-max=45 bitrate=512 ! video/x-h264,profile=baseline,stream-
format=avc,alignment=au,width=640,height=480,framerate=30/1 ! kvssink stream-
name="your-stream-name" access-key=your_accesskey_id secret-key=your_secret_access_key
```

For information about how to determine the parameters for the gst-launch-1.0 command, see GStreamer Element Parameter Reference (p. 121).

Note

If you are using IoT credentials instead of your access key and secret key, you can supply them as parameters to the gst-launch-1.0 command. The following example demonstrates using IoT parameters to stream video from an RTSP camera:

```
gst-launch-1.0 rtspsrc location=rtsp://YourCameraRtspUrl short-header=TRUE ! rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-name="your-iot-stream" iot-certificate="iot-certificate,endpoint=endpoint,cert-path=/path/to/certificate,key-path=/path/to/private/key,ca-path=/path/to/cacert,role-aliases=role-aliases"
```

4. Alternatively, you can set the following environment variables and use one of our pre-build sample applications.

```
export AWS_ACCESS_KEY_ID=YOUR_ACCESS_KEY
export AWS_SECRET_ACCESS_KEY=YOUR_SECRET_ACCESS_KEY
```

5. To stream video from a PC webcam, run the sample application from the kinesis-video-native-build\Release directory using the following command:

```
kinesis video qstreamer sample app.exe my-stream-name
```

6. To stream video from an RTSP (network) camera, run the sample application from the kinesis-video-native-build\Release directory using the following command:

```
kinesis_video_gstreamer_sample_rtsp_app.exe RTSP-camera-URL my-test-rtsp-stream
```

Using the C++ Producer SDK on Raspberry Pi

The Raspberry Pi is a small, inexpensive computer that can be used to teach and learn basic computer programming skills. This tutorial describes how you can set up and use the Amazon Kinesis Video Streams C++ Producer SDK on a Raspberry Pi device. The steps also include how to verify the installation using the GStreamer demo application.

Topics

- Prerequisites (p. 57)
- Create an IAM User with Permission to Write to Kinesis Video Streams (p. 58)
- Join Your Raspberry Pi to Your Wi-Fi Network (p. 59)
- Connect Remotely to Your Raspberry Pi (p. 59)
- Configure the Raspberry Pi Camera (p. 60)
- Install Software Prerequisites (p. 60)
- Download and Build the Kinesis Video Streams C++ Producer SDK (p. 61)
- Stream Video to Your Kinesis Video Stream and View the Live Stream (p. 61)

Prerequisites

Before you set up the C++ Producer SDK on your Raspberry Pi, ensure that you have the following prerequisites:

- A Raspberry Pi device with the following configuration:
 - Board version: 3 Model B or later.
 - · A connected camera module.
 - An SD card with a capacity of at least 8 GB.
 - The Raspbian operating system (kernel version 4.9 or later) installed. You can download the latest Raspbian image from the Raspberry Pi Foundation website. Follow the Raspberry Pi instructions to install the downloaded image on an SD card.
- An AWS account with a Kinesis video stream. For more information, see Getting Started with Kinesis Video Streams.

Note

The C++ Producer SDK uses the US West (Oregon) (us-west-2) Region by default. To use the default AWS Region, create your Kinesis video stream in the US West (Oregon) Region. To use a different Region for your Kinesis video stream, do one of the following:

• Set the following environment variable to your Region (for example, us-east-1):

```
export AWS_DEFAULT_REGION=us-east-1
```

 After downloading the source code (see the section called "Download and Build the Kinesis Video Streams C++ Producer SDK" (p. 61)), change the following values in the amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-producer/
DefaultCallbackProvider.h file to your Region:

```
const std::string DEFAULT_AWS_REGION = "us-east-1";
const std::string KINESIS_VIDEO_SERVICE_NAME = "kinesisvideo";
const std::string DEFAULT_CONTROL_PLANE_URI = "https://kinesisvideo.us-east-1.amazonaws.com";
```

Create an IAM User with Permission to Write to Kinesis Video Streams

If you haven't already done so, set up an AWS Identity and Access Management (IAM) user with permissions to write to a Kinesis video stream.

- Sign in to the AWS Management Console and open the IAM console at https:// console.aws.amazon.com/iam/.
- 2. In the navigation menu on the left, choose Users.
- 3. To create a new user, choose Add user.
- 4. Provide a descriptive User name for the user, such as kinesis-video-raspberry-pi-producer.
- 5. Under Access type, choose Programmatic access.
- 6. Choose Next: Permissions.
- Under Set permissions for kinesis-video-raspberry-pi-producer, choose Attach existing policies directly.
- 8. Choose Create policy. The Create policy page opens in a new web browser tab.
- 9. Choose the JSON tab.
- 10. Copy the following JSON policy and paste it into the text area. This policy gives your user permission to create and write data to Kinesis video streams.

```
{
  "Version": "2012-10-17",
  "Statement": [{
      "Effect": "Allow",
      "Action": [
      "kinesisvideo:DescribeStream",
      "kinesisvideo:CreateStream",
      "kinesisvideo:GetDataEndpoint",
      "kinesisvideo:PutMedia"
    ],
      "Resource": [
      "*"
    ]
}]
```

- 11. Choose Review policy.
- 12. Provide a Name for your policy, such as kinesis-video-stream-write-policy.
- 13. Choose Create policy.
- 14. Return to the **Add user** tab in your browser, and choose **Refresh**.
- 15. In the search box, type the name of the policy you created.
- 16. Select the check box next to your new policy in the list.
- 17. Choose Next: Review.
- 18. Choose Create user.

19. The console displays the **Access key ID** for your new user. Choose **Show** to display the **Secret access key**. Record these values; they are required when you configure the application.

Join Your Raspberry Pi to Your Wi-Fi Network

You can use the Raspberry Pi in *headless* mode, that is, without an attached keyboard, monitor, or network cable. If you are using an attached monitor and keyboard, proceed to Configure the Raspberry Pi Camera (p. 60).

- 1. On your computer, create a file named wpa_supplicant.conf.
- 2. Copy the following text and paste it into the wpa_supplicant.conf file:

```
country=US
ctrl_interface=DIR=/var/run/wpa_supplicant GROUP=netdev
update_config=1

network={
    ssid="<YOUR_WIFI_SSID>"
    scan_ssid=1
    key_mgmt=WPA-PSK
    psk="<YOUR_WIFI_PASSWORD>"
}
```

Replace the ssid and psk values with the information for your Wi-Fi network.

- Copy the wpa_supplicant.conf file to the SD card. It must be copied to the root of the boot volume.
- 4. Insert the SD card into the Raspberry Pi, and power the device. It joins your Wi-Fi network, and SSH is enabled.

Connect Remotely to Your Raspberry Pi

You can connect remotely to your Raspberry Pi in headless mode. If you are using your Raspberry Pi with a connected monitor and keyboard, proceed to Configure the Raspberry Pi Camera (p. 60).

- Before connecting to your Raspberry Pi device remotely, do one of the following to determine its IP address:
 - If you have access to your network's Wi-Fi router, look at the connected Wi-Fi devices. Find the device named Raspberry Pi to find your device's IP address.
 - If you don't have access to your network's Wi-Fi router, you can use other software to find devices
 on your network. Fing is a popular application that is available for both Android and iOS devices.
 You can use the free version of this application to find the IP addresses of devices on your
 network.
- When you know the IP address of the Raspberry Pi device, you can use any terminal application to connect.
 - On macOS or Linux, use ssh:

```
$ ssh pi@<IP address>
```

• On Windows, use PuTTY, a free SSH client for Windows.

For a new installation of Raspbian, the user name is pi, and the password is raspberry. We recommend that you change the default password.

Configure the Raspberry Pi Camera

Follow these steps to configure the Raspberry Pi camera to send video from the device to a Kinesis video stream.

1. Open an editor to update the modules file with the following command:

```
$ sudo nano /etc/modules
```

2. Add the following line to the end of the file, if it's not already there:

```
bcm2835-v4l2
```

- 3. Save the file and exit the editor (Ctrl-X).
- 4. Reboot the Raspberry Pi:

```
$ sudo reboot
```

- 5. When the device reboots, connect to it again through your terminal application if you are connecting remotely.
- 6. Open raspi-config:

```
$ sudo raspi-config
```

- 7. Choose **Interfacing Options**, **Camera**. Enable the camera if it's not already enabled, and reboot if prompted.
- 8. Verify that the camera is working by typing the following command:

```
$ raspistill -v -o test.jpg
```

The display shows a five-second preview from the camera, takes a picture (saved to test.jpg), and displays informational messages.

Install Software Prerequisites

The C++ Producer SDK requires that you install the following software prerequisites on Raspberry Pi.

1. Install Git:

```
$ sudo apt-get update
$ sudo apt-get install git
```

2. Install Yacc, Lex, and OpenJDK (Open Java Development Kit):

```
$ sudo apt-get install byacc flex
$ sudo apt-get install openjdk-8-jdk
```

Set the JAVA_HOME environment variable:

```
$ export JAVA_HOME=/usr/lib/jvm/java-1.8.0-openjdk-armhf/
```

Note

If you reboot the device before building the SDK, you must repeat this step. You can also set this environment variable in your ~/.profile file.

4. CMake is used to build the SDK. Install CMake with the following command:

```
$ sudo apt-get install cmake
```

Copy the following PEM file to /etc/ssl/cert.pem:

https://www.amazontrust.com/repository/SFSRootCAG2.pem

Download and Build the Kinesis Video Streams C++ Producer SDK

1. Install the C++ Producer SDK:

```
\verb§ git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp]
```

2. Change your current working directory to the install directory:

```
$ cd amazon-kinesis-video-stream-producer-sdk-cpp/kinesis-video-native-build
```

3. Make the install script executable:

```
$ chmod +x install-script
```

4. Run the install script. The script downloads the source and builds several open-source projects. It might take several hours to run the first time it is executed:

```
$ ./install-script
```

5. Type Y to verify. Then the build script runs.

Stream Video to Your Kinesis Video Stream and View the Live Stream

- 1. To run the sample application, you need the following information:
 - The name of the stream you created in the Prerequisites (p. 57) section.
 - The account credentials (access key ID and secret access key) that you created in Create an IAM User with Permission to Write to Kinesis Video Streams (p. 58).
- 2. Run the sample application using the following command:

```
$ export AWS_ACCESS_KEY_ID=<Access Key ID>
export AWS_SECRET_ACCESS_KEY=<Secret Access Key>
./kinesis_video_gstreamer_sample_app Stream Name
```

3. You can specify the image size, framerate, and bitrate as follows:

4. If the sample application exits with a library not found error, type the following commands to verify that the project is correctly linked to its open-source dependencies:

Amazon Kinesis Video Streams Developer Guide Using Logging

```
$ rm -rf ./kinesis-video-native-build/CMakeCache.txt ./kinesis-video-native-build/
CMakeFiles
$ ./kinesis-video-native-build/install-script
```

- 5. Open the Kinesis Video Streams console at https://console.aws.amazon.com/kinesisvideo/.
- 6. Choose the **Stream name** of the stream you created.

The video stream that is sent from the Raspberry Pi appears in the console.

When the stream is playing, you can experiment with the following features of the Kinesis Video Streams console:

- In the Video preview section, use the navigation controls to rewind or fast-forward the stream.
- In the **Stream info** section, notice the codec, resolution, and bitrate of the stream. The resolution and bitrate values are set purposefully low on the Raspberry Pi to minimize bandwidth usage for this tutorial. To view the Amazon CloudWatch metrics that are being created for your stream, choose **View stream metrics in CloudWatch**.
- Under **Data retention period**, notice that the video stream is retained for one day. You can edit this value and set it to **No data retention**, or set a value from one day to several years.

Under server-side encryption, notice that your data is being encrypted at rest using a key maintained by the AWS Key Management Service (AWS KMS).

Using Logging with the C++ Producer SDK

You configure logging for C++ Producer SDK applications in the kvs_log_configuration file in the kinesis-video-native-build folder.

The following example shows the first line of the default configuration file, which configures the application to write DEBUG-level log entries to the AWS Management Console:

```
log4cplus.rootLogger=DEBUG, KvsConsoleAppender
```

You can set the logging level to INFO for less verbose logging.

To configure the application to also write log entries to a log file, update the first line in the file to the following:

```
log4cplus.rootLogger=DEBUG, KvsConsoleAppender, KvsFileAppender
```

This configures the application to write log entries to kvs.log in the kinesis-video-native-build/log folder.

To change the log file location, update the following line with the new path:

```
log4cplus.appender.KvsFileAppender.File=./log/kvs.log
```

Note

If DEBUG-level logging is written to a file, the log file can use up the available storage space on the device quickly.

Producer SDK Reference

This section contains limits, error codes, and other reference information for the Kinesis Video Streams Producer Libraries (p. 34).

Topics

- Producer SDK Limits (p. 63)
- Error Code Reference (p. 65)
- Network Abstraction Layer (NAL) Adaptation Flag Reference (p. 87)
- Producer SDK Structures (p. 88)
- Kinesis Video Stream Structures (p. 89)
- Producer SDK Callbacks (p. 101)

Producer SDK Limits

The following table contains the current limits for values in the Producer Libraries (p. 34).

Note

Before setting these values, you must validate your inputs. The SDK doesn't validate these limits, and a runtime error occurs if the limits are exceeded.

Value	Limit	Notes
Max stream count	128	The maximum number of streams that a producer object can create. This is a soft limit (you can request an increase). It ensures that the producer doesn't accidentally create streams recursively.
Max device name length	128 characters	
Max tag count	50 per stream	
Max stream name length	256 characters	
Min storage size	10 MiB = 10 * 1024 * 1024 bytes	
Max storage size	10 GiB = 10 * 1024 * 1024 * 1024 bytes	
Max root directory path length	4,096 characters	
Max auth info length	10,000 bytes	
Max URI string length	10,000 characters	
Max tag name length	128 characters	
Max tag value length	1,024 characters	
Min security token period	30 seconds	
Security token grace period	40 minutes	If the specified duration is longer, it is limited to this value.

Amazon Kinesis Video Streams Developer Guide Producer SDK Limits

Value	Limit	Notes
Retention period	0 or greater than one hour	0 indicates no retention.
Min cluster duration	1 second	The value is specified in 100 ns units, which is the SDK standard.
Max cluster duration	30 seconds	The value is specified in 100 ns units, which is the SDK standard. The backend API may enforce a shorter cluster duration.
Max fragment size	50 MB	For more information, see Kinesis Video Streams Limits (p. 148).
Max fragment duration	10 seconds	For more information, see Kinesis Video Streams Limits (p. 148).
Max connection duration	45 minutes	The backend closes the connection after this time. The SDK rotates the token and establishes a new connection within this time.
Max ACK segment length	1,024 characters	Maximum segment length of the acknowledgement sent to the ACK parser function.
Max content type string length	128 characters	
Max codec ID string length	32 characters	
Max track name string length	32 characters	
Max codec private data length	1 MiB = 1 * 1024 * 1024 bytes	
Min timecode scale value length	100 ns	The minimum timecode scale value to represent the frame timestamps in the resulting MKV cluster. The value is specified in increments of 100 ns, which is the SDK standard.
Max timecode scale value length	1 second	The maximum timecode scale value to represent the frame timestamps in the resulting MKV cluster. The value is specified in increments of 100 ns, which is the SDK standard.
Min content view item count	10	
Min buffer duration	20 seconds	The value is specified in increments of 100 ns, which is the SDK standard.
Max update version length	128 characters	

Amazon Kinesis Video Streams Developer Guide Error Code Reference

Value	Limit	Notes
Max ARN length	1024 characters	
Max fragment sequence length	128 characters	
Max retention period	10 years	

Error Code Reference

This section contains error and status code information for the Producer Libraries (p. 34).

For information about solutions to common issues, see Troubleshooting Kinesis Video Streams (p. 151).

Errors and Status Codes Returned by PutFrame Callbacks

The following sections contain error and status information that is returned by callbacks for the PutFrame operation.

Topics

- Error and Status Codes Returned by the Client Library (p. 65)
- Error and Status Codes Returned by the Duration Library (p. 79)
- Error and Status Codes Returned by the Common Library (p. 79)
- Error and Status Codes Returned by the Heap Library (p. 80)
- Error and Status Codes Returned by the MKVGen Library (p. 81)
- Error and Status Codes Returned by the Trace Library (p. 85)
- Error and Status Codes Returned by the Utils Library (p. 85)
- Error and Status Codes Returned by the View Library (p. 86)

Error and Status Codes Returned by the Client Library

The following table contains error and status information that is returned by methods in the Kinesis Video Streams Client library.

Code	Message	Description	Recommended Action
0x52000001	STATUS_MAX_STREAM_COUN	The maximum stream count was reached.	Specify a larger max stream count in DeviceInfo as specified in Producer SDK Limits (p. 63).
0x52000002	STATUS_MIN_STREAM_COUN	Minimum stream count error.	Specify the max number of streams greater than 0 in DeviceInfo.
0x52000003	STATUS_INVALID_DEVICE_	<u>រោណអាវ៉ា្នា ៨៤៧</u> ៤៤ ខាន់ ខាន់ ខាន់ ខាន់ ខាន់ ខាន់ ខាន់ ខាន់	Refer to the max device name length in characters that is specified in Producer SDK Limits (p. 63).
0x52000004	STATUS_INVALID_DEVICE_	_ inval idv ression Info structure version.	Specify the correct current version of the structure.

Amazon Kinesis Video Streams Developer Guide Error Code Reference

Code	Message	Description	Recommended Action
0x52000005	STATUS_MAX_TAG_COUNT	The maximum tag count was reached.	Refer to the current max tag count that is specified in Producer SDK Limits (p. 63).
0x52000006	STATUS_DEVICE_FINGERP	RINT_LENGTH	
0x52000007	STATUS_INVALID_CALLBAC	t hsvalicksa DNbacks structure version.	Specify the correct current version of the structure.
0x52000008	STATUS_INVALID_STREAM_	_ invad idv s:Rsaan Info structure version.	Specify the correct current version of the structure.
0x52000009	STATUS_INVALID_STREAM_	<u>MawसicLsbwear</u> म name length.	Refer to the max stream name length in characters that is specified in Producer SDK Limits (p. 63).
0x5200000a	STATUS_INVALID_STORAGE	E_Asτίσε Ralid storage size was specified.	The storage size in bytes must be within the limits specified in Producer SDK Limits (p. 63).
0x5200000b	STATUS_INVALID_ROOT_D	kkavakidek <u>roo</u> ntahkerkory string length.	Refer to the max root directory path length that is specified in Producer SDK Limits (p. 63).
0x5200000c	STATUS_INVALID_SPILL_I	A nval id spill ratio.	Express the spill ratio as a percentage from 0 to 100.
0x5200000d	STATUS_INVALID_STORAGE	<u>Inwatol s/e&sagaI</u> nfo structure version.	Specify the correct current version of the structure.
0x5200000e	STATUS_INVALID_STREAM_	Shestream is in a state that doesn't permit the current operation.	Most commonly, this error occurs when the SDK fails to reach the state that it needs to perform the requested operation. For example, it occurs if the GetStreamingEndpoint API call fails, and the client application ignores it and continues putting frames into the stream.
0x5200000f	STATUS_SERVICE_CALL_CALL_CALL_CALL_CALL_CALL_CALL_CA	ATIMERCEKEL MEICHES NG structure has missing function entry points for some mandatory functions.	Ensure that the mandatory callbacks are implemented in the client application. This error is exposed only to PIC (Platform Independent Code) clients. C++ and other higher-level wrappers satisfy these calls.

Code	Message	Description	Recommended Action
0x52000010	STATUS_SERVICE_CALL_N	O ʻN_catuaun badized b_ERROR	Verify the security token/ certificate/security token integration/expiration. Ensure that the token has the correct associated rights with it. For the Kinesis Video Streams sample applications, ensure that the environment variable is set correctly.
0x52000011	STATUS_DESCRIBE_STREA	M <u>DARGY i</u> BASIBBAM API failure.	This error is returned after the DescribeStream API retry failure. The PIC client returns this error after it gives up retrying.
0x52000012	STATUS_INVALID_DESCRI	B in valke AM_RESPONSE DescribeStreamResp structure.	The structure that ownsepassed to the DescribeStreamResultEve is either null or contains invalid items like a null Amazon Resource Name (ARN).
0x52000013	STATUS_STREAM_IS_BEIN	<u>G Tibierst insain</u> isslaein g deleted.	An API failure was caused by the stream being deleted. Ensure that no other processes are trying to delete the stream while the stream is in use.
0x52000014	STATUS_SERVICE_CALL_I	N vavalid_ang ci <u>n</u> mentor were specified for the service call.	The backend returns this error when a service call argument is not valid or when the SDK encounters an error that it can't interpret.
0x52000015	STATUS_SERVICE_CALL_D	e Vhe<u>ed</u>avõde_wasund terr found.	Offensure that the device is not deleted while in use.
0x52000016	STATUS_SERVICE_CALL_D	E Vine<u>ede</u>vore_พลอทอธ ion provisioned.	EEDn <u>s</u> EURER Obsat the device has been provisioned.
0x52000017	STATUS_SERVICE_CALL_R	ESSIMECTE TRACTURE OF MODE E found returned from the service.	RHORerror occurs when the service can't locate the resource (for example, a stream). It might mean different things in different contexts, but the likely cause is the usage of APIs before the stream is created. Using the SDK ensures that the stream is created first.

Code	Message	Description	Recommended Action
0x52000018	STATUS_INVALID_AUTH_LE	invalid auth info length.	Refer to the current values that are specified in Producer SDK Limits (p. 63).
0x52000019	STATUS_CREATE_STREAM_C	Aine Gweatherstream API call failed.	Refer to the error string for more detailed information about why the operation failed.
0x5200002a	STATUS_GET_STREAMING_T	Okmen_CALL_FAILED GetStreamingToken call failed.	Refer to the error string for more detailed information about why the operation failed.
0x5200002b	STATUS_GET_STREAMING_F		Refer to the error string for intore detailed information about why the operation failed.
0x5200002c	STATUS_INVALID_URI_LEN	An invalid URI string length was returned from the GetStreamingEndpo:	Refer to the current maximum values that are specified in Producer SDK introducts (p. 63).
0x5200002d	STATUS_PUT_STREAM_CALI	_TinemenMedia API call failed.	Refer to the error string for more detailed information about why the operation failed.

Code	Message	Description	Recommended Action
0x5200002e	STATUS_STORE_OUT_OF_ME	EMORE Content store is out of memory.	The content store is shared between the streams and should have enough capacity to store the maximum durations for all the streams + ~20% (accounting for the defragmentation). It's important to not overflow the storage. Choose values for the maximum duration per stream that correspond to the cumulative storage size and the latency tolerances. It's better to drop the frames as they fall out of the content view window versus just being put (content store memory pressure). This is because dropping the frames triggers the stream pressure notification callbacks. Then the application can adjust the upstream media components (like the encoder) to thin the bitrate, drop frames, or act accordingly.
0x5200002f	STATUS_NO_MORE_DATA_AV	স্ মানেক্ষ্যন্তে data is available currently for a stream.	This is a potential valid result when the media pipeline produces more slowly than the networking thread consumes the frames to be sent to the service. Higher-level clients (for example, C++, Java, or Android) do not see this warning because it's handled internally.
0x52000030	STATUS_INVALID_TAG_VER	R\$ITVENTICE Tag structure version.	Specify the correct current version of the structure.
0x52000031	STATUS_SERVICE_CALL_UN	generic error was returned from the networking stack.	See the logs for more detailed information.
0x52000032	STATUS_SERVICE_CALL_RE	: Sesaor<u>e</u>in_usa e_erro	Returned from the service. For more information, see the Kinesis Video Streams API Reference.

Code	Message	Description	Recommended Action
0x52000033	STATUS_SERVICE_CALL_C	. Chinen<u>t</u> limit t_error	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000034	STATUS_SERVICE_CALL_DI	e vDrwiceLinn it t_ERROR	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000035	STATUS_SERVICE_CALL_S	r Strog<u>n</u>a intit _error	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000036	STATUS_SERVICE_CALL_R	E Sineresommenvæs o_ERF deleted or is being deleted.	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000037	STATUS_SERVICE_CALL_T	Minguse <u>r</u> vire oall timed out.	Calling a particular service API resulted in a timeout. Ensure that you have a valid network connection. The PIC will retry the operation automatically.
0x52000038	STATUS_STREAM_READY_CA	A Sit Beack readyLED notification.	This notification is sent from the PIC to the client indicating that the async stream has been created.
0x52000039	STATUS_DEVICE_TAGS_COU	J im<u>v</u>alion<u>ta</u>gsroe<u>re</u>ags_n specified.	UTHE tag count is not zero, but the tags are empty. Ensure that the tags are specified or the count is zero.
0x5200003a	STATUS_INVALID_STREAM		NSpecify the correct current version of the structure.
0x5200003b	STATUS_INVALID_TAG_NAM	M b<u>n</u>vækid tag name length.	Refer to the limits for the tag name that are specified in Producer SDK Limits (p. 63).
0x5200003c	STATUS_INVALID_TAG_VA	. ប់ត<u>េ</u>valich itag value length.	Refer to the limits for the tag value that are specified in Producer SDK Limits (p. 63).
0x5200003d	STATUS_TAG_STREAM_CAL	_Thewagresource API failed.	The TagResource API call failed. Check for a valid network connection. See the logs for more information about the failure.

Code	Message	Description	Recommended Action
0x5200003e	STATUS_INVALID_CUSTOM_	_DNAVERIId custom data calling PIC APIs.	Invalid custom data has been specified in a call to the PIC APIs. This can occur only in the clients that directly use PIC.
0x5200003f	STATUS_INVALID_CREATE_		The structure or its member afields are invalid (that is, the ARN is null or larger than what's specified in Producer SDK Limits (p. 63)).
0x52000040	STATUS_CLIENT_AUTH_CAI	I <u>Clieat aot</u> h failed.	The PIC failed to get proper auth information (that is, AccessKeyId or SecretAccessKey) after a number of retries. Check the authentication integration. The sample applications use environment variables to pass in credential information to the C++ Producer Library.
0x52000041	STATUS_GET_CLIENT_TOKE	ស្មើ ៤ដែល<u>ក</u>្នុ the ន៦ខយ rity token call failed.	This situation can occur for clients that use PIC directly. After a number of retries, the call fails with this error.
0x52000042	STATUS_CLIENT_PROVISIO	DIP <u>r</u> ovaisio <u>n</u> nag delor.	Provisioning is not implemented.
0x52000043	STATUS_CREATE_CLIENT_C	க் ங்<u>e</u>ர்க் மம் இது te the producer client.	A generic error returned by the PIC after a number of retries when the client creation fails.
0x52000044	STATUS_CLIENT_READY_CA	Alfailed ito get the producer client to a READY state.	Returned by the PIC state machine if the PIC fails to move to the READY state. See the logs for more information about the root cause.
0x52000045	STATUS_TAG_CLIENT_CALI	_Therragresource for the producer client failed.	The TagResource API call failed for the producer client. See the logs for more information about the root cause.

Code	Message	Description	Recommended Action
0x52000046	STATUS_INVALID_CREATE	Dewice:ProducenSE creation failed.	The higher-level SDKs (for example, C++ or Java) don't implement the device/producer creation API yet. Clients that use PIC directly can indicate a failure using the result notification.
0x52000047	STATUS_ACK_TIMESTAMP_I	NOThe Ithin Yestemn pu Dhibbou received ACK is not in the view.	This error occurs if the frame corresponding to the received ACK falls out of the content view window. Generally, this occurs if the ACK delivery is slow. It can be interpreted as a warning and an indication that the downlink is slow.
0x52000048	STATUS_INVALID_FRAGME	N Inwiki_DEaSMON tAck structure version.	Specify the correct current version of the FragmentAck structure.
0x52000049	STATUS_INVALID_TOKEN_	expiration.	The security token expiration should have an absolute timestamp in the future that is greater than the current timestamp, with a grace period. For the limits for the grace period, see the Producer SDK Limits (p. 63).
0x5200004a	STATUS_END_OF_STREAM	End of stream (EOS) indicator.	In the GetStreamData API call, indicates that the current upload handle session has ended. This occurs if the session ends or errors, or if the session token has expired and the session is being rotated.
0x5200004b	STATUS_DUPLICATE_STREAT	A lDuplite te stream name.	Multiple streams can't have the same stream name. Choose a unique name for the stream.
0x5200004c	STATUS_INVALID_RETENT	om <u>v</u> ætickrædention period.	An invalid retention period is specified in the StreamInfo structure. For information about the valid range of values for the retention period, see Producer SDK Limits (p. 63).

Code	Message	Description	Recommended Action
0x5200004d	STATUS_INVALID_ACK_KEY	Z _ISVEAKT FragmentAck.	Failed to parse the fragment ACK string. Invalid key start indicator. The fragment ACK string might be damaged. It can self-correct and this error can be treated as a warning.
0x5200004e	STATUS_INVALID_ACK_DUB	P lnvælif E_KEY_NAME FragmentAck.	Failed to parse the fragment ACK string. Multiple keys have the same name. The fragment ACK string might be damaged. It can self-correct and this error can be treated as a warning.
0x5200004f	STATUS_INVALID_ACK_INV	/ Amxalic VALUE_START FragmentAck.	Failed to parse the fragment ACK string because of an invalid key value start indicator. The fragment ACK string might be damaged. It can self-correct, and this error can be treated as a warning.
0x52000050	STATUS_INVALID_ACK_INV	/Amwai<u>ic</u>VALUE_END FragmentAck.	Failed to parse the fragment ACK string because of an invalid key value end indicator. The fragment ACK string might be damaged. It can self-correct and this error can be treated as a warning.
0x52000051	STATUS_INVALID_PARSED_	Anvalit PPE FragmentAck.	Failed to parse the fragment ACK string because an invalid ACK type was specified.
0x52000052	STATUS_STREAM_HAS_BEEN	ī <u>S\$neammenava</u> s stopped.	The stream has been stopped, but a frame is still being put into the stream.
0x52000053	STATUS_INVALID_STREAM_	_Mmsvækidcs_VERSION StreamMetrics structure version.	Specify the correct current version of the StreamMetrics structure.
0x52000054	STATUS_INVALID_CLIENT_	_Mmvxkitcs_VERSION ClientMetrics structure version.	Specify the correct current version of the ClientMetrics structure.
0x52000055	STATUS_INVALID_CLIENT_	READVCE INITIALIZATION failed to reach a READY state.	Failed to reach the READY state during the producer client initialization. See the logs for more information.

Code	Message	Description	Recommended Action
0x52000056	STATUS_STATE_MACHINE_	s trates: n alost a te ound machine error.	Not a publicly visible error.
0x52000057	STATUS_INVALID_FRAGME	Nh <u>watkl_ACE</u> type is specified in the FragmentAck structure.	The FragmentAck structure should contain ACK types defined in the public header.
0x52000058	STATUS_INVALID_STREAM	knizedralsstates machine transition error.	Not a publicly visible error.
0x52000059	STATUS_CLIENT_FREED_BI	Endowestermanbject was freed after the producer was freed.	There was an attempt to free a stream object after the producer object was freed. This can only occur in clients that directly use PIC.
0x5200005a	STATUS_ALLOCATION_SIZE	e <u>iistendalestouagaveireo</u> u	that the actual allocating that the actual allocation size from the content store is smaller than the size of the packaged frame/fragment.
0x5200005b	STATUS_VIEW_ITEM_SIZE	driemansk <u>toprage</u> eardoo	Altrostored size of the allocation in the content view is greater than the allocation size in the content store.
0x5200005c	STATUS_ACK_ERR_STREAM	SELECTION RESOCKER PROFESSION ACK.	An error that the ACK returned from the backend indicating a stream read/ parsing error. This generally occurs when the backend fails to retrieve the stream. Auto-restreaming can usually correct this error.

Code	Message	Description	Recommended Action
0x5200005d	STATUS_ACK_ERR_FRAGMEN	រ T<u>h</u>ឧាវាអល់ HED fragment size was reached.	The max fragment size in bytes is defined in Producer SDK Limits (p. 63). This error indicates that there are either very large frames, or there are no key frames to create manageable size fragments. Check the encoder settings and ensure that key frames are being produced properly. For streams that have very high density, configure the encoder to produce fragments at smaller durations to manage the maximum size.
0x5200005e	STATUS_ACK_ERR_FRAGMEN	TheuraxinownREACHED fragment duration was reached.	The max fragment duration is defined in Producer SDK Limits (p. 63). This error indicates that there are either very low frames per second or there are no key frames to create manageable duration fragments. Check the encoder settings and ensure that key frames are being produced properly at the regular intervals.
0x5200005f	STATUS_ACK_ERR_CONNECT		
		connection duration was reached.	enforces the max connection duration as specified in the Producer SDK Limits (p. 63). The Producer SDK automatically rotates the stream/token before the maximum is reached, and so clients using the SDK should not receive this error.
0x52000060	STATUS_ACK_ERR_FRAGMEN	T <u>imnewoodessære</u> Nood <u>t</u> MON monotonically increasing.	O団
0x52000061	STATUS_ACK_ERR_MULTI_1	ያ ሉ Audik i phext racks in the MKV.	The Producer SDK enforces single track streams, so clients using the SDK should not receive this error.

Code	Message	Description	Recommended Action
0x52000062	STATUS_ACK_ERR_INVALII	o <u>l</u> mwak <u>id</u> omkwa data.	The backend MKV parser encountered an error parsing the stream. Clients using the SDK might encounter this error if the stream is corrupted in the transition or if the buffer pressures force the SDK to drop tail frames that are partially transmitted. In the latter case, we recommend that you either reduce the FPS/resolution, increase the compression ratio, or (in the case of a "bursty" network) allow for larger content store and buffer duration to accommodate for the temporary pressures.
0x52000063	STATUS_ACK_ERR_INVALII		The service returns this error
		timestamp.	ACK if the producer clock has a large drift into the future. Higher-level SDKs (for example, Java or C++) use some version of the system clock to satisfy the current time callback from PIC. Ensure that the system clock is set properly. Clients using the PIC directly should ensure that their callback functions return the correct timestamp.
0x52000064	STATUS_ACK_ERR_STREAM_	<u>inoactiversit</u> vaam.	A call to a backend API was made while the stream was not in an "Active" state. This occurs when the client creates the stream and immediately continues to push frames into it. The SDK handles this scenario through the state machine and recovery mechanism.
0x52000065	STATUS_ACK_ERR_KMS_KEY	ZANGS底外SS_BECCESED denied error.	Returned when the account has no access to the specified key.
0x52000066	STATUS_ACK_ERR_KMS_KEY	Z_AWYS_AKBASERey is disabled	The specified key has been disabled.

Code	Message	Description	Recommended Action
0x52000067	STATUS_ACK_ERR_KMS_KE	Z <u>AWAS KIMAS kow</u> ERROR validation error.	Generic validation error. For more information, see the AWS Key Management Service API Reference.
0x52000068	STATUS_ACK_ERR_KMS_KEY	z <u>AWMS WAMS</u> k ey E unavailable.	The key is unavailable. For more information, see the AWS Key Management Service API Reference.
0x52000069	STATUS_ACK_ERR_KMS_KEY	z <u>Inwatiatuse</u> ons Avus KMS key.	The AWS KMS key is not configured to be used in this context. For more information, see the AWS Key Management Service API Reference.
0x5200006a	STATUS_ACK_ERR_KMS_KEY	z_ AtM9#XIMS i <u>n</u> 8/ AÅid E state.	For more information, see the AWS Key Management Service API Reference.
0x5200006b	STATUS_ACK_ERR_KMS_KEY	z <u>A</u> ฟฟร <u>์ Kirtós ห้อ</u> y not found.	The key was not found. For more information, see the AWS Key Management Service API Reference.
0x5200006c	STATUS_ACK_ERR_STREAM_	បាំងខេះវាខារកា has been or is being deleted.	The stream is being deleted by another application or through the AWS Management Console.
0x5200006d	STATUS_ACK_ERR_ACK_IN	Perror	Generic service internal error.
0x5200006e	STATUS_ACK_ERR_FRAGMEN	N F<u>r</u>agnommvarchine kor error.	Returned when the service fails to durably persist and index the fragment. Although it's rare, it can occur for various reasons. By default, the SDK retries sending the fragment.
0x5200006f	STATUS_ACK_ERR_UNKNOWN	<u>Lankao</u> maroror.	The service returned an unknown error.
0x52000070	STATUS_MISSING_ERR_ACE	K <u>Mis</u> sing ACK information.	The ACK parser completed parsing, but the FragmentAck information is missing.
0x52000071	STATUS_INVALID_ACK_SEC	ន រាការជ<u>ៅ</u>ជេរៈភ©K segment length.	An ACK segment string with an invalid length was specified to the ACK parser. For more information, see Producer SDK Limits (p. 63).

Code	Message	Description	Recommended Action
0x52000074	STATUS_MAX_FRAGMENT_ME	number of metadata items has been added to a fragment.	A Kinesis video stream can add up to 10 metadata items to a fragment, either by adding a nonpersistent item to a fragment, or by adding a persistent item to the metadata queue. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 12).
0x52000075	STATUS_ACK_ERR_FRAGMEN	metadata count, metadata count, metadata name length, or metadata value length) has been reached.	the number and size of metadata items. This error does not occur unless the limits in the Producer SDK code are changed. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 12).
0x52000076	STATUS_BLOCKING_PUT_IN	v inkotri di potredi e do je stredi a M_T	ERMINATED
0x52000077	STATUS_INVALID_METADAT	r A_heame tadata name is not valid.	The metadata name cannot start with the string "AWS". If this error occurs, the metadata item is not added to the fragment or metadata queue. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 12).
0x52000078	STATUS_END_OF_FRAGMENT	Threamd of WALID_STA fragment frame is in an invalid state.	The end of fragment should not be sent in a non-key-frame fragmented stream.
0x52000079	STATUS_TRACK_INFO_MISS	SIMBCK information is missing.	The track number must be greater than 0 and it must match the track id.
0x5200007a	STATUS_MAX_TRACK_COUNT	is exceeded.	You can have a maximum of 3 tracks per stream.
0x5200007b	STATUS_OFFLINE_MODE_WI	Thezofflonestreamings mode retention time is set to zero.	The offline streaming mode retention time should not be set to zero.
0x5200007c	STATUS_ACK_ERR_TRACK_N	of the error ACK is mismatched.	

Code	Message	Description	Recommended Action
0x5200007d	STATUS_ACK_ERR_FRAMES_	หัวสภยต<u>าเ</u>รอลฐาริคช ห track.	
0x5200007e	STATUS_ACK_ERR_MORE_TH	AMBAMILOW BIJOURECKS_ number of tracks is exceeded.	FOUND
0x5200007f	STATUS_UPLOAD_HANDLE_A	ኔ ደሲঘመደው handle is aborted.	
0x52000080	STATUS_INVALID_CERT_PA	ুক্রা মেরেশ র্টাcate path length.	
0x52000081	STATUS_DUPLICATE_TRACE	к <u>Duplicate</u> ntrack ID found.	

Error and Status Codes Returned by the Duration Library

The following table contains error and status information that is returned by methods in the Duration library.

Code	Message
0xfffffffffffff	INVALID_DURATION_VALUE

Error and Status Codes Returned by the Common Library

The following table contains error and status information that is returned by methods in the Common library.

Note

These error and status information codes are common to many APIs.

Code	Message	Description
0x00000001	STATUS_NULL_ARG	NULL was passed for a mandatory argument.
0x00000002	STATUS_INVALID_ARG	An invalid value was specified for an argument.
0x00000003	STATUS_INVALID_ARG_LEN	An invalid argument length was specified.
0x00000004	STATUS_NOT_ENOUGH_MEMORY	Could not allocate enough memory.
0x00000005	STATUS_BUFFER_TOO_SMALL	The specified buffer size is too small.
0x00000006	STATUS_UNEXPECTED_EOF	An unexpected end of file was reached.
0x00000007	STATUS_FORMAT_ERROR	An invalid format was encountered.

Code	Message	Description
0x0000008	STATUS_INVALID_HANDLE_ERRO	สทงalid handle value.
0x0000009	STATUS_OPEN_FILE_FAILED	Failed to open a file.
0x0000000a	STATUS_READ_FILE_FAILED	Failed to read from a file.
0x000000b	STATUS_WRITE_TO_FILE_FAILE	IFailed to write to a file.
0х0000000с	STATUS_INTERNAL_ERROR	An internal error that normally doesn't occur and might indicate an SDK or service API bug.
0x000000d	STATUS_INVALID_OPERATION	There was an invalid operation, or the operation is not permitted.
0x0000000e	STATUS_NOT_IMPLEMENTED	The feature is not implemented.
0x000000f	STATUS_OPERATION_TIMED_OUT	The operation timed out.
0x00000010	STATUS_NOT_FOUND	A required resource was not found.

Error and Status Codes Returned by the Heap Library

The following table contains error and status information that is returned by methods in the ${\tt Heap}$ library.

Code	Message	Description
0x01000001	STATUS_HEAP_FLAGS_ERROR	An invalid combination of flags was specified.
0x01000002	STATUS_HEAP_NOT_INITIALIZE	An operation was attempted before the heap was initialized.
0x01000003	STATUS_HEAP_CORRUPTED	The heap was corrupted or the guard band (in debug mode) was overwritten. A buffer overflow in the client code might lead to a heap corruption.
0x01000004	STATUS_HEAP_VRAM_LIB_MISSI	Marche VRAM (video RAM) user or kernel mode library cannot be loaded or is missing. Check if the underlying platform supports VRAM allocations.
0x01000005	STATUS_HEAP_VRAM_LIB_REOPE	Failed to open the VRAM library.
0x01000006	STATUS_HEAP_VRAM_INIT_FUNC	<u>F</u> ភ្ជា វាសដល់ load the INIT function export.
0x01000007	STATUS_HEAP_VRAM_ALLOC_FUN	r <u>Fa</u> d ⊭ d it o load the ALLOC function export.

Code	Message	Description
0x01000008	STATUS_HEAP_VRAM_FREE_FUNC	<u>F</u> នា វារដថា load the FREE function export.
0x01000009	STATUS_HEAP_VRAM_LOCK_FUNC	<u>P</u> នារ៉ាមដល់ load the LOCK function export.
0x0100000a	STATUS_HEAP_VRAM_UNLOCK_FU	ห <u>ลilยชหอดอad the UNLOCK</u> function export.
0x0100000b	STATUS_HEAP_VRAM_UNINIT_FU	ห <u>ลilยชหองก</u> ad the บทเทเซ function export.
0x0100000c	STATUS_HEAP_VRAM_GETMAX_FU	ห <u>ลิเ</u> โ ลฟหอดอ ad the GETMAX function export.
0x0100000d	STATUS_HEAP_DIRECT_MEM_INI	Failed to initialize the main heap pool in the hybrid heap.
0x0100000e	STATUS_HEAP_VRAM_INIT_FAIL	理he VRAM dynamic initialization failed.
0x0100000f	STATUS_HEAP_LIBRARY_FREE_F	'Æ ቯiled to de-allocate and free the VRAM library.
0x01000010	STATUS_HEAP_VRAM_ALLOC_FAI	TITTE VRAM allocation failed.
0x01000011	STATUS_HEAP_VRAM_FREE_FAIL	ன்ற VRAM free failed.
0x01000012	STATUS_HEAP_VRAM_MAP_FAILE	The VRAM map failed.
0x01000013	STATUS_HEAP_VRAM_UNMAP_FAI	IIItne VRAM unmap failed.
0x01000014	STATUS_HEAP_VRAM_UNINIT_FA	IIII TED VRAM deinitialization failed.

Error and Status Codes Returned by the MKVGen Library

The following table contains error and status information that is returned by methods in the MKVGen library.

Code	Message	Description / Recommended Action
0x32000001	STATUS_MKV_INVALID_FRAME_D	Admalid members of the Frame data structure. Ensure that the duration, size, and frame data are valid and are within the limits specified in Producer SDK Limits (p. 63).
0x32000002	STATUS_MKV_INVALID_FRAME_T	IMPAIDAMAME timestamp. The calculated PTS (presentation timestamp) and DTS (decoding timestamp) are greater or equal to the timestamp of the start frame of the fragment. This is an indication of a

Code	Message	Description / Recommended Action
		potential media pipeline restart or an encoder stability issue. For troubleshooting information, see Error: "Failed to submit frame to Kinesis Video client" (p. 156)
0x32000003	STATUS_MKV_INVALID_CLUSTER	ADURIVATION ragment duration was specified. For more information, see Producer SDK Limits (p. 63).
0x32000004	STATUS_MKV_INVALID_CONTENT	string length. For more information, see Producer SDK Limits (p. 63).
0x32000005	STATUS_MKV_NUMBER_TOO_BIG	There was an attempt to encode a number that's too large to be represented in EBML (Extensible Binary Meta Language) format. This should not be exposed to the SDK clients.
0x32000006	STATUS_MKV_INVALID_CODEC_1	D <u>nvalid</u> បាលdec ID string length. For more information, see Producer SDK Limits (p. 63).
0x32000007	STATUS_MKV_INVALID_TRACK_N	NAMWalteMark name string length. For more information, see Producer SDK Limits (p. 63).
0x32000008	STATUS_MKV_INVALID_CODEC_E	data length. For more information, see Producer SDK Limits (p. 63).
0x32000009	STATUS_MKV_CODEC_PRIVATE_N	Nulte codec private data (CPD) is NULL, whereas the CPD size is greater than 0.
0x3200000a	STATUS_MKV_INVALID_TIMECOI	Bingalid timecode scale value. For more information, see Producer SDK Limits (p. 63).
0x3200000b	STATUS_MKV_MAX_FRAME_TIMEC	colline frame timecode is greater than the maximum. For more information, see Producer SDK Limits (p. 63).

Code	Message	Description / Recommended Action	
0x3200000c	STATUS_MKV_LARGE_	FRAME_TIMECTED TEACH STATE AND THE STATE AND	
0x3200000d	STATUS_MKV_INVALI	D_ANNEXB_NALIDVANGEARMS_BATART code was encountered. For example, the Annex-B adaptation flag was specified and the code encounters an invalid start sequence of more than three zeroes. A valid Annex-B format should have an "emulation prevention" sequence to escape a sequence of three or more zeroes in the bytestream. For more information, see the MPEG specification. For information about this error on Android, see STATUS_MKV_INVALID_ANNEXB_NALU_ (0x3200000d) error on Android (p. 159).	
0x3200000e	STATUS_MKV_INVALI	STATUS_MKV_INVALID_AVCC_NATIONATIONATIONATIONATIONATIONATIONATIO	
0x3200000f	STATUS_MKV_BOTH_A	STATUS_MKV_BOTH_ANNEXB_AND_BothcadsptingFAVOC and Annex-B NALs were specified. Specify either one, or specify none.	
0x32000010	STATUS_MKV_INVALI	D_ANNEXB_NAvalid Andero-B format of CPD when the adapting Annex-B flag is specified. Ensure that the CPD is in valid Annex-B format. If it is not, then remove the CPD Annex-B adaptation flag.	

Code	Message	Description / Recommended Action
0x32000011	STATUS_MKV_PTS_DTS_ARE_NOT	enforces the PTS (presentation timestamp) and DTS (decoding timestamp) to be the same for the fragment start frames. These are the key frames that start the fragment.
0x32000012	STATUS_MKV_INVALID_H264_H2	ৰি <u>ন্ধ।</u> eelায়o parse H264/H265 codec private data.
0x32000013	STATUS_MKV_INVALID_H264_H2	ச <u>ெந்</u> திக் <u>o</u> vex breac t the width from the codec private data.
0x32000014	STATUS_MKV_INVALID_H264_H2	ச <u>ெப்</u> பை <u>க்க</u> ப்போthe height from codec private data.
0x32000015	STATUS_MKV_INVALID_H264_H2	devalids <u>H</u> 1265 SPS NALu.
0x32000016	STATUS_MKV_INVALID_BIH_CPD	Invalid bitmap info header format in the codec private data.
0x32000017	STATUS_MKV_INVALID_HEVC_NA	រ ាប<u>្</u>រវេល្បអា ថ្ងៃh Efficiency Video Coding (HEVC) Network Abstraction Layer units (NALU) count.
0x32000018	STATUS_MKV_INVALID_HEVC_FC	मामञ्ज्ञांd HEVC format.
0x32000019	STATUS_MKV_HEVC_SPS_NALU_M	্রাপ্রান্তর্জাত্ত্ব HEVC NALUs in the Sequence Parameter Set (SPS).
0x3200001a	STATUS_MKV_INVALID_HEVC_SF	s <u>n</u> walidu <u>H</u> £ប©ESPS NALU size.
0x3200001b	STATUS_MKV_INVALID_HEVC_SF	singalkonaroanamatotoc.
0x3200001c	STATUS_MKV_INVALID_HEVC_SE	dnwalងtក្សស្ត្រ reserved SPS.
0x3200001d	STATUS_MKV_MIN_ANNEX_B_CPD	Mirabum Annex-b codec private beta value size. For H264, this value must be equal to or greater that 11. For H265, this value must be equal to or greater than 15.
0x3200001e	STATUS_MKV_ANNEXB_CPD_MISS	រ ាមចែ<u>s</u>ina្យលេន lec private data in Annex-B NALUs.
0x3200001f	STATUS_MKV_INVALID_ANNEXB_	d ពប <u>al</u> it ង cous ec private beta in Annex-B NALUs.
0x32000020	STATUS_MKV_INVALID_TAG_NAM	ម <u>េក្</u> េតស្រែដ អ្វ name length. Valid value is greater than zero and less than 128.

Code	Message	Description / Recommended Action
0x32000021	STATUS_MKV_INVALID_TAG_VAI	ឋ ន_alixht អូប្រាប់ length. valid value is greater than zero and less than 256.
0x32000022	STATUS_MKV_INVALID_GENERAT	'd R<u>v</u>atidAឲ្យខ ្មា ញឩ៤៤ r state tags.
0x32000023	STATUS_MKV_INVALID_AAC_CPD	lswith.AAG ordeoweivate datex sampling frequency index.
0x32000024	STATUS_MKV_INVALID_AAC_CPD	<u>lawalithAAC</u> cconter private data channel configuration.
0x32000025	STATUS_MKV_INVALID_AAC_CPD	Invalid AAC codec private data.
0x32000026	STATUS_MKV_TRACK_INFO_NOT_	_ คัดยฝ อinformation not found.
0x32000027	STATUS_MKV_INVALID_SEGMENT	_Irvalid segment UUID.
0x32000028	STATUS_MKV_INVALID_TRACK_U	¹¹o valid track UID.

Error and Status Codes Returned by the Trace Library

The following table contains error and status information that is returned by methods in the Trace library.

Code	Message
0x10100001	STATUS_MIN_PROFILER_BUFFER

Error and Status Codes Returned by the Utils Library

The following table contains error and status information that is returned by methods in the Utils library.

Code	Message
0x4000001	STATUS_INVALID_BASE64_ENCODE
0x4000002	STATUS_INVALID_BASE
0x4000003	STATUS_INVALID_DIGIT
0x4000004	STATUS_INT_OVERFLOW
0x4000005	STATUS_EMPTY_STRING
0x4000006	STATUS_DIRECTORY_OPEN_FAILED
0x4000007	STATUS_PATH_TOO_LONG
0x4000008	STATUS_UNKNOWN_DIR_ENTRY_TYPE
0x4000009	STATUS_REMOVE_DIRECTORY_FAILED

Code	Message
0x4000000a	STATUS_REMOVE_FILE_FAILED
0x400000b	STATUS_REMOVE_LINK_FAILED
0x400000c	STATUS_DIRECTORY_ACCESS_DENIED
0x400000d	STATUS_DIRECTORY_MISSING_PATH
0x4000000e	STATUS_DIRECTORY_ENTRY_STAT_ERROR

Error and Status Codes Returned by the View Library

The following table contains error and status information that is returned by methods in the View library.

Code	Message	Description
0x30000001	STATUS_MIN_CONTENT_VI	EW_ITEMS invalid content view item count was specified. For more information, see Producer SDK Limits (p. 63).
0x30000002	STATUS_INVALID_CONTEN	T_VIEWAndimatid (200 ntent view duration was specified. For more information, see Producer SDK Limits (p. 63).
0x30000003	STATUS_CONTENT_VIEW_N	O_MOR EA<u>rt</u> artis on the head position.
0x30000004	STATUS_CONTENT_VIEW_I	NVALI D<u>A</u>rī invaki d index is specified.
0x30000005	STATUS_CONTENT_VIEW_I	timestamp or a timestamp overlap. The frame decoding timestamp should be greater or equal to the previous frame timestamp, plus the previous frame duration: `DTS(n) >= DTS(n-1) + Duration(n-1)`. This error often indicates an "unstable" encoder. The encoder produces a burst of encoded frames, and their timestamps are smaller than the intra-frame durations. Or the stream is configured to use SDK timestamps, and the frames are sent faster than the frame durations. To help with some "jitter" in the encoder, specify a smaller frame duration in the StreamInfo.StreamCaps structure. For example, if the

Amazon Kinesis Video Streams Developer Guide NAL Adaptation Flags

Code	Message	Description
		stream is 25FPS, each frame's duration is 40 ms. However, to handle the encoder jitter, we recommend that you use half of that frame duration (20 ms). Some streams require more precise control over the timing for error detection.
0x30000006	STATUS_INVALID_CONTENT_VIEW	/_AJENGTHd content view item data length was specified.

Network Abstraction Layer (NAL) Adaptation Flag Reference

This section contains information about available flags for the StreamInfo.NalAdaptationFlags enumeration.

The elementary stream in an application can be in either **Annex-B** or **AVCC** format:

- The **Annex-B** format delimits NALUs (Network Abstraction Layer units) with two bytes of zeroes, followed by one or three bytes of zeroes, followed by the number 1 (called a **start code**, for example, 0000001).
- The AVCC format also wraps NALUs, but each NALU is preceded by a value that indicates the size of the NALU (usually four bytes).

Many encoders produce the Annex-B bitstream format. Some higher-level bitstream processors (such as a playback engine or the Media Source Extensions (MSE) player in the AWS Management Console) use the AVCC format for their frames.

The codec private data (CPD), which is SPS/PPS (Sequence Parameter Set/Picture Parameter Set) for the H.264 codec, can also be in Annex-B or AVCC format. However, for the CPD, the formats are different from those described previously.

The flags tell the SDK to adapt the NALUs to AVCC or Annex-B for frame data and CPD as follows:

Flag	Adaptation	
NAL_ADAPTATION_FLAG_NONE	No adaptation	
NAL_ADAPTATION_ANNEXB_NALS	Adapt Annex-B NALUs to AVCC NALUs	
NAL_ADAPTATION_AVCC_NALS	Adapt AVCC NALUs to Annex-B NALUs	
NAL_ADAPTATION_ANNEXB_CPD_	Madapt Annex-B NALUs for the codec private data to AVCC format NALUs	
NAL_ADAPTATION_ANNEXB_CPD_	AND THE THE THE LINE IN THE CODE CODE CODE CODE CODE CODE CODE COD	

For more information about NALU types, see **Section 1.3: Network Abstraction Layer Unit Types** in RFC 3984.

Producer SDK Structures

This section includes information about structures that you can use to provide data to the Kinesis Video Streams Producer object.

Topics

- DeviceInfo/DefaultDeviceInfoProvider (p. 88)
- StorageInfo (p. 88)

DeviceInfo/DefaultDeviceInfoProvider

The **DeviceInfo** and **DefaultDeviceInfoProvider** objects control the behavior of the Kinesis Video Streams Producer object.

Member Fields

- **version**: An integer value used to ensure that the correct version of the structure is used with the current version of the code base. The current version is specified using the DEVICE_INFO_CURRENT_VERSION macro.
- name: The human-readable name for the device.
- tagCount/tags: Not currently used.
- streamCount: The maximum number of streams that the device can handle. This pre-allocates the storage for pointers to the stream objects initially, but the actual stream objects are created later. The default is 16 streams, but you can change this number in the DefaultDeviceInfoProvider.cpp file.
- **storageInfo**: An object that describes the main storage configuration. For more information, see StorageInfo (p. 88).

StorageInfo

Specifies the configuration of the main storage for Kinesis Video Streams.

The default implementation is based on a low-fragmentation fast heap implementation, which is optimized for streaming. It uses the MEMALLOC allocator, which can be overwritten on a given platform. Some platforms have virtual memory allocation without backing the allocation with physical pages. As the memory is used, the virtual pages are backed by the physical pages. This results in low-memory pressure on the overall system when storage is underused.

Calculate the default storage size based on the following formula. The DefragmentationFactor should be set to 1.2 (20 percent).

```
Size = NumberOfStreams * AverageFrameSize * FramesPerSecond * BufferDurationInSeconds * DefragmentationFactor
```

In the following example, a device has audio and video streams. The audio stream has 512 samples per second, with an average sample of 100 bytes. The video stream has 25 frames per second, with an average of 10,000 bytes. Each stream has 3 minutes of buffer duration.

```
Size = (512 * 100 * (3 * 60) + 25 * 10000 * (3 * 60)) * 1.2 = (9216000 + 45000000) * 1.2 = 65059200 = <math>\sim 66MB.
```

If the device has more available memory, it is recommended that you add more memory to storage to avoid severe fragmentation.

Ensure that the storage size is adequate to accommodate the full buffers for all streams at high encoding complexity (when the frame size is larger due to high motion) or when the bandwidth is low. If the producer hits memory pressure, it emits storage overflow pressure callbacks (StorageOverflowPressureFunc). However, when no memory is available in the content store, it drops the frame that's being pushed into Kinesis Video Streams with an error (STATUS_STORE_OUT_OF_MEMORY = 0x5200002e). For more information, see Error and Status Codes Returned by the Client Library (p. 65). This can also happen if the application acknowledgements (ACKs) are not available, or the persisted ACKs are delayed. In this case, the buffers fill to the "buffer duration" capacity before the older frames start dropping out.

Member Fields

- version: An integer value used to ensure that the correct version of the structure is used with the current version of the code base.
- storageType: A DEVICE_STORAGE_TYPE enumeration that specifies the underlying backing/implementation of the storage. Currently the only supported value is DEVICE_STORAGE_TYPE_IN_MEM. A future implementation will support DEVICE_STORAGE_TYPE_HYBRID_FILE, indicating that storage falls back to the file-backed content store
- storageSize: The storage size in bytes to preallocate. The minimum allocation is 10 MB, and the maximum allocation is 10 GB. (This will change with the future implementation of the file-backed content store.)
- spillRatio: An integer value that represents the percentage of the storage to be allocated from the direct memory storage type (RAM), as opposed to the secondary overflow storage (file storage). Not currently used.
- rootDirectory: The path to the directory where the file-backed content store is located. Not currently used

Kinesis Video Stream Structures

You can use the following structures to provide data to an instance of a Kinesis video stream.

Topics

- StreamDefinition/ StreamInfo (p. 89)
- ClientMetrics (p. 99)
- StreamMetrics (p. 100)

StreamDefinition/StreamInfo

The StreamDefinition object in the C++ layer wraps the StreamInfo object in the platform-independent code, and provides some default values in the constructor.

Member Fields

Field	Data Type	Description	Default Value
stream_name	string	An optional stream name. For more information about the length of the stream	If no name is specified, a name is generated randomly.

Field	Data Type	Description	Default Value
		name, see Producer SDK Limits (p. 63) . Each stream should have a unique name.	
retention_period	<pre>duration<uint64_t, ratio<3600="">></uint64_t,></pre>	The retention period for the stream, in seconds. Specifying o indicates no retention.	3600 (One hour)
tags	<pre>const map<string, string="">*</string,></pre>	A map of key-value pairs that contain user information. If the stream already has a set of tags, the new tags are appended to the existing set of tags.	No tags
kms_key_id	string	The AWS KMS key ID to be used for encrypting the stream. For more information, see Using Server-Side Encryption with Kinesis Video Streams (p. 18).	The default KMS key (aws/kinesis- video.)
streaming_type	STREAMING_TYPE enumeration	The only supported value is STREAMING_TYPE_REAL	TIME.
content_type	string	The content format of the stream. The Kinesis Video Streams console can play back content in the video/h264 format.	video/h264
max_latency	<pre>duration<uint64_t, milli=""></uint64_t,></pre>	The maximum latency in milliseconds for the stream. The stream latency pressure callback (if specified) is called when the buffer duration exceeds this amount of time. Specifying 0 indicates that no stream latency pressure callback will be called.	milliseconds::zero(

Field	Data Type	Description	Default Value
fragment_duration	duration <uint64_t></uint64_t>	The fragment duration that you want, in seconds. This value is used in combination with the key_frame_fragmenta value. If this value is false, Kinesis Video Streams generates fragments on a key frame after this duration elapses. For example, an Advanced Audio Coding (AAC) audio stream has each frame as a key frame. Specifying key_frame_fragmenta = false causes fragmentation to happen on a key frame after this duration expires, resulting in 2-second fragments.	

Field	Data Type	Description	Default Value
timecode_scale	<pre>duration<uint64_t, milli=""></uint64_t,></pre>	The MKV timecode scale in milliseconds, which specifies the granularity of the timecodes for the frames within the MKV cluster. The MKV frame timecode is always relative to the start of the cluster. MKV uses a signed 16-bit value (0-32767) to represent the timecode within the cluster (fragment). Therefore, you should ensure that the frame timecode can be represented with the given timecode scale. The default timecode scale value of 1 ms ensures that the largest frame that can be represented is 32767 ms ~= 32 seconds. This is over the maximum fragment duration that is specified in Kinesis Video Streams Limits (p. 148), which is 10 seconds.	1
key_frame_fragmentation	pibool	Whether to produce fragments on a key frame. If true, the SDK produces a start of the fragment every time there is a key frame. If false, Kinesis Video Streams waits for at least fragment_duration and produces a new fragment on the key frame following it.	true

Field	Data Type	Description	Default Value
frame_timecodes	bool	Whether to use frame timecodes or generate timestamps using the current time callback. Many encoders don't produce timestamps with the frames. So specifying false for this parameter ensures that the frames are timestamped as they are put into Kinesis Video Streams.	true
absolute_fragment_time	eshool	Kinesis Video Streams uses MKV as its underlying packaging mechanism. The MKV specification is strict about frame timecodes being relative to the beginning of the cluster (fragment). However, the cluster timecodes can be either absolute or relative to the starting time for the stream. If the timestamps are relative, the PutMedia service API call uses the optional stream start timestamp and adjust the cluster timestamps. The service always stores the fragments with their absolute timestamps.	true
fragment_acks	bool	Whether to receive application level fragment ACKs (acknowledgements) or not.	true, meaning that the SDK will receive the ACKs and act accordingly.
restart_on_error	bool	Whether to restart on specific errors.	true, meaning that the SDK tries to restart the streaming if any errors occur.

Field	Data Type	Description	Default Value
recalculate_metrics	bool	Whether to recalculate the metrics. Each call to retrieve the metrics can recalculate those to get the latest "running" value, which might create a small CPU impact. You might need to set this to false on extremely low-power/footprint devices to spare the CPU cycles. Otherwise, it's not advised to use false for this value.	true

Field	Data Type	Description	Default Value
nal_adaptation_flags	uint32_t	Specifies the Network Abstraction Layer unit (NALU) adaptation flags. If the bitstream is H.264 encoded, it can then be processed as raw or packaged in NALUs. Those are either in the Annex-B or AVCC format. Most of the elementary stream producers/ consumers (read encoders/decoders) use the Annex-B format because it has some advantages, such as error recovery. Higherlevel systems use the AVCC format, which is the default format for MPEG, HLS, DASH, and so on. The console playback uses the browser's MSE (media source extensions) to decode and play back the stream that uses the AVCC format. For H.264 (and for M-JPEG and H.265), the SDK provides adaptation capabilities. Many elementary streams are in the following format. In this example, Ab is the Annex-B start code (001 or 0001). Ab(Sps)Ab(Pps)Ab(I-frame)Ab(P/B-frame)Ab(P/B-frame)Ab(P/B-frame)Ab(P/B-frame) Ab(P/B-frame) Ab(Sps)Ab(Pps)Ab(I-frame)Ab(P/B-frame) Ab(Sps)Ab(Pps)Ab(I-frame)Ab(P/B-frame)	The default is to adapt Annex-B format to AVCC format for both the frame data and for the codec private data.

Field	Data Type	Description	Default Value
		be adapted to the AVCC format. Unless the media pipeline gives the CPD separately, the application can extract the CPD from the frame. It can do this by looking for the first IDR frame (which should contain the SPS/PPS), extract the two NALUs (which are Ab(Sps)Ab(Pps)), and set it in the CPD in StreamDefinition. For more information, see NAL Adaptation Flags (p. 87).	
frame_rate	uint32_t	The expected frame rate. This value is used to better calculate buffering needs.	25
avg_bandwidth_bps	uint32_t	The expected average bandwidth for the stream. This value is used to better calculate buffering needs.	4 * 1024 * 1024

Field	Data Type	Description	Default Value
buffer_duration	duration <uint64_t></uint64_t>	The stream buffer duration, in seconds. The SDK keeps the frames in the content store for up to the buffer_duration, after which the older frames are dropped as the window moves forward. If the frame that is being dropped has not been sent to the backend, the dropped frame callback is called. If the current buffer duration is greater than max_latency, then the stream latency pressure callback is called. The buffer is trimmed to the next fragment start when the fragment persisted ACK is received. This indicates that the content has been durably persisted in the cloud, so storing the content on the local device is no longer needed.	120

Field	Data Type	Description	Default Value
replay_duration	duration <uint64_t></uint64_t>	The duration to roll the current reader backward to replay during an error if restarting is enabled, in seconds. The rollback stops at the buffer start (in case it has just started streaming or the persisted ACK has come along). The rollback tries to land on a key frame that indicates a fragment start. If the error that is causing the restart is not indicative of a dead host (that is, the host is still alive and contains the frame data in its internal buffers), the rollback stops at the last received ACK frame. It then rolls forward to the next key frame, because the entire fragment is already stored in the host memory.	40
connection_staleness	duration <uint64_t></uint64_t>	The time, in seconds, after which the stream staleness callback is called if the SDK does not receive the buffering ACK. It indicates that the frames are being sent from the device, but the backend is not acknowledging them. This condition indicates a severed connection at the intermediate hop or at the load balancer.	30
codec_id	string	The codec ID for the MKV track.	V_MPEG4/ISO/AVC
track_name	string	The MKV track name.	kinesis_video

Field	Data Type	Description	Default Value
codecPrivateData	unsigned char*	The codec private data (CPD) buffer. If the media pipeline has the information about the CPD before the stream starts, it can be set in StreamDefinition.co The bits are copied, and the buffer can be reused or freed after the call to create the stream. However, if the data is not available when the stream is created, it can be set in one of the overloads of the KinesisVideoStream. function.	
codecPrivateDataSize	uint32_t	The codec private data buffer size.	0

ClientMetrics

The **ClientMetrics** object is filled by calling getKinesisVideoMetrics.

Member Fields

Field	Data Type	Description	
version	UINT32	The version of the structure, defined in the CLIENT_METRICS_CURRENT_VERS macro.	
contentStoreSize	UINT64	The overall content store size in bytes. This is the value specified in DeviceInfo.StorageInfo.stor	
ontentStoreAvailableSize	UINT64	Currently available storage size in bytes.	
contentStoreAllocatedSize	UINT64	Currently allocated size. The allocated plus the available sizes should be slightly smaller than the overall storage size, due to the internal bookkeeping and the implementation of the content store.	
totalContentViewsSize	UINT64	The size of the memory allocated for all content views	

Field	Data Type	Description
		for all streams. This is not counted against the storage size. This memory is allocated using the MEMALLOC macro, which can be overwritten to provide a custom allocator.
totalFrameRate	UINT64	The total observed frame rate across all the streams.
totalTransferRate	UINT64	The total observed stream rate in bytes per second across all the streams.

StreamMetrics

The **StreamMetrics** object is filled by calling getKinesisVideoMetrics.

Member Fields

Field	Data Type	Description
version	UINT32	The version of the structure, defined in the STREAM_METRICS_CURRENT_VERS macro.
currentViewDuration	UINT64	The duration of the accumulated frames. In the fast networking case, this duration is either 0 or the frame duration (as the frame is being transmitted). If the duration becomes longer than the max_latency specified in the StreamDefinition, the stream latency callback is called if it is specified. The duration is specified in 100 ns units, which is the default time unit for the PIC layer.
overallViewDuration	UINT64	The overall view duration. If the stream is configured with no ACKs or persistence, this value grows as the frames are put into the Kinesis video stream and becomes equal to the buffer_duration in the StreamDefinition. When ACKs are enabled and the persisted ACK is received, the buffer is trimmed to the next key frame, because the ACK timestamp indicates

Amazon Kinesis Video Streams Developer Guide Callbacks

Field	Data Type	Description
		the beginning of the entire fragment. The duration is specified in 100-ns units, which is the default time unit for the PIC layer.
currentViewSize	UINT64	The size in bytes of the current buffer.
overallViewSize	UINT64	The overall view size in bytes.
currentFrameRate	UINT64	The observed frame rate for the current stream.
currentTransferRate	UINT64	The observed transfer rate in bytes per second for the current stream.


Producer SDK Callbacks

The classes and methods in the Amazon Kinesis Video Streams Producer SDK do not maintain their own processes. Instead, they use the incoming function calls and events to schedule callbacks to communicate with the application.

There are two callback patterns that the application can use to interact with the SDK:

- CallbackProvider: This object exposes every callback from the platform-independent code (PIC) component to the application. This pattern allows full functionality, but it also means that the implementation must handle all of the public API methods and signatures in the C++ layer.
- StreamCallbackProvider (p. 102) and ClientCallbackProvider (p. 102): These objects expose the stream-specific and client-specific callbacks, and the C++ layer of the SDK exposes the rest of the callbacks. This is the preferred callback pattern for interacting with the Producer SDK.

The following diagram illustrates the object model of the callback objects:



In the preceding diagram, DefaultCallbackProvider derives from CallbackProvider (which exposes all of the callbacks in the PIC) and contains StreamCallbackProvider and ClientCallbackProvider.

This topic contains the following sections:

- ClientCallbackProvider (p. 102)
- StreamCallbackProvider (p. 102)

- ClientCallbacks Structure (p. 102)
- Callback Implementations to Retry Streaming (p. 105)

ClientCallbackProvider

The ClientCallbackProvider object exposes client-level callback functions. The details of the functions are described in the ClientCallbacks (p. 102) section.

Callback methods:

- getClientReadyCallback: Reports a ready state for the client.
- getStorageOverflowPressureCallback: Reports storage overflow or
 pressure. This callback is called when the storage utilization drops below the
 STORAGE_PRESSURE_NOTIFICATION_THRESHOLD value, which is 5 percent of the overall storage
 size. For more information, see StorageInfo (p. 88).

For the source code for ClientCallbackProvider, see Include.h.

StreamCallbackProvider

The StreamCallbackProvider object exposes stream-level callback functions.

Callback methods:

- getDroppedFragmentReportCallback: Reports a dropped fragment.
- getDroppedFrameReportCallback: Reports a dropped frame.
- getFragmentAckReceivedCallback: Reports that a fragment ACK is received for the stream.
- getStreamClosedCallback: Reports a stream closed condition.
- getStreamConnectionStaleCallback: Reports a stale connection condition. In this condition, the producer is sending data to the service but is not receiving acknowledgements.
- getStreamDataAvailableCallback: Reports that data is available in the stream.
- getStreamErrorReportCallback: Reports a stream error condition.
- getStreamLatencyPressureCallback: Reports a stream latency condition, which is when the accumulated buffer size is larger than the max_latency value. For more information, see StreamDefinition/ StreamInfo (p. 89).
- getStreamReadyCallback: Reports a stream ready condition.
- getStreamUnderflowReportCallback: Reports a stream underflow condition. This function is not currently used and is reserved for future use.

For the source code for StreamCallbackProvider, see StreamCallbackProvider.h.

ClientCallbacks Structure

The ClientCallbacks structure contains the callback function entry points that the PIC calls when specific events occur. The structure also contains version information in the CALLBACKS_CURRENT_VERSION field, and a customData field for user-defined data that is returned with the individual callback functions.

The client application can use a this pointer for the custom_data field to map member functions to the static ClientCallback functions at runtime, as shown in the following code example:

Amazon Kinesis Video Streams Developer Guide Callbacks

```
STATUS TestStreamCallbackProvider::streamClosedHandler(UINT64 custom_data, STREAM_HANDLE
stream_handle, UINT64 stream_upload_handle) {
   LOG_INFO("Reporting stream stopped.");

TestStreamCallbackProvider* streamCallbackProvider =
   reinterpret_cast<TestStreamCallbackProvider*> (custom_data);
streamCallbackProvider->streamClosedHandler(...);
```

Events

Function	Description	Туре
CreateDeviceFunc	Not currently implemented on the backend. This call fails when called from Java or C++. Other clients perform platformspecific initialization.	Backend API
CreateStreamFunc	Called when the stream is created.	Backend API
DescribeStreamFunc	Called when DescribeStream is called.	Backend API
GetStreamingEndpointFunc	Called when GetStreamingEndpoint is called.	Backend API
GetStreamingTokenFunc	Called when GetStreamingToken is called.	Backend API
PutStreamFunc	Called when PutStream is called.	Backend API
TagResourceFunc	Called when TagResource is called.	Backend API
CreateMutexFunc	Creates a synchronization mutex.	Synchronization
FreeMutexFunc	Frees the mutex.	Synchronization
LockMutexFunc	Locks the synchronization mutex.	Synchronization
TryLockMutexFunc	Tries to lock the mutex. Not currently implemented.	Synchronization
UnlockMutexFunc	Unlocks the mutex.	Synchronization
ClientReadyFunc	Called when the client enters a ready state.	Notification
DroppedFrameReportFunc	Reports when a frame is dropped.	Notification

Amazon Kinesis Video Streams Developer Guide Callbacks

Function	Description	Туре
DroppedFragmentReportFunc	Reports when a fragment is dropped. This function is not currently used and is reserved for future use.	Notification
FragmentAckReceivedFunc	Called when a fragment ACK (buffering, received, persisted, and error) is received.	Notification
StorageOverflowPressureFur	cCalled when the storage utilization drops below the STORAGE_PRESSURE_NOTIFICAT value, which is defined as 5 percent of the overall storage size.	Notification
StreamClosedFunc	Called when the last bits of the remaining frames are streamed.	Notification
StreamConnectionStaleFunc	Called when the stream enters a stale connection state. In this condition, the producer is sending data to the service but is not receiving acknowledgements.	Notification
StreamDataAvailableFunc	Called when stream data is available.	Notification
StreamErrorReportFunc	Called when a stream error occurs. The PIC automatically closes the stream under this condition.	Notification
StreamLatencyPressureFunc	Called when the stream enters a latency condition, which is when the accumulated buffer size is larger than the max_latency value. For more information, see StreamDefinition/ StreamInfo (p. 89).	Notification
StreamReadyFunc	Called when the stream enters the ready state.	Notification
StreamUnderflowReportFunc	This function is not currently used and is reserved for future use.	Notification
DeviceCertToTokenFunc	Returns the connection certificate as a token.	Platform integration
GetCurrentTimeFunc	Returns the current time.	Platform integration

Amazon Kinesis Video Streams Developer Guide Callbacks

Function	Description	Туре
GetDeviceCertificateFunc	Returns the device certificate. This function is not currently used and is reserved for future use.	Platform integration
GetDeviceFingerprintFunc	Returns the device fingerprint. This function is not currently used and is reserved for future use.	Platform integration
GetRandomNumberFunc	Returns a random number between 0 and RAND_MAX.	Platform integration
GetSecurityTokenFunc	Returns the security token that is passed to the functions that communicate with the backend API. The implementation can specify the serialized AccessKeyId, SecretKeyId, and the session token.	Platform integration
LogPrintFunc	Logs a line of text with the tag and the log level. For more information, see PlatformUtils.h.	Platform integration

For the platform integration functions in the preceding table, the last parameter is a ServiceCallContext structure, which has the following fields:

- · version: The version of the struct.
- callAfter: An absolute time after which to call the function.
- timeout: The timeout of the operation in 100 nanosecond units.
- customData: A user-defined value to be passed back to the client.
- pAuthInfo: The credentials for the call. For more information, see the following (__AuthInfo) structure.

The authorization information is provided using the __AuthInfo structure, which can be either serialized credentials or a provider-specific authentication token. This structure has the following fields:

- version: The version of the __AuthInfo structure.
- type: An AUTH_INFO_TYPE value defining the type of the credential (certificate or security token).
- data: A byte array containing the authentication information.
- size: The size of the data parameter.
- expiration: The expiration of the credentials in 100 nanosecond units.

Callback Implementations to Retry Streaming

The Kinesis Video Producer SDK provides the status of streaming through callback functions. It is recommended that you implement the following callback mechanisms to recover from any momentary network issues encountered during streaming.

Amazon Kinesis Video Streams Developer Guide Callbacks

- Stream latency pressure callback this callback mechanism gets triggered when the SDK encounters a stream latency condition. This happens when the accumulated buffer size is larger than the MAX_LATENCY value. When the stream is created, the streaming application sets MAX_LATENCY to the default value of 60 seconds. The typical implementation for this callback is to reset the connection. You can use the sample implementation at https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp/blob/master/kinesis-video-gstreamer-plugin/plugin-src/StreamLatencyStateMachine.cpp as needed. Note that there is no option to store the frames undelivered due to network outage into a secondary storage for back-fill.
- Stream staleness callback this callback gets triggered when the producer can send data to the AWS KVS service (uplink) but it's not able to get the acknowledgements (buffered ACK) back in time (default is 60 seconds). Depending on the network settings, either the stream latency pressure callback or the stream staleness callback, or both can get triggered. Similar to the stream latency pressure callback retry implementation, the typical implementation is to reset the connection and start a new connection for streaming. You can use the sample implementation at https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp/blob/master/kinesis-video-gstreamer-plugin/plugin-src/ConnectionStaleStateMachine.cpp as needed.
- Stream error callback this callback gets triggered when the SDK encounters a timeout on the network connection or other errors during the call to the KVS API service calls. To recover from network timeout errors, you can refer to and use the sample implementation for recreating the stream at https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp/blob/master/kinesis-video-gst-demo/kinesis_video_gstreamer_sample_app.cpp#L1023.
- **Dropped frame callback** this callback gets triggered when the storage size is full either due to slow network speed or a stream error. If the network speed results in dropped frames, then you can either increase the storage size, reduce the video frame size or frame rate to match the network speed.

Kinesis Video Stream Parser Library

The Kinesis Video Stream Parser Library is an easy-to-use set of tools you can use in Java applications to consume the MKV data in a Kinesis video stream.

The library includes the following tools:

- StreamingMkvReader (p. 108): This class reads specified MKV elements from a video stream.
- FragmentMetadataVisitor (p. 109): This class retrieves metadata for fragments (media elements) and tracks (individual data streams containing media information, such as audio or subtitles).
- OutputSegmentMerger (p. 110): This class merges consecutive fragments or chunks in a video stream.
- KinesisVideoExample (p. 111): This is a sample application that shows how to use the Kinesis Video Stream Parser Library.

The library also includes tests that show how the tools are used.

Procedure: Using the Kinesis Video Stream Parser Library

This procedure includes the following steps:

- the section called "Step 1: Download and Configure the Code" (p. 108)
- the section called "Step 2: Write and Examine the Code" (p. 108)
- the section called "Step 3: Run and Verify the Code" (p. 113)

Prerequisites

You must have the following to examine and use the Kinesis Video Stream Parser Library:

- An Amazon Web Services (AWS) account. If you don't already have an AWS account, do the following:
 - Open https://aws.amazon.com/, and then choose Create an AWS Account.

Note

This might be unavailable in your browser if you previously signed in to the AWS Management Console. In that case, choose **Sign In to the Console**, and then choose **Create a new AWS account**.

· Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call and entering a PIN using the phone keypad.

Note your AWS account ID because you need it for configuring programmatic access to Kinesis video streams.

• A Java integrated development environment (IDE), such as Eclipse Java Neon or JetBrains IntelliJ Idea.

Step 1: Download and Configure the Code

In this section, you download the Java library and test code, and import the project into your Java IDE.

For prerequisites and other details about this procedure, see Stream Parser Library (p. 107).

Create a directory and clone the library source code from the GitHub repository (https://github.com/aws/amazon-kinesis-video-streams-parser-library).

```
$ git clone https://github.com/aws/amazon-kinesis-video-streams-parser-library
```

- Open the Java IDE that you are using (for example, Eclipse or IntelliJ IDEA) and import the Apache Maven project that you downloaded:
 - In Eclipse: Choose File, Import, Maven, Existing Maven Projects, and navigate to the kinesis-video-streams-parser-lib folder.
 - In IntelliJ Idea: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.

For more information, see the related IDE documentation.

Next Step

the section called "Step 2: Write and Examine the Code" (p. 108)

Step 2: Write and Examine the Code

In this section, you examine the Java library and test code, and learn how to use the tools from the library in your own code.

The Kinesis Video Stream Parser Library contains the following tools:

- StreamingMkvReader (p. 108)
- FragmentMetadataVisitor (p. 109)
- OutputSegmentMerger (p. 110)
- KinesisVideoExample (p. 111)

StreamingMkvReader

This class reads specified MKV elements from a stream in a non-blocking way.

The following code example (from FragmentMetadataVisitorTest) shows how to create and use a Streaming MkvReader to retrieve MkvElement objects from an input stream called inputStream:

Amazon Kinesis Video Streams Developer Guide FragmentMetadataVisitor

```
while (mkvStreamReader.mightHaveNext()) {
   Optional<MkvElement> mkvElement = mkvStreamReader.nextIfAvailable();
   if (mkvElement.isPresent()) {
        mkvElement.get().accept(fragmentVisitor);
        ...
      }
   }
}
```

FragmentMetadataVisitor

This class retrieves metadata for fragments (media elements) and tracks (individual data streams containing media information, such as codec private data, pixel width, or pixel height).

The following code example (from the FragmentMetadataVisitorTest file) shows how to use FragmentMetadataVisitor to retrieve data from a MkvElement object:

```
FragmentMetadataVisitor fragmentVisitor = FragmentMetadataVisitor.create();
       StreamingMkvReader mkvStreamReader =
               StreamingMkvReader.createDefault(new InputStreamParserByteSource(in));
       int segmentCount = 0;
       while(mkvStreamReader.mightHaveNext()) {
            Optional<MkvElement> mkvElement = mkvStreamReader.nextIfAvailable();
            if (mkvElement.isPresent()) {
                mkvElement.get().accept(fragmentVisitor);
(MkvTypeInfos.SIMPLEBLOCK.equals(mkvElement.get().getElementMetaData().getTypeInfo()))) {
                    MkvDataElement dataElement = (MkvDataElement) mkvElement.get();
                   Frame frame = ((MkvValue<Frame>)dataElement.getValueCopy()).getVal();
                   MkvTrackMetadata trackMetadata =
fragmentVisitor.getMkvTrackMetadata(frame.getTrackNumber());
                    assertTrackAndFragmentInfo(fragmentVisitor, frame, trackMetadata);
                if
(MkvTypeInfos.SEGMENT.equals(mkvElement.get().getElementMetaData().getTypeInfo())) {
                    if (mkvElement.get() instanceof MkvEndMasterElement) {
                        if (segmentCount < continuationTokens.size()) {</pre>
                            Optional<String> continuationToken =
fragmentVisitor.getContinuationToken();
                            Assert.assertTrue(continuationToken.isPresent());
                            Assert.assertEquals(continuationTokens.get(segmentCount),
continuationToken.get());
                        segmentCount++;
                    }
                }
       }
```

The preceding example shows the following coding pattern:

- Create a FragmentMetadataVisitor to parse the data, and a StreamingMkvReader (p. 108) to provide the data.
- For each MkvElement in the stream, test if its metadata is of type SIMPLEBLOCK.
- If it is, retrieve the MkvDataElement from the MkvElement.
- Retrieve the Frame (media data) from the MkvDataElement.
- $\bullet \ \ {\tt Retrieve} \ the \ {\tt MkvTrackMetadata} \ for \ the \ {\tt Frame} \ from \ the \ {\tt FragmentMetadataVisitor}.$
- Retrieve and verify the following data from the Frame and MkvTrackMetadata objects:

Amazon Kinesis Video Streams Developer Guide OutputSegmentMerger

- · The track number.
- · The frame's pixel height.
- · The frame's pixel width.
- The codec ID for the codec used to encode the frame.
- That this frame arrived in order. That is, verify that the track number of the previous frame, if present, is less than that of the current frame.

To use FragmentMetadataVisitor in your project, pass MkvElement objects to the visitor using their accept method:

```
mkvElement.get().accept(fragmentVisitor);
```

OutputSegmentMerger

This class merges metadata from different tracks in the stream into a stream with a single segment.

The following code example (from the FragmentMetadataVisitorTest file) shows how to use OutputSegmentMerger to merge track metadata from a byte array called inputBytes:

```
FragmentMetadataVisitor fragmentVisitor = FragmentMetadataVisitor.create();
ByteArrayOutputStream outputStream = new ByteArrayOutputStream();
OutputSegmentMerger outputSegmentMerger =
    OutputSegmentMerger.createDefault(outputStream);
CompositeMkvElementVisitor compositeVisitor =
   new TestCompositeVisitor(fragmentVisitor, outputSegmentMerger);
final InputStream in = TestResourceUtil.getTestInputStream("output_get_media.mkv");
StreamingMkvReader mkvStreamReader =
    StreamingMkvReader.createDefault(new InputStreamParserByteSource(in));
while (mkvStreamReader.mightHaveNext()) {
   Optional<MkvElement> mkvElement = mkvStreamReader.nextIfAvailable();
    if (mkvElement.isPresent()) {
        mkvElement.get().accept(compositeVisitor);
 (MkvTypeInfos.SIMPLEBLOCK.equals(mkvElement.get().getElementMetaData().getTypeInfo()))) {
       MkvDataElement dataElement = (MkvDataElement) mkvElement.get();
       Frame frame = ((MkvValue<Frame>) dataElement.getValueCopy()).getVal();
       Assert.assertTrue(frame.getFrameData().limit() > 0);
       MkvTrackMetadata trackMetadata =
 fragmentVisitor.getMkvTrackMetadata(frame.getTrackNumber());
       assertTrackAndFragmentInfo(fragmentVisitor, frame, trackMetadata);
    }
}
```

The preceding example shows the following coding pattern:

- Create a FragmentMetadataVisitor (p. 109)to retrieve the metadata from the stream.
- Create an output stream to receive the merged metadata.
- Create an OutputSegmentMerger, passing in the ByteArrayOutputStream.
- Create a CompositeMkvElementVisitor that contains the two visitors.
- Create an InputStream that points to the specified file.

• Merge each element in the input data into the output stream.

KinesisVideoExample

This is a sample application that shows how to use the Kinesis Video Stream Parser Library.

This class performs the following operations:

- Creates a Kinesis video stream. If a stream with the given name already exists, the stream is deleted
 and recreated.
- Calls PutMedia to stream video fragments to the Kinesis video stream.
- Calls GetMedia to stream video fragments out of the Kinesis video stream.
- Uses a StreamingMkvReader (p. 108) to parse the returned fragments on the stream, and uses a FragmentMetadataVisitor (p. 109) to log the fragments.

Delete and recreate the stream

The following code example (from the StreamOps. java file) deletes a given Kinesis video stream:

```
//Delete the stream
amazonKinesisVideo.deleteStream(new
DeleteStreamRequest().withStreamARN(streamInfo.get().getStreamARN()));
```

The following code example (from the StreamOps.java file) creates a Kinesis video stream with the specified name:

```
amazonKinesisVideo.createStream(new CreateStreamRequest().withStreamName(streamName)
.withDataRetentionInHours(DATA_RETENTION_IN_HOURS)
.withMediaType("video/h264"));
```

Call PutMedia

The following code example (from the PutMediaWorker. java file) calls PutMedia on the stream:

```
putMedia.putMedia(new PutMediaRequest().withStreamName(streamName)
.withFragmentTimecodeType(FragmentTimecodeType.RELATIVE)
.withProducerStartTimestamp(new Date())
.withPayload(inputStream), new PutMediaAckResponseHandler() {
...
});
```

Call GetMedia

The following code example (from the GetMediaWorker. java file) calls GetMedia on the stream:

```
GetMediaResult result = videoMedia.getMedia(new
GetMediaRequest().withStreamName(streamName).withStartSelector(startSelector));
```

Parse the GetMedia result

This section describes how to use StreamingMkvReader (p. 108), FragmentMetadataVisitor (p. 109) and CompositeMkvElementVisitor to parse, save to file, and log the data returned from GetMedia.

Read the output of GetMedia with StreamingMkvReader

The following code example (from the GetMediaWorker.java file) creates a StreamingMkvReader (p. 108) and uses it to parse the result from the GetMedia operation:

```
StreamingMkvReader mkvStreamReader = StreamingMkvReader.createDefault(new
InputStreamParserByteSource(result.getPayload()));
log.info("StreamingMkvReader created for stream {} ", streamName);
try {
    mkvStreamReader.apply(this.elementVisitor);
} catch (MkvElementVisitException e) {
    log.error("Exception while accepting visitor {}", e);
}
```

In the preceding code example, the StreamingMkvReader (p. 108) retrieves MKVElement objects from the payload of the GetMedia result. In the next section, the elements are passed to a FragmentMetadataVisitor (p. 109).

Retrieve Fragments with FragmentMetadataVisitor

The following code examples (from the KinesisVideoExample.java and StreamingMkvReader.java files) create a FragmentMetadataVisitor (p. 109). The MkvElement objects iterated by the StreamingMkvReader (p. 108) are then passed to the visitor using the accept method.

from KinesisVideoExample.java:

```
FragmentMetadataVisitor fragmentMetadataVisitor = FragmentMetadataVisitor.create();
```

from StreamingMkvReader.java:

```
if (mkvElementOptional.isPresent()) {
   //Apply the MkvElement to the visitor
   mkvElementOptional.get().accept(elementVisitor);
   }
```

Log the elements and write them to a file

The following code example (from the KinesisVideoExample.java file) creates the following objects and returns them as part of the return value of the GetMediaProcessingArguments function:

- A LogVisitor (an extension of MkvElementVisitor) that writes to the system log.
- An OutputStream that writes the incoming data to an MKV file.
- A BufferedOutputStream that buffers data bound for the OutputStream.
- An the section called "OutputSegmentMerger" (p. 110) that merges consecutive elements in the GetMedia result with the same track and EBML data.
- A CompositeMkvElementVisitor that composes the FragmentMetadataVisitor (p. 109), the section called "OutputSegmentMerger" (p. 110), and LogVisitor into a single element visitor

```
//A visitor used to log as the GetMedia stream is processed.
LogVisitor logVisitor = new LogVisitor(fragmentMetadataVisitor);
```

Amazon Kinesis Video Streams Developer Guide Next Step

The media processing arguments are then passed into the GetMediaWorker, which is in turn passed to the ExecutorService which executes the worker on a separate thread:

Next Step

the section called "Step 3: Run and Verify the Code" (p. 113)

Step 3: Run and Verify the Code

The Kinesis Video Stream Parser Library contains tools that are intended for you to use in your own projects. The project contains unit tests for the tools that you can run to verify your installation.

The following unit tests are included in the library:

- mkv
 - ElementSizeAndOffsetVisitorTest
 - MkvValueTest
 - StreamingMkvReaderTest
- utilities
 - FragmentMetadataVisitorTest
 - OutputSegmentMergerTest

Amazon Kinesis Video Streams Examples

The following code examples demonstrate how to work with the Kinesis Video Streams API:

Examples: Sending Data to Kinesis Video Streams

- Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 115): Shows how to build the Kinesis Video Streams Producer SDK to use as a GStreamer destination.
- Run the GStreamer Element in a Docker Container (p. 119): Shows how to use a pre-built Docker image for sending RTSP video from an IP camera to Kinesis Video Streams.
- Example: Streaming from an RTSP Source (p. 127): Shows how to build your own Docker image and send RTSP video from an IP camera to Kinesis Video Streams.
- Example: Sending Data to Kinesis Video Streams Using the PutMedia API (p. 124): Shows how to use the Using the Java Producer Library (p. 35) to send data to Kinesis Video Streams that is already in a container format (MKV) using the PutMedia API.

Examples: Retrieving Data from Kinesis Video Streams

- KinesisVideoExample (p. 111): Shows how to parse and log video fragments using the Kinesis Video Streams Parser Library.
- Example: Parsing and Rendering Kinesis Video Streams Fragments (p. 128): Shows how to parse and render Kinesis video stream fragments using JCodec and JFrame.
- the section called "Amazon SageMaker" (p. 130): Demonstrates a solution that uses Amazon SageMaker to determine when certain objects appear in a video stream.

Examples: Playing Back Video Data

• Example: Using HLS in HTML and JavaScript (p. 9): Shows how to retrieve an HLS streaming session for a Kinesis video stream and play it back in a webpage.

Prerequisites

- In the sample code, you provide credentials by specifying a profile that you set in your AWS
 credentials profile file, or by providing credentials in the Java system properties of your integrated
 development environment (IDE). So if you haven't already done so, first set up your credentials. For
 more information, see Set up AWS Credentials and Region for Development.
- We recommend that you use a Java IDE to view and run the code, such as one of the following:
 - Eclipse Java Neon

· JetBrains IntelliJ IDEA

Example: Kinesis Video Streams Producer SDK GStreamer Plugin

This topic shows how to build the Amazon Kinesis Video Streams Producer SDK to use as a GStreamer plugin.

Topics


- Download, Build, and Configure the GStreamer Element (p. 116)
- Run the GStreamer Element (p. 116)
- Example GStreamer Launch Commands (p. 117)
- Run the GStreamer Element in a Docker Container (p. 119)
- GStreamer Element Parameter Reference (p. 121)

GStreamer is a popular media framework used by a multitude of cameras and video sources to create custom media pipelines by combining modular plugins. The Kinesis Video Streams GStreamer plugin greatly simplifies the integration of your existing GStreamer media pipeline with Kinesis Video Streams. After integrating GStreamer, you can get started with streaming video from a webcam or RTSP (Real Time Streaming Protocol) camera to Kinesis Video Streams for real-time or later playback, storage, and further analysis.

The GStreamer plugin automatically manages the transfer of your video stream to Kinesis Video Streams by encapsulating the functionality provided by the Kinesis Video Streams Producer SDK in a GStreamer sink element, kvssink. The GStreamer framework provides a standard managed environment for constructing media flow from a device such as a camera or other video source for further processing, rendering, or storage.

The GStreamer pipeline typically consists of the link between a source (video camera) and the sink element (either a player to render the video, or storage for offline retrieval). In this example, you use the Producer SDK element as a *sink*, or media destination, for your video source (webcam or IP camera). The plugin element that encapsulates the SDK then manages sending the video stream to Kinesis Video Streams.

This topic shows how to construct a GStreamer media pipeline capable of streaming video from a video source, such as a web camera or RTSP stream, typically connected through intermediate encoding stages (using H.264 encoding) to Kinesis Video Streams. When your video stream is available as a Kinesis video stream, you can use the Kinesis Video Stream Parser Library for further processing, playback, storage, or analysis of your video stream.



Download, Build, and Configure the GStreamer Flement

The GStreamer Plugin example is included with the Kinesis Video Streams C++ Producer SDK. For information about SDK prerequisites and downloading, see Step 1: Download and Configure the C++ Producer Library Code (p. 47).

To build the Producer SDK GStreamer sink as a dynamic library on macOS, Ubuntu, Raspberry Pi, or Windows, execute the following command in the kinesis-video-native-build directory:

./gstreamer-plugin-install-script

After the sink is built, you can execute gst-launch-1.0 from the following directory:

<YourSdkFolderPath>/kinesis-video-native-build/downloads/local/bin

You can either run qst-launch-1.0 from this directory, or add it to the PATH environment variable:

\$ export PATH=<YourSdkFolderPath>/kinesis-video-native-build/downloads/local/bin:\$PATH

Add the library directory to your path so that the GStreamer plugin can be found:

export GST_PLUGIN_PATH=<YourSdkFolderPath>/kinesis-video-native-build/downloads/local/lib: \$GST_PLUGIN_PATH

Set the library path for the SDK:

export LD_LIBRARY_PATH=<\footnote{YourSdkFolderPath}/kinesis-video-native-build/downloads/local/lib

Run the GStreamer Element

To run GStreamer with the Kinesis Video Streams Producer SDK element as a sink, execute the gst-launch-1.0 command. Use settings that are appropriate for the GStreamer plugin to use—for example, v412src for v412 devices on Linux systems, or rtspsrc for RTSP devices. Specify kvssink as the sink (final destination of the pipeline) to send video to the Producer SDK.

The kvssink element has the following required parameters:

- stream-name: The name of the destination Kinesis video stream.
- storage-size: The storage size of the device in kilobytes. For information about configuring device storage, see StorageInfo (p. 88).
- access-key: The AWS access key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- secret-key: The AWS secret key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- credential-path: A path to a file containing your credentials for accessing Kinesis Video Streams.
 For example credential files, see Sample Static Credential and Sample Rotating Credential. For more information on rotating credentials, see Managing Access Keys for IAM Users. You must provide either this parameter or access-key and secret-key.

For information about kvssink optional parameters, see GStreamer Element Parameter Reference (p. 121).

Amazon Kinesis Video Streams Developer Guide Launch Commands

For the latest information about GStreamer plugins and parameters, see GStreamer Plugins, or execute the following command to list options:

gst-inspect-1.0 kvssink

Example GStreamer Launch Commands

These examples demonstrate how to use a GStreamer plugin to stream video from different types of devices.

Example 1: Stream Video from an RTSP Camera on Ubuntu

The following command creates a GStreamer pipeline on Ubuntu that streams from a network RTSP camera, using the rtspsrc GStreamer plugin:

```
$ gst-launch-1.0 rtspsrc location="rtsp://YourCameraRtspUrl" short-header=TRUE !
  rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-
name="YourStreamName" storage-size=512 access-key="YourAccessKey" secret-
key="YourSecretKey" aws-region="YourAWSRegion"
```

Example 2: Encode and Stream Video from a USB Camera on Ubuntu

The following command creates a GStreamer pipeline on Ubuntu that encodes the stream from a USB camera in H.264 format, and streams it to Kinesis Video Streams. This example uses the v412src GStreamer plugin.

```
$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! videoconvert ! video/
x-raw,format=I420,width=640,height=480,framerate=30/1 ! x264enc bframes=0 key-int-
max=45 bitrate=500 ! video/x-h264,stream-format=avc,alignment=au,profile=baseline !
kvssink stream-name="YourStreamName" storage-size=512 access-key="YourAccessKey" secret-
key="YourSecretKey" aws-region="YourAWSRegion"
```

Example 3: Stream Pre-Encoded Video from a USB Camera on Ubuntu

The following command creates a GStreamer pipeline on Ubuntu that streams video that the camera has already encoded in H.264 format to Kinesis Video Streams. This example uses the v412src GStreamer plugin.

```
$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! h264parse ! video/x-
h264,stream-format=avc,alignment=au ! kvssink stream-name="plugin" storage-size=512 access-
key="YourAccessKey" secret-key="YourSecretKey" aws-region="YourAWSRegion"
```

Example 4: Stream Video from a Network Camera on macOS

The following command creates a GStreamer pipeline on macOS that streams video to Kinesis Video Streams from a network camera. This example uses the rtspsrc GStreamer plugin.

```
$ gst-launch-1.0 rtspsrc location="rtsp://YourCameraRtspUrl" short-header=TRUE !
rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-
```

Amazon Kinesis Video Streams Developer Guide Launch Commands

name="YourStreamName" storage-size=512 access-key="YourAccessKey" secretkey="YourSecretKey" aws-region="YourAWSRegion"

Example 5: Stream Video from a Network Camera on Windows

The following command creates a GStreamer pipeline on Windows that streams video to Kinesis Video Streams from a network camera. This example uses the rtspsrc GStreamer plugin.

```
$ gst-launch-1.0 rtspsrc location="rtsp://YourCameraRtspUrl" short-header=TRUE !
  rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-
name="YourStreamName" storage-size=512 access-key="YourAccessKey" secret-
key="YourSecretKey" aws-region="YourAWSRegion"
```

Example 6: Stream Video from a Camera on Raspberry Pi

The following command creates a GStreamer pipeline on Raspberry Pi that streams video to Kinesis Video Streams. This example uses the v412src GStreamer plugin.

\$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! videoconvert ! video/x-raw,format=I420,width=640,height=480,framerate=30/1 ! omxh264enc control-rate=1 target-bitrate=5120000 periodicity-idr=45 inline-header=FALSE ! h264parse ! video/x-h264,stream-format=avc,alignment=au,width=640,height=480,framerate=30/1,profile=baseline ! kvssink stream-name="YourStreamName" frame-timestamp=dts-only access-key="YourAccessKey" secret-key="YourSecretKey" aws-region="YourAWSRegion"

Example 7: Stream Video from a Camera on Raspberry Pi and Specify Region

The following command creates a GStreamer pipeline on Raspberry Pi that streams video to Kinesis Video Streams in the US East (N. Virginia) region. This example uses the v412src GStreamer plugin.

\$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! videoconvert ! video/xraw,format=I420,width=640,height=480,framerate=30/1 ! omxh264enc control-rate=1 targetbitrate=5120000 periodicity-idr=45 inline-header=FALSE ! h264parse ! video/x-h264,streamformat=avc,alignment=au,width=640,height=480,framerate=30/1,profile=baseline ! kvssink
 stream-name="YourStreamName" frame-timestamp=dts-only access-key="YourAccessKey" secretkey="YourSecretKey" aws-region="YourAWSRegion"

Example 8: Stream both audio and video in Raspberry-PI and Ubuntu

See how to run the gst-launch-1.0 command to start streaming both audio and video in Raspberry-PI and Liberty

Example 9: Stream both audio and video in MacOS

See how to run the gst-launch-1.0 command to start streaming both audio and video in MacOS.

Example 10: Stream both audio and video in Windows using MSVC

See how to run the gst-launch-1.0 command to start streaming both audio and video in Windows using MSVC.

Example 11: Stream both audio and video in Windows using MSYS2

See how to run the gst-launch-1.0 command to start streaming both audio and video in Windows using MSYS2.

Run the GStreamer Element in a Docker Container

Docker is a platform for developing, deploying, and running applications using containers. Using Docker to create the GStreamer pipeline standardizes the operating environment for Kinesis Video Streams, which greatly simplifies building and executing the application.

To install and configure Docker, see the following:

- · Docker download instructions
- · Getting started with Docker

After installing Docker, you can download the Kinesis Video Streams C++ Producer SDK (and GStreamer plugin) from Amazon Elastic Container Registry using the docker pull command.

To run GStreamer with the Kinesis Video Streams Producer SDK element as a sink in a Docker container, do the following:

Topics

- Authenticate your Docker Client (p. 119)
- Download the Docker Image for Ubuntu, macOS, Windows, or Raspberry Pi (p. 119)
- Run the Docker Image (p. 120)

Authenticate your Docker Client

Authenticate your Docker client to the Amazon ECR registry that you intend to pull your image from. You must get authentication tokens for each registry used, and the tokens are valid for 12 hours. For more information, see Registry Authentication in the Amazon Elastic Container Registry User Guide.

Example: Authenticate with Amazon ECR

```
aws ecr get-login --no-include-email --region us-west-2 --registry-ids 546150905175
```

The preceding command produces output similar to the following:

```
docker login -u AWS -p <Password> https://YourAccountId.dkr.ecr.us-west-2.amazonaws.com
```

The resulting output is a Docker login command that you use to authenticate your Docker client to your Amazon ECR registry.

Download the Docker Image for Ubuntu, macOS, Windows, or Raspberry Pi

Download the Docker image to your Docker environment using one the following commands, depending on your operating system:

Download the Docker Image for Ubuntu

sudo docker pull 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdkcpp-amazon-linux:latest

Download the Docker Image for macOS

sudo docker pull 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdkcpp-amazon-linux:latest

Download the Docker Image for Windows

docker pull 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-amazon-windows:latest

Download the Docker Image for Raspberry Pi

sudo docker pull 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdkcpp-raspberry-pi:latest

To verify that the image was successfully added, use the following command:

docker images

Run the Docker Image

Use one of the following commands to run the Docker image, depending on your operating system:

Run the Docker Image on Ubuntu

```
sudo docker run -it --network="host" --device=/dev/video0 546150905175
.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-amazon-linux /bin/bash
```

Run the Docker Image on macOS

Run the Docker Image on Windows

docker run -it 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cppwindows <AWS_ACCESS_KEY_ID> <AWS_SECRET_ACCESS_KEY> <RTSP_URL> <STREAM_NAME>

Run the Docker Image on Raspberry Pi

```
sudo docker run -it --device=/dev/video0 --device=/dev/vchiq -v /opt/vc:/opt/vc 546150905175 .dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-raspberry-pi /bin/bash
```

Docker launches the container, and presents you with a command prompt for executing commands within the container.

In the container, set the environment variables using the following command:

Amazon Kinesis Video Streams Developer Guide Parameter Reference

export LD_LIBRARY_PATH=/opt/awssdk/amazon-kinesis-video-streams-producer-sdk-cpp/kinesisvideo-native-build/downloads/local/lib:\$LD_LIBRARY_PATH

export PATH=/opt/awssdk/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-nativebuild/downloads/local/bin:\$PATH

export GST_PLUGIN_PATH=/opt/awssdk/amazon-kinesis-video-streams-producer-sdk-cpp/kinesisvideo-native-build/downloads/local/lib:\$GST PLUGIN PATH

Start streaming from the camera using the gst-launch-1.0 command that is appropriate for your device.

Note

On macOS, you can only stream video from a network camera when running GStreamer in a Docker container. Streaming video from a USB camera on macOS in a Docker container is not supported.

For examples of using the gst-launch-1.0 command to connect to a local web camera or a network RTSP camera, see Launch Commands (p. 117).

GStreamer Element Parameter Reference

To send video to the Amazon Kinesis Video Streams Producer SDK, you specify kwssink as the sink, or final destination of the pipeline. This reference provides information about kwssink required and optional parameters. For more information, see the section called "GStreamer" (p. 115).

The kvssink element has the following required parameters:

- stream-name: The name of the destination Kinesis video stream.
- storage-size: The storage size of the device in kilobytes. For information about configuring device storage, see StorageInfo (p. 88).
- access-key: The AWS access key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- secret-key: The AWS secret key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- credential-path: A path to a file containing your credentials for accessing Kinesis Video Streams. For example credential files, see Sample Static Credential and Sample Rotating Credential. You must provide either this parameter or access-key and secret-key.

The kvssink element has the following optional parameters. For more information about these parameters, see Kinesis Video Stream Structures (p. 89).

Parameter	Description	Unit/ Type	Default
absolute-fragment- times	Whether to use absolute fragment times.	Boolean	true
avg-bandwidth-bps	The expected average bandwidth for the stream.	Bytes per second	4194304
aws-region	The AWS region to use.	String	us-west-2
buffer-duration	The stream buffer duration.	Seconds	180
codec-id	The codec ID of the stream.	String	"V_MPEG4/ISO/AVC"

Amazon Kinesis Video Streams Developer Guide Parameter Reference

Parameter	Description	Unit/ Type	Default
connection- staleness	The time after which the stream staleness callback is called.	Seconds	60
content-type	The content type of the stream.	String	"video/h264"
fragment-acks	Whether to use fragment ACKs.	Boolean	true
fragment-duration	The fragment duration that you want.	Milliseconds	2000
framerate	The expected frame rate.	Frames per second	25
frame-timecodes	Whether to use frame timecodes or generate timestamps using the current time callback.	Boolean	true
frame-timestamp	(0): pts-only: Set the decoding timestamp (DTS) equal to the presentation timestamp (PTS) for every frame sent to Kinesis Video Streams. (1): dts. only: Set	Enum GstKvsSinkFrameTime	default-timestamp stampType
	 (1): dts-only: Set PTS equal to DTS for every frame sent to Kinesis Video Streams. (2): default- timestamp: Try to use both PTS and DTS. If one is not available, then use the other. 		
key-frame- fragmentation	Whether to produce fragments on a key frame.	Boolean	true
log-config	The log configuration path.	String	"./ kvs_log_configuration
max-latency	The maximum latency for the stream.	Seconds	60
recalculate- metrics	Whether to recalculate the metrics.	Boolean	true

Amazon Kinesis Video Streams Developer Guide Parameter Reference

Parameter	Description	Unit/ Type	Default
replay-duration	The duration to roll the current reader backward to replay during an error if restarting is enabled.	Seconds	40
restart-on-error	Whether to restart when an error occurs.	Boolean	true
retention-period	The length of time the stream is preserved.	Hours	2
rotation-period	The key rotation period. For more information, see Rotating Customer Master Keys.	Seconds	2400
streaming-type	The streaming type. Valid values include: • 0: real time • 1: near real time (not currently supported) • 2: offline (not currently supported)	Enum GstKvsSinkStreaming	0: real time Type
timecode-scale	The MKV timecode scale.	Milliseconds	1
track-name	The MKV track name.	String	"kinesis_video"
iot-certificate	IoT credentials to be used in the kvssink element. Accepts the following keys and values:	String	None
	 endpoint=iotcredential cert-path=/ localdirectorypath / to/certificate key-path=/ localdirectorypath / to/private/key ca-path=/ localdirectorypath/ to/ca-cert role-aliases=role- aliases 	sproviderendpoint	

Example: Sending Data to Kinesis Video Streams Using the PutMedia API

This example demonstrates how to use the PutMedia API. It shows how to send data that is already in a container format (MKV). If your data needs to be assembled into a container format before sending (for example, if you are assembling camera video data into frames), see Kinesis Video Streams Producer Libraries (p. 34).

Note

The PutMedia operation is available only in the C++ and Java SDKs, due to the full-duplex management of connections, data flow, and acknowledgements. It is not supported in other languages.

This example includes the following steps:

- Step 1: Download and Configure the Code (p. 124)
- Step 2: Write and Examine the Code (p. 125)
- Step 3: Run and Verify the Code (p. 126)

Step 1: Download and Configure the Code

In this section, you download the Java example code, import the project into your Java IDE, configure the library locations, and configure the code to use your AWS credentials.

1. Create a directory and clone the example source code from the GitHub repository. The PutMedia example is part of the Java Producer Library (p. 35).

\$ git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-java

- 2. Open the Java IDE that you are using (for example, Eclipse or IntelliJ IDEA), and import the Apache Maven project that you downloaded:
 - In Eclipse: Choose File, Import, Maven, Existing Maven Projects, and navigate to the root of the downloaded package. Select the pom.xml file.
 - In IntelliJ Idea: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.

For more information, see the related IDE documentation.

- 3. Update the project so that the IDE can find the libraries that you imported.
 - For IntelliJ IDEA, do the following:
 - a. Open the context (right-click) menu for the project's lib directory, and choose Add as library.
 - b. Choose File, Project Structure.
 - c. Under Project Settings, choose Modules.
 - d. In the Sources tab, set Language Level to 7 or higher.
 - For Eclipse, do the following:
 - a. Open the context (right-click) menu for the project, and choose **Properties**, **Java Build Path**, **Source**. Then do the following:
 - 1. On the **Source** tab, double-click **Native library location**.

- 2. In the Native Library Folder Configuration wizard, choose Workspace.
- 3. In the Native Library Folder selection, choose the lib directory in the project.
- b. Open the context (right-click) menu for the project, and choose **Properties**. Then do the following:
 - 1. On the Libraries tab, choose Add Jars.
 - 2. In the **JAR selection** wizard, choose all the .jars in the project's lib directory.

Step 2: Write and Examine the Code

The PutMedia API example (PutMediaDemo) shows the following coding pattern:

Topics

- Create the PutMediaClient (p. 125)
- Stream Media and Pause the Thread (p. 126)

The code examples in this section are from the PutMediaDemo class.

Create the PutMediaClient

Creating the PutMediaClient object takes the following parameters:

- The URI for the PutMedia endpoint.
- An InputStream pointing to the MKV file to stream.
- The stream name. This example uses the stream that was created in the Using the Java Producer Library (p. 35) (my-stream). To use a different stream, change the following parameter:

```
private static final String STREAM_NAME="my-stream";
```

Note

The PutMedia API example does not create a stream. You must create a stream either by using the test application for the Using the Java Producer Library (p. 35), by using the Kinesis Video Streams console, or by using the AWS CLI.

- The current timestamp.
- The time code type. The example uses RELATIVE, indicating that the timestamp is relative to the start of the container.
- An AWSKinesisVideoV4Signer object that verifies that the received packets were sent by the authorized sender.
- · The maximum upstream bandwidth in Kbps.
- An AckConsumer object to receive packet received acknowledgements.

The following code creates the PutMediaClient object:

```
/* actually URI to send PutMedia request */
final URI uri = URI.create(KINESIS_VIDEO_DATA_ENDPOINT + PUT_MEDIA_API);
/* input stream for sample MKV file */
final InputStream inputStream = new FileInputStream(MKV_FILE_PATH);
/* use a latch for main thread to wait for response to complete */
```

Amazon Kinesis Video Streams Developer Guide Step 3: Run and Verify the Code

```
final CountDownLatch latch = new CountDownLatch(1);
/* a consumer for PutMedia ACK events */
final AckConsumer ackConsumer = new AckConsumer(latch);
/* client configuration used for AWS SigV4 signer */
final ClientConfiguration configuration = getClientConfiguration(uri);
/* PutMedia client */
final PutMediaClient client = PutMediaClient.builder()
        .putMediaDestinationUri(uri)
        .mkvStream(inputStream)
        .streamName(STREAM NAME)
        .timestamp(System.currentTimeMillis())
        .fragmentTimeCodeType("RELATIVE")
        .siqnWith(getKinesisVideoSigner(configuration))
        .upstreamKbps(MAX_BANDWIDTH_KBPS)
        .receiveAcks(ackConsumer)
        .build();
```

Stream Media and Pause the Thread

After the client is created, the sample starts asynchronous streaming with putMediaInBackground. The main thread is then paused with latch.await until the AckConsumer returns, at which point the client is closed.

```
/* start streaming video in a background thread */
    client.putMediaInBackground();

    /* wait for request/response to complete */
    latch.await();

    /* close the client */
    client.close();
```

Step 3: Run and Verify the Code

To run the PutMedia API example, do the following:

- 1. Create a stream named my-stream in the Kinesis Video Streams console or by using the AWS CLI.
- 2. Change your working directory to the Java producer SDK directory:

```
$ cd /<YOUR_FOLDER_PATH_WHERE_SDK_IS_DOWNLOADED>/amazon-kinesis-video-streams-producer-
sdk-java/
```

3. Compile the Java SDK and demo application:

```
mvn package
```

4. Create a temporary filename in the /tmp directory:

```
$ jar_files=$(mktemp)
```

5. Create a classpath string of dependencies from the local repository to a file:

```
$ mvn -Dmdep.outputFile=$jar_files dependency:build-classpath
```

6. Set the value of the LD_LIBRARY_PATH environment variable as follows:

Amazon Kinesis Video Streams Developer Guide RTSP and Docker

```
$ export LD_LIBRARY_PATH=/<YOUR_FOLDER_PATH_WHERE_SDK_IS_DOWNLOADED>/amazon-kinesis-
video-streams-producer-sdk-cpp/kinesis-video-native-build/downloads/local/lib:
$LD_LIBRARY_PATH
$ classpath_values=$(cat $jar_files)
```

7. Run the demo from the command line as follows, providing your AWS credentials:

```
$ java -classpath target/kinesisvideo-java-demo-1.0-SNAPSHOT.jar:$classpath_values
-Daws.accessKeyId=${ACCESS_KEY} -Daws.secretKey=${SECRET_KEY} -Djava.library.path=/
opt/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-native-build
com.amazonaws.kinesisvideo.demoapp.DemoAppMain
```

8. Open the Kinesis Video Streams console at https://console.aws.amazon.com/kinesisvideo/, and choose your stream on the **Manage Streams** page. The video plays in the **Video Preview** pane.

Example: Streaming from an RTSP Source

The C++ Producer Library (p. 44) contains a definition for a Docker container that connects to an RTSP (Real Time Streaming Protocol) network camera. Using Docker standardizes the operating environment for Kinesis Video Streams, which greatly simplifies building and executing the application.

To use the RTSP demo application, first install and build the C++ Producer Library (p. 44).

The following procedure demonstrates how to set up and use the RTSP demo application.

Topics

- Prerequisites (p. 127)
- Build the Docker Image (p. 127)
- Run the RTSP Example Application (p. 128)

Prerequisites

To run the Kinesis Video Streams RTSP example application, you must have the following:

- Docker: For information about installing and using Docker, see the following links:
 - · Docker download instructions
 - Getting started with Docker
- RTSP network camera source: For information about recommended cameras, see System Requirements (p. 3).

Build the Docker Image

First, you build the Docker image that the demo application will run inside.

- Create a new directory and copy the following files from the docker_native_scripts directory to the new directory:
 - Dockerfile
 - start_rtsp_in_docker.sh
- 2. Change to the directory that you created in the previous step.

Build the Docker image using the following command. This command creates the image and tags it as rtspdockertest.

```
docker build -t rtspdockertest .
```

4. Record the image ID that was returned in the previous step (for example, 54f0d65f69b2).

Run the RTSP Example Application

Start the Kinesis Video Streams Docker container using the following command. Provide the image ID from the previous step, your AWS credentials, the URL of your RTSP network camera, and the name of the Kinesis video stream to send the data.

```
$ docker run -
it <IMAGE_ID> <AWS_ACCESS_KEY_ID> <AWS_SECRET_ACCESS_KEY> <RTSP_URL> <STREAM_NAME>
```

To customize the application, comment or remove the ENTRYPOINT command in Dockerfile, and launch the container using the following command:

```
docker run -it <IMAGE_ID> bash
```

You are then prompted inside the Docker container to customize the sample application and start streaming.

Example: Parsing and Rendering Kinesis Video Streams Fragments

The Stream Parser Library (p. 107) contains a demo application named KinesisVideoRendererExample that demonstrates parsing and rendering Amazon Kinesis video stream fragments. The example uses JCodec to decode the H.264 encoded frames that are ingested using the Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 115) application. After the frame is decoded using JCodec, the visible image is rendered using JFrame.

This example shows how to do the following:

- Retrieve frames from a Kinesis video stream using the GetMedia API and render the stream for viewing.
- View the video content of streams in a custom application instead of using the Kinesis Video Streams console.

You can also use the classes in this example to view Kinesis video stream content that isn't encoded as H.264, such as a stream of JPEG files that don't require decoding before being displayed.

The following procedure demonstrates how to set up and use the Renderer demo application.

Prerequisites

To examine and use the Renderer example library, you must have the following:

 An Amazon Web Services (AWS) account. If you don't already have an AWS account, see Getting Started with Kinesis Video Streams. • A Java integrated development environment (IDE), such as Eclipse Java Neon or JetBrains IntelliJ Idea.

Running the Renderer Example

1. Create a directory, and then clone the example source code from the GitHub repository.

```
$ git clone https://github.com/aws/amazon-kinesis-video-streams-parser-library
```

- Open the Java IDE that you are using (for example, Eclipse or IntelliJ IDEA), and import the Apache Maven project that you downloaded:
 - In Eclipse: Choose File, Import, Maven, Existing Maven Projects. Navigate to the kinesis-video-streams-parser-lib directory.
 - In IntelliJ Idea: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.

Note

If IntelliJ can't find your dependencies, you might have to do the following:

- Build clean: Choose File, Settings, Build, Execution, Deployment, Compiler. Ensure that Clear output directory on rebuild is selected, and then choose Build, Build Project.
- Reimport the project: Open the context (right-click) menu for the project, and choose Maven, Reimport.

For more information, see the related IDE documentation.

- From your Java IDE, open src/test/java/com.amazonaws.kinesisvideo.parser/ examples/KinesisVideoRendererExampleTest.
- 4. Remove the @Ignore directive from the file.
- 5. Update the .stream parameter with the name of your Kinesis video stream.
- 6. Run the KinesisVideoRendererExample test.

How It Works

The example application demonstrates the following:

- Sending MKV data (p. 129)
- Parsing MKV Fragments into Frames (p. 130)
- Decoding and Displaying the Frame (p. 130)

Sending MKV data

The example sends sample MKV data from the rendering_example_video.mkv file, using PutMedia to send video data to a stream named render-example-stream.

The application creates a PutMediaWorker:

```
PutMediaWorker putMediaWorker = PutMediaWorker.create(getRegion(),
    getCredentialsProvider(),
    getStreamName(),
    inputStream,
    streamOps.amazonKinesisVideo);
executorService.submit(putMediaWorker);
```

Amazon Kinesis Video Streams Developer Guide Amazon SageMaker

For information about the PutMediaWorker class, see Call PutMedia (p. 111) in the Stream Parser Library (p. 107) documentation.

Parsing MKV Fragments into Frames

The example then retrieves and parses the MKV fragments from the stream using a GetMediaWorker:

```
GetMediaWorker getMediaWorker = GetMediaWorker.create(getRegion(),
    getCredentialsProvider(),
    getStreamName(),
    new StartSelector().withStartSelectorType(StartSelectorType.EARLIEST),
    streamOps.amazonKinesisVideo,
    getMediaProcessingArgumentsLocal.getFrameVisitor());
executorService.submit(getMediaWorker);
```

For more information about the GetMediaWorker class, see Call GetMedia (p. 111) in the Stream Parser Library (p. 107) documentation.

Decoding and Displaying the Frame

The example then decodes and displays the frame using JFrame.

The following code example is from the KinesisVideoFrameViewer class, which extends JFrame:

```
public void setImage(BufferedImage bufferedImage) {
  image = bufferedImage;
  repaint();
}
```

The image is displayed as an instance of java.awt.image.BufferedImage. For examples that show how to work with BufferedImage, see Reading/Loading an Image.

Example: Identifying Objects in Video Streams Using Amazon SageMaker

This example demonstrates how to create a solution that uses Amazon SageMaker to identify when certain objects appear in an Amazon Kinesis video stream. Amazon SageMaker is the managed platform for developers and data scientists to build, train, and deploy machine learning models quickly and easily.

The example consists of a Docker container that includes the application functionality, and an AWS CloudFormation template that automates the deployment of the application's AWS resources.

The AWS CloudFormation template creates the following resources:

- An Amazon Elastic Container Service (Amazon ECS) cluster that uses the AWS Fargate compute engine that runs the library software.
- An Amazon DynamoDB table that maintains checkpoints and related state across workers that run on Fargate tasks.
- A Kinesis data stream that captures the inference outputs generated from Amazon SageMaker.
- An AWS Lambda function that parses the output from Amazon SageMaker.
- AWS Identity and Access Management (IAM) resources for providing access across services.
- Amazon CloudWatch resources for monitoring the application.

Amazon Kinesis Video Streams Developer Guide Prerequisites

The application is compatible with any Amazon SageMaker endpoint that processes data. This example contains instructions for creating an Amazon SageMaker endpoint that uses a sample object identification algorithm template. You can modify or replace the algorithm based on your application's use cases and requirements.

Topics

- Prerequisites (p. 131)
- Creating the Application (p. 132)
- Monitoring the Application (p. 133)
- Extending the Application (p. 134)
- Cleaning up the Application (p. 135)

Prerequisites

The example application has the following prerequisites:

- Amazon SageMaker (p. 131)
- Kinesis Video Stream (p. 131)
- Service-Linked Role (p. 131)

Amazon SageMaker

This example requires an Amazon SageMaker notebook. For information about creating a notebook, see Creating a Notebook Instance in the Amazon SageMaker Developer Guide. Note the following when creating your notebook:

- Add the object_detection_image_json_format.ipynb example (from the Introduction to Amazon Algorithms section in the SageMaker Examples tab of the Jupyter console) to the notebook.
- Create an Amazon Simple Storage Service (Amazon S3) bucket, and provide its name in the **Prerequisites** step when adding the example.
- After you create the notebook, choose Endpoint configuration on the Amazon SageMaker console, and make a note of the Endpoint name.

Kinesis Video Stream

This example requires one or more Kinesis video streams that have live video data. For information about creating a Kinesis video stream and sending data to it from a camera, see GStreamer (p. 115). Make a note of your Kinesis video stream name.

Service-Linked Role

This example requires that your account have a service-linked role for AWS Fargate operation. New AWS accounts have this role enabled by default. If you see the following error when creating the application, you must enable the service-linked role:

Unable to assume the service linked role. Please verify that the ECS service linked role exists

To enable the service-linked role, run the following command:

aws iam create-service-linked-role --aws-service-name ecs.amazonaws.com

Creating the Application

To create the sample application, you use AWS CloudFormation and the templates that are provided.

To use AWS CloudFormation to create the application

- 1. Sign in to the AWS Management Console and open the AWS CloudFormation console using one of the following links for your AWS Region. The link launches the correct stack for your Region:
 - Launch in Asia Pacific (Sydney) Region (ap-southeast-2)
 - Launch in Asia Pacific (Tokyo) Region (ap-northeast-1)
 - Launch in EU (Frankfurt) Region (eu-central-1)
 - · Launch in EU (Ireland) Region (eu-west-1)
 - Launch in US East (N. Virginia) Region (us-east-1)
 - Launch in US West (Oregon) Region (us-west-2)
- 2. On the Create Stack page, provide the following values:
 - Give the stack a unique name (for example, username-KVS-SageMaker).
 - Provide the Amazon SageMaker endpoint name (not the endpoint ARN) that you created in the previous section.
 - Provide the name of your Kinesis video stream. If you have more than one Kinesis video stream, provide the stream names in quotation marks and separated by commas.
 - Keep the rest of the settings as they are.

Choose Next.

- 3. On the **Options** page, keep the settings as they are.
- Select the I acknowledge that AWS CloudFormation might create IAM resources check box. Choose Next.

AWS CloudFormation creates the application.

The following table lists several parameters used by the Docker container when you create a stack using this AWS CloudFormation template. Their values are predefined in the SSM resource in the template, but you can customize them as needed.

Resource name	Default value	Description
inferenceInterval	6	The sampling ratio for video frames that are sout of every 6 I-Frames is sent to the SageMa
sageMakerTaskQueueSize	5000	The size of the queue that maintains the pend 'sageMakerTaskTimeoutInMilli'. If sagemaker
sageMakerTaskThreadPoolSize	20	Number of threads that is used to concurrent
sageMakerTaskTimeoutInMilli	20000	The maximum duration allowed for a single r
sageMakerTaskThreadPoolName	SageMakerThreadF %d	Pool- The name of the threadpool that is sending re

To customize the values of these parameters, download the AWS CloudFormation template by choosing the template URL on the **Create stack** page, and then locate these parameters in the Params section of the template that looks like this:

Amazon Kinesis Video Streams Developer Guide Monitoring the Application

Monitoring the Application

The application created by the AWS CloudFormation template includes an Amazon CloudWatch dashboard and a CloudWatch log stream that you use to monitor application metrics and events.

Application Dashboard

The application includes a CloudWatch dashboard for monitoring application metrics. To view the application dashboard, open the CloudWatch console at https://console.aws.amazon.com/cloudwatch/ and choose **Dashboards** in the left navigation bar.

Choose the **KVS-SageMaker-Driver-KvsSageMakerIntegration-**aws-region dashboard. The dashboard shows the following information:

- Frame Metrics: Metrics for processing the video stream, sending frames to the Amazon SageMaker endpoint, and writing to the Kinesis data stream that connects the Amazon SageMaker notebook with the AWS Lambda function that processes Amazon SageMaker inference output results.
- **IngestToProcessLatency:** The time difference between when a video frame is ingested into the Kinesis Video Streams service and when the application receives the frame.
- **Current Lease Total:** The application is granted permissions to read from the Kinesis video stream using a lease. This metric shows the number of active leases. The application uses one lease per Kinesis video stream, and one lease for synchronization between streams.
- Lease Sync Metrics: The frequency and duration of permission lease synchronization.
- LeaseCount per Worker: The distribution of leases among the Amazon SageMaker worker threads.
- **Number of Workers:** The number of Amazon SageMaker workers processing streams. Each task in an Amazon ECS cluster has one worker running. One worker can process more than one stream.
- ECS Service Utilization: Usage metrics for the Amazon ECS cluster.
- KinesisDataStream: Usage metrics of the Kinesis data stream.
- SageMaker: Operations performed by the Amazon SageMaker notebook.
- Lambda: Number and duration of the Lambda function that processes the output from the Amazon SageMaker notebook.

If any of the information in these graphs indicates an operational issue (such as a value steadily increasing rather than being stable), see the following section about how to read the application logs to determine the issue.

CloudWatch Logs

The application includes two CloudWatch logs:

Topics

- The Application Log (p. 134)
- The Lambda Function Log (p. 134)

The Application Log

You can use the application log to monitor application events and error conditions. This log is helpful if you need to contact product support with an issue.

To read the Application Log

- 1. Open the Amazon ECS console at https://console.aws.amazon.com/ecs.
- 2. Choose the KVS-Sagemaker-Driver cluster.
- 3. Choose the **stack-name-SageMakerDriverService** service in the **Services** tab.
- 4. Choose the **Logs** tab.

The application log shows events such as initialization, configuration, and lease activity.

The Lambda Function Log

You can use the Lambda function log to track successful object identifications.

To read the Lambda log

- 1. Open the AWS Lambda console at https://console.aws.amazon.com/lambda.
- Choose the Lambda function for your application. The Lambda function name is in the following format:

```
stack-name-LambdaFunction-A1B2C3D4E5F6G
```

- 3. Choose the Monitoring panel.
- Choose View logs in CloudWatch.

The CloudWatch log for the application shows successful identifications of objects in the Kinesis video stream and other application events.

Extending the Application

You can add custom functionality to your application by modifying the values that you provide in the AWS CloudFormation template window as follows:

- EndPointAcceptContentType: You can change this value if your Amazon SageMaker endpoint does not accept frames in JPG format. The following formats are supported:
 - image/jpeg
 - image/png
 - image/bmp
 - image/gif
 - application/x-image

- LambdaFunctionBucket, LambdaFunctionKey: The provided settings use an AWS Lambda function that processes the Amazon SageMaker output and writes it to CloudWatch Logs. If you want to send the Amazon SageMaker output elsewhere, you can provide your own Lambda function.
- Tag Filters: If you have streams that are tagged using the the section called "TagStream" (p. 185) action, you can specify the tags of streams that you want to process. For example, if you have two streams that have the Location key with the values Front and Parking, you would filter to only use those streams using the following entry:

```
{"key":"Location","values":["Front","Parking"]}
```

Cleaning up the Application

After you've finished with the application that you created for this tutorial, we recommend that you delete any resources that you don't want to keep, to avoid incurring any ongoing charges.

- 1. Amazon SageMaker endpoint: If you created the Amazon SageMaker endpoint for this tutorial rather than using an existing endpoint, delete the endpoint. In the Amazon SageMaker control panel, choose Endpoint configurations. Choose the endpoint you created, and choose Actions, Delete. Confirm the deletion.
- 2. **Amazon SageMaker notebook:** On the Amazon SageMaker console, choose **Notebook instances**. Choose the notebook that you created, and choose **Actions**, **Stop**. When the notebook shows that its **Status** is **Stopped**, choose **Actions**, **Delete**. Confirm the deletion.

Note

For more information on cleaning up Amazon SageMaker resources, see Clean up in the Amazon SageMaker developer guide.

- Amazon SageMaker execution policy: On the IAM console, in the navigation pane, choose Policies.
 Choose the policy that you created for this tutorial. The name of the policy is similar to the following: AmazonSageMaker-ExecutionPolicy-timestamp
 - Choose Policy actions, Delete. Confirm the deletion.
- 4. Amazon SageMaker execution role: On the IAM console, in the navigation pane, choose Roles. Choose the role that you created for this tutorial. The name of the role is similar to the following: AmazonSageMaker-ExecutionRole-timestamp
 - Choose Delete role. Confirm the deletion.
- AWS CloudFormation stack: On the AWS CloudFormation console, choose the stack that you created for this tutorial. Choose Actions, Delete Stack. Confirm the deletion.
- 6. **Amazon S3 bucket:** On the Amazon S3 console, choose the bucket that you created to store the Amazon SageMaker assets. Choose **Delete**. Enter the name of the bucket and choose **Confirm** to confirm deletion.
- 7. **Kinesis video stream:** On the Kinesis Video Streams console, choose the video stream that you created for the application. Choose **Delete**. Confirm the deletion.

Monitoring Kinesis Video Streams

Monitoring is an important part of maintaining the reliability, availability, and performance of Kinesis Video Streams and your AWS solutions. You should collect monitoring data from all of the parts of your AWS solution so that you can more easily debug a multi-point failure if one occurs. Before you start monitoring Kinesis Video Streams, however, you should create a monitoring plan that includes answers to the following questions:

- · What are your monitoring goals?
- · What resources will you monitor?
- · How often will you monitor these resources?
- · What monitoring tools will you use?
- · Who will perform the monitoring tasks?
- · Who should be notified when something goes wrong?

After you have defined your monitoring goals and have created your monitoring plan, the next step is to establish a baseline for normal Kinesis Video Streams performance in your environment. You should measure Kinesis Video Streams performance at various times and under different load conditions. As you monitor Kinesis Video Streams, you should store a history of monitoring data that you've collected. You can compare current Kinesis Video Streams performance to this historical data to help you to identify normal performance patterns and performance anomalies, and devise methods to address issues that may arise.

Topics

- Monitoring Kinesis Video Streams Metrics with CloudWatch (p. 136)
- Logging Kinesis Video Streams API Calls with AWS CloudTrail (p. 143)

Monitoring Kinesis Video Streams Metrics with CloudWatch

You can monitor a Kinesis video stream using Amazon CloudWatch, which collects and processes raw data from Kinesis Video Streams into readable, near real-time metrics. These statistics are recorded for a period of 15 months, so that you can access historical information and gain a better perspective on how your web application or service is performing.

To access the CloudWatch dashboard for a Kinesis video stream, choose **View stream metrics in CloudWatch** in the **Stream info** section of the console page for the stream.

Kinesis Video Streams provides the following metrics:

Metric	Description
PutMedia.Requests	Number of PutMedia API requests for a given stream.
	Units: Count
PutMedia.IncomingBytes	Number of bytes received as part of PutMedia for the stream.
	Units: Bytes

Amazon Kinesis Video Streams Developer Guide Monitoring Metrics with CloudWatch

Metric	Description
PutMedia.IncomingFragments	Number of complete fragments received as part of PutMedia for the stream.
	Units: Count
PutMedia.IncomingFrames	Number of complete frames received as part of PutMedia for the stream.
	Units: Count
PutMedia.ActiveConnections	The total number of connections to the service host.
	Units: Count
PutMedia.ConnectionErrors	Errors while establishing PutMedia connection for the stream.
	Units: Count
PutMedia.FragmentIngestionLatency	Time difference between when the first and last bytes of a fragment are received by Kinesis Video Streams.
	Units: Milliseconds
PutMedia.FragmentPersistLatency	Time taken from when the complete fragment data is received and archived.
	Units: Count
PutMedia.Latency	Time difference between the request and the HTTP response from InletService while establishing the connection.
	Units: Count
PutMedia.BufferingAckLatency	Time difference between when the first byte of a new fragment is received by Kinesis Video Streams and when the Buffering ACK is sent for the fragment.
	Units: Milliseconds
PutMedia.ReceivedAckLatency	Time difference between when the last byte of a new fragment is received by Kinesis Video Streams and when the Received ACK is sent for the fragment.
	Units: Milliseconds
PutMedia.PersistedAckLatency	Time difference between when the last byte of a new fragment is received by Kinesis Video Streams and when the Persisted ACK is sent for the fragment.
	Units: Milliseconds
PutMedia.ErrorAckCount	Number of Error ACKs sent while doing PutMedia for the stream.
	Units: Count

Amazon Kinesis Video Streams Developer Guide Monitoring Metrics with CloudWatch

PutMedia.Success 1 for each fragment successfully written; O for every failed fragment. The average value of this metric indicates how many complete, valid fragments are sent. Units: Count GetMedia.Requests Number of GetMedia API requests for a given stream. Units: Count GetMedia.OutgoingBytes GetMedia.OutgoingFragments Number of fragments sent out from the service as part of the GetMedia API for a given stream. Units: Bytes Number of fragments sent while doing GetMedia for the stream. Units: Count GetMedia.OutgoingFrames Number of frames sent during GetMedia on the given stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; O for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingBytafotal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFramets apart of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFramets apart of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList API for a given stream. Units: Count	Metric	Description
Number of GetMedia API requests for a given stream. Units: Count	PutMedia.Success	failed fragment. The average value of this metric
Units: Count GetMedia.OutgoingBytes GetMedia.OutgoingFragments Number of fragments sent while doing GetMedia for the stream. Units: Bytes Number of fragments sent while doing GetMedia for the stream. Units: Count GetMedia.OutgoingFrames Number of frames sent during GetMedia on the given stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingBytafal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFraafal number of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFraafal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count		Units: Count
GetMedia.OutgoingBytes Total number of bytes sent out from the service as part of the GetMedia API for a given stream. Units: Bytes GetMedia.OutgoingFragments Number of fragments sent while doing GetMedia for the stream. Units: Count Number of frames sent during GetMedia on the given stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingByted and the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragment of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFragment of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count	GetMedia.Requests	Number of GetMedia API requests for a given stream.
of the GetMedia ÅPI for a given stream. Units: Bytes GetMedia.OutgoingFragments Number of fragments sent while doing GetMedia for the stream. Units: Count GetMedia.OutgoingFrames Number of frames sent during GetMedia on the given stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingByt dotted a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFramestal number of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFramestal number of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count		Units: Count
Number of fragments sent while doing GetMedia for the stream. Units: Count Number of frames sent during GetMedia on the given stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingByt dotal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFragmentList API for a given stream. Units: Count	GetMedia.OutgoingBytes	
the stream. Units: Count Number of frames sent during GetMedia on the given stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingByt detal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragment of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count		Units: Bytes
Number of frames sent during GetMedia on the given stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingBytastal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count	GetMedia.OutgoingFragments	_
stream. Units: Count GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingByt data number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentDist API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFragmentDist API for a given stream. Units: Count		Units: Count
GetMedia.MillisBehindNow Time difference between the current server timestamp and the server timestamp of the last fragment sent. Units: Milliseconds GetMedia.ConnectionErrors The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingBytdstal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentDist API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFragmentDist API for a given stream. Units: Count	GetMedia.OutgoingFrames	_
and the server timestamp of the last fragment sent. Units: Milliseconds The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingByteBatal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFratIntsumber of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.		Units: Count
The number of connections that were not successfully established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingBytdstal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFragmentList number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.	GetMedia.MillisBehindNow	
established. Units: Count GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingBytdstal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFradstalmumber of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFradstal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.		Units: Milliseconds
GetMedia.Success 1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingByt astal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentList api for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count	GetMedia.ConnectionErrors	
failure. The average value indicates the rate of success. Units: Count GetMediaForFragmentList.OutgoingBytestal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count		Units: Count
GetMediaForFragmentList.OutgoingByt detail number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragmentButumber of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.	GetMedia.Success	
of the GetMediaForFragmentList API for a given stream. Units: Bytes GetMediaForFragmentList.OutgoingFragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.		Units: Count
GetMediaForFragmentList.OutgoingFragmentBumber of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.	GetMediaForFragmentList.OutgoingBy	of the GetMediaForFragmentList API for a given
as part of the GetMediaForFragmentList API for a given stream. Units: Count GetMediaForFragmentList.OutgoingFrametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.		Units: Bytes
GetMediaForFragmentList.OutgoingFramesal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.	GetMediaForFragmentList.OutgoingFra	as part of the GetMediaForFragmentList API for a
part of the GetMediaForFragmentList API for a given stream.		Units: Count
Units: Count	GetMediaForFragmentList.OutgoingFra	part of the GetMediaForFragmentList API for a
		Units: Count

Amazon Kinesis Video Streams Developer Guide Monitoring Metrics with CloudWatch

Metric	Description
GetMediaForFragmentList.Requests	Number of GetMediaForFragmentList API requests for a given stream.
	Units: Count
GetMediaForFragmentList.Success	1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success.
	Units: Count
ListFragments.Latency	Latency of the ListFragments API calls for the given stream name.
	Units: Milliseconds
GetHLSStreamingSessionURL.Latency	Latency of the GetHLSStreamingSessionURL API calls for the given stream name.
	Units: Milliseconds
GetHLSStreamingSessionURL.Requests	Number of GetHLSStreamingSessionURL API requests for a given stream.
	Units: Count
GetHLSStreamingSessionURL.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.
	Units: Count
GetHLSMasterPlaylist.Latency	Latency of the GetHLSMasterPlaylist API calls for the given stream name.
	Units: Milliseconds
GetHLSMasterPlaylist.Requests	Number of GetHLSMasterPlaylist API requests for a given stream.
	Units: Count
GetHLSMasterPlaylist.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.
	Units: Count
GetHLSMediaPlaylist.Latency	Latency of the GetHLSMediaPlaylist API calls for the given stream name.
	Units: Milliseconds
GetHLSMediaPlaylist.Requests	Number of GetHLSMediaPlaylist API requests for a given stream.
	Units: Count
GetHLSMediaPlaylist.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.
	Units: Count

Amazon Kinesis Video Streams Developer Guide Monitoring Metrics with CloudWatch

Metric	Description
GetMP4InitFragment.Latency	Latency of the GetMP4InitFragment API calls for the given stream name.
	Units: Milliseconds
GetMP4InitFragment.Requests	Number of GetMP4InitFragment API requests for a given stream.
	Units: Count
GetMP4InitFragment.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.
	Units: Count
GetMP4MediaFragment.Latency	Latency of the GetMP4MediaFragment API calls for the given stream name.
	Units: Milliseconds
GetMP4MediaFragment.Requests	Number of GetMP4MediaFragment API requests for a given stream.
	Units: Count
GetMP4MediaFragment.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.
	Units: Count
GetMP4MediaFragment.OutgoingBytes	Total number of bytes sent out from the service as part of the GetMP4MediaFragment API for a given stream.
	Units: Bytes
GetTSFragment.Latency	Latency of the GetTSFragment API calls for the given stream name.
	Units: Milliseconds
GetTSFragment.Requests	Number of GetTSFragment API requests for a given stream.
	Units: Count
GetTSFragment.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.
	Units: Count
GetTSFragment.OutgoingBytes	Total number of bytes sent out from the service as part of the GetTSFragment API for a given stream.
	Units: Bytes

CloudWatch Metrics Guidance

CloudWatch metrics can be useful for finding answers to the following questions:

Topics

- Is data reaching the Kinesis Video Streams service? (p. 141)
- Why is data not being successfully ingested by the Kinesis Video Streams service? (p. 141)
- Why can't the data be read from the Kinesis Video Streams service at the same rate as it's being sent from the producer? (p. 142)
- Why is there no video in the console, or why is the video being played with a delay? (p. 142)
- What is the delay in reading real-time data, and why is the client lagging behind the head of the stream? (p. 142)
- Is the client reading data out of the Kinesis video stream, and at what rate? (p. 143)
- Why can't the client read data out of the Kinesis video stream? (p. 143)

Is data reaching the Kinesis Video Streams service?

Relevant metrics:

- PutMedia.IncomingBytes
- PutMedia.IncomingFragments
- PutMedia.IncomingFrames

Action items:

- If there is a drop in these metrics, check if your application is still sending data to the service.
- Check the network bandwidth. If your network bandwidth is insufficient, it could be slowing down the rate the service is receiving the data.

Why is data not being successfully ingested by the Kinesis Video Streams service?

Relevant metrics:

- PutMedia.Requests
- PutMedia.ConnectionErrors
- PutMedia.Success
- PutMedia.ErrorAckCount

Action items:

- If there is an increase in PutMedia.ConnectionErrors, look at the HTTP response/error codes received by the producer client to see what errors are occurring while establishing the connection.
- If there is a drop in PutMedia. Success or increase in PutMedia. ErrorAckCount, look at the ack
 error code in the ack responses sent by the service to see why ingestion of data is failing. For more
 information, see AckErrorCode.Values.

Why can't the data be read from the Kinesis Video Streams service at the same rate as it's being sent from the producer?

Relevant metrics:

- PutMedia.FragmentIngestionLatency
- PutMedia.IncomingBytes

Action items:

• If there is a drop in these metrics, check the network bandwidth of your connections. Low-bandwidth connections could cause the data to reach the service at a lower rate.

Why is there no video in the console, or why is the video being played with a delay?

Relevant metrics:

- PutMedia.FragmentIngestionLatency
- PutMedia.FragmentPersistLatency
- PutMedia.Success
- ListFragments.Latency
- PutMedia.IncomingFragments

Action items:

- If there is an increase in PutMedia.FragmentIngestionLatency or a drop in PutMedia.IncomingFragments, check the network bandwidth and whether the data is still being sent.
- If there is a drop in PutMedia.Success, check the ack error codes. For more information, see AckErrorCode.Values.
- If there is an increase in PutMedia.FragmentPersistLatency or ListFragments.Latency, you are most likely experiencing a service issue. If the condition persists for an extended period of time, check with your customer service contact to see if there is an issue with your service.

What is the delay in reading real-time data, and why is the client lagging behind the head of the stream?

Relevant metrics:

- GetMedia.MillisBehindNow
- GetMedia.ConnectionErrors
- GetMedia.Success

Action items:

• If there is an increase in GetMedia. ConnectionErrors, then the consumer might be falling behind in reading the stream, due to frequent attempts to re-connect to the stream. Look at the HTTP response/error codes returned for the GetMedia request.

- If there is a drop in GetMedia.Success, then it's likely due to the service being unable to send the data to the consumer, which would result in dropped connection, and reconnects from consumers, which would result in the consumer lagging behind the head of the stream.
- If there is an increase in GetMedia.MillisBehindNow, look at your bandwidth limits to see if you are receiving the data at a slower rate because of lower bandwidth.

Is the client reading data out of the Kinesis video stream, and at what rate?

Relevant metrics:

- GetMedia.OutgoingBytes
- GetMedia.OutgoingFragments
- GetMedia.OutgoingFrames
- GetMediaForFragmentList.OutgoingBytes
- GetMediaForFragmentList.OutgoingFragments
- GetMediaForFragmentList.OutgoingFrames

Action items:

• These metrics indicate what rate real-time and archived data is being read.

Why can't the client read data out of the Kinesis video stream?

Relevant metrics:

- GetMedia.ConnectionErrors
- GetMedia.Success
- GetMediaForFragmentList.Success
- PutMedia.IncomingBytes

Action items:

- If there is an increase in GetMedia.ConnectionErrors, look at the HTTP response/error codes returned by the GetMedia request. For more information, see AckErrorCode.Values.
- If you are trying to read the latest/live data, check PutMedia.IncomingBytes to see if there is data coming into the stream for the service to send to the consumers.
- If there is a drop in GetMedia.Success or GetMediaForFragmentList.Success, it's likely due to the service being unable to send the data to the consumer. If the condition persists for an extended period of time, check with your customer service contact to see if there is an issue with your service.

Logging Kinesis Video Streams API Calls with AWS CloudTrail

Amazon Kinesis Video Streams is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Amazon Kinesis Video Streams. CloudTrail captures all API calls for Amazon Kinesis Video Streams as events. The calls captured include calls from the Amazon

Amazon Kinesis Video Streams Developer Guide Kinesis Video Streams and CloudTrail

Kinesis Video Streams console and code calls to the Amazon Kinesis Video Streams API operations. If you create a trail, you can enable continuous delivery of CloudTrail events to an Amazon S3 bucket, including events for Amazon Kinesis Video Streams. If you don't configure a trail, you can still view the most recent events in the CloudTrail console in **Event history**. Using the information collected by CloudTrail, you can determine the request that was made to Amazon Kinesis Video Streams, the IP address from which the request was made, who made the request, when it was made, and additional details.

To learn more about CloudTrail, including how to configure and enable it, see the AWS CloudTrail User Guide.

Kinesis Video Streams and CloudTrail

CloudTrail is enabled on your AWS account when you create the account. When supported event activity occurs in Amazon Kinesis Video Streams, that activity is recorded in a CloudTrail event along with other AWS service events in **Event history**. You can view, search, and download recent events in your AWS account. For more information, see Viewing Events with CloudTrail Event History.

For an ongoing record of events in your AWS account, including events for Amazon Kinesis Video Streams, create a trail. A *trail* enables CloudTrail to deliver log files to an Amazon S3 bucket. By default, when you create a trail in the console, the trail applies to all AWS Regions. The trail logs events from all Regions in the AWS partition and delivers the log files to the Amazon S3 bucket that you specify. Additionally, you can configure other AWS services to further analyze and act upon the event data collected in CloudTrail logs. For more information, see the following:

- · Overview for Creating a Trail
- CloudTrail Supported Services and Integrations
- Configuring Amazon SNS Notifications for CloudTrail
- Receiving CloudTrail Log Files from Multiple Regions and Receiving CloudTrail Log Files from Multiple Accounts

Amazon Kinesis Video Streams supports logging the following actions as events in CloudTrail log files:

- CreateStream
- DeleteStream
- DescribeStream
- GetDataEndpoint
- ListStreams
- ListTagsForStream
- TagStream
- UntagStream
- UpdateDataRetention
- UpdateStream

Every event or log entry contains information about who generated the request. The identity information helps you determine the following:

- Whether the request was made with root or AWS Identity and Access Management (IAM) user credentials.
- Whether the request was made with temporary security credentials for a role or federated user.
- Whether the request was made by another AWS service.

For more information, see the CloudTrail userIdentity Element.

Example: Amazon Kinesis Video Streams Log File Fntries

A trail is a configuration that enables delivery of events as log files to an Amazon S3 bucket that you specify. CloudTrail log files contain one or more log entries. An event represents a single request from any source and includes information about the requested action, the date and time of the action, request parameters, and so on. CloudTrail log files aren't an ordered stack trace of the public API calls, so they don't appear in any specific order.

The following example shows a CloudTrail log entry that demonstrates the CreateStream action.

```
"Records": [
        {
            "eventVersion": "1.05",
            "userIdentity": {
                "type": "IAMUser",
                "principalId": "EX_PRINCIPAL_ID",
                "arn": "arn:aws:iam::123456789012:user/Alice",
                "accountId": "123456789012",
                "accessKeyId": "EXAMPLE_KEY_ID",
                "userName": "Alice"
            "eventTime": "2018-05-25T00:16:31Z",
            "eventSource": " kinesisvideo.amazonaws.com",
            "eventName": "CreateStream",
            "awsRegion": "us-east-1",
            "sourceIPAddress": "127.0.0.1",
            "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
            "requestParameters": {
                "streamName": "VideoStream",
                "dataRetentionInHours": 2,
                "mediaType": "mediaType",
                "kmsKeyId": "arn:aws:kms::us-east-1:123456789012:alias",
  "deviceName": "my-device"
            "responseElements": {
  "streamARN":arn:aws:kinesisvideo:us-east-1:123456789012:stream/VideoStream/12345"
            "requestID": "db6c59f8-c757-11e3-bc3b-57923b443c1c",
            "eventID": "b7acfcd0-6ca9-4ee1-a3d7-c4e8d420d99b"
        },
            "eventVersion": "1.05",
            "userIdentity": {
                "type": "IAMUser",
                "principalId": "EX_PRINCIPAL_ID",
                "arn": "arn:aws:iam::123456789012:user/Alice",
                "accountId": "123456789012",
                "accessKeyId": "EXAMPLE KEY ID",
                "userName": "Alice"
            "eventTime": "2018-05-25:17:06Z",
            "eventSource": " kinesisvideo.amazonaws.com",
            "eventName": "DeleteStream",
            "awsRegion": "us-east-1",
            "sourceIPAddress": "127.0.0.1",
            "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
            "requestParameters": {
                "streamARN": "arn:aws:kinesisvideo:us-east-1:012345678910:stream/
VideoStream/12345",
                "currentVersion": "keqrjeqkj9"
```

```
"responseElements": null,
    "requestID": "f0944d86-c757-11e3-b4ae-25654b1d3136",
    "eventID": "0b2f1396-88af-4561-b16f-398f8eaea596"
},
    "eventVersion": "1.05",
    "userIdentity": {
        "type": "IAMUser",
        "principalId": "EX_PRINCIPAL_ID",
        "arn": "arn:aws:iam::123456789012:user/Alice",
        "accountId": "123456789012",
        "accessKeyId": "EXAMPLE KEY ID",
        "userName": "Alice"
    "eventTime": "2014-04-19T00:15:02Z",
    "eventSource": " kinesisvideo.amazonaws.com",
    "eventName": "DescribeStream",
    "awsRegion": "us-east-1",
    "sourceIPAddress": "127.0.0.1",
    "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
    "requestParameters": {
        "streamName": "VideoStream"
    },
    "responseElements": null,
    "requestID": "a68541ca-c757-11e3-901b-cbcfe5b3677a",
    "eventID": "22a5fb8f-4e61-4bee-a8ad-3b72046b4c4d"
},
    "eventVersion": "1.05",
    "userIdentity": {
        "type": "IAMUser",
        "principalId": "EX_PRINCIPAL_ID",
        "arn": "arn:aws:iam::123456789012:user/Alice",
        "accountId": "123456789012",
        "accessKeyId": "EXAMPLE_KEY_ID",
        "userName": "Alice"
    "eventTime": "2014-04-19T00:15:03Z",
    "eventSource": "kinesisvideo.amazonaws.com",
    "eventName": "GetDataEndpoint",
    "awsRegion": "us-east-1",
    "sourceIPAddress": "127.0.0.1",
    "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
    "requestParameters": {
        "streamName": "VideoStream",
        "aPIName": "LIST FRAGMENTS"
    "responseElements": null,
    "requestID": "a6e6e9cd-c757-11e3-901b-cbcfe5b3677a",
    "eventID": "dcd2126f-c8d2-4186-b32a-192dd48d7e33"
    "eventVersion": "1.05",
    "userIdentity": {
        "type": "IAMUser",
        "principalId": "EX_PRINCIPAL_ID",
        "arn": "arn:aws:iam::123456789012:user/Alice",
        "accountId": "123456789012",
        "accessKeyId": "EXAMPLE_KEY_ID",
        "userName": "Alice"
    "eventTime": "2018-05-25T00:16:56Z",
    "eventSource": "kinesisvideo.amazonaws.com",
    "eventName": "ListStreams",
```

Amazon Kinesis Video Streams Developer Guide Example: Amazon Kinesis Video Streams Log File Entries

```
"awsRegion": "us-east-1",
    "sourceIPAddress": "127.0.0.1",
    "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
    "requestParameters": {
        "maxResults": 100,
        "streamNameCondition": {"comparisonValue":"MyVideoStream"
comparisonOperator":"BEGINS_WITH"}}
    },
    "responseElements": null,
    "requestID": "e9f9c8eb-c757-11e3-bf1d-6948db3cd570",
    "eventID": "77cf0d06-ce90-42da-9576-71986fec411f"
    }
]
```

Kinesis Video Streams Limits

Kinesis Video Streams has the following limits:

The limits below are either soft [s], which can be upgraded by submitting a support ticket, or hard [h], which cannot be increased.

Control Plane API limits

The following section describes limits for Control Plane APIs.

When an account-level Request limit is reached, a ClientLimitExceededException is thrown.

When an account-level Streams limit is reached, or a stream-level limit is reached, a StreamLimitExceededException is thrown.

Control Plane API limits

API	Account Limit: Request	Account Limit: Streams	Stream-level limit	Relevant Exceptions and Notes
CreateStream	50 TPS [s]	100 streams per account [s]	5 TPS [h]	Devices, CLIs, SDK-driven access, and the console can all invoke this API. Only one API call succeeds if the stream doesn't already exist.
DescribeStream	300 TPS [h]	N/A	5 TPS [h]	
UpdateStream	50 TPS [h]	N/A	5 TPS [h]	
ListStreams	300 TPS [h]	N/A	5 TPS [h]	
DeleteStream	50 TPS [h]	N/A	5 TPS [h]	
GetDataEndpoir	ත්රි00 TPS [h]	N/A	5 TPS [h]	Called every 45 minutes to refresh the streaming token for most PutMedia/GetMedia use cases. Called every 1,000 fragments for ListFragments/GetMediaForFragmentList. Caching data endpoints is safe if the application reloads them on failure.

Media and Archived Media API limits

The following section describes limits for Media and Archived Media APIs.

When a stream-level limit is exceeded, a StreamLimitExceededException is thrown.

When a connection-level limit is reached, a ConnectionLimitExceededException is thrown.

The following errors or acks are thrown when a fragment-level limit is reached:

Amazon Kinesis Video Streams Developer Guide Media and Archived Media API limits

- A MIN_FRAGMENT_DURATION_REACHED ack is returned for a fragment below the minimum duration.
- A MAX_FRAGMENT_DURATION_REACHED ack is returned for a fragment above the maximum duration.
- A MAX_FRAGMENT_SIZE ack is returned for a fragment above the maximum data size.
- A FragmentLimitExceeded exception is thrown if a fragment limit is reached in a GetMediaForFragmentList operation.

Data Plane API limits

API	Stream- level limit	Connection- level limit	Bandwidth limit	Fragment- level limit	Relevant Exceptions and Notes
PutMedia	5 TPS [h]	1 [s]	12.5 MB/ second, or 100 Mbps [s]	 Minimum fragment duration: 1 second [h] Maximum fragment duration: 10 seconds [h] Maximum fragment size: 50 MB [h] Maximum number of tracks: 3 [s] 	A typical PutMedia request contains data for several seconds, resulting in a lower TPS per stream. In the case of multiple concurrent connections that exceed limits, the last connection is accepted.
GetHLSStream	m f:ng/Se ssiiost/JF 1 TPS Sustained [h]	RIN/A	N/A	N/A	Only 10 sessions per stream can be active at a time [s]. After the limit has been reached, the oldest session is revoked when a new session is created.
GetMedia	5 TPS [h]	3 [s]	25 MB/s or 200 Mbps [s]	N/A	Only three clients can concurrently receive content from the media stream at any moment of time. Further client connections are rejected. A unique consuming client shouldn't need more than 2 or 3 TPS because after the connection is established, we anticipate that the application will read continuously. If a typical fragment is approximately 5 MB, this limit means ~75 MB/ sec per Kinesis video stream.

Amazon Kinesis Video Streams Developer Guide Media and Archived Media API limits

API	Stream- level limit	Connection- level limit	Bandwidth limit	Fragment- level limit	Relevant Exceptions and Notes
					Such a stream would have an outgoing bitrate of 2x the streams' maximum incoming bitrate.
ListFragment	s 5 TPS [h]	N/A	N/A	N/A	
GetMediaForl	r≨g#rœ{thList	5 [s]	25 MB/s or 200 MbpsA [s]	Maximum number of fragments: 1000 [h]	Five fragment-based consuming applications can concurrently get media. Further connections are rejected.

HLS API limits

API	Stream-level limit	Bandwidth limit	Fragment-level limit
GetHLSMasterPlaylist	5 TPS [h]	N/A	N/A
GetHLSMediaPlaylist	5 TPS [h]	N/A	Maximum number of fragments per playlist: 1000 [h]
GetMP4InitFragment	5 TPS [h]	N/A	N/A
GetMP4MediaFragment	10 TPS [h]	N/A	25 MB/s or 200 Mbps [s]
GetTSFragment	10 TPS [h]	N/A	25 MB/s or 200 Mbps [s]

Troubleshooting Kinesis Video Streams

Use the following information to troubleshoot common issues encountered with Amazon Kinesis Video Streams.

Topics

- Troubleshooting General Issues (p. 151)
- Troubleshooting API Issues (p. 151)
- Troubleshooting HLS Issues (p. 153)
- Troubleshooting Java Issues (p. 154)
- Troubleshooting Producer Library Issues (p. 155)
- Troubleshooting Stream Parser Library Issues (p. 159)

Troubleshooting General Issues

This section describes general issues that you might encounter when working with Kinesis Video Streams.

Issues

• Latency too high (p. 151)

Latency too high

Latency might be caused by the duration of fragments that are sent to the Kinesis Video Streams service. One way to reduce the latency between the producer and the service is to configure the media pipeline to produce shorter fragment durations.

To reduce the number of frames sent in each fragment, and thus reduce the amount of time for each fragment, reduce the following value in kinesis_video_gstreamer_sample_app.cpp:

```
g_object_set(G_OBJECT (data.encoder), "bframes", 0, "key-int-max", 45, "bitrate", 512,
NULL);
```

Note

Latencies are higher in the Mozilla Firefox browser due to the internal implementation of video rendering.

Troubleshooting API Issues

This section describes API issues that you might encounter when working with Kinesis Video Streams.

Issues

- Error: "Unknown options" (p. 152)
- Error: "Unable to determine service/operation name to be authorized" (p. 152)
- Error: "Failed to put a frame in the stream" (p. 152)

Amazon Kinesis Video Streams Developer Guide Error: "Unknown options"

- Error: "Service closed connection before final AckEvent was received" (p. 152)
- Error: "STATUS_STORE_OUT_OF_MEMORY" (p. 153)

Error: "Unknown options"

GetMedia and GetMediaForFragmentList can fail with the following error:

```
Unknown options: <filename>.mkv
```

This error occurs if you configured the AWS CLI with an output type of json. Reconfigure the AWS CLI with the default output type (none). For information about configuring the AWS CLI, see configure in the AWS CLI Command Reference.

Error: "Unable to determine service/operation name to be authorized"

GetMedia can fail with the following error:

```
Unable to determine service/operation name to be authorized
```

This error might occur if the endpoint is not properly specified. When you are getting the endpoint, be sure to include the following parameter in the GetDataEndpoint call, depending on the API to be called:

```
--api-name GET_MEDIA
--api-name PUT_MEDIA
--api-name GET_MEDIA_FOR_FRAGMENT_LIST
--api-name LIST_FRAGMENTS
```

Error: "Failed to put a frame in the stream"

PutMedia can fail with the following error:

```
Failed to put a frame in the stream
```

This error might occur if connectivity or permissions are not available to the service. Run the following in the AWS CLI, and verify that the stream information can be retrieved:

```
aws kinesisvideo describe-stream --stream-name StreamName --endpoint https://
ServiceEndpoint.kinesisvideo.region.amazonaws.com
```

If the call fails, see Troubleshooting AWS CLI Errors for more information.

Error: "Service closed connection before final AckEvent was received"

PutMedia can fail with the following error:

com.amazonaws.SdkClientException: Service closed connection before final AckEvent was received

This error might occur if PushbackInputStream is improperly implemented. Ensure that the unread() methods are correctly implemented.

Error: "STATUS_STORE_OUT_OF_MEMORY"

PutMedia can fail with the following error:

The content store is out of memory.

This error occurs when the content store is not allocated with sufficient size. To increase the size of the content store, increase the value of StorageInfo.storageSize. For more information, see StorageInfo (p. 88).

Troubleshooting HLS Issues

This section describes issues that you might encounter when using HTTP Live Streaming (HLS) with Kinesis Video Streams.

Issues

- Retrieving HLS streaming session URL succeeds, but playback fails in video player (p. 153)
- Latency too high between producer and player (p. 154)

Retrieving HLS streaming session URL succeeds, but playback fails in video player

This situation occurs when you can successfully retrieve an HLS streaming session URL using GetHLSStreamingSessionURL, but the video fails to play back when the URL is provided to a video player.

To troubleshoot this situation, try the following:

- Determine whether the video stream plays back in the Kinesis Video Streams console. Consider any errors that the console shows.
- If the fragment duration is less than one second, increase it to one second. If the fragment duration is too short, the service might throttle the player because it is making requests for video fragments too frequently.
- Verify that each HLS streaming session URL is being used by only one player. If more than one player
 is using a single HLS streaming session URL, the service might receive too many requests and throttle
 them.
- Verify that your player supports all of the options that you are specifying for the HLS streaming session. Try different combinations of values for the following parameters:
 - ContainerFormat
 - PlaybackMode
 - FragmentSelectorType
 - DiscontinuityMode
 - MaxMediaPlaylistFragmentResults

Some media players (like HTML5 and mobile players) typically only support HLS with the fMP4 container format. Other media players (like Flash and custom players) may only support HLS with the

MPEG TS container format. Experimenting with the ContainerFormat parameter is a good place to start troubleshooting.

• Verify that each fragment has a consistent number of tracks. Verify that fragments in the stream are not changing between having both an audio and video track and just a video track. Also verify that the encoder settings (resolution, frame rate, etc) are not changing between fragments in each track.

Latency too high between producer and player

This situation occurs when the latency is too high from when the video is captured to when it is played in the video player.

Video is played back through HLS on a per-fragment basis. Therefore, latency can't be less than fragment duration. Latency also includes the time needed for buffering and transferring data. If your solution requires latency of less than one second, consider using the GetMedia API instead.

You can adjust the following parameters to reduce the overall latency, but adjusting these parameters might also reduce the video quality or increase the rebuffering rate.

- Fragment duration: The fragment duration is the amount of video between divisions in the stream as controlled by the frequency of keyframes generated by the video encoder. The recommended value is one second. Having a shorter fragment duration means that less time is spent waiting for the fragment to complete before transmitting the video data to the service. Shorter fragments are also faster for the service to process. However, if the fragment duration is too short, the probability increases that the player will run out of content and have to stop and buffer content. If the fragment duration is less than 500 milliseconds, the producer might create too many requests, causing the service to throttle them.
- **Bitrate**: A video stream with a lower bitrate takes less time to read, write, and transmit. However, a video stream with a lower bitrate usually has a lower video quality.
- Fragment count in media playlists: A latency-sensitive player should only load the newest fragments in a media playlist. Most players start at the oldest fragment instead. By reducing the number of fragments in the playlist, you reduce the time separation between the old and new fragments. With a smaller playlist size, it is possible for a fragment to be skipped during playback, if there is a delay in adding new fragments to the playlist, or if there is a delay in the player getting an updated playlist. We recommend using 3–5 fragments, and to use a player that is configured to load only the newest fragments from a playlist.
- Player buffer size: Most video players have a configurable minimum buffer duration, usually with a 10-second default. For the lowest latency, you can set this value to 0 seconds. However, doing so means that the player rebuffers if there is any delay producing fragments because the player will have no buffer for absorbing the delay.
- Player "catch up": Video players typically don't automatically catch playback up to the front of the video buffer if the buffer fills up, such as when a delayed fragment causes a backlog of fragments to play. A custom player can avoid this by either dropping frames, or increasing the playback speed (for example, to 1.1x) to catch up to the front of the buffer. This causes playback to be choppy or increase in speed as the player catches up, and rebuffering might be more frequent as the buffer size is kept short.

Troubleshooting Java Issues

This section describes how to troubleshoot common Java issues encountered when working with Kinesis Video Streams.

Issues

• Enabling Java logs (p. 155)

Enabling Java logs

To troubleshoot issues with Java samples and libraries, it is helpful to enable and examine the debug logs. To enable debug logs, do the following:

1. Add log4j to the pom.xml file, in the dependencies node:

```
<dependency>
    <groupId>log4j</groupId>
    <artifactId>log4j</artifactId>
    <version>1.2.17</version>
</dependency>
```

2. In the target/classes directory, create a file named log4j.properties with the following contents:

```
# Root logger option
log4j.rootLogger=DEBUG, stdout

# Redirect log messages to console
log4j.appender.stdout=org.apache.log4j.ConsoleAppender
log4j.appender.stdout.Target=System.out
log4j.appender.stdout.layout=org.apache.log4j.PatternLayout
log4j.appender.stdout.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss} %-5p %c{1}:%L -
%m%n
log4j.logger.org.apache.http.wire=DEBUG
```

The debug logs then print to the IDE console.

Troubleshooting Producer Library Issues

This section describes issues that you might encounter when using the Producer Libraries (p. 34).

Issues

- Cannot compile the Producer SDK (p. 156)
- Video stream does not appear in the console (p. 156)
- Error: "Security token included in the request is invalid" when streaming data using the GStreamer demo application (p. 156)
- Error: "Failed to submit frame to Kinesis Video client" (p. 156)
- GStreamer application stops with "streaming stopped, reason not-negotiated" message on OS X (p. 157)
- Error: "Failed to allocate heap" when creating Kinesis Video Client in GStreamer demo on Raspberry Pi (p. 157)
- Error: "Illegal Instruction" when running GStreamer demo on Raspberry Pi (p. 157)
- Camera fails to load on Raspberry Pi (p. 157)
- Camera can't be found on macOS High Sierra (p. 158)
- jni.h file not found when compiling on macOS High Sierra (p. 158)
- Curl errors when running the GStreamer demo application (p. 158)
- Timestamp/range assertion at runtime on Raspberry Pi (p. 158)
- Assertion on gst_value_set_fraction_range_full on Raspberry Pi (p. 159)

- STATUS_MKV_INVALID_ANNEXB_NALU_IN_FRAME_DATA (0x3200000d) error on Android (p. 159)
- Maximum Fragment Duration Was Reached Error (p. 159)

Cannot compile the Producer SDK

Verify that the required libraries are in your path. To verify this, use the following command:

```
$ env | grep LD_LIBRARY_PATH
LD_LIBRARY_PATH=/home/local/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-
video-native-build/downloads/local/lib
```

Video stream does not appear in the console

To display your video stream in the console, it must be encoded using H.264 in AvCC format. If your stream is not displayed, verify the following:

- Your NAL Adaptation Flags (p. 87) are set to NAL_ADAPTATION_ANNEXB_NALS | NAL_ADAPTATION_ANNEXB_CPD_NALS if the original stream is in Annex-B format. This is the default value in the StreamDefinition constructor.
- You are providing the codec private data correctly. For H.264, this is the sequence parameter set (SPS) and picture parameter set (PPS). Depending on your media source, this data may be retrieved from the media source separately or encoded into the frame.

Many elementary streams are in the following format, where Ab is the Annex-B start code (001 or 0001):

```
Ab(Sps)Ab(Pps)Ab(I-frame)Ab(P/B-frame) ... Ab(Sps)Ab(Pps)Ab(I-frame)Ab(P/B-frame) Ab(P/B-frame)
```

The CPD (Codec Private Data) which in the case of H.264 is in the stream as SPS and PPS, can be adapted to the AvCC format. Unless the media pipeline gives the CPD separately, the application can extract the CPD from the frame by looking for the first Idr frame (which should contain the SPS/PPS), extract the two NALUs [which will be Ab(Sps)Ab(Pps)] and set it in the CPD in StreamDefinition.

Error: "Security token included in the request is invalid" when streaming data using the GStreamer demo application

If this error occurs, there is an issue with your credentials. Verify the following:

- If you are using temporary credentials, you must specify the session token.
- Verify that your temporary credentials are not expired.
- · Verify that you have the proper rights set up.
- On macOS, verify that you do not have credentials cached in Keychain.

Error: "Failed to submit frame to Kinesis Video client"

If this error occurs, the timestamps are not properly set in the source stream. Try the following:

- Use the latest SDK sample, which might have an update that fixes your issue.
- Set the high-quality stream to a higher bit rate, and fix any jitter in the source stream if the camera supports doing so.

GStreamer application stops with "streaming stopped, reason not-negotiated" message on OS X

Streaming may stop on OS X with the following message:

```
Debugging information: gstbasesrc.c(2939): void gst_base_src_loop(GstPad *) (): / GstPipeline:test-pipeline/GstAutoVideoSrc:source/GstAVFVideoSrc:source-actual-src-avfvide: streaming stopped, reason not-negotiated (-4)
```

A possible workaround for this is to remove the framerate parameters from the gst_caps_new_simple call in kinesis video gstreamer sample app.cpp:

```
GstCaps *h264_caps = gst_caps_new_simple("video/x-h264",

"profile", G_TYPE_STRING, "baseline",

"stream-format", G_TYPE_STRING, "avc",

"alignment", G_TYPE_STRING, "au",

"width", GST_TYPE_INT_RANGE, 320, 1920,

"height", GST_TYPE_INT_RANGE, 240, 1080,

"framerate", GST_TYPE_FRACTION_RANGE, 0, 1,

NULL);
```

Error: "Failed to allocate heap" when creating Kinesis Video Client in GStreamer demo on Raspberry Pi

The GStreamer sample application tries to allocate 512 MB of RAM, which might not be available on your system. You can reduce this allocation by reducing the following value in KinesisVideoProducer.cpp:

```
device_info.storageInfo.storageSize = 512 * 1024 * 1024;
```

Error: "Illegal Instruction" when running GStreamer demo on Raspberry Pi

If you encounter the following error when executing the GStreamer demo, ensure that you have compiled the application for the correct version of your device. (For example, ensure that you are not compiling for Raspberry Pi 3 when you are running on Raspberry Pi 2.)

```
INFO - Initializing curl.
Illegal instruction
```

Camera fails to load on Raspberry Pi

To check whether the camera is loaded, run the following:

Amazon Kinesis Video Streams Developer Guide Camera can't be found on macOS High Sierra

\$ ls /dev/video*

If nothing is found, run the following:

\$ vcgencmd get_camera

The output should look similar to the following:

supported=1 detected=1

If the driver does not detect the camera, do the following:

- Check the physical camera setup and verify that it's connected properly.
- 2. Run the following to upgrade the firmware:

\$ sudo rpi-update

- Restart the device.
- 4. Run the following to load the driver:

\$ sudo modprobe bcm2835-v412

5. Verify that the camera was detected:

\$ ls /dev/video*

Camera can't be found on macOS High Sierra

On macOS High Sierra, the demo application can't find the camera if more than one camera is available.

jni.h file not found when compiling on macOS High Sierra

To resolve this error, update your installation of Xcode to the latest version.

Curl errors when running the GStreamer demo application

To resolve curl errors when you run the GStreamer demo application, copy this certificate file to /etc/ssl/cert.pem.

Timestamp/range assertion at runtime on Raspberry Pi

If a timestamp range assertion occurs at runtime, update the firmware and restart the device:

\$ sudo rpi-update

\$ sudo reboot

Assertion on gst_value_set_fraction_range_full on Raspberry Pi

The following assertion appears if the uv41 service is running:

```
gst_util_fraction_compare (numerator_start, denominator_start, numerator_end,
  denominator_end) < 0' failed</pre>
```

If this occurs, stop the uv41 service and restart the application.

STATUS_MKV_INVALID_ANNEXB_NALU_IN_FRAME_DATA (0x3200000d) error on Android

The following error appears if the NAL Adaptation Flags (p. 87) are incorrect for the media stream:

```
putKinesisVideoFrame(): Failed to put a frame with status code 0x3200000d
```

If this error occurs, provide the correct .withNalAdaptationFlags flag for your media (for example, NAL_ADAPTATION_ANNEXB_CPD_NALS). Provide this flag in the following line of the Android Producer Library (p. 39):

https://github.com/awslabs/aws-sdk-android-samples/blob/master/AmazonKinesisVideoDemoApp/src/main/java/com/amazonaws/kinesisvideo/demoapp/fragment/StreamConfigurationFragment.java#L169

Maximum Fragment Duration Was Reached Error

This error occurs when a media fragment in a stream exceeds the maximum fragment duration limit. By default, Kinesis Video Streams sets a stream's maximum fragment duration to 10 seconds.

To resolve this issue, try the following:

- If you are using a webcam/USB camera, do one of the following:
 - If the you are using key frame-based fragmentation, then set the encoder to provide key frames within 10 seconds.
 - If you are not using key frame-based fragmentation, then when defining the stream in Step 2: Write and Examine the Code (p. 47), set the maximum fragment duration limit to a value that's less than 10 seconds.
 - If you are using software encoders (like x264) in the GStreamer pipeline, you can set the key-int-max attribute to a value within 10 seconds (for example, set key-int-max to 60, with fps set to 30, to enable key frames every 2 seconds).
- If you are using an RPI camera, set the keyframe-interval attribute to be less than 10 seconds.
- If you are using an IP (RTSP) camera, set the GOP size to 60.

Troubleshooting Stream Parser Library Issues

This section describes issues that you might encounter when using the Stream Parser Library (p. 107).

Issues

- Cannot access a single frame from the stream (p. 160)
- Fragment decoding error (p. 160)

Cannot access a single frame from the stream

To access a single frame from a streaming source in your consumer application, ensure that your stream contains the correct codec private data. For information about the format of the data in a stream, see Data Model (p. 22).

To learn how to use codec private data to access a frame, see the following test file on the GitHub website: KinesisVideoRendererExampleTest.java

Fragment decoding error

If your fragments are not properly encoded in an H.264 format and level that the browser supports, you might see the following error when playing your stream in the console:

Fragment Decoding Error

There was an error decoding the video data. Verify that the stream contains valid H.264 content

If this occurs, verify the following:

- The resolution of the frames matches the resolution specified in the Codec Private Data.
- The H.264 profile and level of the encoded frames matches the profile and level specified in the Codec Private Data.
- The browser supports the profile/level combination. Most current browsers support all profile and level combinations.
- The timestamps are accurate and in the correct order, and no duplicate timestamps are being created.
- Your application is encoding the frame data using the H.264 format.

Document History for Amazon Kinesis Video Streams

The following table describes the important changes to the documentation since the last release of Amazon Kinesis Video Streams.

• Latest API version: 2017-11-29

• Latest documentation update: January 21, 2019

Change	Description	Date
Getting Started: Send Data to a Kinesis video stream	Basic tutorial for sending media data from a camera to a Kinesis video stream. For more information, see Step 3: Send Data to a Kinesis Video Stream (p. 31).	January 21, 2019
Library template for integration with Amazon SageMaker	Sample application for Kinesis Video Streams that uses Amazon SageMaker to identify when certain objects appear in an Amazon Kinesis video stream. For more information, see Amazon SageMaker (p. 130).	November 19, 2018
Streaming metadata	You can use the Producer SDK to embed metadata in a Kinesis video stream. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 12).	September 28, 2018
C++ Producer SDK for Windows	The C++ Producer SDK is now available for Microsoft Windows. For more information, see Using the C++ Producer SDK on Windows (p. 53).	August 30, 2018
C++ Producer SDK logging	You can configure logging for C ++ Producer SDK applications. For more information, see Using Logging with the C++ Producer SDK (p. 62).	July 18, 2018
HLS video streaming	You can now view a Kinesis video stream using HTTP Live Streaming. For more information, see Kinesis Video Streams Playback with HLS (p. 9).	July 13, 2018

Change	Description	Date
Streaming from an RTSP source	Sample application for Kinesis Video Streams that runs in a Docker container and streams video from an RTSP source. For more information, see RTSP and Docker (p. 127).	June 20, 2018
C++ Producer SDK GStreamer Plugin	Shows how to build the C++ Producer Library (p. 44) to use as a GStreamer destination. For more information, see GStreamer (p. 115).	June 15, 2018
Producer SDK callbacks reference documentation	Reference documentation for the callbacks used by the Kinesis Video Streams Producer Libraries (p. 34). For more information, see Producer SDK Callbacks (p. 101).	June 12, 2018
System requirements	Documentation for memory and storage requirements for producer devices and SDK. For more information, see Kinesis Video Streams System Requirements (p. 3).	May 30, 2018
CloudTrail support	Documentation for using CloudTrail to monitor API usage. For more information, see Logging Kinesis Video Streams API Calls with AWS CloudTrail (p. 143).	May 24, 2018
Producer SDK structures reference documentation	Reference documentation for the structures used by the Kinesis Video Streams Producer Libraries (p. 34). For more information, see Producer SDK Structures (p. 88) and Kinesis Video Stream Structures (p. 89).	May 7, 2018
Renderer example documentation	Documentation for the Renderer example application, which shows how to decode and display frames from a Kinesis video stream. For more information, see Example: Parsing and Rendering Kinesis Video Streams Fragments (p. 128).	March 15, 2018

Change	Description	Date
Producer SDK Limits reference documentation	Information about limits for operations in the C++ Producer Library (p. 44). For more information, see Producer SDK Limits (p. 63).	March 13, 2018
C++ Producer SDK for Raspberry Pi	Procedure for setting up and running the C++ Producer Library (p. 44) on a Raspberry Pi device. For more information, see Using the C++ Producer SDK on Raspberry Pi (p. 57).	March 13, 2018
Monitoring	Information about monitoring Kinesis Video Streams metrics and API calls using Amazon CloudWatch and AWS CloudTrail. For more information, see Monitoring Kinesis Video Streams (p. 136).	February 5, 2018
Network Abstraction Layer (NAL) adaptation flag reference	Information about setting NAL adaptation flags when consuming streaming video. For more information, see NAL Adaptation Flags (p. 87).	January 15, 2018
Android support for streaming video	Kinesis Video Streams now supports streaming video from Android devices. For more information, see Android Producer Library (p. 39).	January 12, 2018
Kinesis Video example documentation	Documentation for the Kinesis Video example application, which shows how to use the Kinesis Video Stream Parser Library (p. 107) in an application. For more information, see KinesisVideoExample (p. 111).	January 9, 2018
Kinesis Video Streams documentation released	This is the initial release of the Amazon Kinesis Video Streams Developer Guide.	November 29, 2017

API Reference

This section contains the API Reference documentation.

Actions

The following actions are supported by Amazon Kinesis Video Streams:

- CreateStream (p. 166)
- DeleteStream (p. 170)
- DescribeStream (p. 173)
- GetDataEndpoint (p. 176)
- ListStreams (p. 179)
- ListTagsForStream (p. 182)
- TagStream (p. 185)
- UntagStream (p. 188)
- UpdateDataRetention (p. 190)
- UpdateStream (p. 193)

The following actions are supported by Amazon Kinesis Video Streams Media:

- GetMedia (p. 196)
- PutMedia (p. 200)

The following actions are supported by Amazon Kinesis Video Streams Archived Media:

- GetHLSStreamingSessionURL (p. 206)
- GetMediaForFragmentList (p. 213)
- ListFragments (p. 216)

Amazon Kinesis Video Streams

The following actions are supported by Amazon Kinesis Video Streams:

- CreateStream (p. 166)
- DeleteStream (p. 170)
- DescribeStream (p. 173)
- GetDataEndpoint (p. 176)
- ListStreams (p. 179)
- ListTagsForStream (p. 182)
- TagStream (p. 185)
- UntagStream (p. 188)
- UpdateDataRetention (p. 190)
- UpdateStream (p. 193)

Amazon Kinesis Video Streams De Amazon Kinesis Video Str	veloper Guide eams

CreateStream

Service: Amazon Kinesis Video Streams

Creates a new Kinesis video stream.

When you create a new stream, Kinesis Video Streams assigns it a version number. When you change the stream's metadata, Kinesis Video Streams updates the version.

CreateStream is an asynchronous operation.

For information about how the service works, see How it Works.

You must have permissions for the KinesisVideo: CreateStream action.

Request Syntax

```
POST /createStream HTTP/1.1
Content-type: application/json

{
    "DataRetentionInHours": number,
    "DeviceName": "string",
    "KmsKeyId": "string",
    "MediaType": "string",
    "StreamName": "string",
    "Tags": {
        "string" : "string"
    }
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

DataRetentionInHours (p. 166)

The number of hours that you want to retain the data in the stream. Kinesis Video Streams retains the data in a data store that is associated with the stream.

The default value is 0, indicating that the stream does not persist data.

When the DataRetentionInHours value is 0, consumers can still consume the fragments that remain in the service host buffer, which has a retention time limit of 5 minutes and a retention memory limit of 200 MB. Fragments are removed from the buffer when either limit is reached.

Type: Integer

Valid Range: Minimum value of 0.

Required: No

DeviceName (p. 166)

The name of the device that is writing to the stream.

Note

In the current implementation, Kinesis Video Streams does not use this name.

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [a-zA-Z0-9_.-]+

Required: No KmsKeyId (p. 166)

The ID of the AWS Key Management Service (AWS KMS) key that you want Kinesis Video Streams to use to encrypt stream data.

If no key ID is specified, the default, Kinesis Video-managed key (aws/kinesisvideo) is used.

For more information, see DescribeKey.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 2048.

Required: No MediaType (p. 166)

The media type of the stream. Consumers of the stream can use this information when processing the stream. For more information about media types, see Media Types. If you choose to specify the Media Type, see Naming Requirements for guidelines.

Example valid values include "video/h264" and "video/h264,audio/aac".

This parameter is optional; the default value is null (or empty in JSON).

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: $[\w\-\.\+]+/[\w\-\.\+]+/[\w\-\.\+]+/[\w\-\.\+]+/[\w\-\.\+]+)*$

Required: No StreamName (p. 166)

A name for the stream that you are creating.

The stream name is an identifier for the stream, and must be unique for each account and region.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: Yes

Tags (p. 166)

A list of tags to associate with the specified stream. Each tag is a key-value pair (the value is optional).

Type: String to string map

Key Length Constraints: Minimum length of 1. Maximum length of 128.

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Required: No

Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "StreamARN": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

StreamARN (p. 168)

The Amazon Resource Name (ARN) of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-Z0-9_.-]+/[0-9]+

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

AccountStreamLimitExceededException

The number of streams created for the account is too high.

HTTP Status Code: 400

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

DeviceStreamLimitExceededException

Not implemented.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

InvalidDeviceException

Not implemented.

HTTP Status Code: 400

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

ResourceInUseException

The stream is currently not available for this operation.

HTTP Status Code: 400

TagsPerResourceExceededLimitException

You have exceeded the limit of tags that you can associate with the resource. Kinesis video streams support up to 50 tags.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

DeleteStream

Service: Amazon Kinesis Video Streams

Deletes a Kinesis video stream and the data contained in the stream.

This method marks the stream for deletion, and makes the data in the stream inaccessible immediately.

To ensure that you have the latest version of the stream before deleting it, you can specify the stream version. Kinesis Video Streams assigns a version to each stream. When you update a stream, Kinesis Video Streams assigns a new version number. To get the latest stream version, use the DescribeStream API.

This operation requires permission for the KinesisVideo: DeleteStream action.

Request Syntax

```
POST /deleteStream HTTP/1.1
Content-type: application/json
{
    "CurrentVersion": "string",
    "StreamARN": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

CurrentVersion (p. 170)

Optional: The version of the stream that you want to delete.

Specify the version as a safeguard to ensure that your are deleting the correct stream. To get the stream version, use the DescribeStream API.

If not specified, only the CreationTime is checked before deleting the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: [a-zA-Z0-9]+

Required: No

StreamARN (p. 170)

The Amazon Resource Name (ARN) of the stream that you want to delete.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws: kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+

Required: Yes

Response Syntax

HTTP/1.1 200

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

Invalid Argument Exception

The value for this input parameter is invalid.

HTTP Status Code: 400 **NotAuthorizedException**

The caller is not authorized to perform this operation.

HTTP Status Code: 401

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

Amazon Kinesis Video Streams De Amazon Kinesis Video Str	veloper Guide eams

DescribeStream

Service: Amazon Kinesis Video Streams

Returns the most current information about the specified stream. You must specify either the StreamName or the StreamARN.

Request Syntax

```
POST /describeStream HTTP/1.1
Content-type: application/json
{
    "StreamARN": "string",
    "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

StreamARN (p. 173)

The Amazon Resource Name (ARN) of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-Z0-9_.-]+/[0-9]+

Required: No

StreamName (p. 173)

The name of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "StreamInfo": {
        "CreationTime": number,
        "DataRetentionInHours": number,
        "DeviceName": "string",
        "KmsKeyId": "string",
```

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

```
"MediaType": "string",
    "Status": "string",
    "StreamARN": "string",
    "StreamName": "string",
    "Version": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

StreamInfo (p. 173)

An object that describes the stream.

Type: StreamInfo (p. 220) object

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

Resource Not Found Exception

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java

- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

GetDataEndpoint

Service: Amazon Kinesis Video Streams

Gets an endpoint for a specified stream for either reading or writing. Use this endpoint in your application to read from the specified stream (using the GetMedia or GetMediaForFragmentList operations) or write to it (using the PutMedia operation).

Note

The returned endpoint does not have the API name appended. The client needs to add the API name to the returned endpoint.

In the request, specify the stream either by StreamName or StreamARN.

Request Syntax

```
POST /getDataEndpoint HTTP/1.1
Content-type: application/json

{
    "APIName": "string",
    "StreamARN": "string",
    "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

APIName (p. 176)

The name of the API action for which to get an endpoint.

```
Type: String

Valid Values: PUT_MEDIA | GET_MEDIA | LIST_FRAGMENTS |
GET_MEDIA_FOR_FRAGMENT_LIST | GET_HLS_STREAMING_SESSION_URL

Required: Yes
```

StreamARN (p. 176)

The Amazon Resource Name (ARN) of the stream that you want to get the endpoint for. You must specify either this parameter or a StreamName in the request.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: aws: kinesis video: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/[0-9]+... + [a-zA-Z0-9\_.-]+/[0-9]+... + [a-zA-Z0-9\_.-]+/[0-9]+/[0-9]+... + [a-zA-Z0-9\_.-]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/[0-9]+/
```

Required: No **StreamName (p. 176)**

The name of the stream that you want to get the endpoint for. You must specify either this parameter or a StreamARN in the request.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No

Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "DataEndpoint": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

DataEndpoint (p. 177)

The endpoint value. To read data from the stream or to write data to it, specify this endpoint in your application.

Type: String

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

ListStreams

Service: Amazon Kinesis Video Streams

Returns an array of StreamInfo objects. Each object describes a stream. To retrieve only streams that satisfy a specific condition, you can specify a StreamNameCondition.

Request Syntax

```
POST /listStreams HTTP/1.1
Content-type: application/json

{
    "MaxResults": number,
    "NextToken": "string",
    "StreamNameCondition": {
        "ComparisonOperator": "string",
        "ComparisonValue": "string"
    }
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

MaxResults (p. 179)

The maximum number of streams to return in the response. The default is 10,000.

Type: Integer

Valid Range: Minimum value of 1. Maximum value of 10000.

Required: No

NextToken (p. 179)

If you specify this parameter, when the result of a ListStreams operation is truncated, the call returns the NextToken in the response. To get another batch of streams, provide this token in your next request.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

Required: No

StreamNameCondition (p. 179)

Optional: Returns only streams that satisfy a specific condition. Currently, you can specify only the prefix of a stream name as a condition.

Type: StreamNameCondition (p. 222) object

Required: No

Response Syntax

```
HTTP/1.1 200
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

NextToken (p. 179)

If the response is truncated, the call returns this element with a token. To get the next batch of streams, use this token in your next request.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

StreamInfoList (p. 179)

An array of StreamInfo objects.

Type: Array of StreamInfo (p. 220) objects

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

• AWS Command Line Interface

- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

ListTagsForStream

Service: Amazon Kinesis Video Streams

Returns a list of tags associated with the specified stream.

In the request, you must specify either the StreamName or the StreamARN.

Request Syntax

```
POST /listTagsForStream HTTP/1.1
Content-type: application/json

{
    "NextToken": "string",
    "StreamARN": "string",
    "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

NextToken (p. 182)

If you specify this parameter and the result of a ListTagsForStream call is truncated, the response includes a token that you can use in the next request to fetch the next batch of tags.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

Required: No

StreamARN (p. 182)

The Amazon Resource Name (ARN) of the stream that you want to list tags for.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-z0-9_.-]+/[0-9]+

Required: No

StreamName (p. 182)

The name of the stream that you want to list tags for.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "NextToken": "string",
    "Tags": {
        "string" : "string"
    }
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

NextToken (p. 183)

If you specify this parameter and the result of a ListTags call is truncated, the response includes a token that you can use in the next request to fetch the next set of tags.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

Tags (p. 183)

A map of tag keys and values associated with the specified stream.

Type: String to string map

Key Length Constraints: Minimum length of 1. Maximum length of 128.

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

Invalid Resource Format Exception

The format of the StreamARN is invalid.

HTTP Status Code: 400

NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401 ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

TagStream

Service: Amazon Kinesis Video Streams

Adds one or more tags to a stream. A *tag* is a key-value pair (the value is optional) that you can define and assign to AWS resources. If you specify a tag that already exists, the tag value is replaced with the value that you specify in the request. For more information, see <u>Using Cost Allocation Tags</u> in the *AWS Billing and Cost Management User Guide*.

You must provide either the StreamName or the StreamARN.

This operation requires permission for the KinesisVideo: TagStream action.

Kinesis video streams support up to 50 tags.

Request Syntax

```
POST /tagStream HTTP/1.1
Content-type: application/json

{
    "StreamARN": "string",
    "StreamName": "string",
    "Tags": {
        "string" : "string"
    }
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

```
StreamARN (p. 185)
```

The Amazon Resource Name (ARN) of the resource that you want to add the tag or tags to.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

 $Pattern: arn: aws: kinesis video: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+... + [a-zA-Z0-9_.-]+/[0-9]+... + [a-zA-Z0-9_.-]+/[0-9]+/$

Required: No

StreamName (p. 185)

The name of the stream that you want to add the tag or tags to.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

Tags (p. 185)

A list of tags to associate with the specified stream. Each tag is a key-value pair (the value is optional).

Type: String to string map

Key Length Constraints: Minimum length of 1. Maximum length of 128.

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Required: Yes

Response Syntax

HTTP/1.1 200

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

InvalidResourceFormatException

The format of the StreamARN is invalid.

HTTP Status Code: 400

NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

TagsPerResourceExceededLimitException

You have exceeded the limit of tags that you can associate with the resource. Kinesis video streams support up to 50 tags.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

UntagStream

Service: Amazon Kinesis Video Streams

Removes one or more tags from a stream. In the request, specify only a tag key or keys; don't specify the value. If you specify a tag key that does not exist, it's ignored.

In the request, you must provide the StreamName or StreamARN.

Request Syntax

```
POST /untagStream HTTP/1.1
Content-type: application/json

{
    "StreamARN": "string",
    "StreamName": "string",
    "TagKeyList": [ "string" ]
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

```
StreamARN (p. 188)
```

The Amazon Resource Name (ARN) of the stream that you want to remove tags from.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn:aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-Z0-9_.-]+/[0-9]+

Required: No

StreamName (p. 188)

The name of the stream that you want to remove tags from.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

TagKeyList (p. 188)

A list of the keys of the tags that you want to remove.

Type: Array of strings

Array Members: Minimum number of 1 item. Maximum number of 50 items.

Length Constraints: Minimum length of 1. Maximum length of 128.

Required: Yes

Response Syntax

HTTP/1.1 200

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

InvalidResourceFormatException

The format of the StreamARN is invalid.

HTTP Status Code: 400 **NotAuthorizedException**

The caller is not authorized to perform this operation.

HTTP Status Code: 401

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

UpdateDataRetention

Service: Amazon Kinesis Video Streams

Increases or decreases the stream's data retention period by the value that you specify. To indicate whether you want to increase or decrease the data retention period, specify the Operation parameter in the request body. In the request, you must specify either the StreamName or the StreamARN.

Note

The retention period that you specify replaces the current value.

This operation requires permission for the KinesisVideo: UpdateDataRetention action.

Changing the data retention period affects the data in the stream as follows:

- If the data retention period is increased, existing data is retained for the new retention period. For example, if the data retention period is increased from one hour to seven hours, all existing data is retained for seven hours.
- If the data retention period is decreased, existing data is retained for the new retention period. For example, if the data retention period is decreased from seven hours to one hour, all existing data is retained for one hour, and any data older than one hour is deleted immediately.

Request Syntax

```
POST /updateDataRetention HTTP/1.1
Content-type: application/json

{
    "CurrentVersion": "string",
    "DataRetentionChangeInHours": number,
    "Operation": "string",
    "StreamARN": "string",
    "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

CurrentVersion (p. 190)

The version of the stream whose retention period you want to change. To get the version, call either the DescribeStream or the ListStreams API.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: [a-zA-Z0-9]+

Required: Yes

DataRetentionChangeInHours (p. 190)

The retention period, in hours. The value you specify replaces the current value. The maximum value for this parameter is 87600 (ten years).

Type: Integer

Valid Range: Minimum value of 1.

Required: Yes
Operation (p. 190)

Indicates whether you want to increase or decrease the retention period.

Type: String

Valid Values: INCREASE_DATA_RETENTION | DECREASE_DATA_RETENTION

Required: Yes StreamARN (p. 190)

The Amazon Resource Name (ARN) of the stream whose retention period you want to change.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-z0-9_.-]+/[0-9]+

Required: No StreamName (p. 190)

The name of the stream whose retention period you want to change.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

Response Syntax

HTTP/1.1 200

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400 **NotAuthorizedException**

The caller is not authorized to perform this operation.

HTTP Status Code: 401
ResourceInUseException

The stream is currently not available for this operation.

HTTP Status Code: 400
ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

UpdateStream

Service: Amazon Kinesis Video Streams

Updates stream metadata, such as the device name and media type.

You must provide the stream name or the Amazon Resource Name (ARN) of the stream.

To make sure that you have the latest version of the stream before updating it, you can specify the stream version. Kinesis Video Streams assigns a version to each stream. When you update a stream, Kinesis Video Streams assigns a new version number. To get the latest stream version, use the DescribeStream API.

UpdateStream is an asynchronous operation, and takes time to complete.

Request Syntax

```
POST /updateStream HTTP/1.1
Content-type: application/json

{
    "CurrentVersion": "string",
    "DeviceName": "string",
    "MediaType": "string",
    "StreamARN": "string",
    "StreamName": "string",
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

CurrentVersion (p. 193)

The version of the stream whose metadata you want to update.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: [a-zA-Z0-9]+

Required: Yes

DeviceName (p. 193)

The name of the device that is writing to the stream.

Note

In the current implementation, Kinesis Video Streams does not use this name.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [a-zA-Z0-9_.-]+

Required: No

MediaType (p. 193)

The stream's media type. Use MediaType to specify the type of content that the stream contains to the consumers of the stream. For more information about media types, see Media Types. If you choose to specify the MediaType, see Naming Requirements.

To play video on the console, you must specify the correct video type. For example, if the video in the stream is H.264, specify video/h264 as the MediaType.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Required: No StreamARN (p. 193)

The ARN of the stream whose metadata you want to update.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn:aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-z0-9_.-]+/[0-9]+

Required: No StreamName (p. 193)

The name of the stream whose metadata you want to update.

The stream name is an identifier for the stream, and must be unique for each account and region.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

Response Syntax

HTTP/1.1 200

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400 **NotAuthorizedException**

The caller is not authorized to perform this operation.

HTTP Status Code: 401 ResourceInUseException

The stream is currently not available for this operation.

HTTP Status Code: 400
ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- · AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

Amazon Kinesis Video Streams Media

The following actions are supported by Amazon Kinesis Video Streams Media:

- GetMedia (p. 196)
- PutMedia (p. 200)

GetMedia

Service: Amazon Kinesis Video Streams Media

Use this API to retrieve media content from a Kinesis video stream. In the request, you identify the stream name or stream Amazon Resource Name (ARN), and the starting chunk. Kinesis Video Streams then returns a stream of chunks in order by fragment number.

Note

You must first call the GetDataEndpoint API to get an endpoint. Then send the GetMedia requests to this endpoint using the --endpoint-url parameter.

When you put media data (fragments) on a stream, Kinesis Video Streams stores each incoming fragment and related metadata in what is called a "chunk." For more information, see PutMedia (p. 200). The GetMedia API returns a stream of these chunks starting from the chunk that you specify in the request.

The following limits apply when using the GetMedia API:

- A client can call GetMedia up to five times per second per stream.
- Kinesis Video Streams sends media data at a rate of up to 25 megabytes per second (or 200 megabits per second) during a GetMedia session.

Request Syntax

```
POST /getMedia HTTP/1.1
Content-type: application/json

{
    "StartSelector": {
        "AfterFragmentNumber": "string",
        "ContinuationToken": "string",
        "StartSelectorType": "string",
        "StartTimestamp": number
    },
    "StreamARN": "string",
    "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

StartSelector (p. 196)

Identifies the starting chunk to get from the specified stream.

```
Type: StartSelector (p. 223) object
```

Required: Yes StreamARN (p. 196)

The ARN of the stream from where you want to get the media content. If you don't specify the streamARN, you must specify the streamName.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-Z0-9_.-]+/[0-9]+

Required: No

StreamName (p. 196)

The Kinesis video stream name from where you want to get the media content. If you don't specify the streamName, you must specify the streamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-z0-9_.-]+

Required: No

Response Syntax

```
HTTP/1.1 200
Content-Type: ContentType

Payload
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The response returns the following HTTP headers.

ContentType (p. 197)

The content type of the requested media.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[a-zA-Z0-9_\.\-]+\$

The response returns the following as the HTTP body.

Payload (p. 197)

The payload Kinesis Video Streams returns is a sequence of chunks from the specified stream. For information about the chunks, see PutMedia (p. 200). The chunks that Kinesis Video Streams returns in the GetMedia call also include the following additional Matroska (MKV) tags:

- AWS_KINESISVIDEO_CONTINUATION_TOKEN (UTF-8 string) In the event your GetMedia call
 terminates, you can use this continuation token in your next request to get the next chunk where
 the last request terminated.
- AWS_KINESISVIDEO_MILLIS_BEHIND_NOW (UTF-8 string) Client applications can use this tag
 value to determine how far behind the chunk returned in the response is from the latest chunk on
 the stream.
- AWS_KINESISVIDEO_FRAGMENT_NUMBER Fragment number returned in the chunk.
- AWS KINESISVIDEO SERVER TIMESTAMP Server timestamp of the fragment.
- AWS_KINESISVIDEO_PRODUCER_TIMESTAMP Producer timestamp of the fragment.

The following tags will be present if an error occurs:

- AWS_KINESISVIDEO_ERROR_CODE String description of an error that caused GetMedia to stop.
- AWS_KINESISVIDEO_ERROR_ID: Integer code of the error.

The error codes are as follows:

- 3002 Error writing to the stream
- 4000 Requested fragment is not found
- 4500 Access denied for the stream's KMS key
- 4501 Stream's KMS key is disabled
- 4502 Validation error on the stream's KMS key
- 4503 KMS key specified in the stream is unavailable
- 4504 Invalid usage of the KMS key specified in the stream
- 4505 Invalid state of the KMS key specified in the stream
- 4506 Unable to find the KMS key specified in the stream
- 5000 Internal error

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

ConnectionLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client connections.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

InvalidEndpointException

Status Code: 400, Caller used wrong endpoint to write data to a stream. On receiving such an exception, the user must call GetDataEndpoint with AccessMode set to "READ" and use the endpoint Kinesis Video returns in the next GetMedia call.

HTTP Status Code: 400

NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

ResourceNotFoundException

Status Code: 404, The stream with the given name does not exist.

HTTP Status Code: 404

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

PutMedia

Service: Amazon Kinesis Video Streams Media

Use this API to send media data to a Kinesis video stream.

Note

Before using this API, you must call the GetDataEndpoint API to get an endpoint. You then specify the endpoint in your PutMedia request.

In the request, you use the HTTP headers to provide parameter information, for example, stream name, timestamp, and whether the timestamp value is absolute or relative to when the producer started recording. You use the request body to send the media data. Kinesis Video Streams supports only the Matroska (MKV) container format for sending media data using this API.

You have the following options for sending data using this API:

- Send media data in real time: For example, a security camera can send frames in real time as it generates them. This approach minimizes the latency between the video recording and data sent on the wire. This is referred to as a continuous producer. In this case, a consumer application can read the stream in real time or when needed.
- Send media data offline (in batches): For example, a body camera might record video for hours and store it on the device. Later, when you connect the camera to the docking port, the camera can start a PutMedia session to send data to a Kinesis video stream. In this scenario, latency is not an issue.

When using this API, note the following considerations:

- You must specify either streamName or streamARN, but not both.
- To be able to play the media on the console or via HLS, track 1 of each fragment should contain h.264 encoded video, the CodecID in the fragment metadata should be "V_MPEG/ISO/AVC", and the fragment metadata should include AVCC formatted h.264 codec private data. Optionally, track 2 of each fragment should contain AAC encoded audio, the CodecID in the fragment metadata should be "A_AAC", and the fragment metadata should include AAC codec private data.
- You might find it easier to use a single long-running PutMedia session and send a large number of media data fragments in the payload. For each fragment received, Kinesis Video Streams sends one or more acknowledgements. Potential network considerations might cause you to not get all these acknowledgements as they are generated.
- You might choose multiple consecutive PutMedia sessions, each with fewer fragments to ensure that you get all acknowledgements from the service in real time.

Note

If you send data to the same stream on multiple simultaneous PutMedia sessions, the media fragments get interleaved on the stream. You should make sure that this is OK in your application scenario.

The following limits apply when using the PutMedia API:

- A client can call PutMedia up to five times per second per stream.
- A client can send up to five fragments per second per stream.
- Kinesis Video Streams reads media data at a rate of up to 12.5 MB/second, or 100 Mbps during a PutMedia session.

Note the following constraints. In these cases, Kinesis Video Streams sends the Error acknowledgement in the response.

- Fragments that have time codes spanning longer than 10 seconds and that contain more than 50 MB of data are not allowed.
- Fragments containing more than three tracks are not allowed. Each frame in every fragment must have the same track number as one of the tracks defined in the fragment header. Additionally, every fragment must contain at least one frame for each track defined in the fragment header.
- Each fragment must contain at least one frame for each track defined in the fragment metadata.
- The earliest frame timestamp in a fragment must be after the latest frame timestamp in the previous fragment.
- An MKV stream containing more than one MKV segment or containing disallowed MKV elements (like track*) also results in the Error acknowledgement.

Kinesis Video Streams stores each incoming fragment and related metadata in what is called a "chunk." The fragment metadata includes the following:

- The MKV headers provided at the start of the PutMedia request
- The following Kinesis Video Streams-specific metadata for the fragment:
 - server_timestamp Timestamp when Kinesis Video Streams started receiving the fragment.
 - producer_timestamp Timestamp, when the producer started recording the fragment. Kinesis Video Streams uses three pieces of information received in the request to calculate this value.
 - The fragment timecode value received in the request body along with the fragment.
 - Two request headers: producerStartTimestamp (when the producer started recording) and fragmentTimeCodeType (whether the fragment timecode in the payload is absolute or relative).

Kinesis Video Streams then computes the producer_timestamp for the fragment as follows:

If fragmentTimeCodeType is relative, then

producer_timestamp = producerStartTimeStamp + fragment timecode

If fragmentTimeCodeType is absolute, then

producer timestamp = fragment timecode (converted to milliseconds)

• Unique fragment number assigned by Kinesis Video Streams.

Note

When you make the GetMedia request, Kinesis Video Streams returns a stream of these chunks. The client can process the metadata as needed.

Note

This operation is only available for the AWS SDK for Java. It is not supported in AWS SDKs for other languages.

Note

Kinesis Video Streams does not parse and validate the codec private data during ingestion and archival via the PutMedia API. KVS extracts and validates the necessary information from the codec private data for MPEG-TS and MP4 fragment packaging when consuming the stream via the HLS APIs.

Request Syntax

```
POST /putMedia HTTP/1.1
x-amzn-stream-name: StreamName
x-amzn-stream-arn: StreamARN
x-amzn-fragment-timecode-type: FragmentTimecodeType
```

x-amzn-producer-start-timestamp: ProducerStartTimestamp

Payload

URI Request Parameters

The request requires the following URI parameters.

FragmentTimecodeType (p. 201)

You pass this value as the x-amzn-fragment-timecode-type HTTP header.

Indicates whether timecodes in the fragments (payload, HTTP request body) are absolute or relative to producerStartTimestamp. Kinesis Video Streams uses this information to compute the producer_timestamp for the fragment received in the request, as described in the API overview.

Valid Values: ABSOLUTE | RELATIVE

ProducerStartTimestamp (p. 201)

You pass this value as the x-amzn-producer-start-timestamp HTTP header.

This is the producer timestamp at which the producer started recording the media (not the timestamp of the specific fragments in the request).

StreamARN (p. 201)

You pass this value as the x-amzn-stream-arn HTTP header.

Amazon Resource Name (ARN) of the Kinesis video stream where you want to write the media content. If you don't specify the streamARN, you must specify the streamName.

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-Z0-9_.-]+/[0-9]+

StreamName (p. 201)

You pass this value as the x-amzn-stream-name HTTP header.

Name of the Kinesis video stream where you want to write the media content. If you don't specify the streamName, you must specify the streamARN.

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Request Body

The request accepts the following binary data.

Payload (p. 201)

The media content to write to the Kinesis video stream. In the current implementation, Kinesis Video Streams supports only the Matroska (MKV) container format with a single MKV segment. A segment can contain one or more clusters.

Note

Each MKV cluster maps to a Kinesis video stream fragment. Whatever cluster duration you choose becomes the fragment duration.

Response Syntax

HTTP/1.1 200

Payload

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The response returns the following as the HTTP body.

Payload (p. 203)

After Kinesis Video Streams successfully receives a PutMedia request, the service validates the request headers. The service then starts reading the payload and first sends an HTTP 200 response.

The service then returns a stream containing a series of JSON objects (Acknowledgement objects) separated by newlines. The acknowledgements are received on the same connection on which the media data is sent. There can be many acknowledgements for a PutMedia request. Each Acknowledgement consists of the following key-value pairs:

- AckEventType Event type the acknowledgement represents.
 - **Buffering:** Kinesis Video Streams has started receiving the fragment. Kinesis Video Streams sends the first Buffering acknowledgement when the first byte of fragment data is received.
 - **Received:** Kinesis Video Streams received the entire fragment. If you did not configure the stream to persist the data, the producer can stop buffering the fragment upon receiving this acknowledgement.
 - **Persisted:** Kinesis Video Streams has persisted the fragment (for example, to Amazon S3). You get this acknowledgement if you configured the stream to persist the data. After you receive this acknowledgement, the producer can stop buffering the fragment.
 - Error: Kinesis Video Streams ran into an error while processing the fragment. You can review the error code and determine the next course of action.
 - Idle: The PutMedia session is in-progress. However, Kinesis Video Streams is currently not receiving data. Kinesis Video Streams sends this acknowledgement periodically for up to 30 seconds after the last received data. If no data is received within the 30 seconds, Kinesis Video Streams closes the request.

Note

This acknowledgement can help a producer determine if the PutMedia connection is alive, even if it is not sending any data.

• FragmentTimeCode - Fragment timecode for which acknowledgement is sent.

The element can be missing if the AckEventType is Idle.

- FragmentNumber Kinesis Video Streams-generated fragment number for which the acknowledgement is sent.
- ErrorId and ErrorCode If the AckEventType is ErrorId, this field provides corresponding error code. The following is the list of error codes:
 - · 4000 Error reading the data stream.
 - 4001 Fragment size is greater than maximum limit, 50 MB, allowed.
 - 4002 Fragment duration is greater than maximum limit, 10 seconds, allowed.
 - 4003 Connection duration is greater than maximum allowed threshold.
 - 4004 Fragment timecode is less than the timecode previous time code (within a PutMedia call, you cannot send fragments out of order).
 - 4005 More than one track is found in MKV. (deprecated)

- 4006 Failed to parse the input stream as valid MKV format.
- 4007 Invalid producer timestamp.
- 4008 Stream no longer exists (deleted).
- · 4009 Fragment metadata limit reached.
- 4010 The track number in an MKV frame did not match the tracks in the MKV header.
- 4011 The fragment did not contain any frames for at least one of the tracks in the MKV header.
- 4012 More than the allowed number of tracks found in the input MKV.
- 4500 Access to the stream's specified KMS key is denied.
- 4501 The stream's specified KMS key is disabled.
- 4502 The stream's specified KMS key failed validation.
- 4503 The stream's specified KMS key is unavailable.
- 4504 Invalid usage of the stream's specified KMS key.
- 4505 The stream's specified KMS key is in an invalid state.
- · 4506 The stream's specified KMS key is not found.
- · 5000 Internal service error
- 5001 Kinesis Video Streams failed to persist fragments to the data store.

Note

The producer, while sending the payload for a long running PutMedia request, should read the response for acknowledgements. A producer might receive chunks of acknowledgements at the same time, due to buffering on an intermediate proxy server. A producer that wants to receive timely acknowledgements can send fewer fragments in each PutMedia request.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

ConnectionLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client connections.

HTTP Status Code: 400

InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

InvalidEndpointException

Status Code: 400, Caller used wrong endpoint to write data to a stream. On receiving such an exception, the user must call GetDataEndpoint with AccessMode set to "READ" and use the endpoint Kinesis Video returns in the next GetMedia call.

HTTP Status Code: 400

NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401
ResourceNotFoundException

Status Code: 404, The stream with the given name does not exist.

HTTP Status Code: 404

Example

Acknowledgement Format

The format of the acknowledgement is as follows:

```
{
    Acknowledgement : {
        "EventType": enum
        "FragmentTimecode": Long,
        "FragmentNumber": Long,
        "ErrorId" : String
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- · AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- · AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

Amazon Kinesis Video Streams Archived Media

The following actions are supported by Amazon Kinesis Video Streams Archived Media:

- GetHLSStreamingSessionURL (p. 206)
- GetMediaForFragmentList (p. 213)
- ListFragments (p. 216)

GetHLSStreamingSessionURL

Service: Amazon Kinesis Video Streams Archived Media

Retrieves an HTTP Live Streaming (HLS) URL for the stream. You can then open the URL in a browser or media player to view the stream contents.

You must specify either the StreamName or the StreamARN.

An Amazon Kinesis video stream has the following requirements for providing data through HLS:

- The media must contain h.264 encoded video and, optionally, AAC encoded audio. Specifically, the codec id of track 1 should be V MPEG/ISO/AVC. Optionally, the codec id of track 2 should be A AAC.
- Data retention must be greater than 0.
- The video track of each fragment must contain codec private data in the Advanced Video Coding (AVC) for H.264 format (MPEG-4 specification ISO/IEC 14496-15). For information about adapting stream data to a given format, see NAL Adaptation Flags.
- The audio track (if present) of each fragment must contain codec private data in the AAC format (AAC specification ISO/IEC 13818-7).

Kinesis Video Streams HLS sessions contain fragments in the fragmented MPEG-4 form (also called fMP4 or CMAF), rather than the MPEG-2 form (also called TS chunks, which the HLS specification also supports). For more information about HLS fragment types, see the HLS specification.

The following procedure shows how to use HLS with Kinesis Video Streams:

- 1. Get an endpoint using GetDataEndpoint, specifying GET_HLS_STREAMING_SESSION_URL for the APIName parameter.
- Retrieve the HLS URL using GetHLSStreamingSessionURL. Kinesis Video Streams creates
 an HLS streaming session to be used for accessing content in a stream using the HLS protocol.
 GetHLSStreamingSessionURL returns an authenticated URL (that includes an encrypted session
 token) for the session's HLS master playlist (the root resource needed for streaming with HLS).

Note

Don't share or store this token where an unauthorized entity could access it. The token provides access to the content of the stream. Safeguard the token with the same measures that you would use with your AWS credentials.

The media that is made available through the playlist consists only of the requested stream, time range, and format. No other media data (such as frames outside the requested window or alternate bitrates) is made available.

- 3. Provide the URL (containing the encrypted session token) for the HLS master playlist to a media player that supports the HLS protocol. Kinesis Video Streams makes the HLS media playlist, initialization fragment, and media fragments available through the master playlist URL. The initialization fragment contains the codec private data for the stream, and other data needed to set up the video or audio decoder and renderer. The media fragments contain H.264-encoded video frames or AAC-encoded audio samples.
- 4. The media player receives the authenticated URL and requests stream metadata and media data normally. When the media player requests data, it calls the following actions:
 - **GetHLSMasterPlaylist:** Retrieves an HLS master playlist, which contains a URL for the GetHLSMediaPlaylist action for each track, and additional metadata for the media player, including estimated bitrate and resolution.
 - GetHLSMediaPlaylist: Retrieves an HLS media playlist, which contains a URL to access the MP4 initialization fragment with the GetMP4InitFragment action, and URLs to access the MP4 media fragments with the GetMP4MediaFragment actions. The HLS media playlist also contains metadata about the stream that the player needs to play it, such as whether the PlaybackMode is LIVE or ON_DEMAND. The HLS media playlist is typically static for sessions with a PlaybackType

of ON_DEMAND. The HLS media playlist is continually updated with new fragments for sessions with a PlaybackType of LIVE. There is a distinct HLS media playlist for the video track and the audio track (if applicable) that contains MP4 media URLs for the specific track.

• **GetMP4InitFragment:** Retrieves the MP4 initialization fragment. The media player typically loads the initialization fragment before loading any media fragments. This fragment contains the "fytp" and "moov" MP4 atoms, and the child atoms that are needed to initialize the media player decoder.

The initialization fragment does not correspond to a fragment in a Kinesis video stream. It contains only the codec private data for the stream and respective track, which the media player needs to decode the media frames.

• **GetMP4MediaFragment:** Retrieves MP4 media fragments. These fragments contain the "moof" and "mdat" MP4 atoms and their child atoms, containing the encoded fragment's media frames and their timestamps.

Note

After the first media fragment is made available in a streaming session, any fragments that don't contain the same codec private data cause an error to be returned when those different media fragments are loaded. Therefore, the codec private data should not change between fragments in a session. This also means that the session fails if the fragments in a stream change from having only video to having both audio and video.

Data retrieved with this action is billable. See Pricing for details.

• **GetTSFragment:** Retrieves MPEG TS fragments containing both initialization and media data for all tracks in the stream.

Note

If the ContainerFormat is MPEG_TS, this API is used instead of GetMP4InitFragment and GetMP4MediaFragment to retrieve stream media.

Data retrieved with this action is billable. For more information, see Kinesis Video Streams pricing.

Note

The following restrictions apply to HLS sessions:

- A streaming session URL should not be shared between players. The service might throttle
 a session if multiple media players are sharing it. For connection limits, see Kinesis Video
 Streams Limits.
- A Kinesis video stream can have a maximum of five active HLS streaming sessions. If a new session is created when the maximum number of sessions is already active, the oldest (earliest created) session is closed. The number of active GetMedia connections on a Kinesis video stream does not count against this limit, and the number of active HLS sessions does not count against the active GetMedia connection limit.

You can monitor the amount of data that the media player consumes by monitoring the GetMP4MediaFragment.OutgoingBytes Amazon CloudWatch metric. For information about using CloudWatch to monitor Kinesis Video Streams, see Monitoring Kinesis Video Streams. For pricing information, see Amazon Kinesis Video Streams Pricing and AWS Pricing. Charges for both HLS sessions and outgoing AWS data apply.

For more information about HLS, see HTTP Live Streaming on the Apple Developer site.

Request Syntax

```
POST /getHLSStreamingSessionURL HTTP/1.1
Content-type: application/json
{
```

```
"ContainerFormat": "string",
   "DiscontinuityMode": "string",
   "DisplayFragmentTimestamp": "string",
   "Expires": number,
   "HLSFragmentSelector": {
      "FragmentSelectorType": "string",
      "TimestampRange": {
         "EndTimestamp": number,
         "StartTimestamp": number
      }
   },
   "MaxMediaPlaylistFragmentResults": number,
   "PlaybackMode": "string",
   "StreamARN": "string",
   "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

ContainerFormat (p. 207)

Specifies which format should be used for packaging the media. Specifying the FRAGMENTED_MP4 container format packages the media into MP4 fragments (fMP4 or CMAF). This is the recommended packaging because there is minimal packaging overhead. The other container format option is MPEG_TS. HLS has supported MPEG TS chunks since it was released and is sometimes the only supported packaging on older HLS players. MPEG TS typically has a 5-25 percent packaging overhead. This means MPEG TS typically requires 5-25 percent more bandwidth and cost than fMP4.

The default is FRAGMENTED_MP4.

Type: String

Valid Values: FRAGMENTED_MP4 | MPEG_TS

Required: No

DiscontinuityMode (p. 207)

Specifies when flags marking discontinuities between fragments will be added to the media playlists. The default is ALWAYS when HLSFragmentSelector (p. 227) is SERVER_TIMESTAMP, and NEVER when it is PRODUCER_TIMESTAMP.

Media players typically build a timeline of media content to play, based on the timestamps of each fragment. This means that if there is any overlap between fragments (as is typical if HLSFragmentSelector (p. 227) is SERVER_TIMESTAMP), the media player timeline has small gaps between fragments in some places, and overwrites frames in other places. When there are discontinuity flags between fragments, the media player is expected to reset the timeline, resulting in the fragment being played immediately after the previous fragment. We recommend that you always have discontinuity flags between fragments if the fragment timestamps are not accurate or if fragments might be missing. You should not place discontinuity flags between fragments for the player timeline to accurately map to the producer timestamps.

Type: String

Valid Values: ALWAYS | NEVER

Required: No

DisplayFragmentTimestamp (p. 207)

Specifies when the fragment start timestamps should be included in the HLS media playlist. Typically, media players report the playhead position as a time relative to the start of the first fragment in the playback session. However, when the start timestamps are included in the HLS media playlist, some media players might report the current playhead as an absolute time based on the fragment timestamps. This can be useful for creating a playback experience that shows viewers the wall-clock time of the media.

The default is NEVER. When HLSFragmentSelector (p. 227) is SERVER_TIMESTAMP, the timestamps will be the server start timestamps. Similarly, when HLSFragmentSelector (p. 227) is PRODUCER TIMESTAMP, the timestamps will be the producer start timestamps.

Type: String

Valid Values: ALWAYS | NEVER

Required: No Expires (p. 207)

The time in seconds until the requested session expires. This value can be between 300 (5 minutes) and 43200 (12 hours).

When a session expires, no new calls to GetHLSMasterPlaylist, GetHLSMediaPlaylist, GetMP4InitFragment, or GetMP4MediaFragment can be made for that session.

The default is 300 (5 minutes).

Type: Integer

Valid Range: Minimum value of 300. Maximum value of 43200.

Required: No

HLSFragmentSelector (p. 207)

The time range of the requested fragment, and the source of the timestamps.

This parameter is required if PlaybackMode is ON_DEMAND. This parameter is optional if PlaybackMode is LIVE. If PlaybackMode is LIVE, the FragmentSelectorType can be set, but the TimestampRange should not be set. If PlaybackMode is ON_DEMAND, both FragmentSelectorType and TimestampRange must be set.

Type: HLSFragmentSelector (p. 227) object

Required: No

MaxMediaPlaylistFragmentResults (p. 207)

The maximum number of fragments that are returned in the HLS media playlists.

When the PlaybackMode is LIVE, the most recent fragments are returned up to this value. When the PlaybackMode is ON_DEMAND, the oldest fragments are returned, up to this maximum number.

When there are a higher number of fragments available in a live HLS media playlist, video players often buffer content before starting playback. Increasing the buffer size increases the playback latency, but it decreases the likelihood that rebuffering will occur during playback. We recommend that a live HLS media playlist have a minimum of 3 fragments and a maximum of 10 fragments.

The default is 5 fragments if PlaybackMode is LIVE, and 1,000 if PlaybackMode is ON DEMAND.

The maximum value of 1,000 fragments corresponds to more than 16 minutes of video on streams with 1-second fragments, and more than 2 1/2 hours of video on streams with 10-second fragments.

Type: Long

Valid Range: Minimum value of 1. Maximum value of 1000.

Required: No PlaybackMode (p. 207)

Whether to retrieve live or archived, on-demand data.

Features of the two types of session include the following:

• LIVE: For sessions of this type, the HLS media playlist is continually updated with the latest fragments as they become available. We recommend that the media player retrieve a new playlist on a one-second interval. When this type of session is played in a media player, the user interface typically displays a "live" notification, with no scrubber control for choosing the position in the playback window to display.

Note

In LIVE mode, the newest available fragments are included in an HLS media playlist, even if there is a gap between fragments (that is, if a fragment is missing). A gap like this might cause a media player to halt or cause a jump in playback. In this mode, fragments are not added to the HLS media playlist if they are older than the newest fragment in the playlist. If the missing fragment becomes available after a subsequent fragment is added to the playlist, the older fragment is not added, and the gap is not filled.

• ON_DEMAND: For sessions of this type, the HLS media playlist contains all the fragments for the session, up to the number that is specified in MaxMediaPlaylistFragmentResults. The playlist must be retrieved only once for each session. When this type of session is played in a media player, the user interface typically displays a scrubber control for choosing the position in the playback window to display.

In both playback modes, if FragmentSelectorType is PRODUCER_TIMESTAMP, and if there are multiple fragments with the same start timestamp, the fragment that has the larger fragment number (that is, the newer fragment) is included in the HLS media playlist. The other fragments are not included. Fragments that have different timestamps but have overlapping durations are still included in the HLS media playlist. This can lead to unexpected behavior in the media player.

The default is LIVE.

Type: String

Valid Values: LIVE | ON DEMAND

Required: No StreamARN (p. 207)

The Amazon Resource Name (ARN) of the stream for which to retrieve the HLS master playlist URL.

You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: aws: kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+

Required: No

StreamName (p. 207)

The name of the stream for which to retrieve the HLS master playlist URL.

You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "HLSStreamingSessionURL": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

HLSStreamingSessionURL (p. 211)

The URL (containing the session token) that a media player can use to retrieve the HLS master playlist.

Type: String

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400

InvalidCodecPrivateDataException

The codec private data in at least one of the tracks of the video stream is not valid for this operation.

HTTP Status Code: 400

MissingCodecPrivateDataException

No codec private data was found in at least one of tracks of the video stream.

HTTP Status Code: 400 NoDataRetentionException

A PlaybackMode of ON_DEMAND was requested for a stream that does not retain data (that is, has a DataRetentionInHours of 0).

HTTP Status Code: 400
NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401
ResourceNotFoundException

GetMedia throws this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL throws this error if a session with a PlaybackMode of ON_DEMAND is requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

UnsupportedStreamMediaTypeException

The type of the media (for example, h.264 video or ACC audio) could not be determined from the codec IDs of the tracks in the first fragment for a playback session. The codec ID for track 1 should be V_MPEG/ISO/AVC and, optionally, the codec ID for track 2 should be A_AAC.

HTTP Status Code: 400

See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- · AWS SDK for Python
- AWS SDK for Ruby V2

GetMediaForFragmentList

Service: Amazon Kinesis Video Streams Archived Media

Gets media for a list of fragments (specified by fragment number) from the archived data in an Amazon Kinesis video stream.

Note

You must first call the GetDataEndpoint API to get an endpoint. Then send the GetMediaForFragmentList requests to this endpoint using the --endpoint-url parameter.

The following limits apply when using the GetMediaForFragmentList API:

- A client can call GetMediaForFragmentList up to five times per second per stream.
- Kinesis Video Streams sends media data at a rate of up to 25 megabytes per second (or 200 megabits per second) during a GetMediaForFragmentList session.

Request Syntax

```
POST /getMediaForFragmentList HTTP/1.1
Content-type: application/json
{
    "Fragments": [ "string" ],
    "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

Fragments (p. 213)

A list of the numbers of fragments for which to retrieve media. You retrieve these values with ListFragments (p. 216).

Type: Array of strings

Array Members: Minimum number of 1 item. Maximum number of 1000 items.

Length Constraints: Minimum length of 1. Maximum length of 128.

```
Pattern: ^[0-9]+$
```

Required: Yes

StreamName (p. 213)

The name of the stream from which to retrieve fragment media.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: Yes

Response Syntax

```
HTTP/1.1 200
Content-Type: ContentType

Payload
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The response returns the following HTTP headers.

ContentType (p. 214)

The content type of the requested media.

Length Constraints: Minimum length of 1. Maximum length of 128.

```
Pattern: ^[a-zA-Z0-9_{\cdot}]+$
```

The response returns the following as the HTTP body.

Payload (p. 214)

The payload that Kinesis Video Streams returns is a sequence of chunks from the specified stream. For information about the chunks, see PutMedia. The chunks that Kinesis Video Streams returns in the GetMediaForFragmentList call also include the following additional Matroska (MKV) tags:

- AWS_KINESISVIDEO_FRAGMENT_NUMBER Fragment number returned in the chunk.
- AWS KINESISVIDEO SERVER SIDE TIMESTAMP Server-side timestamp of the fragment.
- AWS_KINESISVIDEO_PRODUCER_SIDE_TIMESTAMP Producer-side timestamp of the fragment.

The following tags will be included if an exception occurs:

- AWS_KINESISVIDEO_FRAGMENT_NUMBER The number of the fragment that threw the exception
- AWS_KINESISVIDEO_EXCEPTION_ERROR_CODE The integer code of the exception
- AWS_KINESISVIDEO_EXCEPTION_MESSAGE A text description of the exception

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400

NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401 ResourceNotFoundException

GetMedia throws this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL throws this error if a session with a PlaybackMode of ON_DEMAND is requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V2

ListFragments

Service: Amazon Kinesis Video Streams Archived Media

Returns a list of Fragment (p. 225) objects from the specified stream and timestamp range within the archived data.

Listing fragments is eventually consistent. This means that even if the producer receives an acknowledgment that a fragment is persisted, the result might not be returned immediately from a request to ListFragments. However, results are typically available in less than one second.

Note

You must first call the GetDataEndpoint API to get an endpoint. Then send the ListFragments requests to this endpoint using the --endpoint-url parameter.

Request Syntax

```
POST /listFragments HTTP/1.1
Content-type: application/json

{
    "FragmentSelector": {
        "FragmentSelectorType": "string",
        "TimestampRange": {
            "EndTimestamp": number,
            "StartTimestamp": number
        }
    },
    "MaxResults": number,
    "NextToken": "string",
    "StreamName": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

FragmentSelector (p. 216)

Describes the timestamp range and timestamp origin for the range of fragments to return.

Type: FragmentSelector (p. 226) object

Required: No

MaxResults (p. 216)

The total number of fragments to return. If the total number of fragments available is more than the value specified in max-results, then a ListFragments:NextToken (p. 217) is provided in the output that you can use to resume pagination.

Type: Long

Valid Range: Minimum value of 1. Maximum value of 1000.

Required: No

NextToken (p. 216)

A token to specify where to start paginating. This is the ListFragments:NextToken (p. 217) from a previously truncated response.

Type: String

Length Constraints: Minimum length of 1.

Required: No

StreamName (p. 216)

The name of the stream from which to retrieve a fragment list.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: Yes

Response Syntax

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

Fragments (p. 217)

A list of archived Fragment (p. 225) objects from the stream that meet the selector criteria. Results are in no specific order, even across pages.

Type: Array of Fragment (p. 225) objects

NextToken (p. 217)

If the returned list is truncated, the operation returns this token to use to retrieve the next page of results. This value is null when there are no more results to return.

Type: String

Length Constraints: Minimum length of 1.

Errors

For information about the errors that are common to all actions, see Common Errors (p. 229).

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400 **NotAuthorizedException**

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401
ResourceNotFoundException

GetMedia throws this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL throws this error if a session with a PlaybackMode of ON_DEMAND is requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- · AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- · AWS SDK for Python
- AWS SDK for Ruby V2

Data Types

The following data types are supported by Amazon Kinesis Video Streams:

- StreamInfo (p. 220)
- StreamNameCondition (p. 222)

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

The following data types are supported by Amazon Kinesis Video Streams Media:

• StartSelector (p. 223)

The following data types are supported by Amazon Kinesis Video Streams Archived Media:

- Fragment (p. 225)
- FragmentSelector (p. 226)
- HLSFragmentSelector (p. 227)
- HLSTimestampRange (p. 228)
- TimestampRange (p. 229)

Amazon Kinesis Video Streams

The following data types are supported by Amazon Kinesis Video Streams:

- StreamInfo (p. 220)
- StreamNameCondition (p. 222)

StreamInfo

Service: Amazon Kinesis Video Streams

An object describing a Kinesis video stream.

Contents

CreationTime

A time stamp that indicates when the stream was created.

Type: Timestamp

Required: No

DataRetentionInHours

How long the stream retains data, in hours.

Type: Integer

Valid Range: Minimum value of 0.

Required: No

DeviceName

The name of the device that is associated with the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [a-zA-Z0-9_.-]+

Required: No

KmsKeyId

The ID of the AWS Key Management Service (AWS KMS) key that Kinesis Video Streams uses to encrypt data on the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 2048.

Required: No

MediaType

The MediaType of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: $[\w\-\.+]+/[\w\-\.+]+(,[\w\-\.+]+/[\w\-\.+]+)*$

Required: No

Status

The status of the stream.

Type: String

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

```
Valid Values: CREATING | ACTIVE | UPDATING | DELETING
   Required: No
StreamARN
   The Amazon Resource Name (ARN) of the stream.
   Type: String
   Length Constraints: Minimum length of 1. Maximum length of 1024.
   Pattern: arn:aws:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
   Required: No
StreamName
   The name of the stream.
   Type: String
   Length Constraints: Minimum length of 1. Maximum length of 256.
   Pattern: [a-zA-Z0-9_.-]+
   Required: No
Version
   The version of the stream.
   Type: String
   Length Constraints: Minimum length of 1. Maximum length of 64.
   Pattern: [a-zA-Z0-9]+
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

• AWS SDK for C++

Required: No

- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for Ruby V2

StreamNameCondition

Service: Amazon Kinesis Video Streams

Specifies the condition that streams must satisfy to be returned when you list streams (see the ListStreams API). A condition has a comparison operation and a value. Currently, you can specify only the BEGINS_WITH operator, which finds streams whose names start with a given prefix.

Contents

ComparisonOperator

A comparison operator. Currently, you can specify only the BEGINS_WITH operator, which finds streams whose names start with a given prefix.

Type: String

Valid Values: BEGINS_WITH

Required: No **ComparisonValue**

A value to compare.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9_.-]+

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for Ruby V2

Amazon Kinesis Video Streams Media

The following data types are supported by Amazon Kinesis Video Streams Media:

• StartSelector (p. 223)

StartSelector

Service: Amazon Kinesis Video Streams Media

Identifies the chunk on the Kinesis video stream where you want the GetMedia API to start returning media data. You have the following options to identify the starting chunk:

- · Choose the latest (or oldest) chunk.
- Identify a specific chunk. You can identify a specific chunk either by providing a fragment number or timestamp (server or producer).
- Each chunk's metadata includes a continuation token as a Matroska (MKV) tag
 (AWS_KINESISVIDEO_CONTINUATION_TOKEN). If your previous GetMedia request terminated, you
 can use this tag value in your next GetMedia request. The API then starts returning chunks starting
 where the last API ended.

Contents

AfterFragmentNumber

Specifies the fragment number from where you want the GetMedia API to start returning the fragments.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[0-9]+\$

Required: No

ContinuationToken

Continuation token that Kinesis Video Streams returned in the previous GetMedia response. The GetMedia API then starts with the chunk identified by the continuation token.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[a-zA-Z0-9_\.\-]+\$

Required: No

StartSelectorType

Identifies the fragment on the Kinesis video stream where you want to start getting the data from.

- NOW Start with the latest chunk on the stream.
- EARLIEST Start with earliest available chunk on the stream.
- FRAGMENT_NUMBER Start with the chunk after a specific fragment. You must also specify the AfterFragmentNumber parameter.
- PRODUCER_TIMESTAMP or SERVER_TIMESTAMP Start with the chunk containing a fragment with the specified producer or server timestamp. You specify the timestamp by adding StartTimestamp.
- CONTINUATION_TOKEN Read using the specified continuation token.

Note

If you choose the NOW, EARLIEST, or CONTINUATION_TOKEN as the startSelectorType, you don't provide any additional information in the startSelector.

Type: String

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams Archived Media

```
Valid Values: FRAGMENT_NUMBER | SERVER_TIMESTAMP | PRODUCER_TIMESTAMP | NOW | EARLIEST | CONTINUATION TOKEN
```

Required: Yes **StartTimestamp**

A timestamp value. This value is required if you choose the PRODUCER_TIMESTAMP or the SERVER_TIMESTAMP as the startSelectorType. The GetMedia API then starts with the chunk containing the fragment that has the specified timestamp.

Type: Timestamp Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for Ruby V2

Amazon Kinesis Video Streams Archived Media

The following data types are supported by Amazon Kinesis Video Streams Archived Media:

- Fragment (p. 225)
- FragmentSelector (p. 226)
- HLSFragmentSelector (p. 227)
- HLSTimestampRange (p. 228)
- TimestampRange (p. 229)

Fragment

Service: Amazon Kinesis Video Streams Archived Media

Represents a segment of video or other time-delimited data.

Contents

FragmentLengthInMilliseconds

The playback duration or other time value associated with the fragment.

Type: Long

Required: No

FragmentNumber

The index value of the fragment.

Type: String

Length Constraints: Minimum length of 1.

Required: No

FragmentSizeInBytes

The total fragment size, including information about the fragment and contained media data.

Type: Long

Required: No

ProducerTimestamp

The timestamp from the producer corresponding to the fragment.

Type: Timestamp

Required: No

ServerTimestamp

The timestamp from the AWS server corresponding to the fragment.

Type: Timestamp

Required: No

See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for Ruby V2

FragmentSelector

Service: Amazon Kinesis Video Streams Archived Media

Describes the timestamp range and timestamp origin of a range of fragments.

Only fragments with a start timestamp greater than or equal to the given start time and less than or equal to the end time are returned. For example, if a stream contains fragments with the following start timestamps:

- 00:00:00
- 00:00:02
- 00:00:04
- 00:00:06

A fragment selector range with a start time of 00:00:01 and end time of 00:00:04 would return the fragments with start times of 00:00:02 and 00:00:04.

Contents

FragmentSelectorType

The origin of the timestamps to use (Server or Producer).

Type: String

Valid Values: PRODUCER_TIMESTAMP | SERVER_TIMESTAMP

Required: Yes
TimestampRange

The range of timestamps to return.

Type: TimestampRange (p. 229) object

Required: Yes

See Also

- · AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Go Pilot
- AWS SDK for Java
- AWS SDK for Ruby V2

HLSFragmentSelector

Service: Amazon Kinesis Video Streams Archived Media

Contains the range of timestamps for the requested media, and the source of the timestamps.

Contents

FragmentSelectorType

The source of the timestamps for the requested media.

When FragmentSelectorType is set to PRODUCER_TIMESTAMP and GetHLSStreamingSessionURL:PlaybackMode (p. 210) is ON_DEMAND, the first fragment ingested with a producer timestamp within the specified FragmentSelector:TimestampRange (p. 226) is included in the media playlist. In addition, the fragments with producer timestamps within the TimestampRange ingested immediately following the first fragment (up to the GetHLSStreamingSessionURL:MaxMediaPlaylistFragmentResults (p. 209) value) are included.

Fragments that have duplicate producer timestamps are deduplicated. This means that if producers are producing a stream of fragments with producer timestamps that are approximately equal to the true clock time, the HLS media playlists will contain all of the fragments within the requested timestamp range. If some fragments are ingested within the same time range and very different points in time, only the oldest ingested collection of fragments are returned.

When FragmentSelectorType is set to PRODUCER_TIMESTAMP and GetHLSStreamingSessionURL:PlaybackMode (p. 210) is LIVE, the producer timestamps are used in the MP4 fragments and for deduplication. But the most recently ingested fragments based on server timestamps are included in the HLS media playlist. This means that even if fragments ingested in the past have producer timestamps with values now, they are not included in the HLS media playlist.

The default is SERVER_TIMESTAMP.

Type: String

Valid Values: PRODUCER_TIMESTAMP | SERVER_TIMESTAMP

Required: No

TimestampRange

The start and end of the timestamp range for the requested media.

This value should not be present if PlaybackType is LIVE.

Type: HLSTimestampRange (p. 228) object

Required: No

See Also

- AWS SDK for C++
- AWS SDK for Go
- · AWS SDK for Go Pilot
- · AWS SDK for Java
- AWS SDK for Ruby V2

HLSTimestampRange

Service: Amazon Kinesis Video Streams Archived Media

The start and end of the timestamp range for the requested media.

This value should not be present if PlaybackType is LIVE.

Note

The values in the HLSTimestampRange are inclusive. Fragments that begin before the start time but continue past it, or fragments that begin before the end time but continue past it, are included in the session.

Contents

EndTimestamp

The end of the timestamp range for the requested media. This value must be within 3 hours of the specified StartTimestamp, and it must be later than the StartTimestamp value.

If FragmentSelectorType for the request is SERVER_TIMESTAMP, this value must be in the past.

If the HLSTimestampRange value is specified, the EndTimestamp value is required.

Note

This value is inclusive. The EndTimestamp is compared to the (starting) timestamp of the fragment. Fragments that start before the EndTimestamp value and continue past it are included in the session.

Type: Timestamp

Required: No StartTimestamp

The start of the timestamp range for the requested media.

If the HLSTimestampRange value is specified, the StartTimestamp value is required.

Note

This value is inclusive. Fragments that start before the StartTimestamp and continue past it are included in the session. If FragmentSelectorType is SERVER_TIMESTAMP, the StartTimestamp must be later than the stream head.

Type: Timestamp

Required: No

See Also

- · AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Go Pilot
- · AWS SDK for Java
- AWS SDK for Ruby V2

TimestampRange

Service: Amazon Kinesis Video Streams Archived Media

The range of timestamps for which to return fragments.

Contents

EndTimestamp

The ending timestamp in the range of timestamps for which to return fragments.

Type: Timestamp

Required: Yes

StartTimestamp

The starting timestamp in the range of timestamps for which to return fragments.

Type: Timestamp

Required: Yes

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- · AWS SDK for C++
- · AWS SDK for Go
- · AWS SDK for Go Pilot
- · AWS SDK for Java
- AWS SDK for Ruby V2

Common Errors

This section lists the errors common to the API actions of all AWS services. For errors specific to an API action for this service, see the topic for that API action.

AccessDeniedException

You do not have sufficient access to perform this action.

HTTP Status Code: 400

IncompleteSignature

The request signature does not conform to AWS standards.

HTTP Status Code: 400

InternalFailure

The request processing has failed because of an unknown error, exception or failure.

HTTP Status Code: 500

InvalidAction

The action or operation requested is invalid. Verify that the action is typed correctly.

Amazon Kinesis Video Streams Developer Guide Common Errors

HTTP Status Code: 400

InvalidClientTokenId

The X.509 certificate or AWS access key ID provided does not exist in our records.

HTTP Status Code: 403
InvalidParameterCombination

Parameters that must not be used together were used together.

HTTP Status Code: 400

InvalidParameterValue

An invalid or out-of-range value was supplied for the input parameter.

HTTP Status Code: 400

InvalidQueryParameter

The AWS query string is malformed or does not adhere to AWS standards.

HTTP Status Code: 400

MalformedQueryString

The query string contains a syntax error.

HTTP Status Code: 404

MissingAction

The request is missing an action or a required parameter.

HTTP Status Code: 400

MissingAuthenticationToken

The request must contain either a valid (registered) AWS access key ID or X.509 certificate.

HTTP Status Code: 403

MissingParameter

A required parameter for the specified action is not supplied.

HTTP Status Code: 400

OptInRequired

The AWS access key ID needs a subscription for the service.

HTTP Status Code: 403

RequestExpired

The request reached the service more than 15 minutes after the date stamp on the request or more than 15 minutes after the request expiration date (such as for pre-signed URLs), or the date stamp on the request is more than 15 minutes in the future.

HTTP Status Code: 400

ServiceUnavailable

The request has failed due to a temporary failure of the server.

HTTP Status Code: 503

Amazon Kinesis Video Streams Developer Guide Common Parameters

ThrottlingException

The request was denied due to request throttling.

HTTP Status Code: 400

ValidationError

The input fails to satisfy the constraints specified by an AWS service.

HTTP Status Code: 400

Common Parameters

The following list contains the parameters that all actions use for signing Signature Version 4 requests with a query string. Any action-specific parameters are listed in the topic for that action. For more information about Signature Version 4, see Signature Version 4 Signing Process in the Amazon Web Services General Reference.

Action

The action to be performed.

Type: string

Required: Yes

Version

The API version that the request is written for, expressed in the format YYYY-MM-DD.

Type: string

Required: Yes

X-Amz-Algorithm

The hash algorithm that you used to create the request signature.

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Valid Values: AWS4-HMAC-SHA256

Required: Conditional

X-Amz-Credential

The credential scope value, which is a string that includes your access key, the date, the region you are targeting, the service you are requesting, and a termination string ("aws4_request"). The value is expressed in the following format: access_key/YYYYMMDD/region/service/aws4_request.

For more information, see Task 2: Create a String to Sign for Signature Version 4 in the Amazon Web Services General Reference.

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Amazon Kinesis Video Streams Developer Guide Common Parameters

Required: Conditional

X-Amz-Date

The date that is used to create the signature. The format must be ISO 8601 basic format (YYYYMMDD'T'HHMMSS'Z'). For example, the following date time is a valid X-Amz-Date value: 20120325T120000Z.

Condition: X-Amz-Date is optional for all requests; it can be used to override the date used for signing requests. If the Date header is specified in the ISO 8601 basic format, X-Amz-Date is not required. When X-Amz-Date is used, it always overrides the value of the Date header. For more information, see Handling Dates in Signature Version 4 in the Amazon Web Services General Reference.

Type: string

Required: Conditional

X-Amz-Security-Token

The temporary security token that was obtained through a call to AWS Security Token Service (AWS STS). For a list of services that support temporary security credentials from AWS Security Token Service, go to AWS Services That Work with IAM in the IAM User Guide.

Condition: If you're using temporary security credentials from the AWS Security Token Service, you must include the security token.

Type: string

Required: Conditional

X-Amz-Signature

Specifies the hex-encoded signature that was calculated from the string to sign and the derived signing key.

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Required: Conditional

X-Amz-SignedHeaders

Specifies all the HTTP headers that were included as part of the canonical request. For more information about specifying signed headers, see Task 1: Create a Canonical Request For Signature Version 4 in the Amazon Web Services General Reference.

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Required: Conditional