Virtual Memory


We have stated that a UNIX process is a virtual computer in which a thread of execution (virtual processor) runs within a private virtual address space. In this unit, we will begin to explore the mechanisms by which this is implemented, both from a generic hardware and a generic kernel standpoint. In a later unit, we will return to this topic and see specific hardware architecture and kernel code.

All addresses used in a program are **virtual addresses**. Before being used to address physical memory or memory-mapped I/O, virtual addresses are **translated** to **physical addresses**. This translation is performed **by hardware** within the processor known as the **Memory Management Unit (MMU)**.

Since the operating system kernel has sole access to the MMU's lookup tables, it has the ability to completely control the view of memory a given process can see.

Address translation is performed with the granularity of a **page**. An address is divided into two parts: The **page number**, comprising the most significant bits, and the **offset**, comprising the least significant bits. Address translation operates on the **virtual page number**, replacing it with the **physical page number**. The offset is passed through unchanged. Typical page sizes are 2K, 4K and 8K. On the X86 32-bit and 64-bit architectures a page size of 4K is used.

Another name for a physical page of memory is a **page frame**, because we can think of physical pages as empty frames into which the actual meaningful content is placed from time to time. We'll see that a given page frame will hold many different virtual page images over time.




The virtual page number (conceptually) indexes the following per-page data:

- **Present bit**: If set, this virtual page is resident (maps to a physical page frame) and the physical page number field is valid. If the Present bit is clear, there is no physical page frame allocated to this virtual address. When there is no translation (page table entry has clear Present bit), it results in a **Page Fault**. As we will see, this is not necessarily a bad thing.
- The **Physical Page Number** (also known as the Page Frame number or PFN) which is translated for this virtual page. If the Present bit is clear, this field is invalid.
- **Protection bits**: Determines what type of accesses are allowed to this page: read, write, execute. An attempt to perform a disallowed access results in a **protection fault**. (Not all hardware maintains all three of these protection bits. In particular,

the x86 architecture prior to Pentium-4 has only two levels of access control: readonly and readwrite, and does not distinguish between protection faults and page faults.)

- **Dirty bit**: Set by hardware when a page is written to via this PTE. Cleared by the kernel when the page has been synced to backing storage.
- Accessed bit: Set by hardware when a page is accessed (read, write or execute) via this PTE. Cleared by the kernel while aging (scanning) page frames for re-use.
- User/Supervisor Bit: When set, this page can be accessed while the processor is in user mode. If clear, the processor must be in Supervisor (aka "kernel") mode to access the page. This allows kernel memory to be mapped into the virtual address space of a process and be visible only when the process enters the kernel. The Linux X86 architecture uses the User/Supervisor Bit approach, but other architectures switch to a different set of page tables upon entry to the kernel.



Multi-Level Page Tables

Conceptually, as depicted above, the virtual page number is an index into an array of Page Table Entries (PTEs), located at a specific physical address. There are several problems which prevent this from being a realistic implementation.


Let us consider a 32-bit architecture with 4K pages, therefore the page numbers are 20 bits long and there are 2^20 possible page numbers. If each PTE is 32 bits long, then each page table would consume 4MB. Although this might seem like a small amount of

memory, remember that each process on the system has its own page table. A system with 100 processes would therefore be wasting a large amount of memory on page tables.

The problem is even more severe on 64-bit machines which have a larger virtual address space. Even if only 48 bits of the address space are recognized, with a 4K page, there would be 2^36 PTEs (each PTE must be 64 bits to handle the longer addresses) consuming 2^39, or 512GB, of physical memory per process!

The problem of large page tables is addressed with **multi-level** page tables. The physical address of the top-level page table is given in the CPU/MMU "BASE" register (register %cr3 on X86). The most significant bits of the virtual address index into this top-level table. The result is not the page table entry, but is the physical address of the corresponding table at the next lower level of the hierarchy. That physical address, plus the bits from the next most significant part of the virtual address, locates the entry in the next page table, etc. At the last step, the actual PTE (page table entry) is fetched, which contains the PFN and the flags.

On modern computer architectures, 2-, 3- or 4-level paging structures are the norm. The illustration below shows 3 levels, and is meant to be schematic, not any particular processor type. 2-level or 3-level structures are typical for 32 bit machines, while 64 bit virtual addresses mandate 4-level structures to achieve any kind of memory efficiency.




Page tables are in effect a data structure, kept in physical memory. The layout of this data structure is mandated by the processor architecture. The kernel has been compiled with architecture-specific code that understands the layout of the page tables and can manipulate and manage them.

X86-32, 2-level page structure

On the X86 32 bit system, the page table is 2-level with the page number split 10/10 bits. The %cr3 special control register in the CPU (which must be running in Supervisor mode to change it) gives the 32-bit physical memory address of the start of the top-level table. The Linux kernel calls this the Page Global Directory (PGD). The PGD is an array of 1024 entries, each 32 bits long, and each entry (known as a PDE: Page Directory Entry) is in the same format as a Page Table Entry (PTE). However, the Page Frame Number (PFN) field of the PDE is a pointer to the next level of the 2-level structure. Each PGD entry represents 2^22 (4MB) of virtual address space.

We see that the PGD consumes 4096 bytes, or one physical page. The next level, the Page Table (PT), contains 1024 PTE (Page Table Entries) each 32 bits (4 bytes) long, thus

each PT also fits within a 4K page. The virtual address space and the physical address space are both 32 bits, or 4GB. There is a mode called Physical Address Extension (PAE), which we will not cover here, that makes physical addresses 64 bits so more than 4GB of physical RAM can be accessed. However, in PAE mode, virtual addresses are still limited to 32 bits. PAE is rarely used since most modern computers would operate in 64 bit mode.



X86-64, 4-level page structure


Under the X86 64 bit architecture, registers are 64 bits wide. Virtual addresses however are actually only 48 bits wide, and are sign-extended into the remaining 16 bits. This

makes addressing somewhat confusing. E.g. valid addresses jump from 0x0000 7FFF FFFF FFFF to 0xFFFF 8000 0000 0000 (spaces inserted for clarity). Therefore, a given virtual address space is limited to "only" 256TB. This point at which the addresses become "negative" is the dividing line in the Linux x86-64 kernel between user and kernel virtual memory. As with the 32-bit model, the kernel takes the upper portion. Now however the user process has 2^47=128TB of virtual address space and the kernel also has 128TB. The Intel X86-64 architecture supports up to 52 bits of physical addressing which is 4PB, although contemporary implementations use a much smaller physical address bus size.

Page size continues to be 4K to retain compatibility with older code. Therefore we have 48-12 = 36 bits remaining as a virtual page number. This is split evenly into four levels (9/9/9/9). Each PTE must be 64 bits wide since 32 bits would not be enough room to encode the 40-bit PFN. Therefore within one 4K table we get $2^9=512$ entries.

The %cr3 register (now 64 bits wide) points to the PGD, as with the 32-bit architecture. Entries in the PGD give the PFNs pointing to instances of the next level, which is called Page Upper Directory (PUD). The PUD in turn contains PFN pointers to instances of Page Middle Directories (PMD), which finally contain the pointers to the Page Tables which contain the PTEs.

Each entry of the PGD in 64 bit mode now references 2³⁹=512 GB of address space. Each PUD references 2³⁰=1GB, each PMD 2²¹=2MB and finally each PTE 2¹²=4KB.




Sparse and Shared Multi-Level Page Tables

It is possible for entries in these tables (other than the lowest-level page table itself) to contain "NULL pointers". This means that the entire contiguous range of virtual addresses corresponding to that entry is not mapped. This "NULL" pointer is implemented by having the Present bit of the entry set to 0. Whenever such a NULL pointer is encountered during the traversal of the multi-level page table structure, it causes a Page Fault, the same as if the Present bit of the PTE were 0.

The Linux kernel uses this advantageously in performing "just in time" page table allocations. All processes get allocated an individual PGD. However, the lower-level tables hanging off the PGD entries are not allocated until the corresponding areas of virtual memory are created (or grown) AND a page fault happens (see more under Page Fault Resolution) Areas of virtual memory which are not used (these can be quite large,

especially with a 64-bit system) do not consume additional resources. This is analogous to sparse file allocation (recall from unit 2 that when one lseeks beyond the current end of file and writes, this creates a "hole" in the file for which actual disk storage may not be allocated)

It is also possible for a given Page Table or PUD or PMD to be pointed at by more than one PGD. The Linux kernel uses this trick so it can create just one instance of the multilevel page table structure for the shared kernel memory, and allow all processes to share that (see more under Linux Address Space).



Translations Cache & Context Switch

Page table entries reside in main memory, and thus consume two important resources: The memory needed to store the page tables and the time required to perform translations. We have seen how multi-level page tables address the former concern. The latter is extremely significant too, since a translation must be performed on every memory access. If the MMU worked literally as described thus far, for a 2-level page table, 2

additional memory accesses would be required for every access attempted, i.e. memory performance would be reduced to one third. Therefore, a cache, often called the **Address Translation Cache (ATC)** or **Translation Lookaside Buffer (TLB)**, is used to speed translations.

Like any cache, the ATC is a content-addressable memory. A **key** is presented, and either the stored **value** is accessed (a **"hit"**), or the key is not found in the cache, which is known as a **cache miss**. Recall that the address translation process takes the page number portion of a virtual address and returns a page table entry. Therefore, the key in this case is the virtual address being translated (or more correctly, the page number portion of the VA), and the value accessed is the PTE.

For every virtual memory access, the ATC is searched to see if a valid, cached PTE exists for the referenced virtual page number. If so, the translation is performed using the cached page table entry. Otherwise, hardware traverses the page table structure and loads the correct translation, keeping it cached for possible future re-use. The cache is of finite (and typically rather small) size, so the insertion of a new cached translation into the ATC generally eradicates an older cache entry to make room.

A **context switch** is when the kernel changes from one process to another which implies a change in both the task and the address space. (in contrast, a **task switch**, at least in the Linux kernel, could be a change from one thread to another while staying in the same address space). To perform a context switch on X86, the kernel simply modifies the %cr3 register with the physical address of the PGD representing the new process. However, this creates a problem with the TLB, since the cached virtual address mappings are no longer valid in the new virtual address space.

On some architectures (e.g. SPARC, MIPS and X86-64), a **context number** or **Address Space ID** is used in conjunction with the ATC/TLB to disambiguate the virtual addresses of multiple processes' translations which might be resident in the cache at once. Each process is assigned a unique context number. A CPU special register contains the current context number and it is that number, combined with the virtual page number, which keys the associative array. To perform a context switch, both the page table base address register and the context number register are changed at the same time.

While the newer 64-bit X86 processors have support for a context number (it is 12 bits), neither the older 64-bit processors nor the 32-bit processors have this feature. Lacking context numbers, when the page table BASE register (%cr3) is changed, meaning a switch to a different address space, the CPU hardware invalidates (flushes) all TLB entries, except those where the cached PTE has a special G (Global) flag set. The Linux kernel creates the PTEs for the shared kernel virtual address space so they all have the G flag. Therefore, when making a context switch, while the user-mode PTEs get flushed, all of the kernel-mode PTEs can remain in the TLB. This is a big performance boost.


Another complication arises when the kernel has to change the PTE mapping for a given virtual page, e.g. an area of memory is being un-mapped, or changed from readonly to

readwrite. If the PTE is cached in the TLB it must be flushed. On older versions of the X86 processors, it was necessary to flush the entire TLB, but modern versions allow specific entries to be flushed individually with a special (supervisor mode) instruction called INVLPG.

Even more fun with TLB flushing comes on multiprocessor systems and especially multithreaded programs, because each processor maintains its own TLB. It could be that two or more physical processors are executing threads in the same address space (process). If the address space is changed in a way that would invalidate TLB entries, the other processors need to be alerted so they can flush their corresponding entries.

Because the TLB is small, performance is greatly improved when memory accesses are clustered so that, other than the first access, they "hit" the TLB cache. The kernel tries to optimize its internal data structures layout so as to keep frequently accessed data together within the same page. Thus the choice of memory address allocation within the kernel can have a profound impact on performance.

The figure below depicts the flow of address on a generic system with an MMU and a TLB, having the context number feature.



The UNIX user-level memory model

We have seen that the virtual address space of a process consists of a number of regions. These include:

- text region: holds the executable code
- data region: initialized global variables

- bss region: uninitialized (0-filled) global variables including dynamically-allocated variables. The ending address of this region is known as the **break address**, and can be queried or set with the brk system call. The break address may turn out to not fall on a page boundary, in which case the bss region really extends to the next page boundary beyond the break address. The standard C library function malloc ultimately uses brk to request additional bss memory from the kernel. Another name for the dynamically allocated part of the bss region is the heap. Typically, the static part of the bss region (corresponding to the declared variables) is the first part (lower memory addresses), and the heap is contiguous with it.
- stack region: function call stack and local variables. With multi-threaded processes, each thread has its own stack. Stack regions have the unusual property that they automatically grow (in the direction in which stacks usually grow, towards low memory addresses on most architectures) without an explicit system call.
- dynamically-linked libraries code
- initialized global variables for dynamically-linked libraries
- uninitialized global variables for dynamically-linked libraries
- shared memory being used for inter-process communication
- memory-mapped files

We will now see that from the kernel's standpoint, these memory region names have no particular significance. The kernel views a virtual address space as a list of regions, each of which has associated with it:

- The starting virtual address of the region (always aligned to a page boundary)
- The length of the region (a multiple of the page size), or equivalently the ending virtual address of the region.
- Bitwise flags which describe properties of the region such as the protections, or the fact that the region automatically grows towards low memory
- Backing store: If the memory region is backed by a node in the filesystem, then this mapping is described by device#/inode# and offset. Otherwise, the region is **anonymous**, and has no corresponding file.

Tracking the Address Space in the Linux Kernel

As depicted in the diagram later in this unit, each task_struct in the kernel contains a pointer to a struct mm_struct which represents an entire virtual address space (think of "mm" as "memory map"). One of the many elements of mm_struct is pgd, the physical address of the PGD. There is also the head of a linked list of memory regions, which are kept in ascending order of starting virtual address, and each of which are described by a struct vm_area_struct:

```
struct mm_struct {
          struct vm_area_struct *mmap; /* Head of linked list of regions */
          /* There's plenty more to this structure that we're skipping */
} ;
 struct vm_area_struct {
          /* And there is more to this structure to be seen later */
};
/* Explanation of vm_flags (bitwise combinations )
VM_READ Read permission
VM_WRITE Write permission
VM_EXEC Execute permission
VM_SHARED Region may be shared among multiple processes
VM_GROWSDOWN Region automatically grows towards lower addresses
VM_EXECUTABLE Region maps to an executable file
VM_LOCKED Region should be locked in memory and never swapped out
VM_IO Special region for memory-mapped I/O
VM_DONTCOPY Discard this region when forking instead of copying
VM_DONTEXPAND Disallow expansion of region with mremap
VM_DENYWRITE Disallow over-write of active text pages
* /
```

Establishing a new region with mmap

```
void *mmap(void *addr, size_t len, int prot, int flags,
                   int file_descriptor, off_t offset)
```

The mmap(2) system call causes the specified file which has already been opened with file_descriptor to be mapped into the process's address space, creating a new region. It can also be used to create a new anonymous memory region; these two choices are mutually exclusive. The first address of the mapped region will correspond to the specified offset in the file, which must be a multiple of the page size, for the specified length len. The virtual address at which to map the segment can be specified explicitly as addr, but usually it is left to the kernel to choose by passing NULL.

prot is a bitwise flag combination which can include the bits PROT_READ, PROT_WRITE or PROT_EXEC.

flags is a bitwise flag which can contain, among others:

- MAP_SHARED: Write operations to mapped region change the contents of the file.
- MAP_PRIVATE: Mutually exclusive with MAP_SHARED: Write operations to the mapped region do not change the contents of the file.
- MAP_DENYWRITE: Setting it will prevent write access to the mapped filed using the traditional write system call. See discussion at end of this unit. However, the Linux kernel currently prevents programs from setting this flag with the mmap system call, although the flag is used internally by the kernel to protect executable files.
- MAP_GROWSDOWN: The region should have the property that it automagically grows towards low memory, i.e. it is intended to be a stack region.
- MAP_ANONYMOUS: A new, anonymous region is being requested. The file_descriptor and offset parameters are ignored.

mmap within the kernel

The effect of (a successful) mmap call inside the kernel is to allocate a new vm_area_struct and to insert it into the singly-linked list of such memory regions that is hanging off the mm_struct. The vm_flags field is initialized based on the flags and prot arguments to the system call. E.g. PROT_READ maps to VM_READ, MAP_GROWSDOWN maps to VM_GROWSDOWN. If MAP_ANONYMOUS was specified, the vm_file is set to NULL, otherwise it points to the struct file (in kernel memory) that the file descriptor was referencing. Because the reference count (f_count) is incremented, the process may close the file descriptor after mmap, and the kernel "hangs on" to the open file instance. vm_pgoff is set to the offset argument, except the latter is specified in bytes, and is divided by 4096 (on X86 architecture) to arrive at vm_pgoff in pages. It is therefore an error to specify an offset which is not page-aligned.

Shared vs Private Mappings

When MAP_SHARED is specified (equivalent to VM_SHARED in kernel), writing to the memory region is immediately and transparently visible to this or any other process through the traditional system calls such as read. Likewise, any changes to the file, e.g. through write, are immediately visible through the mapped region.

When the mapping is MAP_PRIVATE, Copy on Write (see below) happens. Upon the first memory write access to a page in a MAP_PRIVATE region, the association between that virtual page and the file is broken. Thus writes to a MAP_PRIVATE region do NOT cause the associated file to be modified. It is unspecified if writes to the file (e.g. via the write system call) are visible in the memory region, before the association has been

broken by a write to the memory region. On the Linux kernel, they are (but see discussion of MAP_DENYWRITE).

Pages in a MAP_PRIVATE area, once they have been written to, become anonymous pages, because the association of that particular virtual page with that particular area of the mapped file has been broken. Therefore, if they need to be paged-out, they are sent to swap; they can not be paged-out to the original file.

File size not multiple of page size, file truncation

The mapped region may extend beyond the current end of the file. This could happen either because the len parameter specified is larger than the file, or because after the mapping has been established, the file size is reduced (e.g. through the truncate system call). If the process attempts to access memory which corresponds to just beyond the current end of file, but not beyond a page size boundary, it will see bytes with a value of 0. However, when the process tries to go further out, beyond the page boundary, even though the memory address is within the bounds of the mapped region, the kernel will be unable to satisfy the page fault, because the backing store does not exist in the filesystem. Under this condition, the kernel must deliver a **SIGBUS** to the process.

Read and write access via a file-mapped region will set the inode atime and mtime fields appropriately, but not necessarily instantaneously, for reasons which should become clear later in this unit when we look at the PFRA.

mmap'd segments are inherited by child processes in fork, using the copy-on-write mechanism for any writable regions, as described later. Multiple processes can share a mapped segment. In fact, a MAP_ANONYMOUS|MAP_SHARED region can be a useful inter-process communications tool. Note that when a region of memory has the MAP_SHARED property, copy-on-write does not apply to that region, and both processes after a fork continue to share the same physical memory for that region.

Remapping, Unmapping

The munmap system call destroys a memory region and any associated mapping to a file. The mremap system call is used to make an existing memory region larger or smaller, or to move it to another virtual address. mprotect can change the protections (R/W/X) associated with a region (but those new protections must be consistent with how the file descriptor was open in the case of file-mapped regions). The reader is encouraged to read the man pages for these system calls carefully. How these system calls manipulate the vm_area_structs should be obvious.

Exec and virtual memory

During the exec system call, a new address space is initialized and the existing address

space of a process is freed. The page tables themselves are freed and any physical pages that the process had mapped are placed on the free list. It is as if the process had called munmap for each of its regions.


The basis of the initialization of the new address space is the filename passed to the exec system call. This refers to an executable file in one of the binary executable formats which that operating system and processor type can execute. The first few bytes of the file determines the executable format, and are known as the **magic number**. We have seen that the a.out file contains the text region image, the data region initial image (variable initializers), and the initial requested size of the bss region.

In Unit 3, a highly conceptual model was presented of how a new program is loaded into memory during exec. Now that we understand mappings between files and virtual memory, we can take a more refined look and see that executable "loading" is really the establishment of a number of mmap regions.

- The text region is created as if the process had used mmap to create a mapping to the area in the a.out file holding the text image. The protections of the text region are PROT_READ|PROT_EXEC. The flags are MAP_PRIVATE|MAP_DENYWRITE. Note that since page frames are never allocated to virtual address spaces until an actual access occurs, the very first thing which the new program does, upon attempting to fetch its initial opcode from memory and execute it, is to cause a page fault! The program is demand-paged in from the a.out file as needed.
- The data region is created as if by mmap with MAP_PRIVATE|MAP_DENYWRITE. The mapping is to the area of the a.out file which contains the .data section (image of initializer values). The protections are PROT_READ|PROT_WRITE. Because the mapping is MAP_PRIVATE, the program "sees" the correct initializers when they are first accessed, but writes to those variables don't cause the unpleasant consequence of modifying the a.out file.
- The bss region is created, with the size requested in the a.out header, as a MAP_ANONYMOUS|MAP_PRIVATE mapping, with PROT_READ|PROT_WRITE protections. As it is accessed, the kernel will allocate page frames, zero-filling them first. As a MAP_ANONYMOUS region, the bss will be backed by swap space.
- The stack region is created with a small initial size and with the MAP_ANONYMOUS|MAP_GROWSDOWN properties. The protections are PROT_READ|PROT_WRITE. The stack region will be grown as it is accessed, as described previously, with new page frames being zero-filled. The stack is also backed by swap space.

In the example below, a new program has been set up by exec with a text region of 2

pages, data region 1 page long, and an initial bss region of 3 pages.



Why the MAP_DENYWRITE flag?

Both text and data regions are mapped with the MAP_DENYWRITE flag set. The reason for this is the following situation: Let's say a program is running from a particular a.out file, and then someone comes along and re-writes that executable (e.g. it is being recompiled or reinstalled). However, the running program is still mapped to the file, so what gets paged-in would be a mixture of the original contents of the file and the newer contents. Clearly this won't work...it amounts to a corruption of the program. The DENYWRITE flag will prevent any kind of write access to the executable file, including truncation. It will fail with the error ETXTBUSY. However, one can unlink or rename the executing a.out file, and install a new version with the same name. Since the mapping is based on inode number, not pathname, the currently running process (or processes) will

continue to use the old executable, while any new exec's would reference the new executable (since they evaluate a pathname, as if by **open**).

Those for the development of the Linux kernel responsible removed MAP_DENYWRITE from the list of flags that can be specified by the mmap system call (the flag is accepted but silently ignored). The reasoning went like this: User A which has read-only access to a file F could establish a read-only mmap mapping with DENYWRITE, even though they do not have write permission on F. This can create a denial-of-service attack, in that another user B, who does have write permission, would now be prevented from writing to the file. When the kernel sets up a new address space during exec, it is using internal versions of mmap, and is thus not actually using the flag MAP_DENYWRITE, but is specifying VM_DENYWRITE directly.

The Page Frame Pool

Now that we have made an initial exploration of how the kernel manages the virtual address space of processes, let's take a look from the standpoint of physical memory. We'll then put it together and discuss the mechanisms for paging-in and paging-out.

A computer system has a certain amount of physical RAM. Some of that is taken up statically by the kernel, i.e. kernel text, data and bss, and system control structures that must exist at a certain physical address, such as the Interrupt Descriptor Table. There are additional demands for physical memory:

- Dynamically allocated kernel data structures, e.g. the task_struct, kernel-mode stacks, in-core inodes and directory entries, pending signals, loadable kernel modules, and shared kernel/hardware data structures such as page tables.
- User process address space. We've seen that this can be broken down into anonymous regions, which are not persistent, and file-mapped regions where resident pages correspond to specific portions of specific, persistent files.
- I/O buffers. In some cases the I/O buffer corresponds to a portion of a file, but in other cases (e.g. network packet buffers) it does not.
- Filesystem block caches: Filesystems sometimes need to cache disk blocks which are not the actual contents of a given file, e.g. directory entries.

The demand for page frames ebbs and flows throughout the life of the system. At certain times, there may be abundant page frames which are empty and uncommitted, and therefore available for immediate allocation. At other times, the page frame pool may be depleted, causing pressure for page frames to be freed up to satisfy new demand. The kernel, through the Page Frame Reclamation Algorithm (PFRA), always tries to keep a reasonable number of free page frames, so that an allocation request does not fail or encounter excessive delay.

We will now consider how page frames are allocated by kernel routines, and how those

page frames may be subdivided for efficient allocation of smaller objects.

Addressing Issues on X86

Recall that the kernel, in a 32-bit X86 environment, uses the last 1GB of virtual address space for itself, leaving the first 3GB to user-mode. Also recall that all kernel virtual addresses are shared, i.e. there is not a separate kernel virtual address space for each process or component of the kernel. Therefore, it would seem to be impossible for the kernel to have more than 1GB of internal data structures.

This is addressed through an interesting strategy. Linux further subdivides both physical and kernel virtual space so that the first 896MB of physical page frames map directly to the first 896MB of the last GB of virtual address space. This greatly simplifies kernel code as a physical page number can be used directly to compute the virtual address and vice versa. The last 128MB of the kernel's virtual address space is used to establish temporary mappings to physical pages which are above 896MB. The kernel calls these two areas of physical memory zones, the former being the NORMAL zone and the latter the HIGHMEM zone. This klugery is not required for 64 bit architectures, where the kernel has ample virtual address space to make a direct mapping to all physical pages.

When allocating memory for internal data structures, the kernel uses the pool of pages in the NORMAL zone. Since user processes are not confined to the shared 1GB virtual address space, their pages always get pulled from the HIGHMEM zone first, and then, with reluctance, from the NORMAL zone if there is insufficient free memory in the HIGHMEM zone.

Page Descriptor Table

The kernel maintains a single, contiguous array of page descriptor structures, each of which represents one page frame:

```
struct page {
       /* This is a GCC compiler extension known as a blind union */
        union {
                unsigned long private;
                                                // buddy order, et al
               unsigned long private; // buddy order, et struct address_space *mapping; // reverse mapping
                                        /* offset of page within mapping*/
        pgoff_t index;
       struct list_head lru;
                                        /* free/active lists */
       void *virtual;
                                        /* kernel virt address */
};
```

The page descriptor table, called mem_map (another term often used in UNIX kernels other than Linux is "core map") consumes a small amount of memory overhead.

Specifically, on a 32-bit system, each struct page is 32 bytes long, so the overhead is 32/4096 or 0.7%. The page frame number is implicit by the index of the page descriptor within the mem_map array. For any given page, if it falls within the low-memory ("NORMAL") zone, the kernel can easily figure out the direct-mapped virtual address. Otherwise, if the page is currently mapped into kernel memory space, the virtual field says where.

A given page frame is either mapped (there is at least one PTE in somebody's virtual memory area, including the kernel's, that points to it) or it is free. To save space, some fields of the struct page are overloaded with mutually exclusive values. For example, the blind union private / mapping contains either information about the free page or information about the reverse mapping if it is mapped. The _mapcount field will be 0 if the page is free and >0 if the page is mapped somewhere. The confusingly named _count field is a temporary usage counter that is incremented when certain memory management routines are doing something with that page, and is used as a form of locking to prevent pages from disappearing while kernel code is playing with them. The flags field contains bitwise flags of the form PG_xxxxx which encode various status values. For example, the PG_locked flag is set when an I/O operation is in progress on that page. The usage of the other fields in the struct page will be discussed during the rest of this unit.

Page Allocator -- Buddy System

The basic kernel page frame allocator is based on asking for one or more contiguous pages. Although most of the time kernel routines are asking for just one page, sometimes the kernel needs a rather large buffer which spans many pages, e.g. when setting up a Direct Memory Access transfer to/from an I/O device.

In general, memory allocation routines (e.g. malloc() in user mode) are faced with a tradeoff between space efficiency and time efficiency. If there is a request for say 7 contiguous "units" of memory, it is desirable in terms of space efficiency to satisfy that request with exactly 7 units. However, as memory is allocated and freed, **fragmentation** arises. There may be 3 units free, then 1 occupied unit, then 4 more free units. Even though there are 7 free units, they are not contiguous and thus do not satisfy the request.

In some allocation settings, e.g. on-disk filesystems, it is possible to de-fragment the system by swapping storage locations so as to group clumps of free units together. This is not possible in the C programming environment because once memory has been allocated, its raw address has been passed back as a pointer and there is no way to track down all references (including offset references) to that memory region, and thus no way to change the address of the region.

Given that fragmentation is unavoidable, the next best thing in terms of space efficiency is, given a request for N contiguous units, satisfy it with the smallest available contiguous

region of size M units, M>=N. Now this leads to a time efficiency issue: how long will it take to search the list of available memory units to find this "best fit". In the case of the kernel, because memory allocation is a frequent and critical operation, it is desirable that this time be a constant one, not one which grows as the number of distinct free memory units increases because of fragmentation. Therefore, the Linux kernel makes a compromise, and adopts the well-known "buddy system" algorithm to give fairly decent space efficiency and lookup time which, although not strictly constant-time, has a small and fixed upper bound.

The "buddy system" algorithm maintains, for each of the memory allocation zones (e.g. NORMAL and HIGHMEM) an array of 11 pointers. The [0] element of this array points to a circular doubly-linked list of page descriptors for page frames which are free but not contiguous with other free pages. The [1] element points to such a list for groups of 2 contiguous pages. The [2] element does the same for groups of 4 contiguous pages, and so on up to the [10] element which collects groups of 1024 contiguous pages, i.e. 4MB. These lists are chained through the lru field of the page descriptor (which has other uses when the page frame is not free) and furthermore the private field of the first page descriptor in a contiguous chunk holds the order of that chunk. Subsequent page descriptors in the chunk are not part of the list but their existence is inferred by their position in the mem_map.

When a routine in the kernel wants say one page frame, the buddy system tries to take that from the [0] order list of free page frames. If there are none, it grabs a chunk of two page frames from the [1] list and splits it, handing one back to the caller and moving the other to the [0] list. If the [1] list is empty, this process continues moving up the ladder, e.g. taking a clump of 4 contiguous frames, returning 1 to the caller, and splitting the remainder into a single free frame and a pair of frames.

When a page frame or contiguous group of frames is de-allocated by the kernel to be placed back in the free pool, the "buddy system" checks to see if the freed page(s) is/are a contiguous "buddy" of another free page. If so, they are merged to form a higher-order contiguous region. This process can continue up to order 10, i.e. coalescing into a chunk of 1,024 free pages.

Note that the buddy system trades CPU time efficiency for absolute memory efficiency, by introducing an additional restriction. A group of pages on the, e.g. [2] list, i.e. a group of 4 contiguous pages, will always start with a page number divisible by 4. If say page frame numbers 1024-1027 inclusive are free, these can be used to satisfy a request for 4 contiguous pages. However, if 1025-1028 inclusive are free, this does not satisfy the request, because the start of the free area, 1025, is not a multiple of 4. Instead, the buddy system views this as a page of order 0 (#1025), two pages of order 1 (1026-1027) and another page (1028) of order 0.

Given a page frame number a, its order-N buddy with page frame number b therefore satisfies the expression:

```
b==a ^{(1<< N)}
Any page frame number a of order-N has a parent of order N+1 which lives at:
```

These simple bit-arithmetic relationships allow the deallocation and conglomeration algorithm to be performed very quickly, without extensive data structures manipulation and resulting memory accesses. The penalty is increased fragmentation.

Slab Allocator

The kernel subdivides page frames using a system called the **Slab Allocator** for small objects (e.g. allocating a new task_struct). This system is fairly complicated and will not be fully described here. The kernel grabs page frames and uses them as slabs, storing an internal descriptor at the beginning of the slab to track how the page frame or frames is being subdivided. Because the kernel is a tightly-controlled piece of code and the type of data structures which will need to be allocated and released frequently is understood in advance, the slab allocator can be optimized so that it can quickly allocate and free objects of a given type.

When the kernel requires space for a new object of a certain type, it consults the slab associated with that type. The slab descriptor bitmap quickly determines if there is a free slot open, and if so where. If there are no free slots, the slab allocator goes back to the page frame allocator and asks for an additional page (not necessarily contiguous) which is subdivided into slots.

Likewise, de-allocation of an object allocated through the slab allocator means simply noting in the descriptor that the slot is free. If all slots in the page frame are free, the page frame itself is released to the free pool.

The slab allocator is both space efficient (the overhead is just 1 bit in the bitmap per object, plus a few bytes for the overall slab header) and time efficient (no convoluted data structures). This is important because small data structures (such as struct file) are frequently being allocated and released by the kernel.

Address space release (munmap)

When a vm_area is destroyed via the munmap operation, either via the system call or the internal version which is called during exec or exit, the kernel visits the page tables which are spanned by that region. For any PRESENT PTE, the PFN gets us to the struct page. The mapcount is decremented. If this was the last mapping to the page and the count is now 0, the page is moved to the free list. This process is recursive. If an entire page table worth of PTEs have been freed up, the page table itself can be returned to the page frame pool. Finally when the entire process address space is free, the PGD is freed.

If any PTEs indicate that this was an anonymous page that had been swapped out, the kernel updates its *swap map*, decrementing the reference count on that swap slot. When the reference count is 0, the swap slot is free to be re-used.

Upon process termination, the kernel calls an internal version of munmap for each vm_area_struct in that process's address space. Therefore it is never necessary for user code to explicitly free memory prior to program exit!

Copy-On-Write and Fork

When the virtual address space is copied during fork, the kernel makes a deep copy of the struct mm_struct in the parent to form the memory map of the child. This means that each vm_area_struct is copied, forming a new linked list attached to the new mm_struct of the child. The page tables are also deep-copied. The child gets a new PGD which is a copy of the parent's, and any PUD, PMD and PTs are also recursively deep-copied. Each PTE in the parent is thus duplicated to the child, and if the page in question is Present, the reference count of the corresponding struct page is also incremented.

Regions that are writable and MAP_PRIVATE, including the data, bss and stack regions of any process, are set up for **copy-on-write**: the W bit is turned off in both the original parent PTE and the new child PTE. The Linux kernel also turns off the A bit in the child PTE. The vm_page_prot field of the vm_area_struct is modified so that any new PTE mappings in the shared memory regions (which would otherwise have the PTE_WRITE bit turned on because they have VM_WRITE) caused by a page fault are installed with the W bit off, which will allow the page frame to be shared until somebody tries to write to it.

Regions that have the VM_SHARED property (i.e. MAP_SHARED memory mapped regions) are **not** copy-on-write since by definition they are shared after a fork. The PTEs are not modified and the parent and child will continue to map to the same page frames for all pages in this shared region.

By way of contrast, during a clone system call, the task_struct is not deep-copied. The new task_struct of the child is a shallow copy of the parent. This means that the mm_struct and all subsidiary structures will simply be shared. All threads in a multi-threaded program, which are created with clone, thus share the same page frames. Furthermore, system calls such as mmap or munmap made by one thread affect all other threads in that process.


The Trinity of Memory and Addressing

We can look at randomly-addressable things from three standpoints:

- Virtual pages: The set of all virtual memory regions in all address spaces along with their associated properties
- Physical pages (page frames)
- The file and disk I/O system. Each file is randomly-addressable and portions of the file may be cached in physical memory. In addition, a file or a raw disk partition may be used as **swap space** to hold anonymous virtual pages when they have to be paged-out.

There are relationships in both directions between each of these three views, which are managed by various kernel data structures. The diagram near the end of this unit shows all of these together and can be quite intimidating. The relationships, or mappings, are as follows:

- Forward Mapping: Given a virtual page (i.e. a specific virtual memory area and offset within that area), what page frame holds it or, if no page frame holds it, how do we find the canonical contents of that page frame? The page table data structure, which ultimately delivers us to the PTE, determines the page frame. This is an N:1 mapping because a given page frame can be shared among multiple virtual memory regions (e.g. MAP_SHARED mmap). If the PTE is empty, the vm_file and vm_pgoff fields of the vm_area_struct point us in the right direction for finding the corresponding chunk of the file which backs up this virtual memory region.
- **Reverse Mapping**: For a given page frame, find all PTEs that map to it. Different data structures are used for reversed mapping depending on whether the given page is anonymous or file-mapped.
- **I/O Mapping**: When a given page-sized chunk of a file is wanted for a read or write system call, determine if that chunk is already cached in memory and if so, in what page frame?



These mappings form a circle, and thus it is difficult to present this material which has circularities in our comprehension prerequisites. We must jump into it at some point, so we will start with Forward Mapping!

Page Fault Handling -- Forward Mapping

The page fault exception is used by the CPU to indicate an access to an invalid or untranslated virtual address. However, this is usually not a real problem. The kernel enjoys handling page faults, and uses page faults to implement a number of features, one of which is **Demand Paging**: page frames are not actually allocated, and I/O operations (if applicable) are not actually initiated, until a process establishes the need to do so by attempting to access the corresponding virtual page. This is a significant speed and memory usage improvement. Without demand paging, programs would take a long time to load and start, because the entire program code (including all those libraries) and data would have to be read in from disk. With Demand Paging, only the code and data which is actually used consumes reserouces.

The kernel's page fault handler knows:

- The identity of the faulting process (current global variable)
- The attempted virtual address.
- The type of access (read/write).
- Whether the virtual page in question had a valid PTE

• The registers at the time of fault (including user/supervisor flag).

The page fault handler can have one of two general outcomes: Either the page fault is resolved, resulting in the establishment of a valid PTE (which has the appropriate R/W/X permissions for the access being attempted) pointing to a valid page frame with the correct data in it, or the page fault can not be resolved, resulting in the delivery of a SIGSEGV, SIGBUS or SIGKILL to the process. Let's take a look at the page fault handler code:

```
/* Please note: All of this code is fictional, but based on a true story.
 * It is a heavily simplified and cleansed condensation of actual Linux
 * kernel source code for page fault handling. Many of the variable and
* function names have been changed to protect the innocent. The interested
 * reader is invited to begin at /usr/src/linux/mm/memory.c
/* handle_pagefault_usermode() is the fictitious name of the fault handler
 * which is invoked when the MMU gives a page fault and the kernel determines
 * that the fault happened while in user mode. Because this is a synchronous
 * entry into the kernel, the current variable is that of the process which
* caused the page fault. Upon return from this function, we will return to
^{\star} user mode and either the faulted instruction will be re-started or a
* signal handler will be invoked
handle_pagefault_usermode(void *addr, int access_type)
struct vm_area_struct *vma, *growsdown;
void *new_addr;
         if (addr >= KERNEL MEMORY START)
                                             // Attempt to access kmem from user
                  force sig(current, SIGSEGV);
         /* Note: the force_sig function posts the requested signal to the
          * specified task. If that signal is currently being ignored or
          * blocked, the setting is changed to SIG_DFL which usually terminates.
          * We can't ignore or defer the signal because the current instruction
          * has faulted and therefore continued execution makes no sense */
         growsdown=NULL;
         /* Is the fault address inside of a defined region? */
         for (vma=current->mm->mmap; vma; vma=vma->vm_next)
                  if (addr>=vm->vm_start && addr<vm->vm_end) break;
                  if (vm->vm_flags & VM_GROWSDOWN &&
                           vm->vm_start-addr < STACK_FUZZINESS &&
                            regs->esp <= addr + STACK_FUZZINESS)</pre>
                                   growsdown=vma;
         if (!vma && growsdown)
                  vma=growsdown;
                  /* There are additional checks, e.g. will the newly grown
                   * stack exceed resource limits, or collide with another area */
```

vma->vm_start=new_addr;

```
// No valid region found
         if (!vma)
                   return force sig(current, SIGSEGV);
         /* Inside of a region, may have been a protections fault */
         if (!protections_ok(vm->vm_flags,access_type))
                   return force_sig(current, SIGSEGV);
         /* We have now proved that the user's access is valid,
                  let's resolve the page fault */
 try_again:
         vp_addr = addr & ~(PAGE_SIZE-1); // Start of virtual page w/ fault
         switch (handle_mm_fault(current->mm, vma, vp_addr, access_type))
           case VM FAULT OOM:
                   if (current->pid == 1) {     // Oh no, can't kill init!
                                               // Let PFRA work
                            yield();
                            goto try_again;
                   printk("VM: Killing process %d0,current->pid);
                   do exit(SIGKILL);
                   /*NOTREACHED*/
           case VM_FAULT_SIGBUS:
                   force_sig(current, SIGBUS);
                   break;
           case VM FAULT MAJOR:
                   current->maj_flt++;
                   break;
           case VM_FAULT_MINOR:
                   current->min flt++;
                   break;
          }
}
handle_mm_fault(struct mm_struct *mm, struct vm_area_struct *vma,
                                      void *addr,int access_type)
pte_t **pgd, **pud, **pmd, **pt;
pte_t *ptep,pte;
         pgd=mm->pgd;
         /* PGD is always allocated. Make sure PUD/PMD/PT are allocated */
         /* corresponding to the faulted address. The xxx_alloc functions */
         /* return a pointer to the next table, possibly allocating a new */
         /* page frame for the table and installing a pointer to it in the */
         /* enclosing table. Physical addresses are mapped by the kernel */
         /* to virtual addresses for this temporary purpose; this mechanism */
         /* is very arch-specific and beyond the scope of this class */
         if (!(pud=pud_alloc(mm,pgd,addr))) return VM_FAULT_OOM;
         if (!(pmd=pmd_alloc(mm,pud,addr))) return VM_FAULT_OOM;
         if (!(pt=pt_alloc(mm,pmd,addr))) return VM_FAULT_OOM;
         /* Compute offset of PTE within Page Table */
         /* On X86-32, PAGE_SHIFT is 12 bits and PAGE_MASK is 0x000003FF */
```

/* On X86-64, PAGE MASK becomes 0x000001FF */

```
ptep= &pt[((unsigned long)addr >> PAGE_SHIFT) & PAGE_MASK];
         pte= *ptep;
                                                // PRESENT bit is 0
         if (!pte_present(pte))
          {
                                                // First time access or file-backed
                   if (pte == 0)
                   {
                             if (vma->vm file) // File-mapped
                                      return pagein_from_file(mm, vma, addr, ptep, access_type);
                                                          // Anonymous
                             else
                                       return pagein_anon(mm, vma, addr, ptep, access_type);
                   /* PTE encodes swap loc for paged-out anon page */
                   return pagein from swap (mm, vma, addr, pte, ptep, access type);
          /* PTE is present, must be a COW protection fault */
         if (write_attempt(access_type))
                   pfn_t pfn;
                   pfn=((unsigned long)pte >> PFN SHIFT) & PFN MASK;
                   /* This next condition is common after fork-exec */
                   if (mem_map[pfn]._mapcount==1)
                             /* Some code elided to check if MAP_PRIVATE page
                                     that had been marked down for COW but had
                                       only a single mapping, needs to adjust
                                      the radix-64 tree to invalidate
                             *ptep|=PTE WRITE;
                             return VM_FAULT_MINOR;
                   void *new pf;
                   /* Allocate a new page frame and provide a valid temporary */
                   /* virtual address so we can access it */
                   if (!(new_pf=pageframe_alloc(1))) return VM_FAULT_OOM;
                   memcpy(map pf to va(new pf),addr,PAGE SIZE);
                   *ptep|=PTE_WRITE;
                   return VM FAULT MINOR;
         }
}
/* This function is only called for first-time access to an anon virt page */
pagein_anon(struct mm_struct *mm,struct vm_area_struct *vma,void *addr,
                   pte_t *pte_p,int access_type)
 void *new_pf;
                            // 32 bit or 64 bit
  pfn t pfn;
  unsigned pte_bits;
         pte_bits=vma->vm_page_prot | PTE_PRESENT;
         if (read_attempt(access_type))
                   /* For first-time read, we can grab a shared COW 0 page */
```

```
new_pf=global_shared_zeropage_paddr;
                  if (!new_pf) return VM_FAULT_OOM;
                  pte_bits &= "PTE_WRITE; // Not writable -- COW
         else
         {
                  new_pf=pageframe_alloc(1);
                  /* map_pf_to_va provides a (temporary) virt addr */
                  bzero(map_pf_to_va(new_pf),PAGE_SIZE);
         pfn=(unsigned long)new_pf>>PAGE_SHIFT;
         /* Fill in the PTE. PFN_SHIFT is the bit pos of the PFN in the PTE */
         *ptep= (pfn<<PFN_SHIFT) | pte_bits;
         update rss(ANON); // Update rss, highwater, etc. stats.
         return VM_FAULT_MINOR;
}
pagein_from_file(struct mm_struct *mm,struct vm_area_struct *vma,void *addr,
                  pte_t *pte_p,int access_type)
void *new_pf;
struct page *new_pf;
pfn_t pfn;
unsigned long pte_bits;
 int rc;
         /* Determine offset within file, in units of pages */
         va offset=(unsigned long)(addr-vma->vm start) >> PAGE SHIFT;
         file_offset=va_offset+vma->vm_pgoff;
         /* See if that page is already resident in memory */
         rc=VM_FAULT_MINOR;
         if (!(new pf=file address space search(vma->vm file,file offset)))
                  /* No, need to allocate a fresh page frame */
                  if (!(new_pf=pageframe_alloc(1))) return VM_FAULT_OOM;
                  pfn=(unsigned long)new_pf >> PAGE_SHIFT;
                  new pf= &mem map[pfn];
                  /* Ask the filesystem module to initiate a disk read
                   * operation, depositing the result in physical page new_pf.
                   * This puts the task into a non-interruptible SLEEPING state
                   * until the I/O operation completes (or fails
                  if (!do_file_readpage(vma->vm_file,file_offset,new_pf))
                  {
                            pageframe_free(new_pf);
                            return VM_FAULT_SIGBUS;
                  rc=VM_FAULT_MAJOR;
                                    // PFN is implicit by index within array
         pfn= new_pf-mem_map;
         new_pf->_mapcount++;
                                    // Here comes new PTE
         pte_bits=vma->vm_page_prot|PTE_PRESENT;
         *ptep=pfn<<PFN_SHIFT|pte_bits;
         update_rss(FILE);
```

```
return rc;
}
pagein_from_swap(struct mm_struct *mm,struct vm_area_struct *vma,void *addr,
                   pte_t pte,pte_t *pte_p,int access_type)
 void *new_pf;
 pfn_t pfn;
 int pte bits;
 unsigned long swap_area, swap_slot;
         swap_area=(pte&SWAP_AREA_MASK)>>SWAP_AREA_SHIFT;
         swap_slot=(pte&SWAP_SLOT_MASK)>>SWAP_SLOT_SHIFT;
         if (!(new_pf=pageframe_alloc(1))) return VM_FAULT_OOM;
         /* This operation results in a non-interruptible SLEEP */
         if (!read_from_swap(swap_area,swap_slot,new_pf))
                   pageframe_free(new_pf);
                   return VM_FAULT_SIGBUS;
         /* Some more complexity elided to deal with a SHARED, ANON
          * page that had more than one mapping and had been swapped out */
         mark_swap_slot_free(swap_area,swap_slot);
         pfn=(unsigned long)new_pf >> PFN_SHIFT;
         pte_bits=vma->vm_page_prot|PTE_PRESENT;
         *ptep=pfn<<PFN SHIFT|pte bits;
         mem_map[pfn]._mapcount++;
         update_rss(ANON);
         return VM_FAULT_MAJOR;
```

Prior to the code seen above, the kernel examines the faulting address and the user/supervisor mode bit. If the faulting address is inside the kernel's reserved virtual address range AND we were in user mode, then a SIGSEGV is sent to the process, no questions asked. If we were in supervisor mode, then the page fault happened inside kernel code. The kernel tries to avoid any situations where this happens, as the code for handling this is messy. We won't be considering kernel-mode page faults in the Linux kernel any further.

Now that we have determined that it was a user-mode program that got us into the page fault handler, and that the access was not to the kernel reserved address space, we have to see if this was a legitimate virtual memory access. This is done by examining the virtual address space description contained in the list of vm_area_structs to see if the faulting address is inside of an existing valid virtual memory region. If it is, we then need to determine if there has been a protection violation (access attempt mode doesn't match PTE mode). There are two exceptions to this: stacks and copy-on-write.

When the stack grows e.g. through a push instruction, the stack pointer is decremented first and then the write takes place. If the stack pointer is now lower than the current start of the stack region, a fault will be incurred. If the faulted address is "close" to the stack pointer (an allowance is made for certain X86 instructions which access memory on the stack first, then adjust the stack pointer) and if the memory region just above the faulted address has the GROWSDOWN property, then the stack region is expanded by one page toward low memory addresses ("down") as if by the mremap system call. There are checks performed to make sure this doesn't exceed the stack size ulimit resource limit, or cause the stack to collide with another region. This automagical stack growth is quite essential to transparent program execution.

This adjustment of the vm_start address does not by itself resolve the page fault. The logic flow now continues, the same as a page fault in any other valid memory region.

Copy-On-Write (COW)

There are several cases where the kernel must logically make a copy of a page. One common example is during fork(). Another is when a file is mapped MAP_PRIVATE. Actually allocating new page frames and copying, byte-for-byte, the entire contents of each page frame of the region being copied, would be a terrible performance penalty. Instead, the kernel continues to point both virtual mappings to the same page frame, but marks down the PTE entries in question to disallow write access.

As long as none of the processes sharing the mapping attempt to write, there is no need to do anything further. They will each see the correct data which are unchanged from the point of forking, in the first example case, or from the original contents of the file, in the second case. As soon as any process tries to write, it will incur a page/protection fault. The kernel recognizes this COW situation because the faulting address is valid, the virtual memory area flags say we should be allowed to write to this area, AND there was a PTE PRESENT for that address.


To resolve the COW fault, the kernel grabs a new free page frame, copies to contents of the existing (shared) page frame to the new frame, and then updates the PTE of the faulting process to point to the new frame, turning on the PTE Write Enable bit at the same time. The other process(es) sharing that mapping continue to see it read-only.

One important optimization on the above happens when a process forks and then either the parent or the child (but usually the child in the common UNIX programming idiom) execs. Then the shared memory region is unmapped from one of the processes. As we have seen, the kernel maintains a core map data structure giving the state of each page frame, and can track how many references there are to any given page frame. So the unmapping results in the reference count going back down to 1. When the kernel sees this condition, it does not have to allocate a new page frame and memcpy. It merely changes the PTE to turn the write enable bit back on

For MAP_PRIVATE regions we have a hybrid. Consider, for example, the data region of a running program, which is mapped MAP_PRIVATE, PROT_READ|PROT_WRITE to an offset within the executable file where the data initializers are to be found. The region is write-enabled but the PTEs are marked down to force Copy-On-Write. If the process only reads a particular page in the data region, then that page is Demand-Paged in. Multiple processes running the same executable can share the mapping to the physical page frame containing the data. However, as soon as the process tries to write to a data region page, Copy-On-Write kicks in. A private copy is made for the writing process.

While the original page frame still corresponds to the contents of the file, and thus its reverse mapping remains file-backed, the private copy has broken the mapping, and thus is now considered anonymous. If this private copy were later to be paged-out, it will therefore wind up in swap space. The data region of the process, and indeed any writable MAP_PRIVATE region, can therefore contain both file-mapped and anonymous page frames at the same time. We'll see how the mapping field of the page descriptor is used to distinguish, on a page frame by page frame basis, this status.

In the illustration below, before the fork, the parent process has demand-paged one page of text, one page of bss, one page of stack, and two pages of data. It wrote to the first data page but the second page has only be read, so its PTE is still r--. After the fork (second panel), all PTE W bits are off. In the third panel, the child attempts to write to the bss page. This causes copy-on-write. Note that the parent's PTE is not affected.



Invalid Addresses and SIGSEGV

If, however, the faulted address is outside of all regions and is not associated with stack growth, or if the attempted access is a violation of the regions protections, a signal SIGSEGV is forcibly posted to the current process. "Forcibly" means the kernel doesn't care if the process has this signal number blocked or ignored: The user program attempted to access an illegal virtual memory address, and there is no point in letting it continue on its current path. The address will not magically become valid, and therefore the faulted instruction can never be satisfied and would loop forever. The signal then terminates the process.

If the signal has a handler, but the signal is currently being blocked, the signal is unblocked, the handler is reset to SIG_DFL, and once again the signal kills the process. The reasoning is that a handler should not be invoked if the corresponding signal is being blocked.

It is, however, permissible for the signal to be *handled* as that will force execution to jump to another, presumably less flawed part of the program. This technique is often used in complex, modular applications (such as the open-source image editor *The Gimp*) to isolate a flawed module and prevent it from crashing the entire program and possibly leading to a loss of data.


Benign Page Faults / Paging-in

Page faults which are within an existing region and which are not the result of protection violations are therefore not the result of any program error, and need to be resolved by establishing a valid forward mapping PTE that is pointing to a valid physical page frame which contains the correct contents corresponding to the virtual page. This page fault resolution mechanism can have one of four mutually exclusive outcomes:

- Minor fault: The page fault is resolved quickly without requiring a disk I/O operation or putting the process to sleep. E.g. demand-paging new bss pages (just allocate a page, zero fill and return), paging-in file-mapped pages which are still cached in memory, or breaking up a Copy-on-Write shared page frame. Minor faults are good.
- Major fault: It was necessary to sleep pending an I/O operation to satisfy this fault. Major faults are not necessarily evil (e.g. demand paging an executable file from disk) but we would like to minimize their number.
- Bus Error: The kernel was unable to page-in the page because of an error other than being out of memory. E.g. the page is mapped to a disk file but an I/O error occurred trying to access the disk, or the mapping is no longer valid because the file has been truncated. A SIGBUS will be delivered to the process.
- Out of Memory: The kernel ran out of memory to allocate a free page frame or an internal data structure. This is very bad. Under ordinary circumstances, the kernel tries to prevent this from happening by maintaining a pool of free memory. If this does

happen, the kernel has no choice but to terminate the current process. See also discussion below on "over-commit".

The Linux page fault handling algorithm is summarized by the following simplified flowchart:



On-demand creation of Page Tables

Recall that the structure of the page table is multi-level and sparse. Only the top-level Page Global Directory is pre-allocated. The kernel uses **lazy allocation** in creating the page upper directories, page middle directories, and page tables. Therefore, at this time of page fault resolution, the kernel must (recursively) allocate the directories/tables mapping the faulted virtual memory address, if they are not already allocated. When new page tables or page directories are allocated, they are set to 0, meaning none of the entries

are viewed by the hardware as PRESENT yet. The kernel then installs new Page Directory or Page Table Entries as needed.


Paging-in from where?

To complete page fault resolution, the kernel must locate the canonical copy of the data corresponding to the virtual page which is faulted. In brief, this can fall into one of the following cases:

- The virtual page is file-mapped.
- The virtual page is anonymous and not previously written to.
- The virtual page is anonymous and previously dirtied, and swapped out.
- The virtual page is already present in physical memory, and this is a copy-on-write.

The kernel can determine which case applies by looking at the bits of the PTE corresponding to the faulted address, and by looking at the attributes of the corresponding vm_area_struct.

- The PFN field is all zero and the Present bit is 0, and the vm_area_struct indicates that this region is mapped to a file. The corresponding page-sized chunk of the file might already be cached in a page frame because of recent read/write system call activity, or it may require the allocation of a new page frame and the initiation of a disk I/O operation. See "File Mappings"
- The PFN field and Present bit are all 0 and the vm_area_struct tells us that this is an anonymous region. The PTE being entirely 0 tells us that this virtual page is "virgin": it has not previously been written to and swapped out. This situation is always resolvable as a minor fault: The kernel finds a page frame from the free pool and maps it to the faulted virtual page. If the faulted access was a write, the kernel 0-fills the page. However, for a read access, the kernel optimizes by mapping to a single, shared physical page containing all 0, and setting up a COW situation by making the PTE protection bits read-only. At a later time, if the process writes to this page, things will be straightened out by Copy-On-Write. This behavior of zero-filling new anonymous pages is very important for security. Otherwise, sensitive information from another process could be viewed when the page frame is recycled.
- The PFN field of the PTE is non-zero, but the Present bit is 0 (and the Dirty bit is also 0). The kernel deliberately sets up this odd situation to indicate an anonymous page which has been swapped out. The page frame number does not correspond to a real address, but is used as an identifier to help the swap subsystem find the image of the page in the swap area. We will need to initiate an I/O operation to swap-in the page image to a new page frame. This will be discussed further under "Swap Space".
- The Present bit is 1. At this point in the code, we know that it must be a hardware protection violation which tripped the page fault, and we have previously checked that the attempted access is valid for this region. Therefore we need to resolve the copy-on-write as discussed above.



Note that in the above diagram, the order of the bits within the PFN has been abstracted to make a clearer presention. If you dare to look at the X86 documentation, you'd find it differs.

Page Frame Reclamation / Paging-Out

We can think of the pool of page frames as a cache for actively-used data which are otherwise stored on disk (in a file or in swap space). Linux uses a strategy of maintaining a pool of free page frames proactively. Consider what would happen if this strategy were not in place: We call the total number of page frames mapped to a process the **Resident Set Size (RSS)**. As processes request virtual memory and are allocated page frames, their RSS would grow, and the pool of free frames would shrink and shrink. Eventually, there will not be any frames available to satisfy a new request. This could block the

process for a long time while a "victim" page is selected to be written back to backing store and re-assigned.

Instead, the Linux kernel uses a kernel task (a kernel task aka kernel thread is like a user-mode process, but it never leaves kernel mode. It can make system calls, using a slightly modified, internalized syntax. Kernel tasks are scheduled by the scheduler, can go to sleep and wakeup, etc. They do not have their own mm_struct but "borrow" one from a user process, which is OK since they only access the shared kernel memory area) called kswapd to periodically scan the mem_map, looking for possible victims from which to steal back pages and thus reduce the total RSS. There are two parameters which can be tuned by the system administrator establishing low-water and high-water marks for free pages. kswapd works hard to keep the free page count above low-water, and goes to sleep when it reaches the high-water mark. To be more precise, each memory zone (e.g. NORMAL, HIGHMEM) has its own high and low water marks, but we will ignore this detail.

The Page Frame Reclamation Algorithm (PFRA) maintains two lists of non-free page frames: active and inactive. These lists are chained via the <code>lru</code> field of the page descriptor. Periodically, the PFRA scans the page descriptors on the active list with the desire to find hypoactive pages and move them to the inactive list. It uses the reverse mapping (see below) in the page descriptor to find the PTEs mapping to this physical page (when the page is shared there will be multiple PTE pointing to the same physical page). Each PTE is examined to see if the ACCESSED bit is set, then the ACCESSED bit is cleared. The PFRA also keeps a second bitwise flag, <code>PG_referenced</code>, in the <code>flags</code> field of the page descriptor, which stores the previous value of the ACCESSED PTE flag. (when there are multiple PTEs mapping the same page, <code>PG_referenced</code> is the OR of the ACCESSED PTE bits).

When an page which had PG_referenced set to 0 is visited again and the ACCESSED PTE flag(s) is (are all) still clear, it means the page has not been used in two successive scan passes. The PFRA will then move the page to the tail of the *inactive list*.

After the PFRA finishes hunting for active pages to move to the inactive list, it starts trying to pull victims off the inactive list, starting at the head of the list. I.e. it starts with the pages which have been sitting on the inactive list the longest. This is known as the **Least Recently Used (LRU)** ordering. The theory is that pages which have remained inactive for a long time will probably continue to be inactive.

For each inactive page scanned, the ACCESSED bit(s) is (are) checked again. Note that this bit is only cleared when the PFRA has visited the page from the *active* list, therefore if there has been any access whatsoever between the time that the page was moved to inactive and the time it was visited on the inactive list, this PTE bit will be set, and the page is just moved back to the active list. Otherwise, the page will be reclaimed. If the PTE indicates that the page is dirty, a write-back to backing store is begun. This operation might take a while, so kswapd continues to look at additional pages that are

not dirty, until it has reclaimed the desired number of pages. Pages which are not dirty can be reclaimed by simply immediately unmapping the PTE(s). Pages which were in the process of being written back are unmapped when that writeback operation concludes.

Pages that the PFRA has reclaimed are then placed on the free list. Since they are placed at the tail of the free list (for a given buddy order) and the page allocator pulls from the front, this further enhances the notion of Least Recently Used. Pages which are on the free list and haven't been re-used but still contain valid images can be pulled back off so that a page fault can be resolved as a minor fault.

The PFRA is adaptive and if it feels that it isn't reclaiming enough memory, it increases the rate at which it scans active pages, thus making the activity timeout window shorter and increasing the pool of potential inactive pages. This is a delicate balancing act because the PFRA/kswapd consumes CPU resources in doing all of this scanning. Excessive scanning wastes CPU time, but insufficient reclamation can cause memory starvation and severe performance penalties.

Like scheduling, memory allocation and reclamation algorithms are the subject of extensive research and development.

Reverse Mapping

For any given page frame, there may be multiple mappings for it. The kernel must keep track of all of them and prevent inconsistent views. For example, a given page may appear as part of the virtual address space of one or more processes, correspond to a particular offset in a particular memory-mapped file, and furthermore correspond to a particular offset within the hard disk storing that file. The PFRA, when visiting page frames, must be able to find all existing mappings (PTEs) of that page so that it can locate and possibly modify the PTEs. To visit the PTEs, the PFRA must determine the vm_area_struct and offset within that region (there could be multiple regions).

Either a page is mapped to a file, or it is anonymous. These two conditions are mutually exclusive. The mapping field of the page descriptor contains a pointer to one of two objects which will help with the reverse mapping. If the least significant bit is 1, the page is anonymous and mapping &~01 points to a struct anon_vma. If the lsb is 0, the page maps to a file and mapping points to a struct address_space object for the file. This use of the least significant bit is a programming trick: because kernel pointers are always aligned on 4-byte boundaries, the least significant bit can be wasted for this purpose.

Anonymous Mappings

The anon_vma is simply the head of a doubly-linked circular list of memory region

descriptors (vm_area_struct), chaining through the anon_vma_node pointers in the latter. Furthermore, the vm_area_struct contains a pointer (anon_vma) back to the anon_vma list head. More often than not, the list contains just one memory region descriptor. However, when a region becomes shared (e.g. after a fork) this list contains each region in each process which refers to it. This will also be the case for MAP_SHARED regions that were inherited via fork. Therefore, each anon_vma structure represents one anonymous virtual memory region (which might be shared among multiple processes).

A process data region or other MAP_PRIVATE file mappings might find itself on the anon_vma list and also part of a file mapping, because some pages in the region still correspond to the file, but some have been written to making them anonymous. Within this region, mapped-in pages are either "virgin" and still correspond to the original file, or they have been dirtied and are now backed by swap space. This distinction is captured via the least significant bit of the mapping field of the page descriptor as described above.

The PFRA, after getting the anon_vma list start from the page descriptor, can walk the linked list anchored by the struct anon_vma and visit each memory region (vm_area_struct) which maps that page, which gives the starting virtual address of the that region. The index field of the page descriptor gives the offset, in pages, of that particular page within the region. The pgd field of the struct mm_struct, which in turn is accessible from the vm_area_struct, gives the address of the page global directory for the process. It is now a trivial matter to walk through the page table structure and find the PTE.

Swap Space and anonymous page-outs

When an anonymous page is selected for reclamation, the Dirty bit of the PTE is examined. If set, then the page has been written to and therefore must be saved to **swap space**. The kernel maintains one or more swap areas, which are either raw disk partitions, or files, in either case prepared with the system utility command mkswap, and then made available as part of swap space with the swapon command.

Anonymous pages aren't meant to be persistent, and so swap space is just a pool of disk space where we can stash them. There is nothing within a swap area which would tell one the identities of the page images. That information is kept by the kernel in RAM and simply discarded when the system halts. The kernel maintains an array of swap area descriptors, each of which includes a free map. Each slot of a free map gives the reference count of the corresponding page-sized slot of the corresponding swap area.

A particular page frame containing an anonymous page may be mapped by multiple PTEs in one or more processes. Therefore, when that page frame is swapped out, ALL of the PTE must be marked as not present. A free slot in some swap area is chosen (the

algorithm to do so keeps things such as disk I/O performance in mind). Free slots are indicated by a swap map entry of 0. Once the slot is allocated, the swap map entry will reflect the number of mappings that had been pointing at that shared page frame.

Now the Linux kernel uses a slightly dirty trick. The swap area number (a 7-bit integer) combined with the slot number within the area form a unique identifier of the swap slot. 24 bits are allowed for the slot number, meaning the maximum size of one swap area is $2^24*2^12=2^36$ or 64 GB. The total amount of swap space on the system is limited to $2^36+7=8$ TB.

Given this information, the page fault handler can, when the page is once again referenced, find the corresponding swap slot on disk and read it in. This swap identifier is stored in each PTE which had mapped the swapped-out page. There are 31 bits in the identifier and a PTE is 32 bits. The Linux kernel packs the bits into the PTE in such a way that the Present flag is always 0, and the remaining 31 bits are scattered between the PFN and the Flags fields. It isn't a valid PTE but since the Present bit is OFF, the hardware will never look at it or touch it. (On X86-64, there are 63 bits of the PTE to play with for encoding a swap area and swap slot....that's a LOT of swap space!)

File Mappings

For files which are mapped into memory, it is important to be able to locate quickly the page frame which currently contains a particular (page-aligned) offset in the file, and/or to determine that no such page is currently resident. Consider the read system call, the semantics of which must work correctly and transparently with memory-mapped files. read amounts to finding the page frame which holds that part of the file (if there is no such frame, ask the filesystem to bring it in from disk and sleep until that happens), and then copying the requested portion of that page into the user buffer.


Likewise, when faulting-in a memory-mapped file, it could be that the same (page-aligned) area of the file has recently been accessed from the same or different process using the read or write system call, in which case the fault can be resolved a minor fault by pointing the PTE at the existing page frame which contains that image.

An address_space structure is used to provide this quick lookup. One of these is allocated for every open inode. It has many fields, but among them are two types of trees. One is a flexible radix-64 tree which, given an offset (in page-sized units) into the file, finds the struct page corresponding to that part of the file, or NULL if there is none such. Each node of the radix-64 tree has 64 pointers. If the file size is 256K or less (64*4096) then the entire file's address space is handled by a single-level tree. Otherwise, the tree grows. A two-level tree can handle (64*64*4096) or 16MB of file addressing, etc. up to 6 levels.

While the radix tree is great for going from a known offset in the file to a page descriptor, the PFRA is trying to go a different way: find all PTEs which refer to this particular offset within the file. The address_space pointer of the struct page identifies the file, and the index field gives the offset in pages within the file. A simple approach would be to link all regions mapping to the file into a linked list, as is done for the anon_vma structure. However, while sharing of an anonymous region is usually limited to a small number of processes, memory-mapped files, especially those containing a common executable, are shared by many processes. There can also potentially be multiple mappings to different parts of one file (consider an a.out file where the .text and .data section are mapped separately).

Linux uses a Priority Search Tree for *each file*. It is accessed via the address_space structure's i_mmap pointer, and can quickly answer the following question: "given a particular offset within the file, tell me all memory regions which contain it." I.e. the PST sorts the mapping regions by their starting offset. The PFRA examines all memory region descriptors which map to the page. Each descriptor contains the starting virtual address of the region, and the corresponding offset within the file (this is in the vm_pgoff field). Now the offset of the page within the region can be readily calculated, and from there the PTE can be found.

A file-mapped page which needs to be paged out and which is dirty must be part of a MAP_SHARED file-mapped region (if it were MAP_PRIVATE, the dirty pages would be paged-out to swap). We know from the mapping and the index fields of the struct page the file and the offset within that file where the page needs to go. So paging-out a file-mapped dirty page involves asking the underlying filesystem module to write the page to that offset within the file on the disk.



Resource Exhaustion

In an ideal world, systems would always have sufficient resources to handle the jobs which are thrown at them. But that world is not a terribly interesting one in terms of operating systems design. In reality, memory resource exhaustion is often a problem. We can consider two distinct problem areas: Insufficient physical memory, and insufficient swap space.

Thrashing / Swap Token

When memory becomes very scarce, the system can spend much of its time freeing up pages by swapping-out, followed by swapping-in when a process which has had its pages stolen gets scheduled and tries to run. This is an age-old problem known as **thrashing**. Linux tries to ameliorate it by using what Linux calls a "swap token". A process which holds the swap token is given a temporary reprieve by the PFRA. The swap token is given to a process based on heuristic rules...basically a process which has recently been victimized by the PFRA, has good priority and looks like it will do something useful if allowed to run.

This isn't necessarily a perfect solution. To contrast, the Solaris kernel takes a different approach. When memory runs low, a kernel thread called the "swapper" picks entire processes to victimize and steals all of the process' pages. A process thus swapped-out is basically put to sleep and therefore doesn't get scheduled. When things get calmer, the process is released from the swapper's grasp and is allowed to run and fault its pages back in.

Memory over-commit and the out-of-memory killer

Just like an airline which over-books seats, it is possible for the kernel to hand out more virtual memory than it has physical memory and swap to cover. If it happens that all of the memory is demanded at once and there are insufficient free swap slots to page-out to, the kernel will have no choice but to kill processes in order to regain memory. There is an Out-Of-Memory killer which is triggered when the system becomes desperately low of memory. It picks large processes which haven't been running too long.

This might seem like a design flaw. After all, the programmer successfully allocated memory using malloc (which in turn used brk or mmap), so why has the kernel gone back on its promise and why should a process be terminated because of something which is not its fault?

On the other hand, the most conservative approach, which guarantees that one will never run out of memory, is to reserve a swap space slot for each virtual anonymous page allocated. Then there will always be a place to page-out any resident page and we can never get into this trouble. The problem with this approach is that processes will start getting memory allocation failures long before the system has reached a high probability of running out of memory, unless the administrator has configured a very large amount of swap space. The reason: most virtual anonymous pages are never actually paged-out. Consider a large process which forks and then execs. Most of the virtual address space of the child will be discarded.

Older Linux kernels took the first approach. Solaris kernels tend towards to more conservative approach. Modern (2.6+) Linux kernels allow the administrator to tune the memory over-commit policy.

The following is verbatim from \fCDocumentation/vm/overcommit-accounting\fP:

The Linux kernel supports the following overcommit handling modes

- O Heuristic overcommit handling. Obvious overcommits of address space are refused. Used for a typical system. It ensures a seriously wild allocation fails while allowing overcommit to reduce swap usage. root is allowed to allocate slighly more memory in this mode. This is the default.
- 1 Always overcommit. Appropriate for some scientific applications.
- Don't overcommit. The total address space commit for the system is not permitted to exceed swap + a configurable percentage (default is 50) of physical RAM. Depending on the percentage you use, in most situations this means a process will not be killed while accessing pages but will receive errors on memory allocation as appropriate.

The overcommit policy is set via the sysctl 'vm.overcommit_memory'.

The overcommit percentage is set via 'vm.overcommit_ratio'.

The current overcommit limit and amount committed are viewable in /proc/meminfo as CommitLimit and Committed_AS respectively.

Gotchas

The C language stack growth does an implicit mremap. If you want absolute guarantees and run close to the edge you MUST mmap your stack for the largest size you think you will need. For typical stack usage this does not matter much but it's a corner case if you really really care

In mode 2 the MAP_NORESERVE flag is ignored.

The overcommit is based on the following rules

For a file backed map

SHARED or READ-only - 0 cost (the file is the map not swap)
PRIVATE WRITABLE - size of mapping per instance

For an anonymous or /dev/zero map

SHARED - size of mapping

PRIVATE READ-only - 0 cost (but of little use)

PRIVATE WRITABLE - size of mapping per instance

Additional accounting

Pages made writable copies by mmap shmfs memory drawn from the same pool

Appendix: How an executable file is created

In the original UNIX kernel, each program was entirely **statically-linked**, i.e. all of the code required to execute the program, and in particular all of the libraries which the program requires, are put together at compile-time into one large monolithic executable file. This practice began to change during the 1990s, and today almost all programs in almost all UNIX-derived systems are *dynamically linked*. It is still possible to compile a program which is statically linked, but this is exceptional. We will first discuss how statically linked programs are linked together, and then delve into dynamic linking.


Compiling a C program into an executable file is a multi-stage process involving several tools. When one simply runs:

cc test.c

The cc command transparently executes the tools, detailed below, resulting in an executable file called a .out (if there are no fatal errors in compilation). The "a" in "a.out" stands for "Absolute", meaning that all symbolic references have been resolved. An a.out file contains pure machine code that can be directly executed by the processor. The executable file ("a.out") contains everything that the operating system needs to create a program's initial memory configuration and begin execution. The header of the a.out identifies it to the operating system as an executable file and specifies the processor architecture on which the machine code instructions will run. A program compiled for an x86 architecture can not be executed, for example, on a SPARC processor. The header also gives the size of the text, data and bss memory requirements, as explained below.

The a .out file includes the literal bytes of executable code which will be loaded into the process's text region. These are in a contiguous part of the a .out file. The header gives the offset of the beginning of the .text section of the a .out, and also the load address, i.e. the virtual address at which the compilation system expects this text to be loaded.

Likewise, there is a .data section in the a.out which contains an image of what the data region of the process will look like at program startup.




The **bss** section contains all un-initialized global variables. The C language specification states that all such variables, lacking an explicit initializer, must be initialized by the operating system or C run-time environment to 0.

In the example above, j has an explicit initializer, and will be in the data segment. The value of the initializer will be found in the .data section of the a.out. k is uninitialized. Therefore it will reside in the bss segment of memory and will have an initial value of 0. The ISO C standard says that "If an object that has static storage duration is not initialized explicitly, it is initialized implicitly as if every member that has arithmetic type were assigned 0 and every member that has pointer type were assigned a NULL pointer constant". This is satisfied by filling every byte of the bss region with 0, and is performed by the operating system. The variable 1 has automatic storage scope, and therefore will be found on the stack (or, if the compiler is set for heavy optimization and a pointer to 1 is never taken, it may live in a register). Automatic variables are not 0-initialized.

Behind cc-losed doors

The CC command is often and erroneously called "the compiler." In fact, it is a wrapper program which invokes a series of tools. Each tool transforms a specific kind of input file to a specific kind of output file. It is possible to instruct CC to interrupt the process at any stage, and to access and manipulate these intermediate files as needed.



The compiler proper takes C code, passing it through the macro pre-processor, and compiles it into symbolic assembly language. By using the -S option to CC, we can halt the process before the assembler and linker are invoked, and view the intermediate assembly language file, which will have a .s extension.

The assembler takes symbolic assembly language files (.s) and converts them into relocatable object files (which have a .o extension). An object file is similar to an executable ("a.out") file in that it contains machine code, however symbols which can not be resolved (as detailed below) are left dangling. Therefore, it is not ready to run until these dangling links are settled, possibly by linking with additional object files. By giving cc the -c option, the linker will not be run and the .o files will be left for subsequent examination or linking. It is also possible to invoke the assembler directly with the as command.

Although some compilers do not separate the assembler, it is useful to divorce it from the compiler and make it a separate utility. In this way, a common assembler program can be

written and employed by compilers for different languages. For example, the GNU compilers for C, C++ and FORTRAN are all different programs, yet they all call on the as program for assembly. It is also useful to be able to introduce .s files that have been written by hand for certain performance optimizations or platform-specific features.

The linker takes multiple object (.o) files (or libraries of object files, with .a extensions, as discussed below), resolves symbol references, and creates an absolute executable file. If unresolved symbols remain at this point, the linker will not be able to create an absolute executable and an error will result.

Like the assembler, the linker is a separate tool which can be called directly as 1d. The reason for this rather un-mnemonic two-letter name is that historically, the linker has also been called the "loader", because it was responsible for creating the "load deck" of punch cards that could then be directly run by the computer. Besides, 1n was already taken as a command name.

When compiling C programs, it is best to allow the cc wrapper to invoke 1d rather than trying to do it manually as there are a number of complex platform-specific options needed to actually create a run-able program.

The .o files need not have come from C source code. It is possible to distribute binary object files or libraries which can be linked against user-supplied code. It is also possible to create cross-language executables, where part of the code is written directly in low-level assembly language, or in another high-level language (with all due caution about mixed run-time environment expectations).

Separate Compilation

Very simple C programs can be contained in a single .c file. As the size of the project increases, it becomes extremely inefficient to do this. The tasks of pre-processing, compiling and assembling are CPU-intensive. With a single file, any change, no matter how small, requires that the entire file be recompiled.

The program can be split up into a number of smaller .c files. There are varying opinions on how finely to divide the program and on what basis to select which parts go into which file. Some guidelines:

- 1) Groups of functions which form a coherent subsystem are good candidates for including in their own file. In C++ terms, this would be a class. Some subsystems are so complex that they need to be further subdivided.
- 2) Whenever a single .c file is on the order of 1000 lines of code, it is probably getting

too big. On the other hand, having lots of files each containing one or two 10-line functions is also wasteful.

3) Code which is being incorporated from another source, or which is being worked on by a different programmer, should have its own file, or perhaps be structured as a library, to make it easier to deal with changes.

As an example, let's say our program has been divided into files f1.c, f2.c and f3.c. To compile this, we could run: cc f1.c f2.c f3.c, which would perform the entire pre-processing, compiling and assembling process on each of the three files, then invoke the linker to create the a.out. However, suppose we make a change to f1.c only. Why do all that work again for the other two files, which have not changed?

Instead, we can first run: cc - c f1.c f2.c f3.c, which will pre-process, compile and assemble each of the files, creating f1.o, f2.o and f3.o. Then we run: cc f1.o f2.o f3.o. The cc wrapper sees that we are giving it.o files and passes them directly to the linker. Now, if we change f1.c, we run cc - c f1.c to re-compile it alone, and then run cc f1.o f2.o f3.o again to link the program. This process is automated by the tool make, which uses dependency rules and file modification times to determine which compilation phases to invoke and on which files.

The linker vs the compiler


The job of the linker is to take one or more relocatable object files, resolve symbol references, and create an absolute executable file. The linker does not know about C's type algebra, nor should it, since the linker is independent of any particular high-level language.

Unfortunately for the student, the C language also deals in symbols, e.g. variable and function names, and this issue is sometimes difficult to separate from the symbol processing which happens at link time. Here are some things that never appear in an object file and do not concern the linker:

- C language type specifiers (such as "p is a pointer to a pointer to a function returning int and taking two int arguments")
- C language structure, union and enum definitions and typedef names.
- goto labels
- Internal labels that may be generated by the compiler for loops, switch statements, if statements, etc.
- automatic (local) variables. An important exception is a local variable that is declared with the static storage class. This variable has local scope, i.e. its name is not visible outside of the curly-braced block in which it is declared, but it lives in the same

neighborhood as global variables.

Object File



What's in a .o?

Let's see what is actually in an object file and how it gets there:

```
/* f1.c */
extern int i;
f()
{
         i=2;
}
/* f2.c */
int i;
main()
{
         i=1;
         f();
}
```

In fl.c, the extern storage class for variable i tells the compiler that this variable is external to that .c file. Therefore, the compiler does not complain when it does not see a declaration that variable. Instead, it knows that i is a global variable, and should be

accessed by using an absolute addressing mode. Neither the compiler nor the assembler knows what that actual address will be. That is not decided until the linker puts all the object files together and assigns addresses to symbols. Therefore, the assembler must leave a "place-holder" in the object file. Likewise, in f2.0, there will be a reference to the symbol f.

Let us examine the assembly language files produced (using an older gcc under Linux on an x86 system):

```
**** f1.s
       .text
       .qlobl f
       .type f,@function
f:
                   *These instructions set up
      pushl %ebp
      movl %esp, %ebp
                       *the stack frame pointer
      movl $2,i
      leave
                                *Restore frame pointer
      ret
.Lfe1:
      .size f,.Lfe1-f
**** f2.s
       .text
       .globl main
      .type main, @function
main:
      pushl %ebp *These instructions set up
      movl %esp,%ebp
                                *the stack frame pointer
       movl $1,i
      call f
      leave
                                 *Restore frame pointer
      ret
.Lfe1:
      .size main, .Lfe1-main
      .comm i, 4, 4
```

The assembler directive .text tells the assembler that it is assembling opcodes to go in the .text section of the object file. The .globl directive will cause the assembler to export the associated symbol as a defining instance. .type is used to pass along information into the object file as to the type of the symbol. Please note that it has nothing to do with the C language notion of type. Symbol types may either be functions or variables. The linker is able to catch gross errors such as if f were defined as a variable in fl.c instead of a function. The .size directive calculates the size of the function by subtracting the value of the symbol representing the first instruction of the function (e.g. main) from a placeholder assembler symbol (e.g. .lfel) representing the end of the function. Note that the CALL to function f is done symbolically, as is the assignment into global variable i.

The resulting object file is similar to an a.out file, however all addresses are relative. In addition, the object file will have a section known as the **symbol table** containing an entry for every symbol that is either defined or referenced in the file, and another section called the **relocations table**, described below.

Now, let us view the .text section of fl.o (the listing below was re-formatted from the output of objdump -d):

```
Offset Opcodes Disassembly 0000 55 pushl %ebp  
0001 89E5 movl %esp,%ebp  
0003 C70500000000000000 movl $2,0  
000D C9 leave  
000E C3 ret
```

First, note that the offset of the first instruction is 0. Obviously, this can not be a valid memory address. All offsets in object files are relative to the object file. It isn't until the linker kicks in that symbols gain absolute, usable addresses.

Next note that in the instruction beginning at offset 0003, the constant 2 is moved to memory address 0. We know from examining the corresponding assembly language input file that this is the instruction that moves 2 into variable i. The assembler has left a place-holder of 00000000 in the object file where the linker will have to fill in the actual 32-bit address of symbol i once that is known. C705 is the x86 machine language opcode for the MOVL instruction where the source addressing mode is Immediate and the destination mode is Absolute. The next 4 bytes are the destination address and the final 4 bytes of the instruction are the source operand (which is in Intel-style, or "little-endian" byte order).

Here is the dump of f2.0:

Offset	Opcodes	Disassembly
0000	55	pushl %ebp
0001	89E5	movl %esp,%ebp
0003	C705000000001000000	movl \$1,0
000D	E8FCFFFFFF	call 000E
0012	C9	leave
0013	C3	ret

Note that the placeholder in the CALL instruction is FFFFFFC, but the disassembler decodes that as 000E. This is because the CALL instruction uses a Program Counter Relative addressing mode. The address to which execution jumps is the operand in the instruction added to the value of the Program Counter register *corresponding to the byte beyond the last byte of the CALL instruction*. In two's complement, FFFFFFC is -4, therefore the CALL appears to be to the instruction at offset 000E. Of course, all of this is meaningless since it is just a placeholder that will be overwritten by the linker. Nonetheless, it reminds us that there are different **Relocation Types** depending on the

addressing mode being used.

The symbol and relocation tables for the two object files will look something like this:

f1.o:

```
SYMBOL TABLE

NAME TYPE VALUE

f func 0 in .text
i variable [reference]

RELOCATIONS TABLE

SYMBOL=i OFFSET=0005 LENGTH=4 RELTYPE=ABSOLUTE
```

f2.o:

		SYMBOL TABLE
NAME	TYPE	VALUE
f	function	[reference]
i	variable	8 in .bss
main	function	0 in .text
		RELOCATIONS TABLE
SYMBOL=i OFFSET		=0005 RELTYPE=ABSOLUTE
SYMBOL=f OFFSE		=000E RELTYPE=PCRELATIVE

What ld does

The first task of ld is to take inventory of all of the .o files being presented to it. It loads in the symbol tables from all of the object files to create a unified symbol table for the entire program. There is only one global namespace for all linker symbols. This might be considered a deficiency. Let's say we have a module foo.c that defines a function called calculate. If we attempt to incorporate that module into a program written by someone else, they may have also made a function called calculate. It is, after all, a common name.

If there is more than one defining instance of a symbol, i.e. if a symbol is *multiply-defined*, this is generally a fatal error. Consider what would happen if a programmer accidentally included two versions of function f above in two different f is called somewhere in the program, which version should be called?

To ameliorate this problem of flat global linker namespace, a convention exists that one should prepend to one's global variable and function names a reasonably unique prefix. Therefore, we might call our function foo_calculate. This is less likely to conflict with another name. It isn't a perfect solution, but it works fairly well in reality.

In languages like C++, which takes name overloading to an extreme, the identified names used in the source code are **name-mangled** to be non-conflicting when placed into the global linker namespace.

Global variable and function names that are intended to remain private to the .c file in which they are declared should be protected with the static storage class (see below). static symbols still require the assistance of the linker to be relocated. However, the use of static causes the compiler and the assembler to flag that symbol as a LOCAL symbol. The linker will then enter the symbol into a private namespace just for the corresponding object file, and the symbol will never conflict with symbols from other object files.

There are rare cases where it is useful to deliberately redefine a symbol. For instance, we may need to change how a piece of code, available only in library or object file form, calls another function. This all falls under the heading of "wild and crazy ld tricks" and will not be discussed further. Just remember that any duplicate symbol definitions are generally wrong.

There is one antiquated exception which <code>ld</code> still honors: the so-called COMMON block, which is a hangover from FORTRAN. If there are multiple defining instances of a variable in the bss section (i.e. a global variable without an initializer), <code>ld</code> will look the other way. This is because there really isn't a fatal conflict. As long as the definitions all give the same size and all agree that it is a bss symbol, there's no worry about which definition is the correct one. All are equivalent. So, if one accidentally declares a global uninitialized variable twice, the program will compile fine. It is sloppy, however.

Frequently symbols have a defining instance, but they are never actually referenced. For example, the programmer may write a function, but never call it, or declare a global variable, yet never use it in an expression. The linker doesn't care about this.

However, it cares deeply about the opposite case: a symbol that is referenced (by appearing in a relocations table) but which has no defining instance. Such a situation makes it impossible for the linker to complete its task of creating an absolute executable file with no dangling references. Therefore, it will stop with a fatal error, reporting the undefined symbol and the object file or files in which it is referenced.

Once all of the symbol definitions and references are resolved, 1d will assemble the a.out file by concatenating all of the text sections of all of the object files, forming the single .text section of the a.out. In doing so, the text sections are relocated. An instruction which was at offset 10 in a particular object file's text section may now be at offset 1034 in the a.out.

Furthermore, 1d has a concept of the load address of the program, i.e. the memory address at which the first byte of the .text section of the a.out will be loaded. This knowledge is part of configuring 1d for a particular operating system and processor type, and is not normally something that the programmer needs to worry about. The load

address is also placed in the a.out file so the operating system is sure to load the program at the address for which it was linked. Knowing the size of each object file's .text section, 1d can calculate the absolute address that it will occupy in the final image, and can thus complete the symbol table, assigning absolute values to each text symbol.

A similar process is undertaken for the data and bss sections. 1d assigns an absolute address to each data or bss symbol, based on the configured starting address of the data and bss memory regions. In the case of data symbols, the initializers contained in the individual object files are concatenated, forming the .data section of the a.out, which will thus contain the byte-for-byte image of what that section will look like when the program starts. For bss symbols, there are obviously no initializers. 1d keeps track of the total number of bss bytes needed, and places that information into the a.out header so the operating system can allocate the memory when the program is loaded. During this process, each data or bss symbol is assigned an absolute address in the symbol table.

Now 1d concatenates the various object files, processing the relocation records, replacing each "placeholder" with the actual, absolute address that the associated symbol is now known to have. In the case of Program-Counter-Relative relocation types, the proper offset is calculated with respect to the absolute address of the placeholder in question.

Libraries

When you write a C program, you expect certain functions, such as printf, to be available. These are supplied in the form of a **library**. A library is basically a collection of .o files, organized together under a common wrapper format called a .a file. It is similar to a "tar" or "zip" archive (although no compression is provided).

Convention is that a library ZZZ is contained in the library file: libZZZ.a. Using the -l option to cc tells the cc program to ask the linker to link with the specified library. For example: cc myprog.c -lm asks for the system library file libm.a (the math library) to be additionally linked. By default, cc always links the standard C library libc.a. These libraries are located in a system directory, typically /usr/lib.

Although a library embodies a collection of object files, the behavior when linking to a library is slightly different than if one just linked in all of the object files individually. In the latter case, the .text and .data sections of each object file would wind up in the a.out, regardless of whether or not anything in a particular object file was actually used. With a library, 1d builds a symbol table of all the object files in the library, and then only selects those object files that are actually needed for inclusion into the executable.

Dynamic Linking

When dynamic (shared) libraries are used, there are two parts to the linkage process. At compile time, 1d links against the dynamic library (which has a .so extension in UNIX) for the purpose of learning which symbols are defined by it. However, none of the code or data initializers from the dynamic library are actually included in the a.out file. Instead, 1d records which dynamic libraries were linked against.

At execution time, the second phase takes place before the main gets invoked. A small helper program called ld.so (typically, actual names vary depending on operating system build) is loaded into the process address space by the kernel and executed. The intervention of ld.so is made possible by the binary interpreter feature of the ELF (Extensible Linker Format) a.out format. Like the #! method for shell script (and other languages) interpreters, a flag in the a.out header informs the kernel that it needs to actually load ld.so, which is passed the absolute pathname of the a.out file as an argument. ld.so then does a series of mmap calls to establish the text, data and bss regions for the conventional (statically linked) part of the program, based on the a.out header information. It then locates each of the required dynamic libraries (also information from the header) and for each one, mmaps that library's text, data and bss (if needed) regions.

When using strace on Linux to trace system calls and we are tracing the exec of a dynamically linked program, we'll see the execve of that program. We won't see ld.so getting loaded because that happens as an internal kernel function, not a system call. Then next we'll see the various opens and mmaps.

Some additional magic is required to link the static and the dynamic portions of the executable. This aspect is extremely specific to the operating system and processor architecture. In general, for functions which are defined in a shared library, dummy stubs are provided in what is known as a Procedure Linkage Table. These stubs contain jumps to addresses which are filled in by the dynamic linker. This allows the static code to make function calls without being dynamic-aware. Likewise, a table known as the Global Offset Table provides transparent access to any global variables which a shared library exports. The dynamic libraries themselves need to be compiled in such as way that they are capable of being loaded at any virtual address. This is done with the -fpic (position independent code) flag to the compiler. The ld.so dynamic linker fills in the entries in the PLT and GOT based on the actual addresses that got assigned at runtime. The program is now completed linked and ready to execute, so ld.so jumps to the _start address contained in the a.out header. Since ld.so is designed to work in concert with the C library, this start function (the code of which is located in the text region associated with libc.so) does an munmap to destroy the text region that had contained the ld.so code.

There is a slight performance penalty when using dynamic libraries. In additional to the delay in executing the program imposed by needing to load and link the libraries, calls to functions in the dynamic library require an additional branch, and accesses to global symbols from within the shared library must use a position-independent addressing method, which generally requires an indirect addressing mode.

One down-side of dynamic linking is that a missing dynamic library (".so" files in UNIX terms, or "DLL"s in Windows-speak) will prevent a program from running, even if it was complete and correct at compile time. However, this disadvantage is more than outweighed by the reduction in executable size and the convenience of being able to correct errors in system libraries on the fly, without having to locate and recompile each and every executable based on the faulty library.

The program 1dd can be used to debug dynamic library resolution problems. This example shows the dynamic libraries that are needed for 1s on a 32-bit Linux system:

The numbers in parentheses are the addresses at which each of the dynamic libraries would load if the program were actually being executed.

Under certain circumstances, such as security-sensitive applications, it may be appropriate to use static linkage. This ensures that the program will always be able to run, and will always run with exactly the expected code.