# pyg2p 2.0

Version	2.0	
Author	Domenico Nappo (domenico.nappo(at)gmail.com)	
Release Date	2016-01	

# **Table of Contents**

ygzp 2.0		ا
Introduction		3
Manual in:	stallation of dependencies	4
	from v 1.x	
Configuration	1	е
Advanced	configuration	6
Execution	templates	8
Full list of	options	10
Usage		13
Grabbing i	information from GRIB files	13
Input argu	ments	13
Check out	put maps	15
Interpolation	modes	16
	creation	
GRIB API	interpolation methods	16
Scipy inter	rpolation methods	17
OutMaps of	configuration	18
Aggregation		19
Average		19
Accumula	tion	20
	rite formulas	
	ppotential file is used?	
1001		
_	ecution parameters	
Adding ge	opotential file to configuration	27

#### pyg2p 2.0

Appendix A - Execution JSON files Examples	28
Appendix B – mapping between grib2pcraster and pyg2p	
Differences in glossary	
Mapping variables	
Known parameters mapping with conversions	
Execution parameters mapping	
Difference in dealing with multiresolution	
Differences in Correction.	
Differences in Aggregation	34
Differences in Interpolation	
Appendix C – Glossary	
Appendix D – Developer notes	
Developer notes about correction formulas	

# **Introduction**

pyg2p is a tool to convert GRIB files into PCRASTER maps.

It reads georeferenced variables from GRIB version 1 and 2 files and it produces PCRaster maps, after some manipulation steps (conversion, aggregation). Execution parameters are passed via command line arguments and/or ISON template files.

Manipulations are completely configurable in execution JSON files and are of three types:

- conversion (formulas are to configure in parameters.json)
- correction (correction formulas are based on DEM maps and geopotential message and are to be configured in templates)
- aggregation (accumulation or average).

The interpolation mode is also configurable and it's needed to resample the input GRIB grid to the PCRaster target grid (which is determined by latitude and longitudes maps).

What you need to execute conversion with pyg2p version 2.0 is enlisted below:

- 1. The input grib file that contains the variable you want to convert, identified by its shortName
- 2. The geopotential message in a separate grib file (if not included with input grib file), for temperature altitude correction.
- 3. PCRaster coordinate maps (latitudes and longitudes) of target GRID for interpolation. DEM of target GRID for correction.

# Installation

To install package, you can use a python virtual environment or directly install dependencies and package at system level (executable script will be saved into /usr/local/bin in this case).

**IMPORTANT**: Before to launch setup, you need to configure geopotentials and intertables paths in configuration/global\_global\_conf.json. These paths are used by pyg2p to read geopotentials and intertables already configured. You may need to download files from FTP (use -W option for this). Users running pyg2p installed by a different user (ie. root) will configure similar paths for their own intertables and geopotentials under his home folder. These paths will need write permissions.

Grab last archive and follow these steps:

- \$ tar xzvf pyg2p.tar.gz
- \$ cd pyg2p
- \$ vim configuration/global/global\_conf.json # to edit shared paths !!!
- \$ python setup.py install

After installation, you will have all dependencies installed and an executable script 'pyg2p' (in a virtual environment, script is located under <*VIRTUALENV\_PATH>/bin* folder otherwise under /*usr/local/bin*). Some python packages can be problematic to install at first shot. Read following paragraph for details.

# Manual installation of dependencies

Default setup.py may have troubles in installing dependencies or you may prefer to install them manually.

Check this table to install dependencies manually (follow the order) and try to install again.

Python packages	
NumPy>=1.10.1	Scientific packages for array operations and reading/writing
Numexpr>=2.4.6	<ul> <li>encoded files. They depends on several C libraries that must exist</li> <li>on your system before to proceed.</li> </ul>
SciPy>=0.16	\$pip install numpy>=1.10.1
gribapi*	<pre>\$pip install numexpr \$pip install scipy&gt;=0.16.0</pre>
GDAL python**	\$pip install GDAL
	* If you have GDAL C/C++ libraries already installed on your system, you might need to install the exact GDAL python matching the C GDAL version.  ** For gribapi python package, please refer to GRIB
	API documentation.
dask[array] dask[bag] toolz	Light packages for parallelization (used in GRIB API interpolation methods):  \$pip install toolz  \$pip install dask[bag]  \$pip install dask[array]
xmljson	Used to convert old XML pyg2p v1 to v2 JSON format (-C command line argument):  \$pip install xmljson
memory_profiler (optional)	Memory usage information for test suite (for development).  \$pip install memory_profiler  \$pip install psutil

#### Migrating from v 1.x

If you migrate from a pyg2p version 1.x, you can convert existing XML configuration files to json (execution command files, parameters.xml and geopotentials.xml) and also convert old intertables (only grib api methods intertables).

- 1. Copy all your old XML configuration into a folder ./xml\_backup. You can create different subfolders for convenience because conversion will be recursive.
- 2. Convert files (recursively) from XML to JSON with command: \$pyg2p.py -C ./xml\_backup
- 3. Copy parameters.json and geopotentials.json from ./xml\_backup into user folder ~/.pyg2p/
- 4. Copy your geopotential files to folder defined in your .conf file in GEOPOTENTIALS variable.

You can also convert your existing interpolation tables made with pyg2p version 1.x GRIB\_API methods to be compliant with new format. New files will be copied under folder defined in INTERTABLES variable and intertables is no configuration will be updated during conversion.

\$pyg2p.py -z <path\_to\_convert>

Note: Intertables for rotated grids are not valid (GRIB\_API 1.14.4) so they won't be converted. You need to configure scipy interpolation methods for this kind of grid for the time being.

Intertables created with scipy methods cannot be converted but they are generally quite fast to create (seconds or minutes).

# **Configuration**

First thing to configure for an user running pyg2p, is GEOPOTENTIALS and INTERTABLES variables with paths to folders with write permissions.

These variables contains user paths and must be configured in a .conf file (e.g. paths.conf) under  $\sim /.pyq2p/$  directory. This can look like:

```
GEOPOTENTIALS=/dataset/pyg2p_data_user/geopotentials
INTERTABLES=/dataset/pyg2p_data_user/intertables
```

User intertables (for interpolation) are read/write from INTERTABLES and geopotentials (for correction) are read from GEOPOTENTIALS.

Pyg2p will use its default configuration for available intertables and geopotentials. These are read from paths configured during installation in global conf.json.

If you need to download default files from ECMWF FTP, just launch pyg2p with -W option and the dataset argument (argument can be geopotentials or intertables) and files are saved in user paths configured above:

```
$pyg2p -W intertables
```

You can edit FTP authentication parameters in ~/.pyg2p/ftp.json

### **Advanced configuration**

User json configuration files are empty. If you need a new parameter or geopotential that is not configured internally in pyg2p, you can setup new items (or overwrite internal configuration).

#### Adding a parameter to ~/.pyg2p/parameters.json

If you are extracting a parameter with shortName xy from a grib file that is not already globally configured, add an element as shown below (only part in **bold** has been added):

You can configure (more than) a conversion element with different ids and functions. You will use shortName and conversionId in the execution JSON templates.

```
{
      "xy": { "@description": "Variable description",
       "@shortName": "xy",
       "@unit": "unitstring"
      },
      "xyz": {
      "@description": "Variable description",
      "@shortName": "xyz",
      "@unit": "unitstring/unistring2",
      "Conversion": [
        {
            "@cutOffNegative": true,
            "@function": "x=x*(-0.13)**2",
            "@id": "conv xyz1",
            "@unit": "g/d"
        },
            "@cutOffNegative": true,
            "@function": "x=x/5466 - (x**2)".
            "@id": "conv_xyz2",
            "@unit": "g/h"
        }
     },
}
```

Note: Aware the syntax of conversion functions. They must start with x= followed by the actual conversion formula where x is the value to convert. Units are only used for logging.

#### Adding a geopotential for correction

If the input grib file has a geopotential message, pyg2p will use it for correction. Otherwise, it will read the file from user data paths or global data paths.

To add a geopotential GRIB file to pyg2p configuration, use this command:

#### \$pyg2p -g path\_to\_geopotential\_grib

This will copy the file to folder defined in GEOPOTENTIALS variable and will update geopotentials.json with the new item.

#### Interpolation tables

Interpolation tables are read from user or global data folders.

If the table is missing, it will create it into user data folder for future interpolations (you must pass -B option to pyg2p).

Depending on source and target grids size, and on interpolation method, table creation can take from minutes to days. To speed up interpolation table creation, use parallel option -X to have up to x6 speed gain.

#### **Execution templates**

Execution templates are JSON files that you will use to configure a conversion. You will pass path to the file to pyg2p with command line option'-c'.

Most of options can be both defined in this JSON file and from command line. Note that command line options overwrite JSON template.

If you have a large set of conversions for same parameters, it's more convenient to define a single template where you define parameter, interpolation and aggregation and pass the rest of parameters from command line.

Here some examples of JSON commands files:

```
"Execution": {
   "@name": "Octahedral test 1",
   "Aggregation": {
        "@step": 24,
        "@type": "average"
   "OutMaps": {
        "@cloneMap": "/dataset/maps/europe5km/dem.map".
        "@ext": 1,
        "@fmap": 1,
        "@namePrefix": "t2",
        "@unitTime": 24,
        "Interpolation": {
            "@latMap": "/dataset/maps/europe5km/lat.map".
            "@lonMap": "/dataset/maps/europe5km/long.map",
            "@mode": "grib nearest"
   "Parameter": {
        "@applyConversion": "k2c",
```

#### pyg2p 2.0

There are four sections of configuration.

#### Aggregation

Defines the aggregation method and step. Method can be accumulation, average or instantaneous.

#### **OutMaps**

Here you define interpolation method and paths to coordinates PCRaster maps, output unit time, the clone map etc.

#### Interpolation

This is a subelement of OutMaps. Here you define interpolation method (see later for details), paths to coordinates maps.

#### **Parameter**

In this section, you configure the parameter to select by using its shortName, as stored in GRIB file. You also configure conversion with *applyConversion* property set to a conversion id. Parameter *shortName* must be already configured in ~/.pyg2p/parameters.json along with conversion ids.

If you need to apply correction based on DEM files and geopotentials, you can configure formulas and the path to DEM map.

#### Path configuration

You can use variables in JSON files to define paths. Variables can be configured in .conf files under  $\sim$ /.pyg2p/ folder.

/home/domenico/.pyg2p/myconf.conf

```
EUROPE_MAPS=/dataset/maps/europe5km
DEM_MAP=/dataset/maps/dem05.map
EUROPE_DEM=/dataset/maps/europe/dem.map
EUROPE_LAT=/dataset/maps/europe/lat.map
EUROPE_LON=/dataset/maps/europe/long.map
```

Usage of user defined paths in JSON command file:

```
{ "Execution": {
        "@name": "eue_t24",
        "Aggregation": {
            "@step": 24,
            "@type": "average"
        "OutMaps": {
            "@cloneMap": "{EUROPE_MAPS}/lat.map",
            "@ext": 1,
            "@fmap": 1,
            "@namePrefix": "pT24",
            "@unitTime": 24,
            "Interpolation": {
                "@latMap": "{EUROPE_MAPS}/lat.map",
                "@lonMap": "{EUROPE_MAPS}/long.map",
                "@mode": "grib_nearest"
        },
        "Parameter": {
            "@applyConversion": "k2c",
            "@correctionFormula": "p+gem-dem*0.0065",
            "@demMap": "{DEM_MAP}",
            "@gem": "(z/9.81)*0.0065",
            "@shortName": "2t"
    }
}
```

# **Full list of options**

#### Main structure

Attribute/Tag	Details
name	The short name of the parameter, as it is in the grib file. The application use this to select messages.
Parameter	See relative table
Aggregation	See relative table
OutMaps	See relative table

# Parameter property

Attribute/Tag	Details
shortName	The parameter short name, as it is in the grib file. Must be configured in the parameters.json file, otherwise the application exits with an error. Main grib selector.
tstart	Optional grib selectors perturbationNumber, tstart, tend, dataDate and dataTime can also be
tend	issued via command line arguments (-m, -s, -e,
perturbationNumber	-D, -T), which overwrite the ones in the execution JSON file.
dataDate	
dataTime	
level	
applyConversion	The conversion id to apply, as in the parameters.json file for the parameter to select. The combination parameter/conversion must be properly configured in parmaters.json file, otherwise the application exits with an error.
correctionFormula <sup>1</sup>	Formula to use for parameter correction with p, gem, dem variables, representing parameter value, converted geopotential to gem, and DEM map value. E.g.: p+gem*0.0065-dem*0.0065
demMap	The dem map used for correction.
gem	Formula for geopotential conversion for correction.

# OutMaps property

Attribute/Tag	Details
cloneMap	The clone map with area ( <u>must have a REAL cell type and missing values for points outside area of interest.</u> A dem map works fine. A typical <u>area boolean map will not</u> ).
unitTime	Time unit in hours of output maps. Tipical value is 24 (daily maps).
namePrefix	Prefix for maps. Default is parameter shortName.

<sup>1</sup> When configuring correction, all properties *gem*, *correctionFormula*, and *demMap* must be present.

#### pyg2p 2.0

fmap	First map number. Default 1.
Interpolation	See relative table.
ext	Extension mode. It's the integer number defining the step numbers to skip when writing maps. Same as old grib2pcraster. Default 1.

# Aggregation property

Attribute/Tag	Details
step	Step of aggregation in hours.
type	Type of aggregation (it was Manipulation in grib2pcraster). It can be <i>average</i> or <i>accumulation</i> .
forceZeroArray	Optional. In case of "accumulation", and only then, if this attribute is set to"y" (or any value different from "false", "False", "FALSE", "no", "NO", "No", "0"), the program will use a zero array as message at step 0 to compute the first map, even if the GRIB file has a step 0 message.

# Interpolation property

Attribute/Tag	Details
mode	Interpolation mode. Possible values are: "nearest", "invdist", "grib_nearest", "grib_invdist"
latMap	PCRaster map of target latitudes.
lonMap	PCRaster map of target longitudes.
intertableDir	Alternative home folder for interpolation lookup tables, where pyg2p will load/save intertables. Folder must be existing. If not set, pyg2p will use intertables from ~/.pyg2p/intertables/

# <u>Usage</u>

To use the application, after the main configuration you need to configure a template JSON file for each type of extraction you need to perform.

### Grabbing information from GRIB files.

To configure the application and compile your JSON templates, you might need to know the variable shortName as stored in the input GRIB file you're using or in the geopotential GRIB. Just execute the following GRIB tool command:

```
grib get -p shortName /path/to/grib
```

Other keys you would to know for configuration or debugging purposes are:

- startStep
- endStep (for instantaneous messages, it can be the same of startStep)
- perturbationNumber (the EPS member number)
- stepType (type of field: instantaneous: 'instant', average: 'avg', cumulated: 'cumul')
- longitudeOfFirstGridPointInDegrees
- longitudeOfLastGridPointInDegrees
- latitudeOfFirstGridPointInDegrees
- latiitudeOfLastGridPointInDegrees
- Ni (it can be missing)
- Nj (it states the resolution: it's the number of points along the meridian)
- numberOfValues
- gridType (e.g.: regular II, reduced gg, rotated II)

See Mapping variables section in Appendix B – mapping between grib2pcraster and pyg2p for further information.

### Input arguments

If you run pyg2p without arguments, it shows help of all input arguments.

```
usage: pyg2p [-h] [-c json_file] [-o out_dir] [-i input_file]
[-l input_file_2nd] [-s tstart] [-e tend] [-m eps_member]
[-T data_time] [-D data_date] [-f fmap] [-x extension_step]
[-n outfiles_prefix] [-l log_level] [-N intertable_dir] [-B] [-X]
[-t cmds_file] [-g geopotential] [-C path] [-z path] [-W dataset]
```

Execute the grib to pcraster conversion using parameters from the input json

configuration. Read user manual. optional arguments: -h, --help show this help message and exit -c json file, --commandsFile json file Path to ison command file -o out dir, --outDir out dir Path where output maps will be created. -i input\_file, --inputFile input\_file Path to input grib. -I input file 2nd, --inputFile2 input file 2nd Path to 2nd resolution input grib. -s tstart, --start tstart Grib timestep start. It overwrites the tstart in ison execution file. -e tend, --end tend Grib timestep end. It overwrites the tend in json execution file. -m eps member, --perturbationNumber eps member eps member number -T data time, --dataTime data time To select messages by dataTime key value -D data\_date, --dataDate data\_date <YYYYMMDD> to select messages by dataDate key value -f fmap, --fmap fmap First map number -x extension\_step, --ext extension\_step Extension number step -n outfiles prefix, --namePrefix outfiles prefix Prefix name for maps -l log level, --loggerLevel log level Console logging level -N intertable dir, --intertableDir intertable dir interpolation tables dir -B, --createIntertable create intertable file -X, --interpolationParallel Use parallelization tools to make interpolation faster. If -B option is not passed or intertable already exists it does not have any effect. -t cmds file, --test cmds file Path to a text file containing list of commands, defining a battery of tests. Then it will create diff pcraster maps and log alerts if differences are higher than a threshold (edit configuration in test.json) -g geopotential, --addGeopotential geopotential Add the file to geopotentials.json configuration file, to use for correction. The file will be copied into the right folder (configuration/geopotentials) Note: shortName of geopotential must be "fis" or "z"

```
-C path, --convertConf path
```

Convert old xml configuration to new json format

-z path, --convertIntertables path

Convert old pyg2p intertables to new version and copy

to user folders

-W dataset, --downloadConf dataset

Download intertables and geopotentials (FTP settings

defined in ftp.json)

#### Usage examples:

```
pyg2p -c ./exec1.json -i ./input.grib -o /out/dir -s 12 -e 36
```

pyg2p -c ./exec2.json -i ./input.grib -o /out/dir -m 10 -l INFO

pyg2p -c ./exec3.json -i ./input.grib -l /input2ndres.grib -o /out/dir -m 10 -l DEBUG

pyg2p -g /path/to/geopotential/grib/file # add geopotential to configuration

pyg2p -t /path/to/test/commands.txt


pyg2p -h

### **Check output maps**

After the execution, you can check how output maps were written using the PCRaster<sup>2</sup> Aguila viewer.

You can also compare maps from grib2pcraster with those from pyg2p you just created:

#### aguila ./eue/T24a0000.001+10 /dataset/test 2013330702/T24aEFAS.001+10



Maps will be written in the folder specified by **-o** input argument. If this is missing, you will find maps in the folder where you launched the application (./).

Refer to PCRaster documentation for further information about Aguila.

<sup>2 &</sup>lt;a href="http://pcraster.geo.uu.nl/">http://pcraster.geo.uu.nl/</a>

# **Interpolation modes**

Interpolation is configured in JSON execution templates using the *Interpolation* attribute inside *OutMaps*.

There are four interpolation methods available. Two are using GRIB\_API nearest neighbours routines while the other two levereage on Scipy kd tree module.

**Note**: GRIB\_API does not implement nearest neighbours routing for rotated grids. You have to use scipy methods and regular target grids (i.e.: latitudes and longitudes PCRaster maps).

#### Intertable creation

Interpolation will use precompiled intertables. They will be found in the path configured in INTERTABLES folder (take into account that can potentially contains gigabytes of files) or in global data path. You can also define an alternate intertables directory with -N argument (or @intertableDir attribute in template).

If interlookup table doesn't exist, the application will create it into INTERTABLES folder and update intertables.json configuration **only if -B option is passed**, otherwise program will exit.

Be aware that for certain combination of grid and maps, the creation of the interlookup table (which is a numpy array saved in a binary file) could take several hours or even days for GRIB interpolation methods. To have better performances (up to x6 of gain) you can pass -X option to enable parallel processing.

Performances are not comparable with scipy based interpolation (seconds or minutes) but this option could not be viable for all GRIB inputs.

# **GRIB API interpolation methods**

To configure the interpolation method for conversion, set the @mode attribute in Execution/OutMaps/Interpolation property.

#### grib\_nearest:

This method uses GRIB API to perform nearest neighbour query.

To configure this method, define:

```
"Interpolation": {
    "@latMap": "/dataset/maps/europe5km/lat.map",
    "@lonMap": "/dataset/maps/europe5km/long.map",
    "@mode": "grib_nearest"
}
```

#### grib invdist:

It uses GRIB\_API to query for four neighbours and relative distances. It applies inverse distance calculation to compute the final value.

To configure this method:

```
"Interpolation": {
    "@latMap": "/dataset/maps/europe5km/lat.map",
    "@lonMap": "/dataset/maps/europe5km/long.map",
    "@mode": "grib_invdist"
}
```

### Scipy interpolation methods

#### nearest:

It's the same nearest neighbour algorithm of grib\_nearest but it uses the *scipy kd\_tree*<sup>3</sup> module to obtain neighbours and distances.

```
"Interpolation": {
    "@latMap": "/dataset/maps/europe5km/lat.map",
    "@lonMap": "/dataset/maps/europe5km/long.map",
    "@mode": "nearest"
}
```

#### invdist:

It's the inverse distance algorithm with *scipy.kd\_tree* , using 8 neighbours.

```
"Interpolation": {
    "@latMap": "/dataset/maps/europe5km/lat.map",
    "@lonMap": "/dataset/maps/europe5km/long.map",
    "@mode": "invdist"
}
```

Attributes p, leafsize and eps for the kd tree algorithm are default in scipy library:

Attribute	Details
р	2 (Euclidean metric)
eps	0
leafsize	10

<sup>3</sup> http://docs.scipv.org/doc/scipv/reference/generated/scipv.spatial.KDTree.html

# **OutMaps configuration**

Interpolation is configured under the **outMaps** tag. With additional attributes, you also configure resulting PCRaster maps. Output dir is ./ by default or you can set it via command line using the option -o (--outDir).

Attribute	Details
namePrefix	Prefix name for output map files. Default is the value of shortName key.
unitTime	Unit time in hours for results. This is used during aggregation steps.
fmap	Extension number for the first map. Default 1.
ext	Extension mode. It's the integer number defining the step numbers to skip when writing maps. Same as old grib2pcraster. Default 1.
cloneMap	Path to a PCRaster clone map, needed by PCRaster libraries to write a new map on disk.

# **Aggregation**

Values from grib files can be aggregated before to write the final PCRaster maps. There are two kind of aggregations available: average and accumulation. The relative JSON configuration in the execution file will look like:

```
"Aggregation": {
    "@type": "average"
},
```

To better understand what these two types of aggregations do, the DEBUG output of execution is presented later in same paragraph.

#### **Average**

Temperatures are often extracted as averages on 24 hours or 6 hours. Here's a typical execution configuration and the output of interest:

#### cosmo\_t24.json:

```
"Execution": {
    "@name": "cosmo T24",
    "Aggregation": {
        "@step": 24,
        "@type": "average"
    "OutMaps": {
        "@cloneMap": "/dataset/maps/europe/dem.map",
        "@ext": 4,
        "@fmap": 1,
        "@namePrefix": "T24",
        "@unitTime": 24,
        "Interpolation": {
             "@latMap": "/dataset/maps/europe/lat.map",
            "@lonMap": "/dataset/maps/europe/lon.map",
             "@mode": "nearest"
    "Parameter": {
```

```
pyg2p 2.0
```

```
"@applyConversion": "k2c",
    "@correctionFormula": "p+gem-dem*0.0065",
    "@demMap": "/dataset/maps/europe/dem.map",
    "@gem": "(z/9.81)*0.0065",
    "@shortName": "2t"
}
}
```

#### Command:

```
pyg2p -l DEBUG -c /execution_templates/cosmo_t24.json -i
/dataset/cosmo/2012111912_pf10_t2.grb -o ./cosmo -m 10
```

#### ext parameter

ext value will affect numbering of output maps.

```
[2013-07-12 00:06:18,545] :./cosmo/T24a0000.001 written!
[2013-07-12 00:06:18,811] :./cosmo/T24a0000.005 written!
[2013-07-12 00:06:19,079] :./cosmo/T24a0000.009 written!
[2013-07-12 00:06:19,349] :./cosmo/T24a0000.013 written!
[2013-07-12 00:06:19,620] :./cosmo/T24a0000.017 written!
```

This is needed because we performed 24 hours average over 6 hourly steps.

#### **Accumulation**

For precipitation values, accumulation over 6 or 24 hours is often performed. Here's an example of configuration and execution output in DEBUG mode.

#### Configuration dwd\_r06.json:

```
pyg2p 2.0
```

#### Command:

```
pyg2p -I DEBUG -c /execution_templates/dwd_r06.json -i /dataset/dwd/2012111912_pf10_tp.grb -o ./cosmo -m 10
```

#### Output:

**Note:** If you want to perform <u>accumulation</u> from Ts to Te with an aggregation step Ta, and **Ts-Ta=0** (e.g. Ts=6h, Te=48h, Ta=6h), the program will select the first message at step 0 if present in the GRIB file, while you would use a zero values message instead.

To use a zero values array, set the attribute forceZeroArray to "true" in the Aggregation configuration element.

For some DWD<sup>4</sup> and COSMO<sup>5</sup> accumulated precipitation files, the first zero message is an instant precipitation and the decision at EFAS was to use a zero message, as it happens for UKMO<sup>6</sup> extractions, where input GRIB files don't have a first zero step message.

\$ grib get -p units,name,stepRange,shortName,stepType 2012111912 pf10 tp.grb

kg m\*\*-2 Total Precipitation 0 tp **instant** kg m\*\*-2 Total Precipitation 0-6 tp accum

kg m\*\*-2 Total Precipitation 0-12 tp accum

kg m\*\*-2 Total Precipitation 0-18 tp accum

...

kg m\*\*-2 Total Precipitation 0-48 tp accum

<sup>4 &</sup>lt;a href="http://www.dwd.de/">http://www.dwd.de/</a>

<sup>5 &</sup>lt;a href="http://www.cosmo-model.org/">http://www.cosmo-model.org/</a>

<sup>6 &</sup>lt;a href="http://www.metoffice.gov.uk/">http://www.metoffice.gov.uk/</a>

# **Correction**

Values from grib files can be corrected with respect to their altitude coordinate (Lapse rate formulas). Formulas will use also a geopotential value (to read from a GRIB file, see later in this chapter for configuration).

Correction has to be configured in the Parameter element, with three mandatory attributes.

- correctionFormula (the formula used for correction, with input variables parameter value (p), gem, and dem value.
- gem (the formula to obtain gem value from geopotential z value)
- demMap (path to the DEM PCRaster map)

Tested configurations are only for temperature and are specified as follows:

#### **Temperature correction:**

```
"Parameter": {
    "@applyConversion": "k2c",
    "@correctionFormula": "p+gem-dem*0.0065",
    "@demMap": "/dataset/maps/europe/dem.map",
    "@gem": "(z/9.81)*0.0065",
    "@shortName": "2t"
}
```

#### **Evotranspiration correction:**

```
"Parameter": {
        "@applyConversion": "k2c",
        "@correctionFormula": "p/gem*(10**((-0.159)*dem/1000))",
        "@demMap": "/dataset/maps/europe/dem.map",
        "@gem": "(10**((-0.159)*(z/9.81)/1000))",
        "@shortName": "2t"
}
```

#### How to write formulas

**z** is the geopotential value as read from the grib file

**gem** is the value resulting from the formula specified in gem attribute *l.e.*: (gem = "(10\*\*((-0.159)\*(z/9.81)/1000)))"

**dem** is the dem value as read from the PCRaster map

Be aware that if your dem map has directions values, those will be replicated in the final map.

### Which geopotential file is used?

The application will try to find a geopotential message in input GRIB file. If a geopotential message is not found, pyg2p will select a geopotential file from user or global data paths, by selecting filename from configuration according the geodetic attributes of GRIB message. If it doesn't find any suitable grib file, application will exit with an error message.

Geodetic attributes compose the key *id* in the JSON configuration (note the \$ delimiter):

longitudeOfFirstGridPointInDegrees\$longitudeOfLastGridPointInDegrees\$Ni\$Nj\$numberOfValues\$gridType

If you want to add another geopotential file to the configuration, just execute the command:

#### pyg2p -g /path/to/geopotential/grib/file

The application will copy the geopotential GRIB file into GEOPOTENTIALS folder (under user home directory) and will also add the proper JSON configuration to geopotentials.json file.

# **Conversion**

Values from GRIB files can be converted before to write final output maps. Conversions are configured in the *parameters.json* file for each parameter (ie. shortName). The right conversion formula will be selected using the id specified in the *applyConversion* attribute, and the *shortName* attribute of the parameter that is going to be extracted and converted.

Refer to Parameter configuration paragraph for details.

# Logging

Console logger level is INFO by default and can be optionally set by using **-I** (or **-loggerLevel**) input argument.

Possible logger level values are ERROR, WARN, INFO, DEBUG, in increasing order of verbosity.

# pyq2p API

From version 1.3, pyg2p comes with a simple API to import and use from other python programs (e.g. pyEfas).

The pyg2p API is intended to mimic the pyg2p.py script execution from command line so it provides a Command class with methods to set input parameters and a *run\_command(cmd)* module level function to execute pyg2p.

#### **Setting execution parameters**

First, create a pyg2p command:

```
>>> import pyg2p
>>> command = pyg2p.command()
```

Then, set up the execution parameters using a chain of methods or single calls:

```
>>>command.with_cmdpath('a.json')
>>>command.with_inputfile('0.grb')
>>>command.with_log_level('ERROR')
>>>command.with_outdir('/dataout/').with_tstart('6').with_tend('24').with_eps('10').with_fmap('1')
>>>command.with_ext('4')
>>> print(str(command))
pyg2p.py -c a.json -e 240 -f 1 -i 0.grb -l ERROR -m 10 -o /dataout/test -s 6 -x 4
```

You can also create a command object using the input arguments as you would do when execute pyg2p from shell:

```
>>>args_string = '-I ERROR -c /pyg2p_git/execution_templates_devel/eue_t24.json -i /dataset/test_2013330702/EpsN320-2013063000.grb -o /dataset/testdiffmaps/eueT24 -m 10' >>>command2 = pyg2p.command(args_string)
```

#### **Execute**

Use the *run\_command* function from pyg2p module. This will delegate the main method, without shell execution.

#### >>>ret = pyg2p.run\_command(command)

The function returns the same value pyg2p returns if executed from shell (0 for correct executions, included those for which messages are not found).

### Adding geopotential file to configuration

You can add a geopotential file to configuration from pyg2p API as well, using the addGeo function:

#### >>>pyg2p.addGeo('/dataset/maps/fredrik/T3999.gph.grb')

The result will be the same of ./pyg2p -g /dataset/maps/fredrik/T3999.gph.grb

# **Appendix A - Execution JSON files Examples**

This paragraph will explain typical execution json configurations.

#### Example 1: Correction with dem and geopotentials

# pyg2p -c example1.json -i /dataset/cosmo/2012111912\_pf2\_t2.grb -o ./out\_1 example1.json

```
{
    "Execution": {
        "@name": "eue t24",
        "Aggregation": {
            "@step": 24,
            "@type": "average"
        "OutMaps": {
            "@cloneMap": "{EUROPE MAPS}/lat.map",
            "@ext": 1,
            "@fmap": 1,
            "@namePrefix": "pT24",
            "@unitTime": 24,
            "Interpolation": {
                 "@latMap": "{EUROPE MAPS}/lat.map",
                 "@lonMap": "{EUROPE MAPS}/long.map",
                 "@mode": "grib nearest"
        "Parameter": {
            "@applyConversion": "k2c",
            "@correctionFormula": "p+gem-dem*0.0065",
            "@demMap": "{DEM MAP}",
            "@gem": "(z/9.81)*0.0065",
            "@shortName": "2t"
}
```

This configuration, will select the 2t parameter from time step 0 to 12, out of a cosmo t2 file. Values will be corrected using the dem map and a geopotential file as in geopotentials.json configuration.

Maps will be written under ./out\_1 folder (the folder will be created if not existing yet). The clone map is set as same as dem.map. Note that paths to maps uses variables EUROPE\_MAPS and

DEM\_MAP. You will set these variables in myconf.conf file under ~/.pyg2p/ folder.

The original values will be converted using the conversion "k2c". This conversion must be configured in the parameters.json file for the variable which is being extracted (2t). See Parameter property configuration at Parameter.

The interpolation method is *grib\_nearest*. Latitudes and longitudes values will be used only if the interpolation lookup table (intertable) hasn't be created yet but it's mandatory to set latMap and lonMap because the application uses their metadata raster attributes to select the right intertable.

The table filename to be read and used for interpolation is automatically found by the application, so there is no need to specify it in configuration. However, lat and lon maps are mandatory configuration attributes.

#### Example 2: Dealing with multiresolution files

```
pyg2p -c example1.json -i 20130325_en0to10.grib -I 20130325_en11to15.grib -o ./out_2
```

Performs accumulation 24 hours out of sro values of two input grib files having different vertical resolutions. You can also feed pyg2p with a single multiresolution file.

#### pyg2p -c example1.json -i 20130325\_sro\_0to15.grib o ./out\_2 -m 0

```
{"Execution": {
        "@name": "multi sro",
        "Aggregation": {
             "@step": 24,
             "@type": "accumulation"
        "OutMaps": {
             "@cloneMap": "/dataset/maps/global/dem.map",
             "@fmap": 1,
             "@namePrefix": "psro",
             "@unitTime": 24,
             "Interpolation": {
                 "@latMap": "/dataset/maps/global/lat.map",
                 "@lonMap": "/dataset/maps/global/lon.map",
                 "@mode": "grib nearest"
        },
        "Parameter": {
             "@applyConversion": "m2mm",
             "@shortName": "sro",
             "@tend": 360,
             "@tstart": 0
    }
}
```

This execution configuration will extract global overlapping messages sro (perturbation number 0) from two files at different resolution.

Values will be converted using "tomm" conversion and maps (interpolation used here is grib nearest) will be written under ./out 6 folder.

#### Example 3: Accumulation 24 hours

./pyg2p.py -i /dataset/eue/EpsN320-2012112000.grb -o ./out\_eue -c execution\_file\_examples/execution\_9.json

```
"Execution": {
        "@name": "eue_tp",
        "Aggregation": {
             "@step": 24,
             "@type": "accumulation"
        "OutMaps": {
             "@cloneMap": "/dataset/maps/europe5km/lat.map",
             "@fmap": 1,
             "@namePrefix": "pR24",
             "@unitTime": 24,
             "Interpolation": {
                 "@latMap": "/dataset/maps/europe5km/lat.map",
                 "@lonMap": "/dataset/maps/europe5km/long.map",
                 "@mode": "grib nearest"
        },
        "Parameter": {
             "@applyConversion": "tomm",
             "@shortName": "tp"
    }
}
```

# Appendix B – mapping between grib2pcraster and pyg2p

This appendix aims to help to migrate from grib2pcraster to pyg2p.

### **Differences in glossary**

- The Manipulation as intended in grib2pcraster becomes Aggregation in pyg2c; if you read the term manipulation in the pyg2c documentation, that means a more generic term, including correction and conversion. Anyway, if you read the python code, the python class which performs aggregation is called Manipulator itself.
- What it's called TypeOfField in grib2pcraster becomes stepType in pyg2p (as for the GRIB standard). It defines the aggregated nature of the variable which can be instant, averaged, or cumulated.
- In grib2pcraster, the variable to extract is called parameter and it's referenced by a couple of numbers: **x.y**, where:
  - **x** is the value of the *indicatorOfParameter* key as found in the GRIB message
  - y is an internal number identifying the TableVersion as found in the parameters.xml file of grib2pcraster.
- In pyg2p, while the Parameter term was retained, it is identified by the *shortName* key as found in the GRIB message. This is an independent version key and it's only related to the variable itself and not to the *generating centre* of the file, since this is already coded in GRIB API tables. That is, in pyg2p the concepts of generating centre and table parameter versions don't need to exist.

# **Mapping variables**

To "translate" the parameter code **x.y** used in grib2pcraster to the **shortName** form of pyg2c, just follow these simple steps:

- 1. Identify the parameter in grib2pcraster's parameters.xml file using **y** to find the *gribTablesVersionNo* and **x** to find the single item *Param*.
- 2. Take note of abbreviation and field description strings of the Param above.
- 3. Use some basic GRIB tools (and meteorological) skills to find the **shortName** value of the grib:

grib get -p shortName,parameterName /path/to/grib/file.grib2

# Known parameters mapping with conversions

Variable	grib2pcraster selectors (indicatorOfParameter.gribT ablesVersionNo)	pyg2p.py shortName	Configured conversions in grib2pcraster
2 meters Dew- point	<ul><li>17.2</li><li>168.128</li></ul>	• 2D	• x-273.15
2 meters Temperature	• 11.2 • 500011.0 • 167.128	<ul><li>t_2m</li><li>td_2m</li><li>2t</li></ul>	• x-273.15
Total precipitation	• 61.2 • 228.128	• tp	<ul><li>Only cut off</li><li>x*1000 + cut off</li></ul>
Latent heat flux	• 500086.0 • 121.2	• alhfl_s	<ul> <li>x*(-0.0353) +         cut off         [default]</li> <li>x*(-0.00147) +         cut off</li> </ul>
Surface Latent heat flux	• 147.128	• slhf	No conversion
Surface Runoff	• 8.230 • 8.128	• sro	• x*1000 + cut off
Sub-Surface Runoff	• 9.230 • 9.128	• ssro	• x*1000 + cut off
Large scale precipitation	• 142.128	• Isp	• x*1000 + cut off
Convective precipitation	• 143.128	Not tested. It needs to be added to parameters.xml if used.	• x*1000 + cut off
Evaporation	• 182.128	• e	• x*(-1000)
Runoff	• 205.128	Not tested. It needs to be added to parameters.xml if used.	<ul> <li>x*1000 + cut off (not as default, it needs to be set by command line withunit parameter)</li> </ul>
Surface precipitation amount, rain, grid scale	• 102.201	• rain_gsp	Only cut off
Surface precipitation amount, rain,	• 113.201	• rain_con	Only cut off

#### pyg2p 2.0

convective			
Large scale rain rate	• 500134.0	Not tested. It needs to be added to parameters.xml if used.	Only cut off
Snow fall	• 144.128	Not tested. It needs to be added to parameters.xml if used.	• x*1000
Snow depth	• 141.128	Not tested. It needs to be added to parameters.xml if used.	X*1000 (not as default, it needs to be set by command line withunit parameter)

# **Execution parameters mapping**

Argument	grib2pcraster	pyg2p.py
Input file	-i	-i
Variable	-p x.y	json <sup>7</sup> (shortName)
Output directory	-0	-0
EPS perturbationNumber	-m	-m
Variable level	level	json
Aggregation type	Default in parameters.xml. Overwriting withma	json (type)
Aggregation step	-t	json (step)
Start step	-S	-s or json (tstart)
End step	-е	-e or json (tend)
Output map unittime	unittime	json (unitTime)
Interpolation	-r,-l,-a or –intertable	json (see relative section in this manual).
Conversion	parameters.xml	parameters.json and json command file (applyConversion)
Correction	Two formulas hardcoded and configured	json (attributes

In this table, "json" means that the corresponding parameter configuration is in the execution json template where you configure your extraction and pass to the pyg2p with the -c input argument. If not indicated otherwise, the json tag/attribute name is the same as the grib2pcraster input argument (e.g.: --level=10 becomes the json attribute level="10").

	by default in parameters.xml or withtemp andevap.	correctionFormula, gem, dem)
Map extension naming	fmap,ext	json
Map prefix name	-n	json
Logging	report. Loggers directory is under program installation folder	Console logger level overwritable with -I (default is INFO).

# Difference in dealing with multiresolution

Multiresolution extraction can be made in one step with pyg2p, using both -i and -I for input files or even a single multiresolution file. The grib2pcraster application needs to perform two executions, instead.

#### **Differences in Correction**

There is a sort of bug in grib2pcraster when come to correction, since the dem values it uses are stored in its interlookup tables and, if the DEM has changed for some reasons, the corrected values will be wrong unless the interlookup table is not regenerated using the new DEM map.

However, here the main difference is that the correction formulas are editable directly by the user in pyg2p.

# **Differences in Aggregation**

The type of aggregation and its step window must be specified in pyg2p, using the **Aggregation** attribute.

In grib2pcraster, instead, the type of aggregation for the specific variable is being extract (i.e. manipulation) is read from *ManipulationFlag* attribute in *parameters.xml* file: "1" for average and "2" for accumulation. The step window is 24 hours by default and it can be overwritten with -t parameter.

### **Differences in Interpolation**

Resampling of grids in grib2pcraster is made using GRIB API. Available interpolation methods are:

- nearest neighbours
- inverse distance

The interpolation table file is declared with the input argument –intertable, or otherwise by configuration, using one of the tables in *interpolation.xml*.

In **pyg2p** there are two additional resampling modes (see the relative Interpolation modes paragraph in this document). Results are very similar to GRIB\_API based interpolation methods but interlookup table is being created in seconds rather than hours (in our tests, interlookup table creation for high resolution or global scale grids take almost two days with GRIB\_API methods while

#### pyg2p 2.0

it takes one minute with scipy based methods).

They are *nearest* and *invdist* modes, performed using scipy routines to find neighbours and distances.

Interlookup tables are read/written by default using ~/.pyg2p/intertables as folder where to load existing intertables or save new ones. An alternative folder can be specified using the intertableDir attribute in the *Interpolation* property of the json template configuration.

# **Appendix C - Glossary**

Brief description of terms you find in this manual, with their synonims.

Term	Synonims	Description
Interpolation lookup table	Intertable, interlookup table	It's a numpy binary file containing indexes correspondences and coefficients/distances. Each combination of <b>GRIB grid/</b> PCRaster target coordinates maps/Interpolation mode has its own intertable. Since there are four interpolation modes using intertables, there can be four different intertables for each combination of <b>GRIB grid/</b> PCRaster lat/lon maps.
Aggregation		Average or accumulation
Interpolation	Resampling	Resampling between the original <b>GRIB grid</b> and the target raster lat/lon coordinates.
Execution JSON template file	Execution template, commands file, execution file, json template, json configuration	The JSON file where most of <b>execution parameters</b> are configured. It's being passed by the mandatory CLI argument <b>-c</b> .
Parameter	Variable	The meteorological variable stored in the input grib file.
Command line Input argument	Input argument, CLI argument, option	Input arguments to the application passed via command line. They are -i,-I,-o,-m,-I,-d,-c
Execution parameter	Parameter, input argument	All configured options (via CLI or json files) that define the execution context.
GRIB grid	Grid	It's the set of geodetic attributes identifying the coordinate system and the specific projected area. The set includes <b>gridType</b> , first and last values of latitude and longitudes, number of

Term	Synonims	Description
		points along the meridian.
GRIB message's gridType	Grid type, grid	It's the specific grid type of the <b>GRIB message</b> and can be regular_rr, regular_II, rotated_rr, rotated_II, reduced_II and so on.
GRIB message	Grib	It's a single message extracted from a <b>GRIB file</b> .
GRIB API		C library (and its wrappers) from ECMWF to deal with <b>grib files</b> .
GRIB file	Grib	An input file encoded using GRIB format.
Geopotential GRIB values	Geopotential	Geopotential values encoded in grib files, used for correction.
Gem value	Gem	In correction, the <b>gem value</b> is being obtained using the formula configured with <i>gem</i> property, where <i>z</i> is the geopotential value.  E.g. gem = "(z/9.81)*0.0065"

# <u>Appendix D – Developer notes</u>

# **Developer notes about correction formulas**

Previous correction formulas were derived directly from grib2pcraster C code. The need to set up two formulas – one for the gem value and one for the final corrected value (which uses the previously formulated gem value) – exists because the correction formulas are based on DEM and geopotential values. DEM values are in PCRaster format while geopotential data is a GRIB message, which needs to be interpolated before to put it into the correction formula. That means that the correction process is applied in two steps with a split formula as configured.

#### **Grib2pcraster correction process:**

In this paragraph, some C code is shown from the original grib2pcraster C application.

Geopotential value is read from a grib file as (note the correction):

```
} else if (intCorrectionFlag == 2)//evap correction
{
    for (i = 0; i < values_len; i++) {
        pgeopotential[i] = pgeopotential[i] / 9.81;
        pgeopotential[i] = pow(10, ((-0.159) * (pgeopotential[i]) / 1000));
    }
}</pre>
```

Then, the actual correction is made during the interpolation process (some not relevant code was removed and comments added to the real code):

```
//interpolation
float tmpValue = (pGRIBValues[grid[i].indexInGRIBArrNode1]) *
(grid[i].CoefficientNode1) + (pGRIBValues[grid[i].indexInGRIBArrNode2]) *
(grid[i].CoefficientNode2) + (pGRIBValues[grid[i].indexInGRIBArrNode3]) *
(grid[i].CoefficientNode3)
                                                                       + (pGRIBValues[grid[i].indexInGRIBArrNode4]) *
(grid[i].CoefficientNode4);
if (intCorrectionFlag != 0) {
     //interpolation of geopotential as read before
    float tmpGeo = (geopotential[grid[i].indexInGRIBArrNode1]) *
                                                                                       (geopotential[grid[i].indexInGRIBArrNode2]) *
(grid[i].CoefficientNode1) +
(grid[i].CoefficientNode2) + (geopotential[grid[i].indexInGRIBArrNode3]) *
(grid[i].CoefficientNode3)
+ (geopotential[grid[i].indexInGRIBArrNode4]) * (grid[i].CoefficientNode4);
       //correction formula is applied here (the correctionFormula in pyg2p)
      if (intCorrectionFlag == 1)//temperature correction
                                   tmpValue = (tmpValue + tmpGeo) - (grid[i].demValue * 0.0065);
      if (intCorrectionFlag == 2)//evap correction
                                          tmpValue = (tmpValue / tmpGeo) * (pow(10, ((-0.159) * tmpValue)) * (pow(10, ((-0.159) * tmpValue)) * (pow(10, ((-0.159) * tmpValue))) * (pow(10, ((-0.15
(grid[i].demValue) / 1000)));
 //store value in the output array
pPCRasterValues[grid[i].indexInPCRasterArr] = tmpValue;
```

#### pyg2p correction process

The process in pyg2p is almost the same, that means:

read geopotential from grib, and apply the correction formula as configured in json execution

#### pyg2p 2.0

- file (gem="(z/9.81)\*0.0065")
- interpolate the gem values so obtained to the PCRaster output grid
- read grib values and interpolate them
- apply the final correction formula as configured (correctionFormula="p+gem-dem\*0.0065")

The only difference is that in pyg2p formulas are configurable, as explained in this chapter (read Configuration manual as well), while in grib2pcraster you can choose, with a binary flag in parameters.json file, between two hard coded formulas (one for temperature and one for evaporation).