

StochSS: Stochastic Simulation Service

User Guide and Tutorial



Contents

C	Contents				
1	Installation 1.1 Mac OS X 1.2 Linux 1.3 Windows 1.4 Note on security	5			
2	Basic Introduction				
	2.1 Creating Administrator and Standard User Accounts	8			
	2.2 Importing a Model	9			
	2.3 Creating a New Model	9			
	2.4 Running a Simulation and Visualizing results	11			
	2.5 Backup and Transfer your Data	12			
3	Sensitivity Analysis	13			
	3.1 Example: Michaelis-Menten	13			
4	StochOptim: Parameter Estimation	14			
	4.1 Example: Estimate parameters of a birth-death model	14			
5	Spatial Stochastic Simulations	16			
	5.1 Example: Annihilation of two species in a cylinder	16			
	5.2 Visualization (of Annhihilation of two species in a cylinder)	17			
6	Cloud Computing	19			
	6.1 Credentials	19			
	6.2 Job Reproduction	20			
	6.3 Cost Analysis	21			
7	Flex Cloud				
	7.1. Setting Un Flex Cloud Compute Machines	23			

CONTENTS	3
ONTENTS	3

8	Imp	ort a custom mesh	25
	8.1	Mesh library	25
	8.2	Using DOLFIN Built-In Geometry with Subdomains Outside of Mesh Library	25
	8.3	Advanced mesh generation	27
	8.4	References	28
Bil	bliogr	aphy	29

Installation

StochSS supports Mac OS X, Linux, and Windows (preliminary) through the Docker platform.

To install StochSS, you'll need to install Docker on your computer, and then use the appropriate StochSS launch application to initialize and run your StochSS Docker container.

1.1 Mac OS X

Running StochSS

- Install Docker Toolbox using directions here: https://docs.docker.com/engine/installation/mac/#installation
- Download the Mac OS X application zip file: http://stochss.org/releases/stochss.mac.1.7.0.zip
- Double click the icon to launch server.

Uninstalling StochSS can be performed with the uninstall app included with the zip file above.

When things go wrong

Leaving StochSS is running while the computer goes to sleep can cause the network configuration of the virtual machine to change unexpectedly when the computer is woken up again. This means that StochSS could become temporarily inaccessible. Performing the following steps may solve this: Open a Docker Quickstart terminal window and run:

- docker-machine start stochss1-7
- docker-machine ssh stochss1-7
- docker stop stochsscontainer1_7
- docker start stochsscontainer1_7
- exit

Our suspicion is that when we ssh into the virtual machine, it's network configuration is reset/corrected.

1.2. LINUX 5

1.2 Linux

StochSS requires Docker to run. The StochSS run script (stochss.sh) uses Docker to download and run StochSS inside a Docker container (this is basically a lightweight virtual machine). Docker and this script are all you need to run Stochss on your Linux computer.

Note: The Ubuntu 12.04 default kernel is too old to support Docker. 12.04 users can instead just run StochSS without the container. Download the package at http://stochss.org/releases/stochss.linux.1.7.0.tgz and refer to the old installation instructions at http://www.stochss.org/wordpress/?page_id=224#linux.

Running StochSS

- Install Docker using directions here: https://docs.docker.com/engine/installation/linux/
- Open up a terminal window
- Download the Ubuntu run script:

```
curl -o stochss.linux.1.7.0.tgz http://stochss.org/releases/stochss.linux.1.7.0.tgz
```

• Untar the folder and navigate inside:

```
tar -xzf stochss.linux.1.7.0.tgz; cd stochss.linux.1.7.0
```

• Run the script (the script will ask for your administrative password):

```
./stochss.sh
```

Uninstalling StochSS

- · Open up a terminal window
- Run:
 - sudo docker stop stochsscontainer1_7
 - sudo docker rm stochsscontainer1_7

1.3 Windows

StochSS requires Docker Toolbox for Windows to run. This means you will need a 64 bit Windows installation that supports Docker (Windows 64 7, 8, and 10, should all work).

Please note:

- 1. StochSS does not run on Microsoft Edge browser. The recommended browser is Google Chrome.
- 2. You may have to enable virtualization in the BIOS (Use this Microsoft Virtualization detector to check if virtualization is enabled in your system: https://www.microsoft.com/en-us/download/details.aspx?id=592. If it's not, please enable it from the BIOS first).

Running StochSS

- 1. Install Docker Toolbox using directions here: https://docs.docker.com/engine/installation/windows/
 - To paste text from your clipboard to Docker Quickstart terminal, *right click* onto the terminal screen.
 - To copy text from the Docker Quickstart terminal onto your clipboard, highlight the desired text and press *enter/return*.
- 2. Open the Docker QuickStart Terminal. Run the following commands:
 - docker-machine start stochss1-7 || docker-machine create --driver virtualbox stochss1-7
 - eval "\$(docker-machine env stochss1-7)"

This will start/create a Virtual Machine called 'stochss1-7', and give you terminal access to it. StochSS will run in this machine. To verify that the machine is running, run the following command:

• docker-machine ls

You should see that the status of machine 'stochss1-7' is running.

Please note the IP address of the of the machine 'stochss1-7'. Run the following command to determine the IP address:

- docker-machine ip stochss1-7
- 3. If this is the first time you're starting StochSS, run the following to start StochSS container:

• docker run -i -t -p 8080:8080 -p 8000:8000 --name=stochsscontainer1_7 stochss/stochss-launcher:1.7 "/bin/bash"

This will download the StochSS docker image, create the StochSS docker container and give terminal access to it. **PLEASE NOTE**: when this is complete you will get the message:

bash: /usr/local/share/dolfin/dolfin.conf: No such file or directory

Otherwise, if you already have a StochSS docker container (i.e. when you use StochSS subsequently), run

- docker start stochsscontainer1_7
- docker exec -ti stochsscontainer1_7 /bin/bash
- 4. Run the following commands to start the server:
 - cd stochss-master
 - ./run.ubuntu.sh -a \textbf{the_ip_address_you_noted_in_Step_2_above} -t secretkey

Navigate to the URL displayed to access StochSS.

5. Follow the instructions on the terminal to kill the server process. After that, run the following commands to stop the container:

1.4. NOTE ON SECURITY 7

- exit
- docker stop stochsscontainer1_7
- docker-machine stop stochss1-7

These commands will stop the container and virtual machine. The terminal window can now be safely closed.

Uninstalling StochSS

- 1. Open the Docker Quickstart terminal
- 2. Run the following command:

```
docker-machine rm stochss1-7
```

When things go wrong

- 1. Launching and using StochSS on Windows is error-prone. Some useful commands that may help you in figuring out what's going on when things don't work as expected are:
 - docker-machine ls
 - docker ps
 - docker ps -aq
- 2. Leaving StochSS is running while the computer goes to sleep can cause the network configuration of the virtual machine to change unexpectedly when the computer is woken up again. This means that StochSS could become temporarily inaccessible. Performing the following steps may solve this:Open a Docker Quickstart terminal window and Run:
 - docker-machine start stochss1-7
 - docker-machine ssh stochss1-7
 - docker stop stochsscontainer1_7
 - docker start stochsscontainer1_7
 - exit

Follow the instructions in this guide to start StochSS.

Our suspicion is that when we ssh into the virtual machine, it's network configuration is reset/corrected.

1.4 Note on security

When you run StochSS, it is encapsulated inside a virtual machine. If something goes wrong with the StochSS virtual machine, it is isolated from everything else on your system.

Basic Introduction

This tutorial will guide you through the basic features of StochSS. You will become familiar with the **Model Editor** and the **Simulation Manager**. You will learn how to create your own model, which can be population or concentration-based, and how to simulate it using either an ordinary differential equation (ODE) solver or the stochastic simulation algorithm (SSA).

2.1 Creating Administrator and Standard User Accounts

At the end of a successful installation process, your default browser will launch and you will be asked to create an admin account as in Figure 2.1 (there is only one admin account for the entire system). Once the admin account is created you will be forwarded to a regular login page where you can log in to StochSS.




Figure 2.1: Administrator login page

2.2. IMPORTING A MODEL

9

Users can click **Create Account** to request an account. The account will not be accessible until the admin approves it in the **Admin Panel** (the admin can also delete active users as well as reset their passwords there).

2.2 Importing a Model

The **Model Editor** will let you create new or modify existing well-mixed stochastic biochemical models as well as deterministic models based on ODEs. The best way to get started with the model editor is to import an example model and look at the different sections.

Importing an existing model

Option 1: StochSS Public Library

- 1. Navigate to the **Model Editor** page.
- 2. Click Import from Public Library in the right-hand toolbar.
- 3. Select a model from the Public Library and click Copy Model to Library.

Option 2: Stochkit2 XML

- 1. Navigate to the **Model Editor** page.
- 2. Click **Import from .XML** in the right-hand toolbar.
- 3. Select an XML file. A collection of example models can be found in the *examples* directory within the StochSS install folder.
- 4. Click Import.

After importing the XML file or public model, StochSS should display the imported model in the model editor. Look through the page to see how the different **Species**, **Parameters**, and **Reactions** are defined. By clicking **Export to .zip** or **Export to Public Library** the model can be shared across computers or shared amongst users of the same StochSS.

2.3 Creating a New Model

An example population model is defined by the following two reactions:

$$S0 + S0 \xrightarrow{k1} S1$$

$$S1 \xrightarrow{k0} \emptyset.$$
(2.1)

To create this model:

- 1. Navigate to the Model Editor.
- 2. Click Add Model and select Population, Well-mixed.
- 3. Rename the model to example.

- 4. Click **Create Species** twice to create two species.
- 5. By default the species are named *S*0 and *S*1. Set the initial condition for *S*0 to 1000 and the initial condition for *S*1 to 0.
- 6. Similarly to above, click Add Parameter twice to add two parameters.
- 7. By default they will be named k0 and k1. Set k0 to 0.0001 and k1 to 0.05.
- 8. Click **Add Reaction** to add two reactions. Select the reactants, products, rates and reaction types corresponding to (2.1). Compare to Figures 2.2 and 2.3 to verify the settings.




Figure 2.2: Dimerization reaction



Figure 2.3: Decay reaction

2.4 Running a Simulation and Visualizing results

For this section, create or import a model using the directions above.

- 1. Navigate to the **Simulation Manager** page.
- 2. Select the model you wish to simulate and click **Next**.
- 3. Setup your simulation parameters: name, time, data storage frequency, realizations and solver type.
 - a) If you are simulating a population-based model you can choose between the deterministic and the stochastic solvers.
 - b) Concentration-based models can only be simulated using the deterministic solver.
- 4. Click **Run Locally**. You will be automatically forwarded to the **Job Status** page.
- 5. Click View to open the Job summary page, where you can visualize the simulation's trajectories.
- 6. Click **Access Local Data** to download a raw copy of the data. This can be used to share data between StochSS installations or perform manual data analysis.

Converting a concentration model to population

Create a concentration model or use the directions above to import one. Both Lotka-Volterra examples are concentration based and are available both as XML files and Public Library models.

- 1. Select the newly minted concentration model.
- 2. Click **Convert to Population** on the right-hand toolbar to start the conversion process. The model conversion page will open.
- 3. To convert a concentration model to a population, a system volume must be specified.
- 4. Given a volume, StochSS converts initial conditions through

$$initial_condition_population = initial_condition_concentration \times volume$$
 (2.2)

and attempts to convert the reaction rates. It is not always possible to convert reaction rates automatically. If automatic conversion fails the conversion still proceeds, but the user now has to correct the reactions that were not automatically converted.

- 5. Click **Finish conversion** at the bottom left of the page to create a population-based model. This newly created population model can be simulated using both deterministic and stochastic solvers.
- 6. Click **Cancel conversion** to cancel the conversion.



The conversion process operates correctly only if the model to be converted is entirely based on the mass action kinetics allowed in Gillespie Stochastic Simulation Algorithm [1]. If the model to be converted is not entirely based on mass action kinetics, the conversion tool only converts what it can.

2.5 Backup and Transfer your Data

You can backup or share your saved models and simulations with the StochSS ZIP format. There are three ways to create StochSS ZIP files:

- Navigate to the **Backup** page in the left-hand toolbar and click **Export**. This exports a ZIP containing all models and simulation results for the current user. There is an option to export all data for all users if this page is accessed with the admin account.
- Select a model on the Model Editor page and click Export to .zip.
- Click View on the Job Status page, and then click Access local data.

These ZIP files can all be imported into StochSS on the **Backup** page. To import the contents of a ZIP file into StochSS:

- 1. Navigate to the **Backup** page.
- 2. Click **Import**.
- 3. Select the ZIP file to upload. The file should automatically begin uploading, and then appear in a table of ZIP archives below.
- 4. Select the ZIP file in the table.
- 5. Define the behavior of the import by either limiting what files get imported or specifying how overlapping names are handled.
- 6. Click **Import** at the bottom of the page.

Exporting data from an old version of StochSS (1.2 or previous)

To create a backup archive from an older version of StochSS, execute the following command from a terminal window in the directory of your new StochSS installation:

./exportserver.py path_to_your_old_StochSS_installation

You can import the backup archive you created as described above.

Sensitivity Analysis

StochSS implements forward sensitivity analysis based on the CVODES ODE solver [2].

For instance, if we consider the population of P and the parameter Vmax in the Michaelis-Menten model in the **Public Library**. The sensitivity of the rate of the increase in population P to the parameter Vmax is defined as the incremental rate of change in P due to incremental changes in Vmax:

$$\frac{\partial P(t)}{\partial V_{max}}. (3.1)$$

These are the sensitivities that StochSS produces. There is no rescaling to make these sensitivities unitless.

3.1 Example: Michaelis-Menten

In this example we will study the Michaelis-Menten model from the StochSS Public Library. Details on the model can be found in [9].

- 1. Import the model from the public library. By default, it will be called *michaelis_menten*.
- 2. Navigate to the Simulation Manager, select the model, and click Next.
- 3. Under **Simulation type**, select *Deterministic + Sensitivity*.
- 4. You can now select the parameters for which you wish to compute sensitivities. For instance you could select Km, k3, mu, and Vmax, to perform sensitivity analysis with only these parameters.
- 5. Click Run Locally.
- Navigate to the **Job Summary** page to analyze the output. You can plot species trajectories as well as sensitivities.

StochOptim: Parameter Estimation

StochSS implements parameter estimation for stochastic biochemical systems, StochOptim, via the Monte Carlo expectation-maximization with Modified Cross-Entropy method (MCEM²) [5]. MCEM² computes maximum likelihood parameter estimates (MLEs) and associated uncertainties in three consecutive phases: cross-entropy, Monte Carlo expectation-maximization (MCEM), and uncertainty quantification [5].

4.1 Example: Estimate parameters of a birth-death model

We consider the Birth-Death model that can be imported from the StochSS Public Library (see Section 2 for instructions on how to import models in StochSS). After the model has been imported:

- 1. Select **Parameter estimation** from the menu on the left of the screen.
- 2. Select the *birthdeath* model and click **Next**. This will open the **Simulation page**.
- 3. Example files (StochOptim input data) for the initial conditions and the trajectories are provided in the *examples* folder (included in your StochSS package) and are named *birthDeathInitial.txt* and *birthDeathTrajectories.txt*, respectively.
- 4. Upload and select these example files.
- 5. Configure the checkboxes to only perform parameter estimation on k1. For the example model, the value of k2 is already optimized.
- 6. Click **Run Locally** to start the parameter estimation.
- 7. Select **Job Status** from the menu on the left of the screen to monitor the status of your submitted job. For the example trajectory data, k1 = 1.0 and k2 = 0.03 are the correct parameter values so the simulation should converge to somewhere close to these.
- 8. Click **View Progress** to access the **Job Summary** page and to view more details about status of your job. Parameter estimation calculations using MCEM² are typically time consuming computations. This simple example takes a little less than 20 minutes on a desktop Intel i7 computer. A more realistic job will take much longer to run.
- 9. When the job has finished, you can generate a new model using the final estimates of the MCEM² calculation by scrolling to the bottom of the **Job Summary** page and click **Create Model from Current Estimates**.

10. If the job doesn't complete in a reasonable amount of time the job can be stopped manually on the **Job Status** page and the parameters can be extracted by clicking **Create Model from Current Estimates**.

StochOptim input file format

The StochOptim input data format consists of two tab-separated text files. The first file represents the initial conditions of the system, and the second file represents trajectories of it. Each file has three base columns. *Time, Rep,* and *Weight.* Additional columns are added for every species in the model that parameter estimation is to be run on.

- The *Time* column contains the time values of the various trajectories (and should be set to zero for the initial conditions file).
- The *Rep* column is used to include multiple trajectories in one file for fitting. Basically each trajectory should have a different *Rep* number.
- The Weight column is currently unused and should be set to 1.
- The rest of the columns should be named after the species (case-sensitive) in the model the data will be fit against, and the columns themselves should contain integers representing the population counts at the various time points.

An example of this can be seen by comparing the files *birthDeathTrajectories.txt* and *birthDeathTrajectoriesMulti.txt* in the *examples* folder included in the StochSS package.

Spatial Stochastic Simulations

The spatial stochastic simulation capabilities in StochSS are based on PyURDME [8]. PyURDME is a general software framework for modeling and simulation of stochastic reaction-diffusion processes on unstructured, tetrahedral (3D) and triangular (2D) meshes. The current core simulation algorithm is based on the mesoscopic reaction-diffusion master equation (RDME) model. The default solver is an efficient implementation of the next subvolume method (NSM) [7].

5.1 Example: Annihilation of two species in a cylinder

We will build a simple annihilation model based on an cylinder geometry. At each end of the cylinder, different chemicals will be produced. When they diffuse and meet at the center, they will annihilate each other.

- 1. Navigate to the main Model editor.
- 2. Add a new model. Select *Population, spatial* in the dropdown menu.
- 3. Click **Mesh** and select *Cylinder*. The cylindrical mesh is divided into three subdomains which can be visualized with the controls below the wireframe view.
- 4. Add two species, *A* and *B*, both with diffusion constant 1.
- 5. Click **Initial Condition**, select *scatter*, and add 500 molecules of species *A* in subdomain 1 and 500 molecules of species *B* in subdomain 3.
- 6. Add two parameters, k0 and k1, and set their values to 1 and 100, respectively.
- 7. Add three reactions:

R1:
$$\emptyset \xrightarrow{k_1} A$$

R2:
$$\emptyset \stackrel{k_1}{\rightarrow} B$$

R3:
$$A + B \stackrel{k_0}{\rightarrow} \emptyset$$

- 8. Reaction *R*1 should be restricted to subdomain 1 and reaction *R*2 to subdomain 3. Reaction *R*3 should be allowed throughout the whole domain.
- 9. The model is now complete and ready to be simulated.

- 10. Navigate to the Simulation manager page.
- 11. Select the spatial model you just created and click Next.
- 12. Setup the simulation parameters: name, time, data storage frequency, and number of realizations.
- 13. You can specify a random seed for the random number generator under Advanced Settings.
- 14. Click Run locally.
- 15. In a few seconds you will be directed to the **Job Status** page where you can check the status of your simulation.
- 16. Once your simulation is complete, click **View results** to open the **Job summary** page, where you can visualize the diffusion of the two species over time within the cylindrical container and download the output files of the simulation.

5.2 Visualization (of Annhihilation of two species in a cylinder)

Full three dimensional spatial stochastic simulations can be difficult to analyze. To simplify the process, StochSS has built in three different methods for visualization of spatial models.

Surface Renderings with Domain Clipping

By default, spatial stochastic simulations are rendered as shown in Figure 5.1. These are surface renderings, but the simulations are volumetric. To see inside the volume, StochSS allows slicing the mesh in half along one axis with a plane and only rendering one of the resultant halves. This is shown in Figure 5.2

Figure 5.1: Surface rendering of cylindrical domain. The actual stochastic simulation is run on the dual of the shown mesh, so the color at each node corresponds to the concentration in the corresponding voxel of the dual mesh. Colors are interpolated linearly between nodes. The color scale is not shown for brevity.

Figure 5.2: Surface rendering of cylindrical domain clipping along the X dimension. It is now possible to see concentrations of voxels inside the cylinder.

Colorized Wireframe Meshes

The second rendering type is similar to the first, but instead of rendering surfaces only edges are rendered (see Figure 5.3). The colorization is the same, it is just ideally easier to see inside the mesh. Similarly to the surface rendering the wireframe renderings can be clipped to get a clearer view of what is happening inside the volume. See Figure 5.4 for a demonstration of clipping a mesh in the Y dimension.

Figure 5.3: Wireframe rendering of cylindrical domain. The colors are handled similarly to in Figure 5.1.

Figure 5.4: Wireframe rendering of cylindrical domain clipped in the Y direction.

Volume Rendering

The final rendering StochSS offers is a volume rendering (Figure **??**). It uses a basic ray-tracing implementation following the one in [10].

Figure 5.5: This is the volume rendering of the same data shown above. The idea behind volume rendering is to color darkly areas with high concentrations and leave volumes with low concentrations transparent. The transparency makes it possible to see inside a volume rendering, and so the slicing as shown in the surface and wireframe renderings is not used.

Cloud Computing

6.1 Credentials

StochSS provides the options to run jobs using the Amazon cloud infrastructures. In order to use Amazon Elastic Computing Cloud (EC2), Simple Storage Service (S3) and DynamoDB database, which are all required for running jobs in the cloud, you need an Amazon Web Services (AWS) account and a credential pair (consisting of a secret key and an access key) in hand.

More information regarding how to create an AWS account and get credentials can be found here: http://aws.amazon.com

Setting Credentials in StochSS

You must set your credentials in StochSS manually (Figure 6.1). Once StochSS validates these, you will be able to launch compute nodes and run jobs in the Amazon cloud.






Figure 6.1: Cloud Computing page - Credentials section

- 1. Navigate to the main Cloud Computing page.
- 2. Copy your access key to the Access Key text box.
- 3. Copy your secret key to the **Secret Key** text box.

4. Click Save credentials to validate and save your credentials.

Launching and Shutting Down Nodes

Once valid credentials are entered, clicking **Launch nodes** (Figure 7.1) by default will launch one c3.large Amazon instance. This first node is designated the **head node**. Any other nodes launched are called **worker nodes**. There can be zero or more worker nodes, and they are c3.larges instance types by default. For information on Amazon instance types, look here: http://aws.amazon.com/ec2/instance-types/. The head node must be a c3.large or c3.xlarge. The worker nodes can be any combination of t1.micro, m1.small, m3.medium, m3.large, c3.large, and c3.xlarge nodes (chosen in the **Advanced settings** menu).

Only one head node is needed to run jobs in the cloud. It is possible to access cloud data even when no head nodes are launched. Compute resources and storage resources are billed separately by Amazon. More details can be found at: http://aws.amazon.com/ec2/pricing/.



Figure 6.2: Cloud Computing page - Compute nodes default setting section

Launching a node takes time. The **Refresh status** button can be used to check the launch progress. The **Terminate all nodes** button terminates all the nodes that StochSS started.

6.2 Job Reproduction

StochSS provides the flexibility to store simulation output in the cloud or delete it and regenerate it later. If simulations are fast but produce large amounts of data, reproducing data only when it is needed can save money.

An Example on Job Reproduction

Reproducing a cloud job is simple:

1. Launch a compute node.

6.3. COST ANALYSIS 21

2. Run a well-mixed or spatial model (everything except parameter estimation jobs can be reproduced).

- 3. Navigate to the Job Status page.
- 4. Click **view** beside the job you would like to reproduce.
- 5. Click **Delete Output** to delete output in the cloud. No reproduction action is available until you delete the output.
- 6. Once the output is deleted, the option to reproduce the job will be appear as shown in Figure 6.3.
- 7. Choose a node type for reproduction. If there is no such instance type running, a warning will show up to guide you to the **Cloud Computing** page to launch one.
- 8. Click **Reproduce Results** to submit the reproduction request. This will automatically redirect to the **Job Status** page where the new job's status can be monitored.




Figure 6.3: Job summary page - reproduction available

6.3 Cost Analysis

Because different instance types cost different amounts of money, it is not obvious which nodes are the cheapest for any given job type. StochSS allows manual measurement of job cost with the cost-analysis tool.



Figure 6.4: Cost Analysis page

An Example on Job Reproduction

- 1. Run a well-mixed or spatial model.
- 2. Navigate to the **Job Status** page.
- 3. Click **view** beside the job you would like to analyze.
- 4. Click **Cost Analysis** in the **Reproduction and Cost Analysis** section.
- 5. By default, cost analysis should be available for whatever instance type the job was run on.
- 6. Click **Analyze** with any other node type you would like to run and analyze the job on. At least one node of this instance type must already be running.
- 7. The run times and costs of simulating the jobs are plotted on the screen as in Figure 6.4.

Flex Cloud

StochSS 1.6 introduces Flex Cloud, an abstraction which allows you to run StochSS jobs on any machine, physical or virtual, provided it is running Ubuntu 12.04 with the required software dependencies installed.

7.1 Setting Up Flex Cloud Compute Machines

Preparing the Flex Cloud compute nodes

- Configure one or more machines running Ubuntu 12.04 (Precise).
- Please make sure the machines have their own IP address and are accessible with just a username and
 a passwordless SSH keypair. If necessary, generate SSH keypairs for the machines. You will need to
 upload the SSH private key to the StochSS user interface to access the machines.
- Configure the firewall on the machines to allow connections on the following ports: 22, 5672, 6379, 11211, 55672, 80, 443, 3306. These are used for various services used by StochSS. If the machines are instances running on a public or private cloud, you may need to enable the ports by modifying the associated cloud security group.
- Install the software prerequisites on the machines by using the command line utility <code>make_flex_vms.py</code> which can be found in the StochSS Github repository in the directory <code>release-tools/flex-cloud</code>. You can either specify the username, IP address, and SSH keys of the machines in a machine config file (an example one is included in the same directory for reference) or you can specify the machines on the command line. The script <code>make_flex_vms.py</code> will also verify that the necessary network ports are open and working. Please see <code>make_flex_vms.py-h</code> for further information.

Configuring the compute nodes in StochSS

- Click **Cloud Computing** to navigate to the main **Cloud Computing** page.
- You have the option of selecting **Amazon AWS Cloud** or **Flex Cloud**. Select **Flex Cloud**. It will redirect you to **Flex Cloud Credentials** page.
 - (Note: You cannot set up both Amazon AWS Cloud or Flex Cloud at the same time. If one cloud computing infrastructure has been set up, the link for the other infrastructure will be disabled on this page.)
- Click **Choose Files** to upload the SSH private keys (see Figure 7.1).




Figure 7.1: Uploaded SSH keys for Flex Machines - Flex Cloud Credentials page

- Next, in the first row of the **Flex Cloud Machine Info** table, type the IP address and username, and select the appropriate key pair for the compute node that should act as the queue head. The Flex Queue Head will act as a coordinate for StochSS jobs, as well as store all output for jobs run in the cloud. This machine should be fairly robust; for EC2 instances a c3.large would be appropriate.
- Click + to add more compute nodes.
- Click **Deploy** to start the Flex Cloud service.
- The compute nodes may take a few minutes to launch. Refresh the page occasionally and wait until all nodes enter the *Running* state as shown in the **Flex Cloud Machine Info** table.
- Once Flex Cloud has been successfully configured, StochSS will run jobs in Flex Cloud when you click
 Run via Cloud as long as Flex Cloud has been successfully configured and the Flex Queue Head node
 is up and running.
- To stop Flex Cloud, click **Stop** on the Flex Cloud configuration page. (Note: **Stop** does not terminate/shut-down/reboot machines).



24

Any data that is not downloaded from the Flex Cloud will be inaccessible while the Flex Cloud is turned off. Reconfiguring the queue head or keys without downloading job results can lead to data loss.

Import a custom mesh

When setting up a spatial problem in StochSS information about the geometry needs to be provided through two files: a file containing the mesh information in DOLFIN XML format and a text file containing information about subdomains. The file with subdomain information is optional in general (if it is not provided the entire mesh will belong to one subdomain). Below is a tutorial on how to provide that information in a variety of cases.

8.1 Mesh library

The first and simplest scenario is using one of the default built-in meshes provided by StochSS in the Mesh Library. These include simple example mesh and subdomain combinations that are common in biological modeling. For example there is a unit sphere with a membrane (i.e. the volume is one subdomain and the surface is another), a unit cube witha membrane, a cylinder with the two ends being different subdomains among others. If for a given problem these are not sufficient then mesh and subdomain information can be provided by attaching files. One simple case where creating and attaching a file may be necessary could involve using the DOLFIN built in meshes but with different subdomains than provided in the Mesh Library. This can be done as follows.

8.2 Using DOLFIN Built-In Geometry with Subdomains Outside of Mesh Library

For example consider a sphere with three different subdomains: the top half of the membrane, the bottom half of the membrane and the volume. This can be done using PyURDME as follows (PyURDME and FEniCS are software packages that are automatically installed during the StochSS installation and DOLFIN is a library within FEniCS).

In an IPython Notebook, import the appropriate libraries:

```
In [1]: import os,pyurdme,dolfin
```

Next classes are constructed to define the desired subdomains:

Then a pyurdme model is created with the desired geometry and marked subdomains:

```
In [3]:
           class sphere_top_bot(pyurdme.URDMEModel):
                   def __init__(self,model_name="polarization"):
                           pyurdme.URDMEModel.__init__(self,model_name)
                           #DefineGeometry
                           sphere=dolfin.Sphere(dolfin.Point(0.0,0.0,0.0),1.0)
                           self.mesh=pyurdme.URDMEMesh(mesh=dolfin.Mesh(sphere,10))
                           cell_function=dolfin.CellFunction("size_t",self.mesh)
                           cell_function.set_all(1)
                           facet_function=dolfin.FacetFunction("size_t",self.mesh)
                           facet_function.set_all(0)
                           top_membrane=top_half_membrane()
                           top_membrane.mark(facet_function,2)
                           bottom_membrane=bottom_half_membrane()
                           bottom_membrane.mark(facet_function,3)
                           self.add_subdomain(cell_function)
                           self.add_subdomain(facet_function)
                           #Define initial populations
                           self.set_initial_condition_scatter({},[1])
```

The subdmain infomation can then be extracted from the model as follows:

And finally two files are created to store the mesh and subdomain information respectively in the the correct format:

```
In [6]: This is a dolfin xml file with mesh information
dolfin.File("sphere_top_bot_mesh.xml") << model.mesh</pre>
```

Now that these two files have been created they can be attached in the Mesh tab of the model editor in StochSS and the rest of the problem can be defined from there. Again it is important to note that if a problem does not involve subdomains then only the mesh XML file is necessary and the entire mesh will be given the same domain! One last situation that could arise in defining spatial information is that a mesh has to be created in external software then converted to the correct format.

8.3 Advanced mesh generation

For many real world applications the geometry involved will be more complicated than the built?in meshes provided by DOFLIN (and by extension StochSS). In these situations a mesh will have to be created in an external program such as Gmsh then converted into the DOLFIN XML format. Once the mesh has been created in an external program the conversion to DOLFIN XML format can easily be done by the built in script dolfin?convert [1]. The following command line code demonstrates how to convert from the Gmsh format (suffix .msh or .gmsh) to DOLFIN XML format.

The following needs to be run from the command line in the Terminal:

```
dolfin-convert mesh.msh mesh.xml
```

File formats that are currently supported by the dolfin-convert script can be found in the table below:

Suffix	File Format
.xml	DOLFIN XML format
.ele / .node	Triangle file format
.mesh	Medit format, generated by TetGen with option?g
.msh / .gmsh	Gmsh version 2.0 format
.grid	Diffpack tetrahedral grid format
.inp	Diffpack tetrahedral grid format
.e / .exo	Sandia Exodus II file format
.ncdf	ncdump'ed Exodus II file format
.vrt / .cell	StarCD tetrahedral grid format

The XML file that is created from the dolfin?convert command can then be used directly in StochSS. If subdomains are required then a text file can be created using code similar to that above. Consider the situation where the XML file created was called "coli.xml" then the code to create a subdomain file consisting of the outer membrane would look as follows:

```
In [10]:
           class ecoli(pyurdme.URDMEModel):
                   def __init__(self,model_name="polarization"):
                           pyurdme.URDMEModel.__init__(self,model_name)
                            \#DefineGeometry
                            self.mesh=pyurdme.URDMEMesh(mesh=dolfin.Mesh('coli.xml'))
                            cell_function=dolfin.CellFunction("size_t",self.mesh)
                            cell_function.set_all(1)
                           facet_function=dolfin.FacetFunction("size_t",self.mesh)
                           facet_function.set_all(0)
                           membrane=Membrane()
                           membrane.mark(facet_function,2)
                            self.add_subdomain(cell_function)
                            self.add_subdomain(facet_function)
                            \#Define initial populations
                            self.set_initial_condition_scatter({},[1])
In [11]:
           model=ecoli()
           sd=model.get_subdomain_vector()
In [12]:
In [13]:
           This is the file to capture information about subdomains
           with open("coli_subdomains.txt",'w') as fd:
                   for ndx,val in enumerate(sd):
                           fd.write("{0},{1}\n".format(ndx,val))
```

Now all of the necessary files have been created. The "coli.xml" file that was created using a dolfin?convert command and the "coli_subdomains.txt" just created can be uploaded directly to StochSS and used accordingly.

8.4 References

1. A. Logg, K.?A. Mardal, G. N. Wells et al. Automated Solution of Partial Differential Equations by the Finite Element Method: The FEniCS Book. Springer 2012.

Bibliography

- [1] D.T. Gillespie. *Exact stochastic simulation of coupled chemical reactions*. J. Phys. Chem., 81(25), 2340-2361 (1977)
- [2] A. C. Hindmarsh et al., SUNDIALS: Suite of nonlinear and differential/algebraic equation solvers. ACM Trans. Math. Softw., 31(3), 363-396 (2005)
- [3] W. A. Link and P. F. Doherty Jr., Scaling in sensitivity analysis. Ecology, 83(12), 3299-3305 (2002)
- [4] M. C. Hill, *Methods and guidelines for effective model calibration*. U.S. Geol. Surv. Water Resour. Invest. Rep. 98-4005 (1998)
- [5] B.J. Daigle et al. Accelerated maximum likelihood parameter estimation for stochastic biochemical systems. BMC Bioinformatics, 13, 68 (2012)
- [6] B.S. Caffo et al. *Ascent-based Monte Carlo expectation-maximization*. J. Royal Statistical Society Series B, 67(2), 235-251 (2005)
- [7] J. Elf and M. Ehrenberg, Spontaneous separation of bi-stable biochemical systems into spatial domains of opposite phases. IEEE Systems Biology, 1, 230-6 (2004)
- [8] B. Drawert, S. Engblom and A. Hellander, *URDME: A modular framework for stochastic simulation of reaction-transport processes in complex geometries.* BMC Systems Biology, 6(76) (2012)
- [9] Michaelis-Menten kinetics. http://en.wikipedia.org/wiki/Michaelis-Menten_kinetics
- [10] Congote, John and Segura, Alvaro and Kabongo, Luis and Moreno, Aitor and Posada, Jorge and Ruiz, Oscar. *Interactive Visualization of Volumetric Data with WebGL in Real-time* In Proceedings of the 16th International Conference on 3D Web Technology (Web3D '11). ACM, New York, NY, USA, 137-146. http://dx.doi.org/10.1145/2010425.2010449