CS 3205 COMPUTER NETWORKS

JAN-MAY 2020

LECTURE 2,3: 14TH 21ST JAN 2020

Text book and section(s) covered in this lecture: Book Kurose and Ross – Sections 1.2, 1.3, 1.4.1,1.4.2


Chapter I: roadmap

- I.I what is the Internet?
- 1.2 network edge
 - end systems, access networks, links
- 1.3 network core
 - packet switching, circuit switching, network structure
- 1.4 delay, loss, throughput in networks
- 1.5 protocol layers, service models
- 1.6 networks under attack: security
- 1.7 history

A closer look at network structure:

network edge:

- hosts: clients and servers
- servers often in data centers
- access networks, physical media: wired, wireless communication links
- network core:
 - interconnected routers
 - network of networks




Access networks and physical media

Q: How to connect end systems to edge router?


- residential access nets
- institutional access networks (school, company)
- mobile access networks

keep in mind:

- bandwidth (bits per second) of access network?
- shared or dedicated?




Access net: digital subscriber line (DSL)



- use existing telephone line to central office DSLAM
 - data over DSL phone line goes to Internet
 - voice over DSL phone line goes to telephone net
- < 2.5 Mbps upstream transmission rate (typically < I Mbps)
- < 24 Mbps downstream transmission rate (typically < 10 Mbps)</p>


DSLAM- Digital Subscriber Line Access Multiplexer BRAS – Broadband Remote Access Server

Access net: cable network




frequency division multiplexing: different channels transmitted in different frequency bands

Access net: cable network



- HFC: hybrid fiber coax
 - asymmetric: up to 30Mbps downstream transmission rate, 2
 Mbps upstream transmission rate
- network of cable, fiber attaches homes to ISP router
 - homes share access network to cable headend
 - unlike DSL, which has dedicated access to central office
- Data Over Cable Service Interface Specification (DOCSIS) is a set of standards for transferring data by CATV and cable modems.

Access net: home network




Access net: home network – WLAN Standards

IEEE Standard	802.11a	802.11b	802.11g	802.11n	802.11ac	802.11ax
Year Released	1999	1999	2003	2009	2014	2019
Frequency	5Ghz	2.4GHz	2.4GHz	2.4Ghz & 5GHz	2.4Ghz & 5GHz	2.4Ghz & 5GHz
Maximum Data Rate	54Mbps	11Mbps	54Mbps	600Mbps	1.3Gbps	10-12Gbps

http://www.ieee802.org/11/ - Web site for 802.11 related information

Enterprise access networks (Ethernet)



- typically used in companies, universities, etc
- 10 Mbps, 100Mbps, 1Gbps, 10Gbps transmission rates
- today, end systems typically connect into Ethernet switch

Wireless access networks

- shared wireless access network connects end system to router
 - via base station aka "access point"


wireless LANs:

- within building (100 ft)
- 802.11b/g (WiFi): 11,54 Mbps transmission rate



wide-area wireless access

- provided by telco (cellular) operator, 10's km
- between I and I0 Mbps
- 3G, 4G: LTE



Wireless - Wide Area Networks

Table 1.7 Performance Evolution of 3GPP Standards


	3GPP	Peak Down-	Peak	
Standard	Release	link Speed	Uplink Speed	Latency
GPRS	Release 97/99	40–80kbps	40–80kbps	600-700ms
EDGE	Release 4	237–474kbps	237kbps	350–450ms
UMTS (WCDMA)	Release 4	384kbps	384kbps	<200ms
HSDPA/UMTS	Release 5	1800kbps	384kbps	<120ms
HSPA	Release 6	3600–7200kbps	2000kbps	<100ms
HSPA+	Release 7 and 8	28-42Mbps	11.5Mbps	<80ms
LTE	Release 8	173–326Mbps	86Mbps	<30ms

	LTE	LTE-Advanced	LTE-Adv. Pro	5G
	2008	2012	2015	2018
3GPP Release	8 & 9	10 to 12	13 & 14	15
Theoretical maximum (DL) speed	300Mbps	>1Gbps	>3Gbps	>10Gbps
Latency	≈50ms	10ms	2ms	1ms
Channel bandwidth	Up to 20MHz	Up to 20MHz	Up to 20MHz	Up to 500MHz
Carriers	1	5	32	16 (LTE+NR)
Antennas(MIMO)	4	8	32	64 to 256

Host: sends packets of data

host sending function:

- takes application message
- breaks into smaller chunks, known as packets, of length L bits
- transmits packet into access network at transmission rate R
 - link transmission rate, aka link capacity, aka link bandwidth



```
transmission delay time needed to transmit L-bit packet into link = \frac{L \text{ (bits)}}{R \text{ (bits/sec)}}
```

Physical media

- bit: propagates between transmitter/receiver pairs
- physical link: what lies between transmitter & receiver
- guided media:
 - signals propagate in solid media: copper, fiber, coax
- unguided media:
 - signals propagate freely, e.g., radio

twisted pair (TP)

- two insulated copper wires
 - Category 5: 100 Mbps, 1
 Gpbs Ethernet
 - Category 6: I0Gbps



If you are interested to know in detail the workings of Ethernet - visit https://www.hardwaresecrets.com/how-gigabit-ethernet-works/
https://en.wikipedia.org/wiki/Ethernet_over_twisted_pair

Physical media: coax, fiber

coaxial cable:

- two concentric copper conductors
- bidirectional
- broadband:
 - multiple channels on cable
 - HFC (Hybrid Fiber Coxial) (Combining optical and coaxial)



fiber optic cable:

- glass fiber carrying light pulses, each pulse a bit
- high-speed operation:
 - high-speed point-to-point transmission (e.g., 10' s-100' s Gpbs transmission rate)
- low error rate:
 - repeaters spaced far apart
 - immune to electromagnetic noise



Physical media: radio

- signal carried in electromagnetic spectrum
- no physical "wire"
- bidirectional
- propagation environment effects:
 - reflection
 - obstruction by objects
 - interference

radio link types:


- terrestrial microwave
 - e.g. up to 45 Mbps channels
- LAN (e.g., WiFi)
 - I I Mbps, 54 Mbps
- wide-area (e.g., cellular)
 - 3G/4G/5G cellular: ~ few Mbps/ Gbps
- satellite
 - Kbps to 45Mbps channel (or multiple smaller channels)
 - 270 msec end-end delay
 - geosynchronous versus low altitude

Chapter I: roadmap


- I.I what is the Internet?
- 1.2 network edge
 - end systems, access networks, links
- 1.3 network core
 - packet switching, circuit switching, network structure
- 1.4 delay, loss, throughput in networks
- 1.5 protocol layers, service models
- 1.6 networks under attack: security
- 1.7 history

The network core

- mesh of interconnected routers
- packet-switching: hosts break application-layer messages into packets
 - forward packets from one router to the next, across links on path from source to destination
 - each packet transmitted at full link capacity



Packet-switching: store-and-forward




- takes L/R seconds to transmit (push out) L-bit packet into link at R bps
- store and forward: entire packet must arrive at router before it can be transmitted on next link
- end-end delay = 2L/R (assuming zero propagation delay)

one-hop numerical example:

- L = 7.5 Mbits
- R = 1.5 Mbps
- one-hop transmissiondelay = 5 sec

more on delay shortly ...

Packet Switching: queueing delay, loss




queuing and loss:

- If arrival rate (in bits) to link exceeds transmission rate of link for a period of time:
 - packets will queue, wait to be transmitted on link
 - packets can be dropped (lost) if memory (buffer) fills up

Two key network-core functions


routing: determines sourcedestination route taken by packets forwarding: move packets from router's input to appropriate router output




Alternative core: circuit switching

end-end resources allocated to, reserved for "call" between source & dest:

- In diagram, each link has four circuits.
 - call gets 2nd circuit in top link and 1st circuit in right link.
- dedicated resources: no sharing
 - circuit-like (guaranteed) performance
- circuit segment idle if not used by call (no sharing)
- Commonly used in traditional telephone networks



Circuit switching: FDM versus TDM



Packet switching versus circuit switching


packet switching allows more users to use network!

example:

- I Mb/s link
- each user:
 - 100 kb/s when "active"
 - active 10% of time



- 10 users
- packet switching:
 - with 35 users, probability > 10 active at same time is less than .0004 *



Q: how did we get value 0.0004?

Q: what happens if > 35 users?

Packet switching versus circuit switching

A Numerical example

Suppose users share a 3 Mbps link. Also suppose each user requires 150 kbps when transmitting, but each user transmits only 10 percent of the time. (See the discussion of packet switching versus circuit switching in Section 1.3.)

- a. When circuit switching is used, how many users can be supported?
- For the remainder of this problem, suppose packet switching is used. Find the probability that a given user is transmitting.
- c. Suppose there are 120 users. Find the probability that at any given time, exactly n users are transmitting simultaneously. (Hint: Use the binomial distribution.)
- d. Find the probability that there are 21 or more users transmitting simultaneously.

Packet switching versus circuit switching


is packet switching a "slam dunk winner?"

- great for bursty data
 - resource sharing
 - simpler, no call setup
- excessive congestion possible: packet delay and loss
 - protocols needed for reliable data transfer, congestion control
- Q: How to provide circuit-like behavior?
 - bandwidth guarantees needed for audio/video apps
 - still an unsolved problem (chapter 7)


Q: human analogies of reserved resources (circuit switching) versus on-demand allocation (packet-switching)?

- End systems connect to Internet via access ISPs (Internet Service Providers)
 - Residential, company and university ISPs
- * Access ISPs in turn must be interconnected.
 - So that any two hosts can send packets to each other
- Resulting network of networks is very complex
 - Evolution was driven by economics and national policies
- Let's take a stepwise approach to describe current Internet structure


Question: given millions of access ISPs, how to connect them together?




Option: connect each access ISP to every other access ISP?




Option: connect each access ISP to a global transit ISP? Customer and provider ISPs have economic agreement.




But if one global ISP is viable business, there will be competitors




But if one global ISP is viable business, there will be competitors which must be interconnected




... and regional networks may arise to connect access nets to ISPS




... and content provider networks (e.g., Google, Microsoft, Akamai) may run their own network, to bring services, content close to end users






- at center: small # of well-connected large networks
 - "tier-I" commercial ISPs (e.g., Level 3, Sprint, AT&T, NTT), national & international coverage
 - content provider network (e.g, Google): private network that connects it data centers to Internet, often bypassing tier-I, regional ISPs

Tier-I ISP: e.g., Sprint




The Indian Scenario




https://main.trai.gov.in/consumer-info/telecom/service-provider-list http://www.ispai.in/UI/organizationlist.php?cmd=resetall

Some Large Interconnections - Reliance



https://www.rcom.co.in/infrastructure/our-global-network/network-maps/

Some Large Interconnections - Vodafone



http://globalnetworkmap.vodafone.com/#/submarine-cable/bay-of-bengal-gateway-bbg http://globalnetworkmap.vodafone.com/


Chapter 1: roadmap


- I.I what is the Internet?
- 1.2 network edge
 - end systems, access networks, links
- 1.3 network core
 - packet switching, circuit switching, network structure
- 1.4 delay, loss, throughput in networks
- 1.5 protocol layers, service models
- 1.6 networks under attack: security
- 1.7 history

How do loss and delay occur?

packets queue in router buffers

- packet arrival rate to link (temporarily) exceeds output link capacity
- packets queue, wait for turn






d_{proc} : nodal processing

- check bit errors
- determine output link
- typically < msec

d_{queue} : queueing delay

- time waiting at output link for transmission
- depends on congestion level of router



d_{trans}: transmission delay:

- L: packet length (bits)
- R: link bandwidth (bps)

•
$$d_{trans} = L/R$$

$$d_{trans} \text{ and } d_{prop}$$

$$very \text{ different}$$


d_{prop}: propagation delay:

- d: length of physical link
- s: propagation speed in medium (~2×10⁸ m/sec)

$$d_{prop} = d/s$$

^{*} Check out the Java applet for an interactive animation on trans vs. prop delay


Caravan analogy



- cars "propagate" at 100 km/hr
- toll booth takes 12 sec to service car (bit transmission time)
- car~bit; caravan ~ packet
- Q: How long until caravan is lined up before 2nd toll booth?

- time to "push" entire caravan through toll booth onto highway = 12*10 = 120 sec
- time for last car to propagate from 1st to 2nd toll both: 100km/(100km/hr)= 1 hr
- A: 62 minutes

Caravan analogy (more)



- suppose cars now "propagate" at 1000 km/hr
- and suppose toll booth now takes one min to service a car
- Q: Will cars arrive to 2nd booth before all cars serviced at first booth?
 - A: Yes! after 7 min, 1st car arrives at second booth; three cars still at 1st booth.

A Numerical example - I

This elementary problem begins to explore propagation delay and transmission delay, two central concepts in data networking. Consider two hosts, A and B, connected by a single link of rate R bps. Suppose that the two hosts are separated by m meters, and suppose the propagation speed along the link is s meters/sec. Host A is to send a packet of size L bits to Host B.


- a. Express the propagation delay, d_{prop} , in terms of m and s.
- Determine the transmission time of the packet, d_{trans}, in terms of L and R.
- Ignoring processing and queuing delays, obtain an expression for the endto-end delay.
- d. Suppose Host A begins to transmit the packet at time t = 0. At time t = d_{trans}, where is the last bit of the packet?
- e. Suppose d_{prop} is greater than d_{trans}. At time t = d_{trans}, where is the first bit of the packet?
- f. Suppose d_{prop} is less than d_{trans}. At time t = d_{trans}, where is the first bit of the packet?
- g. Suppose $s = 2.5 \cdot 10^8$, L = 120 bits, and R = 56 kbps. Find the distance m so that d_{prop} equals d_{trans} .

A Numerical example -2

Consider a packet of length L which begins at end system A and travels over three links to a destination end system. These three links are connected by two packet switches. Let d_i , s_i , and R_i denote the length, propagation speed, and the transmission rate of link i, for i = 1, 2, 3. The packet switch delays each packet by d_{proc} . Assuming no queuing delays, in terms of d_i , s_i , R_i , (i = 1,2,3), and L, what is the total end-to-end delay for the packet? Suppose now the packet is 1,500 bytes, the propagation speed on all three links is $2.5 \cdot 10^8$ m/s, the transmission rates of all three links are 2 Mbps, the packet switch processing delay is 3 msec, the length of the first link is 5,000 km, the length of the second link is 4,000 km, and the length of the last link is 1,000 km. For these values, what is the end-to-end delay?

Queueing delay (revisited)

- R: link bandwidth (bps)
- L: packet length (bits)
- a: average packet arrival rate



- ❖ La/R ~ 0: avg. queueing delay small
- ❖ La/R → I: avg. queueing delay large
- La/R > I: more "work" arriving than can be serviced, average delay infinite!

 $Ia/R \rightarrow 1$

 $La/R \sim 0$

^{*} Check out the Java applet for an interactive animation on queuing and loss

NOTE: The slides covered during the lecture are part of the file.