## Bitwise AND

### The & operator

- takes two values (1,2,4,8 bytes), treats as sequence of bits
- performs logical AND on each corresponding pair of bits
- result contains same number of bits as inputs

### Example:

00100111	AND   O 1
& 11100011	
	0   0 0
00100011	1   0 1

Used for e.g. checking whether a bit is set

## **Exercise: Checking for odd numbers**

One obvious way to check for odd numbers in C

```
int isOdd(int n) {
    return n % 2 == 1;
}
```

Could we use & to achieve the same thing? How?  $\sim$  Aside: an alternative to the above

```
int isOdd(int n) {
    return n & 1;
}
```

## Bitwise OR

#### The | operator

- takes two values (1,2,4,8 bytes), treats as sequence of bits
- performs logical OR on each corresponding pair of bits
- result contains same number of bits as inputs

### Example:

00100111	OR   0 1
11100011	
	0   0 1
11100111	1   1 1

Used for e.g. ensuring that a bit is set

## Bitwise NEG

#### The ~ operator

- takes a single value (1,2,4,8 bytes), treats as sequence of bits
- performs logical negation of each bit
- result contains same number of bits as input

### Example:

Used for e.g. creating useful bit patterns

# Bitwise Operations in C

- everything is ultimately a string of bits
- e.g. unsigned char = 8-bit value
- e.g. literal bit-string 0b01110001
- e.g. literal hexadecimal 0x71
- & = bitwise AND
- | = bitwise OR
- ~ = bitwise NEG

## Bitwise XOR

## The ^ operator

- takes two values (1,2,4,8 bytes), treats as sequence of bits
- performs logical XOR on each corresponding pair of bits
- result contains same number of bits as inputs

## Example:

```
00100111 XOR | 0 1

^ 11100011 ----|----

----- 0 | 0 1

11000100 1 | 1 0
```

Used in e.g. generating hashes, graphic operation, cryptography

## Left Shift

#### The << operator

- takes a single value (1,2,4,8 bytes), treats as sequence of bits
- and a small positive integer x
- moves (shifts) each bit x positions to the left
- left-end bit vanishes; right-end bit replaced by zero
- result contains same number of bits as input

#### Example:

# Right Shift

#### The >> operator

- takes a single value (1,2,4,8 bytes), treats as sequence of bits
- and a small positive integer x
- moves (shifts) each bit x positions to the right
- right-end bit vanishes; left-end bit replaced by zero\*\*
- result contains same number of bits as input

### Example:

00100111 >> 2	00100111 >> 8	
00001001	0000000	

Beware: shifts involving negative values are not portable (implementation defined) - use unsigned values to be safe/portable.

## **Exercise: Bitwise Operations**

Given the following variable declarations:

```
// a signed 8-bit value
unsigned char x = 0x55;
unsigned char y = 0xAA;
```

What is the value of each of the following expressions:

- (x & y) (x ^ y)
- $(x \ll 1)$   $(y \ll 1)$
- (x » 1) (y » 1)

## **Exercise:** Bit-manipulation

Assuming 8-bit quantities and writing answers as 8-bit bit-strings: What are the values of the following:

- 25, 65, ~0, ~~1, 0xFF, ~0xFF
- (01010101 & 10101010), (01010101 | 10101010)
- (x & ~x), (x | ~x)

How can we achieve each of the following:

- ensure that the 3rd bit from the RHS is set to 1
- ensure that the 3rd bit from the RHS is set to 0