### Hearts of Iron 4 Wiki

This is a community maintained wiki. If you spot a mistake then you are welcome to fix it.

Effects (also known as Commands) are used in order to affect the game dynamically from within a specific scope. They are a one-time change to the current condition of the game, without the ability to have a lasting effect. Instead, modifiers are used to have a continuous, everlasting effect on the game's condition that can be represented with a number. Effect blocks cannot be used to apply modifiers directly, however they can add something that can apply modifiers, most commonly with add\_ideas.

Effects are used throughout the game in numerous scopes, most commonly National focuses, Events and Decisions.

Note that certain effects may take a value from a variable, i.e. add\_manpower = var:my\_var This is noted by <variable> in an effect's parameters. See <u>Variables</u> for information on the variable effects

The list of effects may be outdated. A complete, but unsorted, list of effects can be found in /Hearts of Iron IV/documentation/effects\_documentation.html or /Hearts of Iron IV/documentation /effects\_documentation.md.

### **Scopes**[<u>编辑</u> | <u>编辑源代码</u>]

**Hearts of Iron 4 Wiki** 

Main article: Scopes

These don't serve as effects, but rather as scopes that change for whom the effects are being executed.

### Effect scopes[编辑 | 编辑源代码]

## Effect scopes:

Name	Usage	Target type	Example	Description	Version Added
every_possible_country	Always usable	Country	<pre>every_possible_country = { }</pre>	Executes children effects on every country that meets the limit, including those that do not exist.	1.11
every_country	Always usable	Country	every_country = { }	Executes contained effects on every country that meets the limit.	1.0
random_country	Always usable	Country	random_country = { }	Executes contained effects on a random country that meets the limit.	1.0
every_other_country	Within country scope only	Country	<pre>every_other_country = { }</pre>	Executes contained effects on every country that meets the limit and is not the same country as the one this is contained in.	1.0
random_other_country	Within country scope only	Country	random_other_country = { }	Executes contained effects on a random country that meets the limit and is not the same country as the one this is contained in.	1.0
every_country_with_original_tag	Always usable	Country	every_country_with_original_tag = {     original_tag_to_check = TAG     #required     #effects to run }	Executes contained effects on every country that meets the limit and has the specified original tag.	1.9
$random\_country\_with\_original\_tag$	Always usable	Country	random_country_with_original_tag = {     original_tag_to_check = TAG     #required        #effects to run }	Executes contained effects on a random country that meets the limit and has the specified original tag.	
every_neighbor_country	Within country scope only	Country	<pre>every_neighbor_country = { }</pre>	Executes contained effects on every country that meets the limit and borders the country this is contained in.	1.0
random_neighbor_country	Within country scope only	Country	random_neighbor_country = { }	Executes contained effects on a random country that meets the limit and borders the country this is contained in.	1.0
every_occupied_country	Within country scope only	Country	<pre>every_occupied_country = { }</pre>	Executes contained effects on every country that meets the limit and has any core states controlled by the country this is contained in.	1.9
random_occupied_country	Within country scope only	Country	<pre>random_occupied_country = { }</pre>	Executes contained effects on a random country that meets the limit and has any core states controlled by the country this is contained in.	1.9
every_enemy_country	Within country scope only	Country	<pre>every_enemy_country = { }</pre>	Executes contained effects on every country that meets the limit and is at war with the country this is contained in.	1.0
random_enemy_country	Within country scope only	Country	random_enemy_country = { }	Executes contained effects on a random country that meets the limit and is at war with the country this is contained in.	1.0
every_subject_country	Within country scope only	Country	<pre>every_subject_country = { }</pre>	Executes contained effects on every country that meets the limit and is a subject of the country this is contained in.	1.11
random_subject_country	Within country scope only	Country	random_subject_country = { }	Executes contained effects on a random country that meets the limit and is a subject of the country this is contained in.	1.11
every_state	Always usable	State/s	every_state = { }	Executes contained effects on every state that meets the limit.	1.0
random_state	Always usable	State	random_state = {     prioritize = { 123 321 } #optional     #effects to run }	Executes contained effects on a random state that meets the limit.	1.0
every_neighbor_state	Within state scope only	State	<pre>every_neighbor_state = { }</pre>	Executes contained effects on every state that meets the limit and neighbours the state this is contained in.	1.0
random_neighbor_state	Within state scope only	State	random_neighbor_state = { }	Executes contained effects on a random state that meets the limit and neighbours the state this is contained in. Does not support prioritizing.	1.0
every_owned_state	Within country scope only	State	every_owned_state = { }	Executes contained effects on every state that meets the limit and is owned by the country this is contained in.	1.0
random_owned_state	Within country scope only	State	random_owned_state = {     prioritize = { 123 321 } #optional     #effects to run }	Executes contained effects on a random state that meets the limit and is owned by the country this is contained in.	1.0
every_core_state	Within country scope only	State	every_core_state = { }	Executes contained effects on every state that meets the limit and is a core of the country this is contained in.	1.11
random_core_state	Within country scope only	State	random_core_state = {     prioritize = { 123 321 } #optional     #effects to run }	Executes contained effects on a random state that meets the limit and is a core of the country this is contained in.	1.11

Name	Usage	Target type	Example	Description	Version Added
every_controlled_state	Within country scope only	State	every_controlled_state = { }	Executes contained effects on every state that meets the limit and is controlled by the country this is contained in.	1.9
random_controlled_state	Within country scope only	State	random_controlled_state = {     prioritize = { 123 321 } #optional     #effects to run }	Executes contained effects on a random state that meets the limit and is controlled by the country this is contained in.	1.9
random_owned_controlled_state	Within country scope only	State	random_owned_controlled_state = {     prioritize = { 123 321 } #optional     #effects to run }	Executes contained effects on a random state that meets the limit and is owned and controlled by the country this is contained in.	1.3
every_unit_leader	Within country scope only	Unit Leader	every_unit_leader = { }	Executes contained effects on every unit leader (corps commanders, field marshals, admirals) that meets the limit and is recruited by the country this is contained in.	1.5
random_unit_leader	Within country scope only	Unit Leader	random_unit_leader = { }	Executes contained effects on a random unit leader (corps commanders, field marshals, admirals) that meets the limit and is recruited by the country this is contained in.	1.5
every_army_leader	Within country scope only	Unit Leader	every_unit_leader = { }	Executes contained effects on every army leader that meets the limit and is recruited by the country this is contained in.	1.5
random_army_leader	Within country scope only	Unit Leader	random_army_leader = { }	Executes contained effects on a random army leader that meets the limit and is recruited by the country this is contained in.	1.5
global_every_army_leader	Always usable	Unit Leader	<pre>global_every_army_leader = { }</pre>	Executes contained effects on every army leader that meets the limit. Preferable to use every_army_leader unless necessary to use global_every_army_leader.	1.5
every_navy_leader	Within country scope only	Unit Leader	every_navy_leader = { }	Executes contained effects on every navy leader that meets the limit and is recruited by the country this is contained in.	1.5
random_navy_leader	Within country scope only	Unit Leader	random_navy_leader = { }	Executes contained effects on a random navy leader that meets the limit and is recruited by the country this is contained in.	1.5
every_operative	Within country scope or operations only	Operative	every_operative = { }	Executes contained effects on every operative that meets the limit and is recruited by the country this is contained in.	1.9
random_operative	Within country scope or operations only	Operative	random_operative = { }	Executes contained effects on a random operative that meets the limit and is recruited by the country this is contained in.	1.9
every_character	Within country scope only	Character	every_character = { }	Executes contained effects on every character that meets the limit and is recruited by the country this is contained in.	1.11
random_character	Within country scope only	Character	random_character = { }	Executes contained effects on a random character that meets the limit and is recruited by the country this is contained in.	1.11
every_country_division	Within country scope only	Division	every_country_division = { }	Executes contained effects on every division that meets the limit and is owned by the current country.	1.12
random_country_division	Within country scope only	Division	random_country_division = { }	Executes contained effects on a random division that meets the limit and is owned by the current country.	1.12
every_state_division	Within state scope only	Division	<pre>every_state_division = { }</pre>	Executes contained effects on every division that meets the limit and is located within the current state.	1.12
random_state_division	Within state scope only	Division	random_state_division = { }	Executes contained effects on a random division that meets the limit and is located within the current state.	1.12

NOTE: Some of these scopes may have no countries/states that match the criteria

## Effects with scopes[<u>编辑|编辑源代码</u>]

Effects that change the scope include the following:

start civil war, which changes it to the rebelling dynamic country.

 $\underline{\text{create}}\underline{\text{dynamic}}\underline{\text{country}}, \text{which changes it to the newly-created dynamic country}.$ 

### Dual scopes[<u>编辑</u> | <u>编辑源代码</u>]

The following scopes can be used either as effect or trigger scopes; some can also be used as the right side of some effects and triggers as a target. If usage as a target is possible, it's marked within the table.

Several dual scopes may have a scope that varies depending on where it's used, such as variables, which can be set to anything.

#### Dual scopes: 折叠

Name	Usage	Target type	Example	Description	Usable as target	Version Added
TAG	Always usable	Country scope	<pre>SOV = { country_event = my_event.1 }</pre>	The country defined by the tag or tag alias. Tag aliases are defined in /Hearts of Iron IV/common/country_tag_aliases, as a way to refer to a specific country (such as a side in a civil war) in addition to its actual tag.	✓	1.0
<state_id></state_id>	Always usable	State scope	<pre>123 = { transfer_state_to = SCO }</pre>	The state defined by this id.	✓	1.0
<character></character>	Always usable	Character scope	<pre>ENG_theodore_makhno = { set_nationality = UKR }</pre>	On game versions prior to 1.12.8, the character must be already recruited by the country this is scoped from. $$	✓	1.11
ROOT	Always usable	Depends on usage	ENG = {     FRA = {         GER = {             declare_war_on = {                  target = ROOT                  type =         annex_everything         }     } }#GER declares war on ENG (if there is no scope before ENG)	Targets the root node of the block, an inherent property of each block. Most commonly, this is the default scope: for example, ROOT within a national focus will always refer to the country doing the focus and ROOT within a event will always refer to the country getting the event. However, some blocks do distinguish between the default scope and ROOT, such as certain scripted GUI contexts or certain on actions. If a block doesn't have ROOT defined (such as on_startup in on actions), then it is impossible to use it.	✓	1.0
THIS	Always usable	Depends on usage	set_temp_variable = { target_country = THIS.id }	Targets the current scope where it's used. For example, when used in <u>every state</u> , it will refer to the state that's currently being evaluated. Primarily useful for <u>variables</u> or for <u>built-in localisation commands</u> . There is little to no usage outside of these two cases.	<b>√</b>	1.0

第2页 共37页 2023/5/9 5:58

Name	Usage	Target type	Example	Description	Usable as target	Version Added
PREV	Always usable	Depends on usage	FRA = {     random_country = {         GER = {             declare_war_on = {                 target = PREV             type =         annex_everything         }     } } #Germany declares war on random_country	Targets the scope that the current scope is contained in. Can have additional applications where the assumed default scope differs from the ROOT, such as in state events or some on_actions. Can be chained indefinitely as PREV.PREV. Commonly results in broken-looking tooltips: what's shown to the player doesn't always correlate with reality.	✓	1.0
FROM	Always usable	Depends on usage	declare_war_on = {     target = FROM     type = annex_everything     } FROM = {     load_oob = defend_ourselves }	Can be chained indefinitely as FROM.FROM. Used to target various hardcoded scopes inherent to the block, often a secondary scope in addition to ROOT. For example:  In events, this refers to the country that sent the event (i.e. if the event was fired using an effect, then it's the ROOT scope where it was fired).  In targeted decisions or diplomacy scripted triggers, this refers to the scope that is targeted.	1	1.0
overlord	Within country scope only	Country scope	overlord = { }	The overlord of the country if it is a subject. <u>Subject to the 'invalid event target' error.</u>	X	1.3
faction_leader	Within country scope only	Country scope	<pre>faction_leader = { add_to_faction = FROM }</pre>	Faction leader of the faction the country is a part of. <u>Subject to the 'invalid event target' error.</u>	X	1.10.1
owner	Within state or combatant scope only	Country scope	<pre>owner = { add_ideas = owns_this_state }</pre>	In state scope, the country that owns the state. In combatant scope, the country that owns the divisions. In character scope, the country that has recruited the character. Subject to the 'invalid event target' error when used for a state.	X	1.0
controller	Within state scope only	Country	controller = {     ROOT = {         create_wargoal = {             target = PREV         type = take_state_focus             generator = { 123 }         }     } }	The controller of the current state. Subject to the 'invalid event target' error.	X	1.0
capital_scope	Within country scope only	State scope	capital_scope = { }	The state where the capital of the current country is located in. Subject to the 'invalid event target' error in rare cases.	X	1.0
event_target: <event_target_key></event_target_key>	Always usable	Depends on usage	<pre>event_target:my_event_target = { }</pre>	Saved event target or global event target, with no space after the colon. Subject to the 'invalid event target' error.	✓	1.0
var: <variable></variable>	Always usable	Depends on usage	<pre>var:my_variable = { } add_to_faction = my_variable Or add_to_faction = var:my_variable</pre>	Variable set to a scope. When used as a target rather than a scope, the var: can be omitted in most cases.	<b>√</b>	1.5

### Invalid event target[<u>编辑</u> | <u>编辑源代码</u>]

See also: <u>Event targets</u>

In regards to some dual scopes, a possible logged error to get while using them is "Invalid event target", as in common/national\_focus/generic.txt:690: controller: invalid event target: controller, while the scope being used is not necessarily an event target.

This refers to the scope not having any defined target in the context that it is used, i.e. it is impossible to select any single target when it is used. In case of controller = { ... } as in the example, this means that the scope is checked or executed in a state that isn't controlled by any country. Such states are rather unstable and can cause crashes easily (such as if evaluated for an air mission by AI or if doing almost any effect on them), so this error occurring should never happen.

In practice, this gets skipped over entirely when evaluating the effects or triggers: none of the effects would be executed; as a trigger it'll not come up as either true or false. However, since this can be checked every tick, leaving it as is can result in cluttering the error log. To avoid this, it's possible to use the if statement in effects or triggers in such a manner that the dual scope would only be generated when needed, such as by checking that the country is indeed a subject before checking the overlord.

### Any scope[编辑 | 编辑源代码]

Can be used in **country**, **state** or **character** scopes.

### General[編輯 | 編辑源代码]

#### General any-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_dynamic_modifier	modifier = <modifier_string> The name of the Modifier. scope = <scope> If you specify it, your dynamic modifier will be scoped to this scope. Optional. days = x The modifiers will be removed after x days have passed. Optional.</scope></modifier_string>	add_dynamic_modifier = { modifier = example_dynamic_modifier scope = GER days = 14 }	Adds a dynamic modifier to the specified scope (the default scope is ROOT). It will be updated daily, unless forced to update early by force_update_dynamic_modifier effect.	Examples can be found in /Hearts of Iron IV/common /dynamic_modifiers/*.txt. Any modifiers that use variables within of the dynamic modifier will not show up in the tooltip of this effect, while those that are set to a static value will.	1.6
remove_dynamic_modifier	modifier = <modifier_string> The name of the Modifier.</modifier_string>	remove_dynamic_modifier = { modifier = sabotaged_ressources }	Removes a dynamic modifier from the current scope	Examples can be found in /Hearts of Iron IV/common /dynamic_modifiers/*.txt	1.6
force_update_dynamic_modifier	 dbool> Boolean.	force_update_dynamic_modifier = yes	Forces an update to the effects given by variables within dynamic modifiers.	An update is done daily by default; this can be used if the applied values need to be changed urgently, such as if modifiers are checked or used later in the effect block.	1.6
set_global_flag	<flag> An unique string to identify the global flag with.  OR flag = <flag></flag></flag>	set_global_flag = my_flag set_global_flag = { flag = my_flag days = 123	Defines a global flag.	No tooltip is shown. The flag in this effect is used in the meaning of boolean flag', used to store information.	1.0

第3页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	The flag to set.  days = <int> Sets the flag to last for the specified amount of days.  Optional.  value = <int> The new value of the flag on the scale from -2 147 483 648 to 2 147 483 647.</int></int>	value = 1 }			
play_song	<pre><song .asset="" from="" title=""> A music file located in the music folder and .asset</song></pre>	play_song = "general_peace_1"	Plays an audio track	The song must be defined in a music station in order to work. More information can be found in the Music modding page. If you wish to simply play a sound, the sound_effect effect should be used instead.	1.9.3
clr_global_flag	<flag> The unique string of a global flag to clear.</flag>	clr_global_flag = my_flag	Clears a defined global flag.	No tooltip is shown	1.0
modify_global_flag	flag = <flag> The global flag to modify. value = <value> The value to set it to: 0 or 1</value></flag>	modify_global_flag = {   flag = my_flag   value = 1 }	Modifies a global flag.	Use <u>variables</u> instead.	1.0
custom_effect_tooltip	<pre> <string> A localized string to display in the tooltip.</string></pre>	custom_effect_tooltip = my_tooltip_tt	Displays a localized key in the effect tooltip.		1.0
log	<pre><string> An string to in the game.log</string></pre>	log = "myVariable: [?myVariable]"	Displays a string in the user directory's /Hearts of Iron IV/logs/game.log file when executed, as well as showing up in the console if it is open when the logging effect was executed.	Accepts all localisation commands (e.g. [Root.GetName], [GetDateText], etc)	1.5
save_event_target_as	(string) An unique string to identify the event target with.	<pre>capital_scope = {     save_event_target_as =     my_state }</pre>	Saves the current scope as a key. Is cleared once execution ends (i.e. end of event).	Use event_target: <key> to access the scope. Do not use in Scripted GUIs.</key>	1.0
save_global_event_target_as	(string) An unique string to identify the global event target with.	random_other_country = {     save_global_event_target_as =     my_country }	Saves the current scope as a key. Persists after execution until cleared via effect.	Use event_target: <key> to access the scope. Do not use in Scripted GUIs.</key>	1.0
clear_global_event_target	<string> The unique string of the global event target to clear.</string>	clear_global_event_target = my_country	Clears a specific global event target.		1.0
clear_global_event_targets	yes Boolean.	clear_global_event_targets = yes	Clears all global event targets.		1.0
sound_effect	<pre><string> A sound reference from an .asset file.</string></pre>	sound_effect = "boom"	Plays the specified sound once.	The sound effect must be properly defined in /Hearts of Iron IV/sound/ More info can be found in the Sound modding article.	1.0
randomize_weather	<int> A seed integer.</int>	randomize_weather = 12345	Randomizes the weather with the specified seed.		1.0
set_province_name	id = <id> The id of the province to be changed.  name = <string> The name to change the province to.</string></id>	set_province_name = {     id = 325     name = LOC_KEY     } set_province_name = { id = 325     name = "New Name" }	Changes the specified province/victory point's name to the specified name.	Localisation keys are to be defined in /Hearts of Iron IV/localisation /*_l_ <language>.yml</language>	1.3
reset_province_name	<id> The id of the province to reset.</id>	reset_province_name = 325	Resets the specified province's name.		1.3
damage_units	province = <id> Province where to damage units.  state = <id> State where to damage units.  region = <id> State where to damage units.  region = <id> Strategic region where to damage units.  limit = { <trispers} are="" country="" damage="&lt;fraction" delete="" for="" if="" met="" only="" owns="" that="" the="" triggers="" units="" units.="" will="" within="" }=""> The percentage of damage  done to units.  org_damage = <fraction> The percentage of damage  done to units to organisation  in particular.  str_damage = <fraction> The percentage of damage  done to units to organisation  in particular.  str_damage = <fraction> The percentage of damage  done to units to strength in  particular.  ratio = <yes> Will damage a ratio damage  to total organisation/strength  of unit if set.  template = <string> If specified, requires the  template name to match.  army = <bool> Will damage the army units.  navy = <bool> Will damage the navy units.</bool></bool></string></yes></fraction></fraction></fraction></trispers}></id></id></id></id>	damage_units = {     province = 42     state = 5     region = 5     limit = { has_country_flag = TAG_test }     damage = 0.5     org_damage = 0.5     str_damage = 0.5     ratio = yes     template = "template_name"     army = no     navy = yes }	Damages units in the specified area.		1.11
create_entity	entity = <gfx_entry> The entity to spawn, defined within /Hearts of Iron IV/gfx /entities/*.asset files. id = int</gfx_entry>	create_entity = {   entity = entity_name   id = 123   var = var_name   x = 42	Creates an entity.	Uses the the same coordinate system that the map uses. A positive change in rotation results in counter-clockwise rotation, a full 360 degrees rotation is	1.11

第4页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	A number ID which can be referred to by other effects. Optional.  var = <variable> If provided, the id of the entity will be stored using this variable. Optional.  x = <int> The X position of the entity. y = <int> The X position of the entity. y = <int> The Y position of the entity. The Z position of the entity. The Z position of the entity. The province = <int> The province the middle of which to use as the entity's position. state = <int> The state the middle of which to use as the entity's position. rotation = <decimal> The rotation of the entity in radians. scale = <decimal> The size of the entity. min_zoom = <decimal> Minimum zoom level needed to be able to see the entity. visible = <scripted_trigger> The scripted trigger that must be met for a country for it to see the entity.</scripted_trigger></decimal></decimal></decimal></int></int></int></int></int></variable>	y = 21 z = 3 province = 123 state = 42 rotation = 1.2 scale = 10.0 min_zoom = 100.0 visible = scripted_trigger_name }		approximately 6.28 radians. For comparison, default minimum zoom level (closest to the map) is 50 units, while default maximum zoom level is 3000 units.	Added
destroy_entity	The ID of the entity to destroy.	destroy_entity = 123	Deletes an entity	IDs are set by the <u>create_entity</u> <u>effect</u> .	1.11
set_entity_movement	id = <id> The ID of the entity to modify.  ratio = <int> Distance between starting position and target position where the entity is to be placed.  rotation = <int> The rotation to apply after the positioning.  start and target arguments:  x = <int> The X position of the point.  y = <int> The Y position of the point.  z = <int> The Z position of the point.  The Z position of the point.  province = <int> The province the middle of which to use as the point.  state = <int> The state the middle of which to use as the point.</int></int></int></int></int></int></int></id>	set_entity_movement = {     id = 123     start = {         x = 42         y = 21         z = 3     }     target = {         province = 124     }     ratio = 0.5     rotation = 1.2 }	Sets the position and rotation of an entity using two coordinates.	IDs are set by the create_entity_effect. Uses the the same coordinate system that the map uses. A positive change in rotation results in counter-clockwise rotation, a full 360 degrees rotation is approximately 6.28 radians.	1.11
set_entity_position	<pre>id = <id>&gt; x = <int>&gt; y = <int>&gt; cint&gt;&gt; z = <int>&gt; province = <int>&gt; state = <int>&gt;</int></int></int></int></int></id></pre>	set_entity_position = {     id = 123         x = 42         y = 21         z = 3         province = 123         state = 42     }	Sets the position of an existing entity	IDs are set by the <u>create_entity</u> effect. Uses the the <u>same coordinate</u> system that the <u>map uses</u> .	1.11
set_entity_rotation	id = <id> The ID of the entity to modify. rotation = <decimal> The new angle in radians.</decimal></id>	set_entity_rotation = {     id = 123     rotation = 0.23 }	Sets the currently-facing angle of an existing entity.	IDs are set by the <u>create entity</u> <u>effect</u> . A positive change results in counter-clockwise rotation, a full 360 degrees rotation is approximately 6.28 radians.	1.11
set_entity_scale	id = <id> The ID of the entity to modify. scale = <decimal> The scale to change the entity to.</decimal></id>	set_entity_scale = {     id = 123     scale = 5.0 }	Sets the size of an existing entity.	IDs are set by the <u>create_entity</u> effect.	1,11
set_entity_animation	id = <int> The ID of the entity to modify. animation = <animation_type> The animation entry to apply.</animation_type></int>	set_entity_animation = {     id = 123     animation = "shoot_lasers" }	Sets the animation of a specified entity.	IDs are set by the <u>create_entity</u> <u>effect</u> . Animations are defined within the /Hearts of Iron IV/gfx /models/**/*.asset files.	1.11
build_railway	level = <int> Defaults to 1 build_only_on_allied = <bool> No by default, if yes and in a country scope, it will only build on allied territories for the country scoped. fallback = <bool> Defaults to no, if yes each option will try to fallback to the next available one. path = { <list of="" provinces=""> } start_province = <int> target_province = <int> target_state = <int> If using start state/target</int></int></int></list></bool></bool></int>	build_railway = {     level = 1     build_only_on_allied = yes     controller_priority = {         base = 1         modifier = {         tag = MAN         add = 2     }     fallback = yes     path = { 42 10 20 30 40 84 }     start_province = 42     target_province = 84 } build_railway = {     level = 1	Adds a railway level between two provinces or along a predefined path.		1.11

第5页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	state, the game will pick the provinces with the best supply available. If using state province/target province, the game will link those two provinces.	build_only_on_allied = yes controller_priority = { base = 1 modifier = { tag = MAN add = 2 } fallback = yes path = {50 10 20 30 40 100 } start_state = 50 target_state = 100			

## Border wars[<u>編辑 | 編辑源代码</u>]

### Border war-related any-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
start_border_war	change_state_after_war = <bool> Whether the state changes hands after the war.  Attacker or Defender scope state = <id> / (variable) The state the side is fighting on. num_provinces = <id> The tighting on. num_provinces = <id> The number of provinces used in the state. on_win = <id> The event to fire for the side on a win. on_lose = <id> The event to fire for the side on a loss. on_cancel = <id> The event to fire for the side on a draw. modifier = <decimal> The modifier on combat. Defaults to o. dig_in_factor = <decimal> The modifier applied to dig-in bonuses. Defaults to 1. terrain_factor = <decimal> The modifier applied to terrain bonuses. Defaults to 1.</decimal></decimal></decimal></id></id></id></id></id></id></bool>	start_border_war = {     change_state_after_war = no     attacker = {         state = 527         num_provinces = 4         on_win =         japan_border_conflict.2         on_lose =         japan_border_conflict.3         on_cancel =         japan_border_conflict.4         modifier = 0.1         dig_in_factor = 0         terrain_factor = 0     }     defender = {         state = 408         num_provinces = 4         on_lose =         japan_border_conflict.3         on_lose =         japan_border_conflict.2         on_cancel =         japan_border_conflict.4     } }	Starts a border war for the specified attacker and defender. The participating countries are the owners of the specified states.		1.5
set_border_war_data	attacker = <id>/ <variable> The attacker state. defender = <id>/ <variable> The defender state. attacker_modifier = <id>/ <variable> The modifier applied to attacker strength. defender_modifier = <id>/ <variable> The modifier applied to attacker strength. combat_width = <id>/ <variable> The combat_width = <id>/ <variable> The combat width used in the border war battle.</variable></id></variable></id></variable></id></variable></id></variable></id></variable></id>	set_border_war_data = {   attacker = 527   defender = 408   defender_modifier = 0.15   combat_width = 100 }	Sets the bonuses or penalties for the attacker and defender in an ongoing border war. Used after <b>start_border_war</b> .		1.5
cancel_border_war	attacker = <id>/ <variable> The attacker state. defender = <id>/ <variable> The defender state. dont_fire_events = <bool> Stops the events from start_border_war from firing.</bool></variable></id></variable></id>	cancel_border_war = {   dont_fire_events = yes   defender = 408   attacker = 527 }	Cancels an on-going border war without a winner.		1.5
finalize_border_war	attacker = <id>/ <variable> The attacker state. defender = <id>/ <variable> The defender state. attacker_win = <bool> Makes the attacker the winner. defender_win = <bool> Makes the defender the winner.</bool></bool></variable></id></variable></id>	finalize_border_war = {     attacker_win = yes     attacker = 527     defender = 408 }	Ends an on-going border war.		1.5

## Country scope[<u>编辑</u> | <u>编辑源代码</u>]

The effects here must be used within a  ${\bf country}$  scope.

### General[<u>编辑</u> | <u>编辑源代码</u>]

# General country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
set_country_flag	<pre><flag> An unique string to identify the country flag with. OR flag = ⟨flag⟩ The flag to set. days = ⟨int⟩ Sets the flag to last for the specified amount of days. Optional. value = ⟨int⟩ The new value of the flag on the scale from -2 147 483 648 to 2 147 483 647.</flag></pre>	set_country_flag = my_flag set_country_flag = {   flag = my_flag   days = 123   value = 1  }	Defines a country flag.	No tooltip is shown. The flag in this effect is used in the meaning of 'boolean flag', used to store information. In order to change the flag that represents the country, see cosmetic tags.	1.0

第6页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
clr_country_flag	<flag> The unique string of a country flag to clear.</flag>	clr_country_flag = my_flag	Clears a defined country flag.		1.0
modify_country_flag	flag = <flag> The country flag to modify. value = <value> The value to set it to: 0 or 1</value></flag>	modify_country_flag = {     flag = my_flag     value = 1 }	Modifies a country flag.	Use <u>variables</u> instead.	1.3
country_event	id = <event> The event to fire. days = <int> / <variable> Fires the event in the specified number of days. Optional. hours = <int> / <variable> Fires the event in the specified number of hours. Optional. random_hours = <int> / <variable> Adds a random number (between o and random_hours, inclusive) of hours to the scheduled fire time. Optional. random_days = <int> / <variable> Adds a random number (between o and random_days = <int> / <variable> Adds a random number (between o and random_days, inclusive) of days to the scheduled fire time. Optional.</variable></int></variable></int></variable></int></variable></int></variable></int></event>	country_event = {     id = my_event.1     days = 10     random_hours = 12     random_days = 10 } country_event = my_event.1	Fires the specified event for the current country.	Where triggers do not need to be repeatedly checked random can be a performance light alternative to mean_time_to_happen for scheduling events. Shortened variant exists if the event's ID is used instead of arguments.	1.0
news_event	id = <event> The event to fire. days = <int> / <pre></pre></int></event>	news_event = {     id = my_event.1     days = 10     random_hours = 12     random_days = 10 } news_event = my_event.1	Fires the specified news event for the current country.	The news event uses a different interface to the country event. Where triggers do not need to be repeatedly checked random can be a performance light alternative to mean_time_to_happen for scheduling events. Shortened variant exists if the event's ID is used instead of arguments.	1.0
set_cosmetic_tag	<pre><string> The cosmetic tag to switch to.</string></pre>	set_cosmetic_tag = SAF_SOV_communism	Makes the current scope use the specified cosmetic tag, changing name and flag.		1.3
drop_cosmetic_tag	 dool> Boolean.	drop_cosmetic_tag = yes	Makes the current scope drop the current cosmetic tag they are using.		1.3
set_rule	crule> Boolean. desc = <localisation key=""> The localisation used as the rule's description.</localisation>	set_rule = {     desc =     TAG_my_rule_description     can_create_factions = yes }	Toggles the special game rules for the current scope.	Possible rules: can_boost_other_ideologies can_create_factions can_declare_war_on_same_ideology can_declare_war_without_wargoal_when_in_war can_decline_call_to_war can_force_government can_generate_female_aces can_guarantee_other_ideologies can_join_factions can_join_factions_not_allowed_diplomacy can_join_opposite_factions can_lower_tension can_lower_tension can_not_declare_war can_occupy_non_war can_only_justify_war_on_threat_country can_puppet can_send_volunteers can_use_kamikaze_pilots units_deployed_to_overlord (subjects only)	1.0

第7页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
set_party_rule	ideology = <ideology group=""> Ideology group of the party. desc = <localisation key=""> A description used for the rule. Optional, defaults to being the same as default. <rule> = <bool new="" rule's="" td="" value.<=""><td>set_party_rule = {     ideology = democratic     desc =     TAG_my_rule_description     can_create_factions = yes }</td><td>Toggles the special game rules for the current scope's political party.</td><td></td><td>1.12</td></bool></rule></localisation></ideology>	set_party_rule = {     ideology = democratic     desc =     TAG_my_rule_description     can_create_factions = yes }	Toggles the special game rules for the current scope's political party.		1.12
set_relation_rule	target = <scope> Target of the rule. desc = <localisation key=""> A description used for the rule. Optional, defaults to being the same as default. <rule> =  (rule&gt; = &amp;bool&gt; Rule's new value.</rule></localisation></scope>	set_relation_rule = {     target = SOV     desc =     TAG_my_rule_description     can_not_declare_war =     yes     }	Toggles the special game rules for the current scope in diplomacy towards the specified country only.		1.12
scoped_sound_effect	<pre></pre>	scoped_sound_effect = "boom"	Plays the specified sound once only for the current country.	The sound effect must be properly defined in /Hearts of Iron IV/sound/ More info can be found in the <u>Sound modding</u> article.	1.6
scoped_play_song	<pre><song .asset="" from="" title=""> A music file located in the music folder and .asset</song></pre>	scoped_play_song = "general_peace_1"	Plays an audio track for the specified country only.	The song must be defined in a music station in order to work. More information can be found in the <u>Music modding</u> page. If you wish to simply play a sound, the scoped_sound_effect effect should be used instead.	1.9.3
goto_province	The id of the province go to.	goto_province = 325	Moves the camera position over the specified province.		1.0
goto_state	<pre><scope> / <variable> The id of the state go to.</variable></scope></pre>	goto_state = 1 goto_state = var:some_state	Moves the camera position over the specified state.		1.0
change_tag_from	<pre><scope> / <variable> The country to change from.</variable></scope></pre>	change_tag_from = ROOT change_tag_from = var:from.country	Switches the player to the current scope from the target scope.	The country the player becomes needs to be the scope in which the command is used.	1.0
reserve_dynamic_country	<pre><bool></bool></pre>	reserve_dynamic_country = yes	Reserves the dynamic country, making sure that it does not get recycled for civil war even if it does not exist.	Usually used in combination with <u>create_dynamic_country</u> .	1.9
force_update_map_mode	limit = { } Triggers required for the map mode to refresh. Optional. mapmode = <id>The ID of the custom map mode.</id>	force_update_map_mode = {     limit = {         is_ai = no     }     mapmode = my_map_mode }	Forcefully refreshes the specified mapmode for the player, rather than waiting for a daily update.	Map modes are defined in /Hearts of Iron IV/common/map_modes /*.txt	1.11
add_ai_strategy	type = <type> The type of strategy. id = <scope> What country the strategy is against. value = <int> The weighting added by the strategy.</int></scope></type>	add_ai_strategy = {   type = alliance   id = GER   value = 200 }	Sets an AI strategy for the current scope.	See AI Modding for more details.	1.0
create_dynamic_country	original_tag = <tag> The original tag to be used by the country. copy_tag = <tag> If specified, copies stuff from this tag rather than the original tag. <effects> Effects that will be executed on the new dynamic country.</effects></tag></tag>	create_dynamic_country = {     original_tag = POL     copy_tag = SOV     add_political_power =     100     transfer_state = 123 }	Creates a new dynamic country, akin to ones used in civil wars.	The reserve dynamic country effect can be used if the dynamic country does not yet exist in order to ensure that it does not get overwritten by other creations of dynamic countries. If this is not done, the dynamic country will immediately stop existing if no states are transferred in the same scope.  Every state of the original country immediately gets set as a dynamic country's core: if that's unneeded, the cores would need to be removed after creation.	1.9

### **States**[<u>编辑 | <u>编辑源代码</u>]</u>

 $These \ effects \ in \ particular \ are \ country-scoped \ effects \ that \ are \ related \ to \ states \ rather \ than \ effects \ within \ the \ state \ scope.$ 

## State-related country-scoped effects: $\# \mathbb{A}$

Name	Parameters	Examples	Description	Notes	Version Added
add_state_core	<pre><scope> / <variable> The state to add core to.</variable></scope></pre>	add_state_core = 345	Adds a core for the current scope to the specified state.		1.0
remove_state_core	<pre><scope> / <variable> The state to remove core from.</variable></scope></pre>	remove_state_core = 345	Removes the core of the current scope from the specified state.		1.0
set_capital	<scope> / <variable> The state to make capital.</variable></scope>	set_capital = {state = 345} set_capital = { state = 345 remember_old_capital = no }	Makes the specified state the current scope's capital state.	Syntax has been changed in 1.11. It was "set_capital = 345"  Old capital is remembered, if not specified otherwise.	1.0
add_state_claim	<pre><scope> / <variable> The state to add a claim to.</variable></scope></pre>	add_state_claim = 345	Adds a claim for the current scope on the specified state.		1.0

第8页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
remove_state_claim	<pre> <scope> / <variable> The state to remove the claim from.</variable></scope></pre>	remove_state_claim = 345	Removes a claim of the current scope from the specified state.		1.0
set_state_owner	<pre></pre>	set_state_owner = 345	Makes the current scope the owner of the specified state.	This can fail to carry over the control, so it's recommended to instead use <u>transfer_state</u> unless transferring the ownership without transferring over the control.	1.0
set_state_controller	<pre></pre>	set_state_controller = 345	Makes the current scope the controller of the specified state.		1.0
transfer_state	<pre></pre>	transfer_state = 345	Makes the current scope the owner and controller of the specified state.	transfer state to exists as a state-scoped variant.	1.0
set_province_controller	The province to change controller of.	set_province_controller = 2999	Changes the controller of the specified province to the current scope.		1.0

### Mana[<u>编辑</u> | <u>编辑源代码</u>]

Mana in this usage means political power, stability, war support, and other values in the topbar. Fuel is, instead, in the <u>resources section</u>, while convoys can be added/removed with <u>add\_equipment\_to\_stockpile</u>.

## Mana-related country-scoped effects:

Name	Parameters	Examples	Description	Notes	Version
					Added
add_political_power	<int> / <variable> The amount to</variable></int>	add_political_power = 100	Adds the specified amount of political power to the current		1.0
	add.	add_political_power = var:my_var	scope.		
set_political_power	<pre><int> / <variable> The amount to add.</variable></int></pre>	set_political_power = 100	Sets the specified amount of political power for the current scope.		1.0
add_stability	<pre><int> / <variable> The amount to add.</variable></int></pre>	add_stability = 0.1	Adds to the current stability value for the current scope.	Stability values are between 0 and 1.	1.5
set_stability	<pre><int> / <variable> The amount to add.</variable></int></pre>	set_stability = 0.5	Sets the current stability value for the current scope.	Stability values are between 0 and 1.	1.5
add_war_support	<pre><int> / <variable> The amount to add.</variable></int></pre>	add_war_support = 0.1	Adds to the current war support value for the current scope.	War Support values are between 0 and 1.	1.5
set_war_support	<pre><int> / <variable> The amount to set.</variable></int></pre>	set_war_support = 0.5	Sets the current war support value for the current scope.	War Support values are between o and 1.	1.5
$add\_command\_power$	<pre><int> / <variable> The amount to add.</variable></int></pre>	add_command_power = 100	Adds the specified amount of command power to the current scope.		1.5
add_manpower	<int> / <variable> The amount to add.</variable></int>	add_manpower = 100000 add_manpower = var:my_var	Adds the specified amount of manpower to the current scope.		1.0
army_experience	<float> / <variable> The amount to add.</variable></float>	army_experience = 10	Adds the specified amount of army experience to the current scope.		1.0
navy_experience	<float> / <variable> The amount to add.</variable></float>	navy_experience = 10	Adds the specified amount of navy experience to the current scope.		1.0
air_experience	<float> / <variable> The amount to add.</variable></float>	air_experience = 10	Adds the specified amount of air experience to the current scope.		1.0

### Politics[编辑 | 编辑源代码]

# Political country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
hold_election	cscope> The country to hold an election for.	hold_election = ROOT	Executes the events in the <b>on_new_term_election</b> on action for the current scope.		1.0
add_popularity	ideology = <ideology> The party to change. popularity = <int> / <variable> The amount of popularity to change.</variable></int></ideology>	add_popularity = {     ideology = fascism     popularity = -0.5 }	Adjusts the popularity for the specified party in the current scope.	Values used are 0 to 1.	1.0
set_politics	ruling_party = (ideology) The party to set. elections_allowed = (bool) Whether elections are allowed. Optional. last_election = (date) When the last election was. Optional. election_frequency = (int) How often in months an election occurs. Optional. long_name = (string) The long name of the country's new ruling party, appearing when hovering over it. Optional. name = (string) The name of the country's new ruling party. Optional.	set_politics = {     ruling_party = democratic     elections_allowed = no     last_election = "1935.12.17"     election = frequency = 48     long_name = TAG_party_long     name = TAG_party }	Sets the political party setup for the current scope.	Previously included the "parties" parameter, which has been deprecated by the "set_popularities" command. The "parties" parameter no longer works as of version 1.7	1.0 (Updated 1.7)

第9页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
set_popularities	<ideology> = <int>/<variable> The popularity to set.</variable></int></ideology>	set_popularities = {     democratic = 50     neutrality = 15     fascism = 30     communism = 5 }	Sets the political party popularities for the current scope.	The popularities must add up to 100, otherwise the command will have no effect.	1.7
set_political_party	ideology = <ideology> The party to change. popularity = <int> The amount of popularity to set.</int></ideology>	set_political_party = {     ideology = fascism     popularity = 50 }	Sets the popularity for the specified political party in the current scope.		1.0
set_party_name	ideology = <ideology> The party to change. long_name = <string> The new full name for the party. name = <string> The new short name for the party.</string></string></ideology>	set_party_name = {     ideology = neutrality     long_name =     GER_neutrality_party_kaiserreich_long     name =     GER_neutrality_party_kaiserreich }	Changes the name of the specified political party for the current scope.		1.0

## Balance of power[<u>编辑</u> | <u>编辑源代码</u>]

Balance of power is defined in /Hearts of Iron IV/common/bop/\*.txt files.

## Balance of power-related country-scoped effects:

Name	Parameters	Examples	Description	Notes	Version Added
set_power_balance	id = <bop id=""> Balance of power to set/modify. left_side = <bop id="" side=""> The left side of the BOP. right_side = <bop id="" side=""> The right side of the BOP. set_default = <bool> Whether the BOP is considered default. Defaults to false. set_value = <decimal> The new value of the BOP. Optional, defaults to not changing the value.</decimal></bool></bop></bop></bop>	set_power_balance = {     id = my_bop     left_side = my_bop_left_side     right_side = my_bop_right_side }	Sets a new balance of power or edits the existing one.	Necessary for a balance of power to appear.	1.12
remove_power_balance	id = <bop id=""> Balance of power to modify.</bop>	remove_power_balance = {     id = my_bop }	Removes the balance of power in entirety.		1.12
add_power_balance_value	id = <bop id=""> Balance of power to modify. value = <decimal> The value to add. tooltip_side = <bop id="" side=""> The side to show in the tooltip. Optional.</bop></decimal></bop>	add_power_balance_value = {     id = my_bop     value = -0.1     tooltip_side = my_bop_side }	Pushes the balance of power towards one side.		1.12
add_power_balance_modifier	id = <bop id=""> Balance of power to modify. modifier = <static modifier=""> The static modifier to apply.</static></bop>	add_power_balance_modifier = {     id = my_bop     modifier = my_static_modifier }	Applies a balance of power modifier.		1.12
remove_power_balance_modifier	id = <bop id=""> Balance of power to modify. modifier = <static modifier=""> The static modifier to apply.</static></bop>	remove_power_balance_modifier = {     id = my_bop     modifier = my_static_modifier }	Cancels a balance of power modifier.		1.12
$remove\_all\_power\_balance\_modifiers$	id = <80P ID> Balance of power to modify.	remove_all_power_balance_modifiers = { id = my_bop }	Cancels all balance of power modifiers.		1.12
set_power_balance_gfx	id = <bop id=""> Balance of power to modify. side = <bop id="" side=""> The side whose GFX to change. gfx = <sprite> The sprite to change the GFX to.</sprite></bop></bop>	set_power_balance_gfx = {     id = my_bop     side = my_bop_side     gfx = GFX_my_bop_side_new }	Changes the appearance of one of the sides within the balance of power.	Sprites are defined within /Hearts of Iron IV/interface /*.gfx files.	1.12

## Diplomacy[<u>编辑 | 编辑源代码</u>]

### Diplomatic country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
set_major	<bool> Boolean.</bool>	set_major = yes	Makes the current scope a major country.		1.0
create_faction	<pre></pre>	create_faction = MY_FACTION_NAME	Creates a faction with the specified name for the current scope. The current scope and any subjects automatically join the faction.		1.0
add_to_faction	TAG> The TAG of the nation to add to the faction of the current scope.	FACTION_LEADER_TAG = { add_to_faction = TAG_TO_ADD }	Adds the TAG_TO_ADD to the faction of the FACTION_LEADER_TAG.		1.0
leave_faction	<bool> Boolean.</bool>	leave_faction = yes	Removes the current scope from the faction they are part of.		1.5
remove_from_faction	<tag> The target country.</tag>	remove_from_faction = TAG_TO_REMOVE	Removes the specified scope from the faction led by the current scope.		1.0

第10页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
dismantle_faction	<bool> Boolean.</bool>	dismantle_faction = yes	Dismantles the faction of the current scope.		1.0
set_faction_name	Sets a faction name as the loc name.	set_faction_name = SOME_LOC_KEY	Changes faction names.		1.6
set_faction_leader	<bool></bool>	set_faction_leader = yes	Sets the current country as the faction leader.		1.0
set_faction_spymaster	<bool></bool>	set_faction_spymaster = yes	Sets the current country as the faction spymaster.		1.9
release	<scope> The target country.</scope>	release = GER	Releases the specified non-existent country as a free nation within the current country's owned states.	The effect does nothing if the country exists. All states that are cored by the specified country will be given to it. If the current country has a core on a state transferred to the released country, the core will be lost. If looking to make a subject into an independent nation, use set_autonomy. States that are owned but not controlled will be transferred to the released country, but won't be controlled by it.	1.0
release_on_controlled	<scope> The target country.</scope>	release_on_controlled = GER	Releases the specified non-existent country as a free nation within the current country's controlled states.	The effect does nothing if the country exists. All states that are cored by the specified country will be given to it. If the current country has a core on a state transferred to the released country, the core will be lost.	1.9.1
release_puppet	<scope> The target country.</scope>	release_puppet = GER	Releases the specified non-existent country as a puppet of the current scope within the current country's owned states.	The effect does nothing if the country exists. All states that are cored by the specified country will be given to it. If the current country has a core on a state transferred to the released country, the core will be lost. States that are owned but not controlled will be transferred to the released country, but won't be controlled by it.	1.0
release_puppet_on_controlled	<pre> <scope>   The target   country.</scope></pre>	release_puppet_on_controlled = GER	Releases the specified non-existent country as a puppet of the current scope within the current country's controlled states.	The effect does nothing if the country exists. All states that are cored by the specified country will be given to it. If the current country has a core on a state transferred to the released country, the core will be lost.	1.9.1
release_autonomy	tanget = <scope> / <variable> The subject country. autonomy_state = <type> The type of autonomy state to set. freedom_level = <float> The new freedom level value. Optional.</float></type></variable></scope>	release_autonomy = {     target = VIN     autonomy_state = autonomy_puppet     freedom_level = 0.5 }	Releases the specified non-existent country as a subject of the specified autonomy of the current scope within the current country's owned states.	The effect does nothing if the country exists. All states that are cored by the specified country will be given to it. If the current country has a core on a state transferred to the released country, the core will be lost. States that are owned but not controlled will be transferred to the released country, but won't be controlled by it. The autonomy states are found in /Hearts of Iron IV/common/autonomous_states/*.txt.	1.3
give_guarantee	<scope> The target country.</scope>	give_guarantee = GER	The current scope guarantees the target country.	diplomatic relation effect can be used to remove it.	1.0
give_military_access	<scope> The target country.</scope>	give_military_access = GER	The current scope grants military access to the target country.	diplomatic relation effect can be used to remove it.	1.0
recall_attache	<scope> The target country with an attache.</scope>	recall_attache = GER	Recalls the current scope's attaché from the specified country.		1.5
diplomatic_relation	country = <pre><scope></scope></pre> The target country to alter the relationship with ROOT. relation = <type> The relation to change. active = <bool>Whether the relation is started or broken.</bool></type>	diplomatic_relation = {     country = SOV     relation = guarantee     active = no }	Used to define a diplomatic relation between the current scope and target scope country.	Possible relations: non_aggression_pact guarantee puppet military_access docking_rights	1.0
add_opinion_modifier	target = <scope> The target country. modifier = <modifier> The opinion modifier to add.</modifier></scope>	add_opinion_modifier = {     target = GER     modifier = faction_traitor }	The current scope gains the specified opinion modifier towards the target scope. Can also be used to modify trade relations by adding 'trade eyes' in the opinion <modifier> in /Hearts of Iron IV/common /opinion_modifiers/*.txt. If used with a trade opinion_modifier the behaviour is reversed, meaning that the target gains the trade opinion towards the current scope.</modifier>	Opinion modifiers are found in /Hearts of Iron IV/common/opinion_modifiers /*.txt.	1.0
remove_opinion_modifier	target = <scope> The target country. modifier = <modifier> The opinion modifier to remove.</modifier></scope>	remove_opinion_modifier = {     target = GER     modifier = faction_traitor }	The current scope loses the specified opinion modifier <b>towards</b> the <b>target scope</b> .	Opinion modifiers are found in /Hearts of Iron IV/common/opinion_modifiers /*.txt.	1.0

第11页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
reverse_add_opinion_modifier	target = <scope> The target country. modifier = <modifier> The opinion modifier to add.</modifier></scope>	reverse_add_opinion_modifier = {     target = GER     modifier = faction_traitor }	The target scope gains the specified opinion modifier towards the current scope.	Opinion modifiers are found in /Hearts of Iron IV/common/opinion_modifiers /*.txt. Useful for when you don't know what the current scope will be.	1.0
add_relation_modifier	target = <scope> The target country. modifier = <modifier> The relation modifier to add.</modifier></scope>	add_relation_modifier = {     target = SWE     modifier = HUN_dynastic_ties_license }	The current scope gains the specified relation modifier <b>towards the target scope</b> .	Relation modifiers are found in /Hearts of Iron IV/common/modifiers/*.txt files, used to apply a <u>targeted modifier</u> with a non-static target. To change the diplomatic opinion of a country, see <u>add_opinion_modifier</u> .	1.4
remove_relation_modifier	target = <scope> The target country. modifier = <modifier> The relation modifier to remove.</modifier></scope>	remove_relation_modifier = {     target = SWE     modifier = HUN_dynastic_ties_license }	The current scope loses the specified relation modifier for <b>towards the target scope</b> .	Relation modifiers are found in /Hearts of Iron IV/common/modifiers/*.txt, used to apply a targeted modifier with a non-static target. To change the diplomatic opinion of a country, see remove_opinion_modifier.	1.4
add_collaboration	target = (scope) The target country. value = (0-1) How much collaboration to add.	add_collaboration = {   target = TAG   value = 0.3 }	Adds collaboration in TAG with the scoped country.		1.9
set_collaboration	target = <scope> The target country. value = &lt;0-1&gt; How much collaboration will be set.</scope>	set_collaboration = {   target = TAG   value = 0.3 }	Sets the collaboration in TAG with the scoped country.		1.9
recall_volunteers_from	<tag> The target country.</tag>	recall_volunteers_from = SPR	Recalls volunteers sent to the specified country back to the current country.		1.9
set_occupation_law	<pre><law id=""> The new occupation law enacted by the previous scope or default_law.</law></pre>	USA = { GER = { set_occupation_law = foreign_civilian_oversight} } # Changes USA's occupation law for GER. USA = { USA = { set_occupation_law = default_law }} # Changes the USA's default occupation law to the default.	Sets the occupation law of the country.	PREV will be the country for whom the occupation law will be changed. If PREV is not a country, nothing changes. If PREV is the same country, changes the default occupation law. If PREV is different, default_law resets the country-specific law to the global default, otherwise it resets the default law to the occupation law with starting_law = yes in definition.	1.12
set_occupation_law_where_available	<pre><law id=""> The new occupation law enacted by the previous scope or default_law.</law></pre>	USA = { GER = {     set_occupation_law_where_available =     foreign_civilian_oversight } } # Changes     USA's occupation law for GER where     possible.  USA = { USA = {         set_occupation_law_where_available =         default_law } # Changes the USA's         default occupation law to the default         where possible.	Sets the occupation law of the country.	Identical to set occupation law, except if the law is impossible to set, tries again at every smaller sub-set: if default is impossible, tries every single individual occupied country; if the country's law is impossible to change, tries every single state within the country.	1.12
send_embargo	<tag> The target country.</tag>	send_embargo = ITA	Embargos the target country.		1.12
break_embargo	<tag> The target country.</tag>	break_embargo = ITA	Stops embargoing the target country.		1.12

### Autonomy[<u>编辑</u> | <u>编辑源代码</u>]

# Autonomy-related country-scoped effects: 折叠

Version Added Examples Name Parameters Description Notes cscope>
The target country.
OR
target = <scope>
The target country.
end\_wars = cbool>
Whether the target country
will peace out in all of its
non-civil wars it's
participating in. Defaults to
true.
end\_civil\_wars = <bool>
Whether the target country
will peace out in all of its
civil wars it's participating
in. Defaults to true. The autonomous state picked is one which contains default = yes and where allowed = { ... } is fulfilled within the /Hearts of Iron IV/commmon/autonomous\_states/ definition, rather than necessarily being autonomy\_puppet. Results in a crash-to-desktop if the game is unable to find any such autonomous states. Makes the specified country a subject of the current scope. puppet = GER puppet puppet = {
 target = ITA
 end\_wars = no Removes the subject status between the target and the current scope. <scope>
The target country. end\_puppet  $end\_puppet = GER$ Must be used within the overlord's scope. 1.0

Name	Parameters	Examples	Description	Notes	Version Added
add_autonomy_ratio	value = <float> The freedom score to add. localization = <string> The localization key for the modifier.</string></float>	add_autonomy_ratio = {     value = 0.1     localization =     AST_adopt_westminster }	Adds a freedom score ratio modifier to the current scope.	Used in the subject's scope.	1.3
add_autonomy_score	value = <float> The freedom score to add. localization = <string> The localization key for the modifier.</string></float>	add_autonomy_score = {   value = 10   localization = EXAMPLE }	Adds an exact freedom score modifier to the current scope.	Used in the subject's scope.	1.3
set_autonomy	target = <scope> / <variable> The subject country. autonomy_state = <type> The type of autonomy state to set. freedom_level = <float> The new freedom level value. Optional. end_wars = <yes no=""> Will end any wars the subject is involved in. end_civil_wars = <yes no=""> Will end any civil wars the subject is subject to</yes></yes></float></type></variable></scope>	set_autonomy = {     target = AST     autonomy_state =     autonomy_free     end_wars = no     end_civil_wars = no }	Sets the autonomy level for the specified country, including independence.	The autonomy_free state will free the subject, however this effect has to be executed within the scope of the target country's current overlord for this to have effect. The autonomy states are found in /Hearts of Iron IV/common/autonomous_states/*.txt files.	1.3

## Governments in exile[编辑 | 编辑源代码]

# Government in exile-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_legitimacy	Adds legitimacy to a government in exile.	add_legitimacy = 10	Adds legitimacy.		1.6
set_legitimacy	Sets the legitimacy of governments in exile.	set_legitimacy = 10	Sets legitimacy.		1.6
become_exiled_in	Makes a country a government in exile in a set country, with a set starting legitimacy.	become_exiled_in = { target = <host tag=""> legitimacy = &lt;0-100&gt; (starting legitimacy, optional) }</host>	Creates a government in exile.	Must be fired from ROOT, the country that should be exiled, or a TAG specification must be used.	1.6
end_exile	Ends a government in exile.	end_exile = yes	Ends a government in exile.		1.6

# War[<u>编辑 | 编辑源代码</u>]

### War-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_threat	<pre> <int> The amount to change by.</int></pre>	add_threat = 10	Adjusts the level of World Tension.		1.0
add_named_threat	threat = <int> The amount to change by. name = <string> The localization string.</string></int>	add_named_threat = {     threat = 5     name = GER_rhineland }	Adjusts the level of World Tension and adds an entry in the World Tension tooltip.		1.0
annex_country	target = <scope> Which country to annex. transfer_troops = yes Whether to transfer the troops of the annexed country.</scope>	annex_country = {     target = GER     transfer_troops = yes }	Annex the specified country for the current scope.	Without transfering troops, the annexed country's divisions' equipment is lost.	1.0
add_to_war	targeted_alliance = <scope> The country to assist. enemy = <scope> The country attacking the ally. hostility_reason = <string> Localization for the reason for joining. Optional.</string></scope></scope>	add_to_war = {     targeted_alliance = PREV     enemy = HUN     hostility_reason = asked_to_join }	Forces the current scope to join the war of the specified ally against the specified enemy.		1.0
declare_war_on	target = <scope> / <variable> The country to attack. type = <wargoal> The wargoal to declare with. generator = { <state id=""> } The states to supply the wargoal (i.e. take_state_focus).</state></wargoal></variable></scope>	<pre>declare_war_on = {   target = GER   type = annex_everything }</pre>	Makes the current scope declare war on the specified country with the specified wargoal.	Wargoals are found in /Hearts of Iron IV/common/wargoals/*.txt. See also add_civil_war_target in order to assign a war between different countries to be a civil war.	1.0
white_peace	<pre><scope> / <variable> The scope to white peace. OR tag = <scope> / <variable> The scope to white peace. The scope to white peace. message = clocalisation key&gt; The reason for peace showing up in the pop-up.</variable></scope></variable></scope></pre>	white_peace = GER white_peace = {   tag = GER   message = my_peace_tt }	Makes the current scope white peace the specified scope.		1.0
start_peace_conference	tag = <scope> / <variable> The scope to peace with. score_factor = <decimal> / <variable> The fraction of the total score awarded to the winners compared to regular victory. message = <localisation key=""> The reason for peace showing up in the pop-up.</localisation></variable></decimal></variable></scope>	start_peace_conference = {     tag = GER     score_factor = 0.4     message = my_peace_tt }	Makes the current scope start a peace conference with the specified scope on the other side.	Current scope is the winner, target and its subjects are the losers. Can only be used if at war with the target.	1.12
set_truce	target = <scope> The scope to truce with. days = <int> The duration of the truce.</int></scope>	set_truce = {   target = GER   days = 90 }	Makes the current scope truce with the specified scope.		1.0

第13页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
create_wargoal	target = <scope> / <variable> The country to target. type = <wargoal> The wargoal to generate. generator = { <state id=""> } The states to supply the wargoal (i.e. take_state_focus).</state></wargoal></variable></scope>	create_wargoal = {     type = puppet_wargoal_focus     target = ROOT }	Grants the current scope a wargoal against the specified country.		1.0
remove_wargoal	target = <scope> / <variable> The country to target. type = <wargaal> The wargoal to remove. "all" will remove all wargoals.</wargaal></variable></scope>	remove_wargoal = {   type = all   target = ROOT }	Removes wargoals from the current scope to the specified country.		1.10.2
start_civil_war	ideology = <ideology> The ideology of the breakaway country. ruling_party = <ideology> The ruling party = <ideology> The ruling party of the original, player-led country. Optional. size = <float> The size of the breakaway country and the fraction of the original stockpile and military units it will receive by default. Optional, defaults to 0.5.  army_ratio = <float> The size of the land army that the breakaway country gets. Optional, defaults to being the same as size. navy_ratio = <float> The size of the naval forces that the breakaway country gets. Optional, defaults to being the same as size.  air_ratio = <float> The size of the airforce that the breakaway country gets. Optional, defaults to being the same as size.  air_ratio = <float> The size of the airforce that the breakaway country gets. Optional, defaults to being the same as size.  air_ratio = <float> The size of the airforce that the breakaway country. Optional, defaults to random states = { <state>} The states included in the breakway country. Optional, defaults to random states based off size. all will result in all states that meet the filter going to the breakaway.  states_filter = { <triggers> } A trigger block checked for the state that must be met to be transferred to the breakaway. Optional. keep_unit_leaders = { <unit id="" leader=""> } List of unit leaders to be kept by their legacy_id. Optional. keep_unit_leaders_trigger = { <triggers> } Trigger block checked for every unit leader that forces them to be kept if they meet the triggers. The default scope is the unit leader, ROOT is the country were to be switched to that ideology group will be kept by the country or join the revolting ideology group will be kept by the country were to be switched to that ideology group of the revolting ideology group will be kept by the country or join the revolt, yes resulting in the former. Optional, defaults to false. keep_all_characters = yes If true, the revolter will have no characters from the original country transferred to them. Optional, defaults to fals</triggers></unit></triggers></state></float></float></float></float></float></float></ideology></ideology></ideology>	start_civil_war = {     ruling_party = communism     # Original country's ideology     changes to communism     ideology = ROOT     # Breakaway gets old ideology of     ROOT     size = 0.8     capital = 282     states = {         282 533 536 555 529 530 528     }     keep_unit_leaders = {         750 751 752     }     keep_political_leader = yes     keep_political_party_members = yes     }  start_civil_war = {     ideology = democratic     size = 0.1     states = all     states_filter = {         is_on_continent = europe         is_capital = no     }     set_country_flag =     TAG_my_country_tag_alias_trigger     # Sets a country flag that gets used in a country tag aliases)  start_civil_war = {     ideology = neutrality     size = 0.1     army_ratio = 0.5     navy_ratio = 0     air_ratio = 1     keep_unit_leaders_trigger = {         has_trait = my_trait_name     }     keep_all_characters = yes     PREV = {# Original country         TAG_airforce_leader = {#         Character         set_nationality = PREV.PREV         # Transfers to breakaway     }     }     promote_character =     TAG_airforce_leader     }  (See usage for PREV and     PREV.PREV)	Starts a civil war for the current scope with the specified parameters.	states = all would include every single state controlled by the country. If the country's current capital state is set as one of the states that the revolt can gain, it won't fire. set _capital can be used to change the capital beforehand, with On _actions#on_civil_war_end being used to set it back to the default after the civil war ends.  A civil war started via this effect cannot have more than two sides. For adding more sides, this can be simulated by setting an existing war (typically originating from a dynamic country created via create_dynamic_country) as a civil war via add_civil_war_target.	1.0
add_civil_war_target	country> - The country to set as the target.	add_civil_war_target = TAG	Sets that the war between ROOT and TAG is a civil war, resulting in the victory being the annexation of the other side and setting world tension limits on intervention.	ROOT and TAG must already be at war with each other for the effect to take place.	1.9
transfer_units_fraction	target = <country> The country which should receive the units from the current scope.  size = <float> The size of the breakaway country and the fraction of the original stockpile and military units it will receive by default. Optional, defaults to 0.5. army_ratio = <float> The size of the land army that the breakaway country gets. Optional, defaults to being the same as size.  navy_ratio = <float> The size of the naval forces that the breakaway country gets. Optional, defaults to being the same as size.  navy_ratio = <float> The size of the airforce that the breakaway country gets. Optional, defaults to being the same as size.</float></float></float></float></country>	transfer_units_fraction= {     target = SPD     size = 0.5     stockpile_ratio = 0.8     army_ratio = 0.8     navy_ratio = 0.5     air_ratio = 0.5     keep_unit_leaders_trigger = {         has_trait =     trait_SPA_nationalist_sympathies     } }	Transfers a fraction of the military to a target, including units (either type: land, navy, or air), equipment, and unit leaders.		1.9

第14页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	defaults to being the same as size.  keep_unit_leaders = { <unit id="" leader=""> }  List of unit leaders to be kept by their legacy_id. Optional. keep_unit_leaders_trigger = { <triggers> }  Trigger block checked for every unit leader that forces them to be kept if they meet the triggers. The default scope is the unit leader, ROOT is the country receiving the unit leader, while FROM is the original owner of the unit leader. Optional.</triggers></unit>				
add_nuclear_bombs	Adds nuclear bomb to TAG's stockpile.	add_nuclear_bombs = 100	Adds specified number of nukes to the country's stockpile	Needs the Nuke tech to use.	1.6
launch_nuke	province = <id> The specific province to nuke. state = <id> The state to nuke. controller = <iag> Prioritises provinces controlled by this country. use_nuke = <boolean> Whether a nuke should be deducted from the country's stockpile. Defaults to false.</boolean></iag></id></id>	<pre>launch_nuke = {     province = 1234 } launch_nuke = {     state = 42     controller = GER     use_nuke = yes }</pre>	Nukes the specified province or a province in the needed state. If a state is set rather than the specific province, first prioritises the country set in controller, then prioritises the countries at war with the current scope, and then countries that are neutral.	If set to use a nuke, then requires at least one nuclear bomb in the stockpile.	1.6

## Resources[<u>编辑|编辑源代码</u>]

### Resource-related country-scoped effects:

	T		折叠	I	
Name	Parameters	Examples	Description	Notes	Version Added
add_resource	type = <resource> The resource to add. amount = <int> The amount of resource to add. state = <id>Vhich state to add the resource to. Variables can be used.</id></int></resource>	add_resource = {   type = oil   amount = 50   state = 88 }	Adds the specified resource in the specified amount to the specified state.	Can also be used in state scope.	1.0
create_import	resource = <re>cresource&gt; The resource to import. amount = <int> The amount of resource to import. exporter = <id>Which country exports the resource.</id></int></re>	create_import = {   resource = steel   amount = 100   exporter = GER }	Creates an import for the current scope with the specified resource and from the specified exporter.		1.0
give_resource_rights	receiver = <tag> The country that would get the resource rights. state = <state> The state where the resource rights are located. resources = { <resource> &lt;&gt; <resource> } The resources to which give resource rights to. Optional, defaults to all.</resource></resource></state></tag>	give_resource_rights = { receiver = ENG state = 291 } give_resource_rights = { receiver = POL state = 321 resources = { oil } }	Gives all the resources of a state to the target country	The resource rights will only be provided as long as the current country controls the state with resource rights.	1.6
remove_resource_rights	cstate> The state to remove current country's resource rights from.	ENG = { remove_resource_rights = 477 }	Removes given resource rights		1.6
add_fuel	<int> The fuel amount</int>	add_fuel = 400	Adds fuel to the current country.		1.6
set_fuel	<int> Fuel amount.</int>	set_fuel = 400	Sets country's current fuel amount.		1.6
set_fuel_ratio	<pre> <decimal>   The needed ratio of fuel.</decimal></pre>	set_fuel_ratio = 0.5	Set country's current fuel ratio relative to its capacity.		1.6

## Buildings[<u>编辑</u> | <u>编辑源代码</u>]

# Building-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_offsite_building	type = 'The building to add. level = <level> /  <variable>  The maximum level to add.</br></variable></level>	add_offsite_building = { type = arms_factory level = 1 }	Adds an off-map (offmap) building for the current scope that produces its effects without being present in a state.		1.5
modify_building_resources	building = wilding to modify. resource = resource to add. amount = <amount>  The amount of  resource to add.</amount>	modify_building_resources = {    building = synthetic_refinery    resource = oil    amount = 1 }	Modifies the resource output of the specified building for the current scope.		1.5

## National focuses[编辑 | 编辑源代码]

### National focus-related country-scoped effects:

	<u> </u>									
Name	Parameters	Examples	Description	Notes	Version Added					
load_focus_tree	<string> The focus tree to load. Alternatively, as an</string>	load_focus_tree = china_communist_focus load_focus_tree = { tree =	Loads a new focus tree for the current scope, retaining any shared focuses.		1.5					

第15页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	effect block: tree = <string> keep_completed = yes/no</string>	british_focus keep_completed = yes }			
unlock_national_focus	<focus> The focus to unlock.</focus>	unlock_national_focus = my_focus	Bypasses the specified focus for the current scope (marks as complete without firing complete_effect of the focus).		1.0
complete_national_focus	<pre> <focus> The focus to complete.</focus></pre>	complete_national_focus = my_focus	Completes the specified focus for the current scope.		1.0
uncomplete_national_focus	focus = <focus> uncomplete_children =  <bool> Defaults "no". Optional. refund_political_power =   tool&gt; Defaults "no".</br></bool></focus>	uncomplete_national_focus = { focus = GER_oppose_hitler uncomplete_children = yes refund_political_power = no }	Removes a focus from list of completed focus, and potentially all focuses requiring it as a prerequisite. If the focus has one, the 'on_uncomplete' effect will be executed on each uncompleted focus.		1.11
mark_focus_tree_layout_dirty	 dbool> Boolean.	mark_focus_tree_layout_dirty = yes	Refreshes the focus tree for the specified country, restarting the checks in allow branch and position offsets for focuses.	If put within a focus' completion reward, the focus will not be marked as complete at the time the effect is executed, leading to has_completed_focus checks specifying that focus in particular to be marked as false.  This can be bypassed by putting an effect within a hidden event fired immediately within the focus or by reloading the same focus tree with load_focus_tree set to keep completed focuses, marking the focus as complete, before using the effect.	1.9

## Decisions[<u>编辑</u> | <u>编辑源代码</u>]

## Decision-related country-scoped effects: 拒絕

Name	Parameters	Examples	Description	Notes	Version Added
activate_decision	<pre><decision> The decision to activate.</decision></pre>	activate_decision = my_decision	Activates the specified decision for the current scope, ignoring triggers for the decision.	Decisions are found in /Hearts of Iron IV/common/decisions/*.txt	1.0
activate_targeted_decision	target = <scope> The country to target. decision = <decision> The decision to activate.</decision></scope>	activate_targeted_decision = {   target = GER   decision = my_decision }	Activates the specified targeted decision for the specified target for the current scope.	Decisions are found in /Hearts of Iron IV/common/decisions/*.txt	1.5
remove_targeted_decision	<pre></pre>	remove_targeted_decision = {     target = FROM     decision = my_decision }	Removes the specified targeted decision for the current scope.	Decisions are found in /Hearts of Iron IV/common/decisions/*.txt	1.5
unlock_decision_tooltip	<pre><decision> The decision to display.</decision></pre>	unlock_decision_tooltip = my_decision	Displays a special tooltip for the specified decision in the effect tooltip.	Decisions are found in /Hearts of Iron IV/common/decisions/*.txt	1.5
unlock_decision_category_tooltip	<category> The decision category to display.</category>	unlock_decision_category_tooltip = my_category	Displays a special tooltip for the specified decision category in the effect tooltip.	Decision categories are found in /Hearts of Iron IV/common /decisions/catergories/*.txt	1.5
add_days_remove	decision = <decision> The decision to remove days from. days = <int> / <variable> The number of days to remove from the mission.</variable></int></decision>	add_days_remove = {     decision = decision_here     days = 30 }	Adds the number of days to a decision's days_remove.	Decisions are found in /Hearts of Iron IV/common/decisions/*.txt	1.9
remove_decision	Allows to remove specified decision without running remove_effect.	remove_decision = GER_MEPO	Removes a decision.		1.6
remove_decision_on_cooldown	<decision> The decision that is to be removed.</decision>	remove_decision_on_cooldown = TAG_my_decision	If the decision is on cooldown, it gets removed, in order to reactivate or remove completely.		1.11

## Missions[<u>编辑</u> | <u>编辑源代码</u>]

## Mission-related country-scoped effects:

	折叠								
Name	Parameters	Examples	Description	Notes	Version Added				
activate_mission	<pre><mission> The mission to activate.</mission></pre>	activate_mission = my_mission	Activates the specified mission for the current scope, ignoring any triggers for the decision.	Missions are found in /Hearts of Iron IV/common/decisions/*.txt	1.5				
activate_mission_tooltip	<pre><mission> The mission to display.</mission></pre>	activate_mission_tooltip = my_mission	Displays a special tooltip for the specified mission in the effect tooltip.	Missions are found in /Hearts of Iron IV/common/decisions/*.txt	1.5				
remove_mission	<pre><mission> The mission to remove.</mission></pre>	remove_mission = my_mission	Removes the specified mission for the current scope.	Missions are found in /Hearts of Iron IV/common/decisions/*.txt	1.5				
add_days_mission_timeout	mission = <mission> The mission to add days to. days = <int> / <variable> The number of days to add to the mission.</variable></int></mission>	add_days_mission_timeout = {     mission = my_mission     days = 20 }	Adds the number of days to the specified mission.	Missions are found in /Hearts of Iron IV/common/decisions/*.txt	1.9				

### Technologies and doctrines[編輯 | 編輯源代码]

# Technology-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
	<int> The number of slots to add or remove.</int>	add_research_slot = 1	Adjusts the number of research slots the		1.0

第16页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
			current scope has. Can remove slots with negatives.		
set_research_slots	<pre><int> The number of slots to set.</int></pre>	set_research_slots = 4	Sets the number of research slots the current scope has.		1.0
add_tech_bonus	bonus = <float> The bonus to technology given, default 0. uses = <int> The amount of times the bonus can be used, default 1. ahead_reduction = <float> The cost reduction if ahead of time, default 0. category = <string> Which technology category the bonus applies to. Multiple can be defined. technology = <string> Which technology + <string> Which technology the bonus applies to. Multiple can be defined. name = <string> Tooltip shown in research tabs, optional.</string></string></string></string></float></int></float>	add_tech_bonus = { bonus = 0.5 uses = 1 category = radar_tech }	Grants a research bonus to the current scope with the specified parameters.	Research bonus categories are defined in /Hearts of Iron IV/common/technology_tags/*.txt files, while technologies are defined in /Hearts of Iron IV/common/technologies/*.txt files.	1.0
set_technology	<technology> = <int> The technology to add. popup = no To not show the popup after adding technology</int></technology>	set_technology = {     suicide_craft = 1 }	Grants the specified technology to the current scope.	A value of 1 sets the technology. A value of o removes the technology, but if it is a researchable technology, the duration it takes to research isn't reset, meaning it can be researched in 1 day. Technologies that are mutually exclusive with other technologies can not be removed by this effect. Technologies are defined in /Hearts of Iron IV/common/technologies/*.txt files.	1.0
add_to_tech_sharing_group	<pre><string> The group to add the current scope to.</string></pre>	add_to_tech_sharing_group = us_research	Adds the current scope to the specified technology sharing group.	Technology sharing groups are found in Hearts of Iron IV\common\technology_sharing\*.txt	1.3
remove_from_tech_sharing_group	<pre><string> The group to remove the current scope from.</string></pre>	remove_from_tech_sharing_group = us_research	Removes the current scope from the specified technology sharing group.	Technology sharing groups are found in Hearts of Iron IV\common\technology_sharing\*.txt	1.3
modify_tech_sharing_bonus	<pre>id = <string> The group to modify. bonus = <float> The new bonus.</float></string></pre>	modify_tech_sharing_bonus = {     id = us_research     bonus = 0.5 }	Modifies the specified technology sharing group.	Technology sharing groups are found in Hearts of Iron IV\common\technology_sharing\*.txt	1.3
inherit_technology	<tag> The country to inherit technology from.</tag>	inherit_technology = CAN	Makes the current country's researched technologies be copied from the specified country.	Useful when making a country independent.	1.6
add_doctrine_cost_reduction	name = <name> Tooltip showing why the doctrine has reduced cost in the doctrine menu. Optional. cost_reduction = <fraction> Percentage of cost reduced. uses = <integer> Number of times the cost reduction can be used. category = <doctrine category=""> Which doctrine category the cost reduction will apply to. (Ex: cat_mobile_warfare,land_doctrine ,air_doctrine.)</doctrine></integer></fraction></name>	add_doctrine_cost_reduction = {     cost_reduction = 0.5     uses = 2     category = land_doctrine }	Gives bonuses of reducing land doctrine cost to current scope.	Doctrines are defined in /Hearts of Iron IV/common/technologies/*.txt files. For a general doctrine cost reduction, see " <a href="redand/air/naval">redand/air/naval</a> doctrine cost factor" in Modifiers.	1.11

### Ideas[<u>编辑</u> | <u>编辑源代码</u>]

This includes national spirits, laws, designers, and advisors (using the idea\_token)  $\,$ 

Idea-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_ideas	<idea> The idea to add.</idea>	add_ideas = my_idea add_ideas = { my_idea_1 my_idea_2 }	Adds the specified ideas to the current scope.	Can be used as a scope to add multiple at once.	1.0
add_timed_idea	idea = <idea> The idea to add. days = <int> / <variable> The number of days to add the idea for.</variable></int></idea>	add_timed_idea = {     idea = my_idea     days = 180 }	Adds the specified ideas to the current scope for the specified number of days.		1.0
modify_timed_idea	idea = <idea> The idea to modify. days = <int> / <variable> The number of days to add to the idea.</variable></int></idea>	modify_timed_idea = {     idea = my_idea     days = 60 }	Extends the duration of the timed idea by the specified amount.		1.0
swap_ideas	add_idea = <idea> The idea to add. remove_idea = <idea></idea></idea>	swap_ideas = {   remove_idea = my_idea_1   add_idea = my_idea_2	Switches two ideas with a tooltip displaying any modifier differences between them.	If the ideas have the same name in the localisation, it will show up as modifying the idea rather than swapping them.	1.3

第17页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	The idea to remove.	}		The add will occur before the removal of the old idea.	
remove_ideas	<idea> The idea to remove.</idea>	remove_ideas = my_idea remove_ideas = { my_idea_1 my_idea_2 }	Removes the specified idea from the current scope.	Can be used as a scope to remove multiple at once.	1.0
remove_ideas_with_trait	<trait> The trait to target.</trait>	remove_ideas_with_trait = motorized_equipment_manufacturer	Removes all ideas for the current scope that use the specified trait.		1.0
show_ideas_tooltip	<idea> The idea to display.</idea>	show_ideas_tooltip = my_idea	Displays the specified idea in the tooltip for the current effect scope. Does not add the idea.		1.0

## Units[編輯 | 編辑源代码]

### Unit-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
load_oob	Coob> The filename of the order of battle to load, without the .txt extension.	load_oob = "GER_default"	Loads the specified order of battle for the current scope, applying the effects within. The filename with the .txt extension omitted is used as the effect's target.	Orders of battle are stored within /Hearts of Iron IV/history/units /*.txt. Primarily used to spawn divisions at specified locations.	1.0
division_template	name The name of the division. regiments = { <unit> = {x = 0 y = 0}} } support = {     <unit> = {x = 0 y = 0}} } The composition of the division. Subunits are defined in /Hearts of Iron IV/common/units/*.txt files. division_names_group = <group> The division names group that the template will use, deciding on the automatically-generated names of any new divisions built using that template. Optional, assigns one automatically if omitted. These are defined within /Hearts of Iron IV/common/units /names_divisions/*.txt files. is_locked =  bool&gt; Whether the division is locked to modification and deletion. Optional. force_allow_recruiting =  bool&gt; Whether the locked template can have units deployed using it without allowing editing, Optional, only has an effect in locked templates. division_cap = <int> The maximum amount of divisions that this template may have; requires the template to be locked. Optional. priority = <int> The priority the template receives in receiving supplies. Goes from 0 to 2. Optional, 1 by default. template_counter = <int> The icon used by the division as an integer. Optional, defaults to the icon of the most common sub-unit within. The icons are defined as sprites within any /Hearts of Iron IV/interface/*.gfx file (By default subuniticons.gfx) with the pattern of GFX_div_templ_<int>_large and GFX_div_templ_cint&gt;_small. override_model = <entity> Enforces the entity used by the units using this template to be the specified one. Optional.</entity></int></int></int></int></group></unit></unit>		Creates and adds the specified division template to the current scope.	The x and y attributes represent the rows and columns in the division designer and start from o. No tooltip is shown.	1.0
add_units_to_division_template	template_name = <string> The template to change. Optional if used in division scope. regiments = {     <unit> = <column> } support = {     <unit> = <column> } The units to add to the template. Subunits are defined in /Hearts of Iron IV/common/units/*.txt files.</column></unit></column></unit></string>	add_units_to_division_template = {     template_name = "Test"     regiments = {         infantry = 2         infantry = 2     }     support = {         military_police = 0     } }	Adds the specified brigades to first available slots of specified columns to the template (if possible).	Columns go left-to-right starting with o. Can also be used in division scope.	1.0
set_division_template_lock	division_template = <string> The name of the division template. is_locked = <bool> Whether the division is locked or not.</bool></string>	set_division_template_lock = {     division_template = "Infantry Division"     is_locked = yes }	Toggles the locked status on a division template for the current scope, which prevents editing or deletion.		1.5
country_lock_all_division_template	<pre></pre>	country_lock_all_division_template = yes	Locks all division templates for the current scope.	Used to prevent training, disbanding, and editing units.	1.9

第18页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
set_division_force_allow_recruiting	division_template = <string> Template to modify. force_allow_recruiting = <bool> Whether to allow or disallow recruiting. Defaults to true if unset.</bool></string>	<pre>set_division_force_allow_recruiting = {     division_template = "My locked template" }</pre>	Changes whether it's possible to recruit divisions of a locked template without unlocking the template.		1.12
set_division_template_cap	<pre>division_template = <string> The name of the division template. division_cap = <int> The division cap.</int></string></pre>	set_division_template_cap = {     division_template = "Swiss Citizen Militia"     division_cap =     SWI_militia_division_cap }	Sets the cap of a division template. The template has to be locked first.		1.12
clear_division_template_cap	division_template = <string> The name of the division template.</string>	clear_division_template_cap = {     division_template = "Swiss Citizen     Militia"   }	Clears the cap on the template, allowing it to have an unlimited amount of divisions.		1.12
delete_unit_template_and_units	division_template = <string> The name of the division template.</string>	delete_unit_template_and_units = {     division_template = "Infantry Division"     disband = yes #will refund equipment and     manpower }	Deletes the specified division template and all units using it for the current scope.		1.5
delete_unit	state = <number id=""> The id number of the state the unit must be in. template = <string> The template the units must use to be deleted. id = <int> The id given to the unit if created via the create_unit effect. disband = <bool> If true, will refund equipment and manpower.</bool></int></string></number>	delete_unit = {     state = 787     disband = yes #will refund equipment and manpower } delete_unit = {     template = "Infantry Division" }	Deletes all units that meet the filters.	No tooltip is generated. delete_units can be used if deleting all units of a specific template.	1.5
delete_units	division_template = <string> The template the units must use to be deleted. disband = <bool> If true, will refund equipment and manpower.</bool></string>	<pre>delete_units = {     division_template = "Infantry Division"     disband = yes }</pre>	Deletes all units with a certain template.	Generates a tooltip, unlike delete_unit. Mandatory to specify a division_template.	1.9
create_railway_gun	equipment = <type> Equipment type used by the railway gun. name = <string> The name used by the railway gun. Optional. location = <pre>cprovince&gt; Location where the railway gun is created. Assumes the capital by default.</pre></string></type>	create_railway_gun = {     equipment = railway_gun_equipment_1     name = TAG_new_railway_gun     location = 12406 }	Creates a railway gun.		1.11
teleport_railway_guns_to_deploy_province	<pre><boolean></boolean></pre>	teleport_railway_guns_to_deploy_province = yes	Teleports all railway guns to the province where they get deployed.		1.11

## Equipment[<u>编辑 | 编辑源代码</u>]

# Equipment-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
set_equipment_fraction	<float> / <variable> The fraction of equipment to remove.</variable></float>	set_equipment_fraction = 0.5	Reduces the overall equipment stockpile by the specified fraction.	This should <b>not</b> be used in civil wars to simulate stockpile splitting. start_civil_war automatically divides stockpiles according to the respective size.	1.0
add_equipment_to_stockpile	type = <equipment> The equipment to add. Either types and archetypes are accepted. amount = <int> / <variable> The amount to add. producer = <scope> / <variable> Defines who produced the equipment. Optional, defaults to the current scope. variant_name = <string> The equipment variant to add. Mandatory if a variant needs to be created to produce the equipment, optional otherwise.</string></variable></scope></variable></int></equipment>	add_equipment_to_stockpile = {     type = infantry_equipment     amount = -100     producer = GER } add_equipment_to_stockpile = {     type = medium_tank_chassis_1     amount = 100     variant_name = "Panzer III" }	Edits the equipment stockpile of the current scope, adds or removes equipment of a specified type or archetype.	With negative numbers, optionally specifying a producer will ensure only equipment with that producer gets removed. The equipment must be unlocked by the producer for the effect to succeed.	1.0
send_equipment	type = <equipment> The equipment to add. Can be archetype. amount = <int> / <pre> <pre> <pre></pre></pre></pre></int></equipment>	send_equipment = {     equipment = infantry_equipment     amount = 100     target = GER }	Sends the specified amount of equipment to the specified target, removing said equipment from the current scope.	Cannot remove equipment into negatives, in which case equipment will not be received by the target in entirety.	1.0
send_equipment_fraction	value = <0-1> How much equipment to send. target = <scope> / <variable> Which country receives the equipment.</variable></scope>	send_equipment_fraction = {   value = 0.3   target = GER }	Sends the specified fraction of equipment to the specified target, removing said equipment from the current scope.		1.9

第19页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
create_production_license	target = <scope> Which country receives the license. cost_factor = <float> Modifies the production cost. Equipment scope type = <equipment> The equipment the country is licensed to produce. Must be an non-archetype equipment. version = <int> The version indicates which variant should be licensed. The default is 0, meaning the base variant. new_prioritised =   locolean&gt; Whether new equipment is prioritised or not. Yes by default.</int></equipment></float></scope>	<pre>create_production_license = {   target = HUN   equipment = {     type = fighter_equipment_1     version = 0     new_prioritised = no   }   cost_factor = 0 }</pre>	Grants the specified country a license to produce the specified equipment from the current scope.		1.4
create_equipment_variant	name = <string> The name of the variant. type = <equipment> The equipment type the variant is of. parent_version = <int> Ordering for multiple variants of the same equipment. 0 is the oldest, 1 is the second-oldest, etc. Optional, 0 by default. obsolete =   obsolete =   obsolete =   chool&gt; Whether the equipment variant is flagged as obsolete within the GUI and for AL Optional, no by default. name_group = <name group=""> The name group used for equipment. Stored in /Hearts of Iron IV/common/units /names_ships. Optional, can only be defined for ships. role_icon_index = <int>/auto /index of the role icon that will be used, as an integer. If set to "auto", will pick automatically. If set to 0, will be unset. Optional, only can be defined for ships. model = <model name=""> Model that will be used by the equipment on the world map. Optional. licon = <sprite> The icon that will be used by equipment. Stored as a spriteType within /Hearts of Iron IV/interface /*gfx. Optional. Upgrade scope <upre> cupgrade &gt; <amount> The upgrade scope cupgrade &gt; <amount> The upgrade &gt; <amount> The upgrade scope cupgrade &gt; <amount> The up</amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></amount></upre></sprite></model></int></name></int></equipment></string>	create_equipment_variant = {     name = "Vetehinen Class"     type = ship_hull_submarine_1     name_group = FIN_SS_HISTORICAL     role_icon_index = 1     modules = {         fixed_ship_torpedo_slot =         ship_torpedo_slot =         ship_torpedo_slot =         ship_engine_1         fixed_ship_engine_slot =         sub_ship_engine_1         rear_1_custom_slot =         ship_mine_layer_sub     } }  create_equipment_variant = {         name = "He 112"         type = fighter_equipment_o         obsolete = yes         upgrades = {             plane_gun_upgrade = 1             plane_range_upgrade = 1         } }  create_equipment_variant = {         name = "Light Tank Mk. IV"         type = light_tank_chassis_1         parent_version = 1         modules = {             main_armament_slot =             tank_heavy_machine_gun         }         upgrades = {             tank_nsb_engine_upgrade = 2         }         icon =         "GFX_ENG_basic_light_tank_medium"         model = ENG_MKIV_light_tank_entity }	Creates the specified equipment variant for the current scope.	Role icons for ships are defined in /Hearts of Iron IV/gfx/army_icons /army_icons.txt. Upgrades are defined within /Hearts of Iron IV/common/units/equipment /upgrades/*.txt. Equipment types, including module slots for them, are defined within /Hearts of Iron IV/common/units /equipment/*.txt. Equipment modules are defined within /Hearts of Iron IV/common/units/equipment/modules/*.txt.	1.0
add_equipment_production	amount = <int> The amount to produce. Optional. requested_factories = <int> The number of factories to assigned initially. Optional. progress = <float> The initial production progress. Optional. efficiency = <float> The initial production efficiency. Optional. Equipment scope type = <equipment> The name of the equipment to produce. creator = <scope> The country which is producing the equipment. Used if root scope isn't producer. Optional. version_name = <string>The name of the variant to produce. Optional.</string></scope></equipment></float></float></int></int>	add_equipment_production = {     equipment = {         type = light_cruiser_2     }     requested_factories = 1     progress = 0.95     amount = 1 }	Starts a production line for the specified equipment for the current scope.		1.0

### Military[<u>编辑</u> | <u>编辑源代码</u>]

### Military-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
destroy_ships	type = <ship> The type of ship to destroy. count = <int> or all The amount to destroy.</int></ship>	destroy_ships = {   type = destroyer   count = all }	Destroys the specified type and amount of ships controlled by the current scope.		1.5
transfer_navy	target = <scope> The target country.</scope>	transfer_navy = {    target = GER }	Transfers the current scope navy to the specified country.		1.5
transfer_ship	<pre>type = <ship> The type of ship to transfer. target = <scope> The target country. prefer_name = <string> Name of ship in origin navy that will preferably be transferred to target navy. Optional. exclude_refitting = <yes no=""> Determines whether ships that are being refitted will be transferred. Optional.</yes></string></scope></ship></pre>	transfer_ship = {     prefer_name = "HMS     Achilles"     type = light_cruiser     target = NZL     exclude_refitting = no }	Transfers the specified type of ship from the current scope to the specified country.		1.4
create_ship	<pre>type = <ship> The type of ship to create. equipment_variant = <string> The equipment variant to use.</string></ship></pre>	FRA = {     create_ship = {       type =	Create a ship from another country and assign it to the reserve fleet. If not set, it will be the scoped country.		1.9

第20页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	creator = <scope> The country that created this ship. Optional. name = <string> Name of the ship. Optional.</string></scope>	ship_hull_submarine_1 equipment_variant = "S Class" creator = ENG name = "My ship name" } }			
add_mines	Add mines to a strategic region for the current country.	add_mines = { region = 42 amount = 100 }	Add mines to a strategic region.		1.6
add_ace	name = <string> The name of the ace. surname = <string> The surname of the ace. callsign = <string> The callsign of the ace. type = <type> The ace type. is_female = <bool> The gender of the ace.</bool></type></string></string></string>	add_ace = {     name = "Amelia"     surname = "Earhart"     callsign = "Revenant"     type = fighter_genius     is_female = yes }	Adds an ace for the current scope.	Ace types found in /Hearts of Iron IV/common /aces/*.txt.	1.0

## Intelligence[编辑 | 编辑源代码]

### Intelligence-related country-scoped effects: 折叠

Name	Parameters	<b>が登</b> <b>Examples</b>	Description	Notes	Version Added
create_intelligence_agency	Allows to create automatically an intelligence agency	<pre>create_intelligence_agency = {     name = "A.G.E.N.C.Y"     icon =     GFX_intelligence_agency_logo_agency }</pre>	Creates an Intelligence Agency.		1.9
upgrade_intelligence_agency	Allows to unlock automatically an intelligence agency uprgrade	upgrade_intelligence_agency = upgrade_form_department upgrade_intelligence_agency = <uper><uperagency< p=""></uperagency<></uper>	Unlocks an Intelligence Agency Upgrade.	Upgrades can be found in common/intelligence_agency_upgrades	1.9
add_decryption	target = <tag> Towards which country to add decryption. amount = <int> How much decryption to add in flat numbers. ratio = &lt;0-1&gt; How much decryption ratio to add.</int></tag>	add_decryption = {   target = GER   amount = 300   }   add_decryption = {   target = GER   ratio = 0.5   }	Adds decryption towards the target country	target and ratio arguments are mutually exclusive.	1.9
add_intel	target = <tag> Towards which country to add intelligence. civilian_intel = <int> How much civilian intel to add. army_intel = <int> How much army intel to add. navy_intel = <int> How much army intel to add. airforce_intel = <int> How much airforce intel to add.</int></int></int></int></tag>	add_intel = {     target = GER     civilian_intel = 3     army_intel = 2     navy_intel = 1     airforce_intel = 2 }	Adds the specified amount of intel towards the specified country.	If an intel argument is left out, o is assumed.	1.9
add_operation_token	tag = <tag> Towards which country to add a token on. token = <id> Which token to add.</id></tag>	add_operation_token = {     tag = GER     token = token_test }	Adds an operation token towards the country, allowing access to more intel or applying a targeted modifier.	Operation tokens are defined in /Hearts of Iron IV/common/operation_tokens/*.	1.9
remove_operation_token	tag = <tag> Towards which country to remove a token from. token = <id> Which token to remove.</id></tag>	remove_operation_token = {     tag = GER     token = token_test }	Removes an operation token from the country.	Operation tokens are defined in /Hearts of Iron IV/common/operation_tokens/*.	1.9
capture_operative	operative = <tag> Which operative to capture. ignore_death_chance = <bool> Whether to ignore the death chance on capture (no by default).</bool></tag>	<pre>capture_operative = {   operative = PREV   ignore_death_chance = yes } capture_operative = PREV</pre>	Captures the specified operative.	Operatives can be referred to by using tags that refer to scopes	1.9
create_operative_leader	bypass_recruitment = <bool> Whether the operative is directly added to the list of available operatives or needs to be recruited. available_to_spy_master = <bool> Whether the operative can be recruited by the spy master. bypass_recruitment should be set to no. portrait_tag_override = <bool> If selecting a random portrait, create one that is from the specified country rather than the current country. name = <string> The name of the operative. GFX = <string> The graphical reference of the picture of the leader, defined as a sprite within any /Hearts of Iron IV/interface/*gfx file. nationalities = { <tag> } The nationalities of the operative.</tag></string></string></bool></bool></bool>	create_operative_leader = {     name = "Jacques Duclos"     GFX =     GFX_portrait_jacques_duclos     traits = { operative_infiltrator     operative_natural_orator }     bypass_recruitment = no     available_to_spy_master = yes     nationalities = { FRA POL } }	Creates an operative for the current scope with the specified attributes.	Traits are found in /Hearts of Iron IV/common /unit_leader/*.txt. All arguments aside from bypass_recruitment are optional. <b>Must use a spriteType for the portrait</b> , a direct link as in "gfx/leaders/TAG/filename.dds" will not work.	1.9

第21页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	The traits the leader spawns with.				
free_operative	<tag> The operative to be freed.</tag>	free_operative = PREV	Frees the specifies operative.	Operatives can be referred to by using tags that refer to scopes	1.9
free_random_operative	captured_by = <tag> The country that captured the operative. all = <bool> Whether to free all operatives or not (Defaults to no).</bool></tag>	free_random_operative = {     captured_by = POL     all = yes }	Frees one random captured operative or all of them.		1.9
kill_operative	operative = <tag> The operative that is killed.</tag>	kill_operative = {     operative = PREV } kill_operative = PREV	Kills the targeted operative.	Operatives can be referred to by using <u>tags that refer</u> to <u>scopes</u>	1.9
turn_operative	operative = <tag> The operative that is turned.</tag>	turn_operative = {     operative = PREV   } turn_operative = PREV	Turns the targeted operative against their own country, transferring them to the current country.	Operatives can be referred to by using <u>tags that refer</u> <u>to scopes</u> . This counts as the operative dying and will trigger the corresponding <u>On action</u> . Logs an error if used against your own operative.	1.9
steal_random_tech_bonus	category = <category name=""> The category to steal from. See /Hearts of Iron IV/common /technology_tags/* for list. folder = naval_folder The folder to steal from. See /Hearts of Iron IV/common /technology_tags/* for list. ahead_reduction = <float> The reduction to the ahead of time penalty. bonus = <float> The bonus to research speed. base_bonus = <float> The backup bonus if no tech is available. instant = <bool> Whether to instantly give a tech instead of a bonus or not. No by default. dynamic = <bool> Changes between instant and non-instant based on type. No by default. name = <localisation key=""> The name of the bonus. target = <tats></tats> = <tats></tats> = <tats></tats> = <tats country="" from.="" steal="" the="" to="" uses="&lt;int"> = <int> How many times the bonus can be used.</int></tats></localisation></bool></bool></float></float></float></category>	steal_random_tech_bonus = {     category = air_equipment     folder = naval_folder     ahead_reduction = 0.8     bonus = 1.2     base_bonus = 1.1     dynamic = yes     name = LOC_KEY     target = POL     uses = 2 }	Steals a random tech bonus from the specified country.	If a country does not have a tech to be stolen, a random bonus will be applied by using base_bonus as a base.	1.9

## Characters[编辑 | 编辑源代码]

## Character-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
set_nationality	target_country = <scope> / <variable> The target country. character = <character> The character to transfer.</character></variable></scope>	set_nationality = {   target_country = TZN   character = OMA_sultan }	Switches the specified character to the specified country.	If you wish to change the nationality of a specific character, and the country getting the effect doesn't have the character recruited already, use the every_possible_country = { limit = { has_character = ID } random_character = { limit = { is_character = ID } set_nationality = TAG } } } } } command to call them up. Only necessary in 1.11 and beyond.	1.11
retire_character	<pre><character></character></pre>	retire_character = GER_Character_Token	Retires the character, removing every role they hold and making them disappear from the game.	Country scope only. The character cannot be re-recruited after retiring.	1.11
set_character_name	character = <character> The character to modify. name = <localisation key=""> The new name of the character.</localisation></character>	<pre>set_character_name = {     character = my_character     name = my_name }</pre>	Sets the new name for the target character.	Can also be used in character scope.	1.11
character_list_tooltip	limit = { <triggers> } Triggers that must be fulfilled to show up in the list.</triggers>	<pre>character_list_tooltip = {     limit = {         has_character_flag =         SOV_targeted_for_purge_flag      } }</pre>	Displays a list of every character meeting the specified limitation and recruited by the current country.		1.11
add_trait	character = <character> The character to modify. slot = <slot> Slot of the character. Necessary for advisors. ideology = <sub-ideology> Ideology type of the character. Necessary for country leaders. trait = <trait> The trait to add.</trait></sub-ideology></slot></character>	add_trait = {     character = TAG_jane_smith     slot = political_advisor     trait = really_good_boss } add_trait = {     character = TAG_my_leader     ideology = liberalism     trait = field_of_gar }	Adds the specified country leader trait to the character.	Can also be used in character scope. Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon. The character slot can be the character's name or id. Using name is recommended because 1.11 made id obsolete.	1.11
remove_trait	character = <character> The character to modify. slot = <slot> Slot of the character. Necessary for advisors. ideology = <sub-ideology></sub-ideology></slot></character>	remove_trait = {     character = TAG_jane_smith     slot = political_advisor     trait = really_good_boss }	Removes the specified trait from the character.	Can also be used in character scope. Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon. The character slot can be the character's name or id. Using name is recommended because 1.11 made id obsolete.	1,11

第22页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	Ideology type of the character. Necessary for country leaders. trait = <trait> The trait to remove.</trait>	remove_trait = {     character = TAG_my_leader     ideology = liberalism     trait = field_of_gar }			

### Unit leaders[<u>编辑</u> | <u>编辑源代码</u>]

### Unit leader-related country-scoped effects: 折叠

Name	Parameters	折叠 Examples	Description	Notes	Version Added
create_corps_commander	name = <string> The name of the leader. picture = <string> The graphical reference of the picture of the leader. skill = <int> The skill of the leader. still = <int> The skill of the leader. defense_skill = <int> The attack skill of the leader. defense_skill = <int> The defense skill of the leader. logistics_skill = <int> The planning_skill = <int> The planning_skill = <int> The logistics_skill = <int> The logistics_skill = <int> The logistics_skill = <int> The traits the leader. leader spawns with. female = <bool> The gender of the leader. leacy_id = <int> The leacy_id</int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></bool></int></int></int></int></int></int></int></int></int></int></string></string>	create_corps_commander = {     name = "Jean de Lattre de Tassigny"     picture = "Portrait_France_Jean_de_Lattre_de_Tassigny.dds"     traits = { trickster brilliant_strategist }     skill = 4     attack_skill = 4     defense_skill = 2     planning_skill = 4     logistics_skill = 3 }	Creates a commander for the current scope with the specified attributes.	Traits are found in /Hearts of Iron IV/common /unit_leader/*.txt. Deprecated, recommended to use add_corps_commander_role instead when possible. The created corps commander will not be able to have a portrait if assigned to be a minister via officer corps, causing errors.	1.0
create_field_marshal	name = <string> The name of the leader. picture = <string> The graphical reference of the picture of the leader. skill = <int> The skill of the leader. skill = <int> The skill of the leader. defense_skill = <int> The defense_skill = <int> The defense_skill = <int> The planning_skill = <int> The leader. logistics_skill = <int> The traits the leader. leader_spawns with. female = <bool> The gender of the leader. legacy_id = <int> The legacy</int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></bool></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></int></string></string>	create_field_marshal = {     name = "Maurice Gamelin"     picture = "Portrait_France_Maurice_Gamelin.dds"     traits = { defensive_doctrine }     skill = 2     attack_skill = 1     defense_skill = 2     logistics_skill = 1 }  }	Creates a field marshal for the current scope with the specified attributes.	Traits are found in /Hearts of Iron IV/common /unit_leader/*.txt. Deprecated, recommended to use add_field_marshal_role instead when possible. The created field marshal will not be able to have a portrait if assigned to be a minister via officer corps, causing errors.	1.0
create_navy_leader	name = <string> The name of the leader. picture = <string> The graphical reference of the picture of the leader. skill = <int> The skill of the leader. traits = { <trait>} The traits the leader spawns with. female = <bool> The gender of the leader. legacy_id = <int> The legacy ID</int></bool></trait></int></string></string>	<pre>create_navy_leader = {     name = "François Darlan"     picture = "Portrait_ France_Francois_Darlan.dds"     traits = { superior_tactician }     skill = 3 }</pre>	Creates a naval leader for the current scope with the specified attributes.	Traits are found in /Hearts of Iron IV/common /unit_leader/*.txt. Deprecated, recommended to use add_naval_commander_role instead when possible.	1.0

第23页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	used for the unit leader. Optional.				
remove_unit_leader	The id of the unit leader.	remove_unit_leader = 70	Removes the specified unit leader by their legacy ID.	Does not work with the character ID. Instead, remove unit leader role within the scope of the character is recommended when possible.	1.0
add_corps_commander_role	character = <character> The character to modify. &lt;&gt; Army leader role definition</character>	add_corps_commander_role = {     Character = GER_Character_token     skill = 4     attack_skill = 2     defense_skill = 3     planning_skill = 3     logistics_skill = 5 }	Sets the specified character to also act as a corps commander.	Can also be used in character scope.	1.11
add_field_marshal_role	character = <character> The character to modify &lt;&gt; Army leader role definition</character>	add_field_marshal_role = {     character = GER_Character_token     skill = 4     attack_skill = 2     defense_skill = 3     planning_skill = 3     logistics_skill = 5 }	Sets the specified character to also act as a field marshal.	Can also be used in character scope.	1.11
add_naval_commander_role	character = <character> The character to modify. &lt;&gt; Navy leader role definition</character>	add_naval_commander_role = {     Character = GER_Character_token     skill = 4     attack_skill = 2     defense_skill = 3     planning_skill = 3     logistics_skill = 5 }	Sets the specified character to also act as an admiral.	Can also be used in character scope.	1.11
show_unit_leaders_tooltip	<pre></pre>	show_unit_leaders_tooltip = TAG_my_leader	Shows the name of the specified character as a tooltip.		1,11

### Country leaders[编辑 | 编辑源代码]

### Country leader-related country-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
create_country_leader	name = <string> The name of the leader. desc = <string> The description of the leader. picture = <spritetype> The graphical reference to the leader portrait. expire = <string> When the leader dies in history. ideology = <string> The sub-ideology of the country leader. Does not accept regular ideologies. female = <bool> The gender of the leader. Traits scope <trait> Traits trait odd. Can add multiple.</trait></bool></string></string></spritetype></string></string>	create_country_leader = {     name = AFG_mohammed_zahir_shah     desc =     "POLITICS_MOHAMMED_ZAHIR_SHAH_DESC"     picture = GFX_AFG_mohammed_zahir_shah     expire = "1965.1.1"     ideology = despotism     traits = {     } }		The portrait uses a spriteType, defined within /Hearts of Iron IV/interface/*.gfx. Sub-ideologies are defined in /Hearts of Iron IV/common/ideologies. Deprecated. Recommended to use add_country_leader_role instead when possible.	1.0
add_country_leader_role	character = ccharacter to modify. country_leader = { } Country leader role definition promote_leader = cbool> Will promote the leader to be the leader of the assigned party. Optional, defaults to false.	<pre>add_country_leader_role = {   character = GER_character_token   promote_leader = yes   country_leader = {     ideology = fascism_type       expire = "1965,1.1.1"       traits = { war_industrialist }   } }</pre>	Sets the specified character to also act as a country leader, promoting to the party leader if specified.	Can also be used in character scope,	1.11
promote_character	ccharacter> The character to promote.  OR character = ccharacter> The character to promote. ideology = cideology type> The ideology type used by the country leader role.	promote_character = GER_erwin_rommel promote_character = {     character = GER_erwin_rommel     ideology = nazism }	Promotes a character to the leader of their political party.	Can also be used in character scope. If the character has multiple country leader roles, specifying the ideology type is mandatory. Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon.	1.11
remove_country_leader_role	character = <character> The character to modify. ideology = <string> The ideology type of</string></character>	remove_country_leader_role = {     character = GER_Character_Token     ideology = socialism }	Removes a country leader role from a character.	Can also be used in character scope. Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon.	1,11

第24页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	the character.				
kill_ideology_leader	<ideology> Ideology.</ideology>	kill_ideology_leader = communism	Kills the country leader of the designated ideology for the current scope.		1.9
retire_ideology_leader	<ideology> Ideology.</ideology>	retire_ideology_leader = fascism	Retires and removes the country leader of the ideology party for the current scope.		1.9
kill_country_leader	<bool> Boolean.</bool>	kill_country_leader = yes	Kills the country leader for the current scope.		1.0
retire_country_leader	<pre></pre>	retire_country_leader = yes	Retires and removes the country leader as head of their party for the current scope.		1.0
set_country_leader_ideology	<pre> <government>   The government to   set.</government></pre>	set_country_leader_ideology = socialism	Changes the country leader's government type for the current scope.		1.0
set_country_leader_description	ideology = <ideology> The ideology of the country leader, optional. desc = <localisation key=""> The new description.</localisation></ideology>	set_country_leader_description = {     ideology = neutrality     desc = LOC_KEY }	Changes the country leader's description.	Must use a localisation key from any /Hearts of Iron IV/localisation/*.yml file, putting the description in quotes will not work. <u>Localisation</u> for more info	1.9.1
set_country_leader_name	ideology = <ideology> The ideology of the country leader, optional. name = <localisation key=""> The new name.</localisation></ideology>	set_country_leader_name = {     ideology = neutrality     name = LOC_KEY }	Changes the country leader's name.		1.9.1
set_country_leader_portrait	ideology = cideology> The ideology of the country leader, optional. portrait = <sprite name=""> The new portrait.</sprite>	set_country_leader_portrait = {     ideology = neutrality     portrait = GFX_IMAGE_NAME }	Changes the country leader's portrait.	The portrait must be defined in /Hearts of Iron IV/interface/*.gfx	1.9.1
add_country_leader_trait	<trait> The trait to add.</trait>	add_country_leader_trait = nationalist_symbol	Adds the specified trait to the current country's country leader.	Traits are found in /Hearts of Iron IV/common /country_leader/*.txt files.	1.0
remove_country_leader_trait	<trait> The trait to remove.</trait>	remove_country_leader_trait = nationalist_symbol	Removes the specified trait from the current scope's country leader.	Traits are found in /Hearts of Iron IV/common /country_leader/*.txt files.	1.0
swap_ruler_traits	Similar to swap_ideas. Removes one trait and adds another.	swap_ruler_traits = { remove = <trait> add = <trait> }</trait></trait>	Swaps traits.	Use <u>swap_country_leader_traits</u> in character scope.	1.6

## Advisors[<u>编</u>辑 | <u>编辑源代码</u>]

## Advisor-related country-scoped effects:

Name	Parameters	Examples	Description	Notes	Version Added
activate_advisor	<pre><character> The character to activate.</character></pre>	activate_advisor = GER_character_token_air_chief	Hires an advisor, placing them into their respective slot.		1.11
deactivate_advisor	<pre><character> The character to deactivate.</character></pre>	deactivate_advisor = GER_character_token_air_chief	Dismisses an advisor from their respective slot, leaving it empty.		1.11
add_advisor_role	character = <character> The character to modify. advisor = { }  Advisor role definition activate = <bool> Will activate the advisor (add them directly when the command is run to the countries government). Optional, defaults to false.</bool></character>	add_advisor_role = {     character = GER_Character_token     activate = yes     advisor = {         slot = air_chief         cost = 50         idea_token =     GER_character_token_air_chief         traits = {             air_chief_ground_support_2         }     } }	Sets the specified character to also act as an advisor, activating if specified.	Can also be used in character scope. Trigger and effect blocks (such as allowed and on_add) cannot be added within advisor definitions created this way.	1.11
remove_advisor_role	character = <character> Specifies the character if the effect is executed in country scope. slot = <int> The slot where to remove the advisor slot from.</int></character>	remove_advisor_role = {     character = "SOV_genrikh_yagoda"     slot = political_advisor     }	Removes the specified advisor role from the character.	Can also be used in character scope.	1.11

## History[<u>编辑</u> | <u>编辑源代码</u>]

These effects can **only be used within history files**, failing when used outside. However, they're considered effects anyway rather than history arguments, as they can be used in if statements.

第25页 共37页 2023/5/9 5:58

Hearts of Iron 4 Wiki

Effects to be used in country history files: 折叠

Name	Parameters	Examples	country history files: 折登  Description	Notes	Version Added
recruit_character	<character></character>	recruit_character = GER_Character_token	Initially assigns the specified character to the current country.		1.11
generate_character	token_base = <string> Mandatory, acts as the character token. name = <localisation key=""> The name used for the character. Generates a random name if not set.</localisation></string>	generate_character = {     token_base =     army_chief_defensive_1     name = funny_name     advisor = {         slot = air_chief         cost = 50         idea_token =     GER_character_token_air_chief         traits = {             air_chief_ground_support_2         }         allowed = {             always = yes         }     } }	Generates a character for current country.		1.11
set_oob	corder of battle> The name of the file used for the order of battle without the .txt extension.	set_oob = BHR_1936	Sets the order of battle to be used for the current country's divisions, overriding every other non-naval and non-air order of battle.	Orders of battle are defined in /Hearts of Iron IV/history /units/*.txt files.	1.0
set_naval_oob	corder of battle> The name of the file used for the order of battle without the .txt extension.	set_naval_oob = BHR_1936_naval_legacy	Sets the order of battle to be used for the current country's divisions, overriding every other naval order of battle.	Orders of battle are defined in /Hearts of Iron IV/history /units/*.txt files.	1.0
set_air_oob	corder of battle> The name of the file used for the order of battle without the .txt extension.	set_air_oob = ITA_1936_air_bba	Sets the order of battle to be used for the current country's divisions, overriding every other air order of battle.	Orders of battle are defined in /Hearts of Iron IV/history /units/*.txt files.	1.12
set_keyed_oob	key = <string> The key used for the file. name = <order battle="" of=""> The name of the file used for the order of battle without the .txt extension.</order></string>	set_keyed_oob = {     key = naval     name = BHR_1936_mtg }	Sets the order of battle to be used for the current country's divisions, overriding every other keyed order of battle that uses the same key.	Orders of battle are defined in /Hearts of Iron IV/history /units/*.txt files.	1.0

### State scope[编辑 | 编辑源代码]

The effects here must be used within a state scope.

### General[<u>编辑</u> | <u>编辑源代码</u>]

# General state-scoped effects: 折叠

Version Added Name Parameters Examples Description Notes id = <event> The event to fire. state\_event = {
 id = my\_event.1
 days = 10
 random = 50 Where triggers do not need to be repeatedly checked random can be state\_event Fires the specified event for the current state. days = <int> / <variable>
Fires the event in the specified number of a performance light alternative to mean\_time\_to\_happen for days. Optional.
hours = <int> / <variable>
Fires the event in the specified number of random\_days = 10 trigger\_for = controller scheduling events.
Using days = <event> /
<variable> or hours may still be hours. Optional.
random = <int> / <variable>
Adds a random number (between o and bugged and will not fire the Adds a random number (between o and random, inclusive) of **hours** to the scheduled fire time. Optional.

random\_days = <int> / <variable>
Adds a random number (between o and random\_days, inclusive) of days to the scheduled fire time. Optional. No tooltip is shown. The flag in this effect is used in the meaning of 'boolean flag', used to store information. set\_state\_flag set\_state\_flag = my\_flag Defines a state flag. An unique string to identify the state flag with.

OR set\_state\_flag = {
 flag = my\_flag
 days = 123 OR flag =  $\langle flag \rangle$  The flag to set. days =  $\langle int \rangle$  Sets the flag to last for the specified amount of days. Optional. value =  $\langle int \rangle$  The new value of the flag on the scale from -2 147 483 648 to 2 147 483 647. value = 1 <flag> The unique string of a state flag to clear. clr state flag clr\_state\_flag = my\_flag Clears a defined state No tooltip is shown. 1.0 flag = <flag> The state flag to modify. value = <value> The value to set it to: 0 or 1 modify\_state\_flag = {
flag = my\_flag modify\_state\_flag Modifies a state flag. Use variables instead. 1.3 value = 1 <string> Defines the new name. set state name = "Funland" Changes the current 1.3 set state name state's name to the specified name. <bool>
Boolean. Resets any changes to the 1.3 reset\_state\_name reset\_state\_name = yes current state's name Adds a claim for the specified country on the add\_claim\_by <scone> / <variable> add\_claim\_by = SOV 1.0 The country to add the claim for. current scope. Removes a claim by the specified country on the remove\_claim\_by scope> / <variable> remove\_claim\_by = SOV 1.0 The country to remove the claim for. current scope. Adds a core for the specified country on the <scope> / <variable>
The country to add the core for. add\_core\_of add\_core\_of = SOV 1.0 current scope.

第26页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
remove_core_of	<pre></pre>	remove_core_of = SOV	Removes a core for the specified country on the current scope.		1.0
set_demilitarized_zone	<bool> Boolean.</bool>	set_demilitarized_zone = yes	Makes the current scope a demilitarized zone.		1.0
set_state_category	category> The category to change to.	set_state_category = rural	Changes the current state category to the specified category.	Categories are found in /Hearts of Iron IV/common /state_category/*.txt	1.3
add_state_modifier	Modifier scope <modifier> = <float> Adds a modifier to the state.</float></modifier>	add_state_modifier = {     modifier = {         local_resources = 2.0     } }	Adds a modifier to the current state.		1.3
add_manpower	<int> / <variable> The amount to add.</variable></int>	add_manpower = 10000	Adds the specified amount of manpower to the current state.		1.0
add_resource	type = <resource> The resource to add. amount = <int> / <variable> The amount to add.</variable></int></resource>	add_resource = {     type = oil     amount = 100 }	Adds the specified resource in the specified amount to the current state.	Can also be used in country scope.	1.0
set_border_war	<bool> Boolean.</bool>	set_border_war = yes	Enables Border War status for the current		1.0
create_unit	division = <division string=""> The division string.  Owner = <scope> The owner of the division.  prioritize_location = <pre> province&gt; If possible, this province within the state gets used. Optional.  allow_spawning_on_enemy_provs = yes Allows the units to be created on provinces owned by the enemy. Defaults to false. The following arguments go within division = "":  name = \"<string>\" The name of the division.  division_template = \"<string>\" The template to be used by the division.  start_experience_factor = <double> Experience of the division, with o being none and 1 being full training. Defaults to 1.  start_equipment_factor = <double> Equipment stockpile of the division.  Defaults to 1.  start_manpower_factor = <double> Manpower stockpile of the division.  Defaults to 1.</double></double></double></string></string></pre></scope></division>	create_unit = {     division = "name = \"Infantry     Division\" division_template =     \"Infantry Division\"     start_experience_factor = 0.5"     owner = GER }	Adds the specified division to the current state.	The division string must be on one line. A linebreak in the middle of division = "" will break the effect and result in no units being spawned.  Can only be used within a state scope, such as capital scope. The effect will do nothing when put into a country's scope.	1.3
teleport_armies	limit = { <triggers> } The condition that must be true for the owner of the armies for them to teleport. to_state_array &lt; array&gt; The state array the armies will get teleported to. to_province = <id> The province the armies will get teleported to. to_state = <id> The state the armies will get teleported to.</id></id></triggers>	teleport_armies = {     limit = {         has_war_together_with = ROOT     }     to_state_array =     owned_controlled_states }	Teleports all armies in the specified state if the owner of the armies meets the condition.	Only define one of to_state_array, to_state, or to_province. If none is specified, it defaults to the capital.	1.9
add_province_modifier	static_modifiers = { <modifiers> } The list of modifiers. province = sid&gt;The province to apply the modifiers to.provinces = {}Scope for selecting multiple provinces: The following arguments have to go inside it: id = sid&gt;The ID of the province. Multiple can be specified. all_provinces = yesSelects all provinces to which the limitations apply. The following arguments require it: limit_to_coastal = yes Limits the selection of provinces to only coastal ones. limit_to_border = yes Limits the selection of provinces to only ones bordering a different country. limit_to_naval_base = yes Limits the selection of provinces to only ones that have a naval base. limit_to_victory_point = yes Limits the selection of provinces to only ones that have a victory point, or a city, in them.</modifiers>	add_province_modifier = {     static_modifiers = {     mod_modifier_1 mod_modifier_2 }     province = 1234 }  add_province_modifier = {     static_modifiers = {         mod_modifier_1 mod_modifier_2 }     province = {         id = 1234         id = 4321     }  }  add_province_modifier = {     static_modifiers = {         mod_modifier_1 mod_modifier_2 }     province = {         all_provinces = yes         limit_to_coastal = yes         limit_to_naval_base = yes         limit_to_victory_point = yes }	Adds a province modifier to the specified provinces in this state.	Province modifiers are defined in /Hearts of Iron IV/common /modifiers/*.txt	1.6
remove_province_modifier	static_modifiers = { <modifiers> } The list of modifiers. province = <id>The province to apply the modifiers to.provinces = {}Scope for selecting multiple provinces. The following arguments have to go inside it: id = <id>The ID of the province. Multiple can be specified. all_provinces = yesSelects all provinces to which the limitations apply. The following arguments require it: limit_to_coastal = yes Limits the selection of provinces to only coastal ones. limit_to_border = yes Limits the selection of</id></id></modifiers>	remove_province_modifier = {     static_modifiers = {     mod_modifier_1 mod_modifier_2 }     province = 1234 }  remove_province_modifier = {     static_modifiers = {     mod_modifier_1 mod_modifier_2 }     province = {         id = 1234         id = 4321     }	Removes a province modifier to the specified provinces in this state.	Province modifiers are defined in /Hearts of Iron IV/common /modifiers/*.txt	1.6

第27页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	provinces to only ones bordering a different country. limit_to_naval_base = yes Limits the selection of provinces to only ones that have a naval base. limit_to_victory_point = yes Limits the selection of provinces to only ones that have a victory point, or a city, in them.	remove_province_modifier = {     static_modifiers = {     mod_modifier_1 mod_modifier_2 }     province = {         all_provinces = yes         limit_to_coastal = yes         limit_to_border = yes         limit_to_naval_base = yes         limit_to_victory_point = yes     }			
add_victory_points	Add victory points to a province	add_victory_points = {     province = 1234     value = 10 }	Adds victory points to a province.	Accepts negative values	1.10
set_victory_points	Set the victory points of a province	set_victory_points = {     province = 1234     value = 10 }	Sets the number of victory point in a province.	Accepts negative values	1.10
set_state_province_controller	controller = <tag> The new controller of the province. limit = { <triggers> } The triggers that must be fulfilled by the province's current controller to be transferred to the new controller.</triggers></tag>	set_state_province_controller = {   controller = POL   limit = {     OR = {         tag = GER         is_in_faction_with = GER     }   } }	Changes the controller of all provinces within that state controlled by countries that meet triggers to the specified country.		1.9
transfer_state_to	<country> Country to transfer the state to.</country>	transfer_state_to = JAM	Sets owner and controller of the state to the given country		1.11
set_state_owner_to	country> Country to set the owner (but not the controller) of the state to.	set_state_owner_to = JAM	Sets the owner of the state to the given country	Use <u>transfer_state_to</u> unless the control specifically shouldn't be given.	1.11
set_state_controller_to	country> Country to set the controller (but not the owner) of the state to.	set_state_controller_to = ITA	Sets the controller of the state to the given country		1.11

## Buildings[編辑 | 編辑源代码]

### Building-related state-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_extra_state_shared_building_slots	cint> / cvariable> The amount of slots to add or remove.	add_extra_state_shared_building_slots = 2	Changes the number of shared building slots for the current state.	Shared buildings slots being the ones used for multiple building types, such as military or civilian factories. This is in contrast to nonshared slots, such as those used by radio stations or air bases, which only can be changed globally with technologies.	1.0
add_building_construction	type = <string> The building to add. level = <into <variable=""> The level to set the building to. instant_build = <bool> Defines whether the buildings are instantly built. province = <id> Defines the exact province to add provincal buildings in. Can be used as a scope. Province scope all_provinces = <bool> Affect all provinces within the state that meet each limit. Used in the province scope. id = <id> Affect the specified province ID. Used in the province scope, will apply for each building if inserted multiple times. limit_to_coastal = <bool> Affect only coastal = <bool> Affect only coastal provinces within the sate that meet exact building if inserted multiple times. limit_to_inaval_base = <bool> Affect only provinces that have naval bases built. Used in the province scope. limit_to_border = <bool> Affect only provinces that have naval bases built. Used in the province scope. limit_to_victory_point = <bool> Affect only provinces that lie on a border between countries. Used in the province scope. limit_to_victory_point =   <intr> intity(bool) Affect only provinces that meet the victory point amount prerequisite. If yes is used in place of a number, any amount of victory points works. Used in the province scope. level = <intr> Affect only provinces with Affect only provinces with</intr></intr></bool></bool></bool></bool></bool></id></bool></id></bool></into></string>	add_building_construction = {     type = bunker     level = 10     instant_build = yes     province = {         all_provinces = yes         limit_to_border = yes         limit_to_victory_point > 1     } } add_building_construction = {     type = bunker     level = 1     instant_build = yes     province = 2999 }	Starts construction in the current state for the specified building.	For provincial buildings, must be done within the scope of the state that contains the province even if done on a specific province. If the controller country doesn't have an order of battle assigned within the history file, the buildings will not show up within the production menu until a recalculation of buildings, such as by changing consumer goods or reloading a savefile. Can only be used within a state scope, such as random owned controlled state. The effect will do nothing when put into a country's scope.	1.0

第28页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	buildings level below, at or above the specified level. Used in the province scope.				
set_building_level	type = <string> The building to add. level = <int> / <variable> The level to set the building to. Instant_build = <bool> Defines whether the buildings are instantly built. province = <ido< td="">   Defines the exact province to add provincal buildings in. Can be used as a scope. Province scope all_provinces = <bool> Affect all provinces. Used in the province scope. limit_to_coastal provinces. Used in the province scope. limit_to_naval_base = <bool> Affect naval base provinces. Used in the provinces. Used in the province scope. limit_to_border = <bool> Affect naval base provinces. Used in the provinces. Used in the province scope. limit_to_border = <bool> Affect onder = <bool> Affect onder = <bool> Affect only provinces. Used in the provinces with buildings level below, at or above the specified level. Used in the province scope. lid = <id> Affect the specified province. Used in the province scope. Affect the specified province. Used in the province scope.</id></bool></bool></bool></bool></bool></bool></ido<></bool></variable></int></string>	set_building_level = {     type = infrastructure     level = 10     instant_build = yes }  set_building_level = {     type = bunker     level = 3     province = {         all_provinces = yes         limit_to_border = yes     level < 3 }  }	Sets the specified building to the current state (or provinces within the state).	The province scope is used for provincal level buildings. You can limit the construction to victory points using: limit_to_victory_point > 5 (only build province buildings on province with VP over 5) limit_to_victory_point = yes (only build province buildings on province with VP) For provincial buildings, must be done within the scope of the state that contains the province even if done on a specific province.	1.4
damage_building	type = <pre>type =  type =  type building to damage.</pre> <pre>damage = <float></float></pre> The amount of damage to inflict. province = <id><id> The province to target for provincal buildings.</id></id>	damage_building = {     type = infrastructure     damage = 1 }	Damages the specified building in the current state.	The health of buildings is determined by the <b>value</b> attribute in a building's definition. This is multiplied by their level to get their total health.	1.3
remove_building	type = type = type = the building to remove. level = tint / <variable>  The levels to remove.</variable>	remove_building = {     type = arms_factory     level = 5 }	Removes the specified building in the current state. For shared buildings level determines the amount, whereas for the others it is the actual level.		1.0

## Resistance and compliance[編辑 | 编辑源代码]

#### Resistance-related state-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_compliance	<int> / <variable> The amount to add.</variable></int>	add_compliance = 30	Adds compliance to the specified state.		1.9
add_resistance	<pre><int> / <variable> The amount to add.</variable></int></pre>	add_resistance = 30	Adds resistance to the specified state.		1.9
add_resistance_target	<pre><int> / <variable> The amount to add.</variable></int></pre>	add_resistance_target = 30	Increases resistance target in the specified state.		1.9
add_resistance_target	id = <int> The ID of the target increase. amount = <int>/(variable&gt; The amount to increase the resistance target by. occupied = <scope> Will only apply the increase if the the occupied country is the specified scope. occupier = <scope> Will only apply the increase if the the occupier is the specified scope. days = <int>/(variable&gt; If set, the resistance target will only be increased for the specified amount of days. tooltip = <string> The tooltip to show in the resistance target tooltip.</string></int></scope></scope></int></int>	add_resistance_target = {     id = 123     amount = 30     occupied = ENG     occupier = GER     days = 365     tooltip = my_localisation_key }	Increases resistance target in the specified state.		1.9
cancel_resistance	<bool> Boolean.</bool>	cancel_resistance = yes	Cancels resistance activity for the current state.		1.9
force_disable_resistance	<scope> The target country.</scope>	force_disable_resistance = GER	Disables resistance for the scoped state when the occupier is the specified country.		1.9
force_disable_resistance	clear = <bool> If set to yes, will clear resistance. occupier = <scope> Resistance will be disabled if the occupier is the specified scope.</scope></bool>	force_disable_resistance = {     clear = yes     occupier = GER     occupied = ENG }	Disables resistance for the scoped state when the occupier is the specified country.		1.9

第29页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	occupied = <scope> Resistance will be disabled if the occupied country is the specified scope.</scope>				
force_enable_resistance	cscope> The target country.	force_enable_resistance = GER	Enables resistance for the scoped state when the occupier is the specified country.	Does not start resistance by itself, only removes the checks forcefully disabling it. Use with start resistance in order to immediately start resistance.	1.9
force_enable_resistance	clear = <bool> If set to yes, will clear resistance. occupier = <scope> Resistance will be enabled if the occupier is the specified scope. occupied = <scope> Resistance will be enabled if the occupied occupied if the occupied country is the specified scope.</scope></scope></bool>	force_enable_resistance = {     clear = yes     occupier = GER     occupied = ENG }	Enables resistance for the scoped state when the occupier is the specified country.	Does not start resistance by itself, only removes the checks forcefully disabling it. Use with start_resistance in order to immediately start resistance.	1.9
remove_resistance_target	<pre><int> / <variable> The id of the resistance target to remove. (Must be set with add_resistance_target)</variable></int></pre>	remove_resistance_target = 30	Removes a set resistance target increase in the specified state.	Has no tooltip.	1.9
set_compliance	<pre></pre>	set_compliance = 30	Sets compliance in the specified state.		1.9
set_resistance	<pre><int> / <variable> The amount to set the resistance to.</variable></int></pre>	set_resistance = 30	Sets resistance in the specified state.		1.9
start_resistance	<bool>&gt;/<scope> Whether to start resistance or not. If set to a scope, starts resistance for the specified scope.</scope></bool>	start_resistance = POL start_resistance = yes	Starts resistance in the specified state.	If used on a state that normally can't start resistance, use alongside with force_enable_resistance.	1.9
set_garrison_strength	<0-1> The new garrison strength.	set_garrison_strength = 0.5	Sets the strength of the garrison in the specified state.		1.9
set_occupation_law	<law id=""> The new occupation law enacted by the previous scope or default_law.</law>	GER = { every_controlled_state = {     set_occupation_law =     military_governor_occupation } } # Changes     GER's occupation law for every controlled     state.	Sets the occupation law of the state.	PREV will be the country for whom the occupation law will be changed. If PREV is not a country, nothing changes. If PREV doesn't occupy the state, nothing happens until it does. If using default_law, resets to the law set by the country's occupation.	1.12

## Character scope[<u>编辑</u> | <u>编辑源代码</u>]

The effects here must be used within a **character** scope.

## General[<u>编辑</u> | <u>编辑源代码</u>]

### General character-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
set_character_flag	<pre></pre>	set_character_flag = my_flag set_character_flag = { flag = my_flag days = 123 value = 1 }	Defines a character flag.	No tooltip is shown. The flag in this effect is used in the meaning of 'boolean flag', used to store information.	1,11
set_character_name	<pre><localisation key=""> The name to use.</localisation></pre>	set_character_name = GER_my_cool_flag	Changes the character's name to the specified localisation key's value.		1.11
modify_character_flag	flag = <flag> The country flag to modify. value = <value> The value to set it to: 0 or 1</value></flag>	modify_character_flag = {   flag = GER_my_cool_flag   value = 5 }	Modifies an existing character flag	Use <u>variables</u> instead.	1.11
clr_character_flag		clr_character_flag = <bool></bool>	Clears a character flag		1.11
retire	<bool> Boolean&gt;</bool>	retire = yes	Retires the current character (removing them).		1.5
set_nationality	<pre><scope> / <variable> The target country.</variable></scope></pre>	set_nationality = GER	Switches the current character to the specified country, giving them the character.	If you wish to change the nationality of a specific character, and the country getting the effect doesn't have the character recruited already, use the every_possible_country = {     limit = { has_character = ID }     random_character = {         limit = { is_character = ID }         set_nationality = TAG     } } command to call them up. Only necessary in 1.11 and beyond.	1.5

第30页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
set_portraits	character = <character> The character name. Optional if in character scope. Army scope: small = <sprite> The sprite used as an advisor. large = <sprite> The sprite used as a general. Character scope:large = <sprite> The sprite used as a country leader.</sprite></sprite></sprite></character>	set_portraits = {     character = my_character     army = { smallCharacterGFX" }     civilian = { large     ="MyMargeCharacterGFX" } }	Changes the specified portraits of a character.	Sprites are defined within /Hearts of Iron IV/interface /*.gfx files.	1.11
add_trait	slot = <slot> Slot of the character. Necessary for advisors. ideology = <sub-ideology> Ideology type of the character. Necessary for country leaders. trait = <trait> The trait to add.</trait></sub-ideology></slot>	add_trait = {     slot = political_advisor     trait = really_good_boss } add_trait = {     ideology = liberalism     trait = field_of_gar }	Adds the specified country leader trait to the character.	Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon. The character slot can be the character's name or id. Using name is recommended because 1.11 made id obsolete.	1.11
remove_trait	slot = <slot> Slot of the character. Necessary for advisors. ideology = <sub-ideology> Ideology type of the character. Necessary for country leaders. trait = <trait> The trait to remove.</trait></sub-ideology></slot>	remove_trait = {     slot = political_advisor     trait = really_good_boss }  remove_trait = {     ideology = liberalism     trait = field_of_gar }	Removes the specified trait from the character.	Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon. The character slot can be the character's name or id. Using name is recommended because 1.11 made id obsolete.	1.11
add_corps_commander_role	Army leader role definition	add_corps_commander_role = {     skill = 4     attack_skill = 2     defense_skill = 3     planning_skill = 3     logistics_skill = 5 }	Sets the specified character to also act as a corps commander.		1.11
add_field_marshal_role	Army leader role definition	add_field_marshal_role = {     skill = 4     attack_skill = 2     defense_skill = 3     planning_skill = 3     logistics_skill = 5 }	Sets the specified character to also act as a field marshal.		1.11
add_naval_commander_role	<> Navy leader role definition	add_naval_commander_role = {     skill = 4     attack_skill = 2     defense_skill = 3     planning_skill = 3     logistics_skill = 5 }	Sets the specified character to also act as an admiral.		1.11
add_country_leader_role	character = <character> The character to modify. country_leader = { } Country_leader role definition promote_leader <pre>cbol&gt; Will promote the leader to be the leader of the assigned party. Optional, defaults to false.</pre></character>	add_country_leader_role = {     character =     GER_character_token     promote_leader = yes     country_leader = {         ideology = fascism_type         expire = "1965.1.1.1"         traits = { war_industrialist }     } }	Sets the specified character to also act as a country leader, promoting to the party leader if specified.		1.11
promote_character	cbool> Boolean. OR cideology type> The ideology type used by the country leader role.	promote_character = yes promote_character = liberalism	Promotes a character to the leader of their political party.	If the character has multiple country leader roles, specifying the ideology type is mandatory. Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon.	1.11
remove_country_leader_role	ideology = <string> The ideology type of the character.</string>	remove_country_leader_role = {     ideology = socialism }	Removes a country leader role from a character.	Ideology type refers to a sub-type of an ideology group assigned to characters, commonly referred to as sub-ideologies in community jargon.	1.11
add_advisor_role	advisor = { } Advisor role definition activate = <bool> Will activate the advisor (add them directly when the command is run to the countries government). Optional, defaults to false.</bool>	<pre>add_advisor_role = {   activate = yes   advisor = {     slot = air_chief     cost = 50     idea_token =   GER_character_token_air_chief     traits = {     air_chief_ground_support_2     }   } }</pre>	Sets the specified character to also act as an advisor, activating if specified.	Trigger and effect blocks (such as allowed and on_add) cannot be added within advisor definitions created this way.	1.11
remove_advisor_role	slot = <int> The slot where to remove the advisor slot from.</int>	remove_advisor_role = {     slot = political_advisor }	Removes the specified advisor role from the character.		1.11

### Unit leaders[<u>编辑</u> | <u>编辑源代码</u>]

These can only be used with characters of the unit leader type.

General unit leader-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added	

第31页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
unit_leader_event	id = <event> The event to fire. days = <int> / <ariable> Fires the event in the specified number of days. Optional. hours = <int> / <ariable> Fires the event in the specified number of hours. Optional. random = <int> / <ariable> Adds a random number (between o and random, inclusive) of hours to the scheduled fire time. Optional. random_days = <int> / <ariable> Adds a random number (between o and random_days, inclusive) of days to the scheduled fire time. Optional.</ariable></int></ariable></int></ariable></int></ariable></int></event>	<pre>unit_leader_event = {   id = my_event.1   days = 10   random = 50   random_days = 10 }</pre>	Fires the specified event for the owner of the current unit leader.	Uses a special interface displaying the current unit leader portrait. Where triggers do not need to be repeatedly checked random can be a performance light alternative to mean_time_to_happen for scheduling events.	1.5
set_unit_leader_flag	<flag> An unique string to identify the unit leader flag with.</flag>	set_unit_leader_flag = my_flag	Defines a unit leader flag.	Deprecated. Use set_character_flag instead. No tooltip is shown.	1.5
clr_unit_leader_flag	<flag> The unique string of a unit leader flag to clear.</flag>	clr_unit_leader_flag = my_flag	Clears a defined unit leader flag.	Deprecated. Use clr_character_flag instead. No tooltip is shown.	1.5
modify_unit_leader_flag	flag = <flag> The unit leader flag to modify. value = <value> The value to set it to: 0 or 1</value></flag>	modify_unit_leader_flag = {     flag = my_flag     value = 1 }	Modifies a unit leader flag.	Deprecated. Use modify_character_flag instead.	1.5
promote_leader	<bool> Boolean</bool>	promote_leader = yes	Promotes the current unit leader to Field Marshal (if Commander).		1.5
demote_leader	<bool> Boolean</bool>	demote_leader = yes	Demotes the current unit leader to Commander (if Field Marshal).		1.5
add_unit_leader_trait	<trait> The trait to add.</trait>	add_unit_leader_trait = old_guard	Adds the specified trait to the current unit leader.	Traits are found in /Hearts of Iron IV/common/unit_leader/*.txt files.	1.0
remove_unit_leader_trait	<trait> The trait to remove.</trait>	remove_unit_leader_trait = old_guard	Removes the specified trait from the current unit leader.	Traits are found in /Hearts of Iron IV/common/unit_leader/*.txt files.	1.0
add_random_trait	<pre><trait> The trait to add.</trait></pre>	add_random_trait = { old_guard brilliant_strategist inflexible_strategist }	Adds a random trait from the list to the character.	Traits are found in /Hearts of Iron IV/common/unit_leader/*.txt files.	1.5
add_timed_unit_leader_trait	<trait> The trait to add. days = <int> The duration of the trait.</int></trait>	add_timed_unit_leader_trait = {     trait = wounded     days = 90 }	Adds the specified trait to the current unit leader for the specified duration.	Traits are found in /Hearts of Iron IV/common/unit_leader/*.txt files.	1.5
replace_unit_leader_trait				Traits are found in /Hearts of Iron IV/common/unit_leader/*.txt files.	1.5
remove_exile_tag	Remove the exile tag on an army leader, making them no longer be considered exile leaders.	remove_exile_tag = yes	Removes a leaders exile tag.		1.6
gain_xp	<int></int>	gain_xp = 5	Adds experience to the current unit leader, promoting to the next skill level if applicable.	Cannot be used with negatives.	1.9
remove_unit_leader	<bool></bool>	remove_unit_leader = yes	Removes the current unit leader.		1.0
remove_unit_leader_role	<bool> Boolean.</bool>	remove_unit_leader_role = yes	Removes every unit leader role from the character		1.11

## Country leaders[編辑 | 編辑源代码]

These can only be used with characters of the country leader type.

## Country leader-scoped effects:

Name	Parameters	Examples	Description	Notes	Version Added
add_country_leader_trait	<trait> The trait to add.  OR: ideology = <sub-ideology> The sub-ideology of the country leader role to which the trait is added. trait = <trait> The trait to add.</trait></sub-ideology></trait>	add_country_leader_trait = nationalist_symbol add_country_leader_trait = { ideology = marxism trait = anti_communist } }	Adds the specified trait to the current character.	Traits are found in /Hearts of Iron IV/common /country_leader/*.txt files. The former only if the character has one country leader role.	1,11
remove_country_leader_trait	<pre><trait> The trait to remove. OR: ideology = <sub-ideology> The sub-ideology of the country leader role to which the trait is added. trait = <trait> The trait to remove.</trait></sub-ideology></trait></pre>	remove_country_leader_trait = nationalist_symbol remove_country_leader_trait = { ideology = marxism trait = anti_communist } }	Removes the specified trait from the current character.	Traits are found in /Hearts of Iron IV/common /country_leader/*.txt files. The former only if the character has one country leader role.	1.11
swap_country_leader_traits	remove = <trait> Trait to remove add = <trait> Trait to add ideology = <sub-ideology> Sub-ideology of the leader where to swap traits.</sub-ideology></trait></trait>	swap_country_leader_traits = {   remove = nationalist_symbol   add = anti_communist   ideology = marxism }	Swaps traits of the current character.	Use <u>swap_ruler_traits</u> in country scope.	1.11

Combat[<u>编辑</u> | <u>编辑源代码</u>]

第32页 共37页 2023/5/9 5:58

## Hearts of Iron 4 Wiki

# Combat-related unit leader-scoped effects: 折叠

Name	Parameters	列室 Examples	Description	Notes	Version Added
supply_units	<pre></pre>	supply_units = 24	Adds the specified amount of hours of supply to troops led by the current unit leader.		1.5
add_max_trait	<pre></pre>	add_max_trait = 1	Adds the specified amount of assignable trait slots to the current unit leader.		1.5
add_skill_level	<int> The skill to add.</int>	add_skill_level = 1	Adds skill to the current unit leader.		1.5
add_logistics	int> How many skill levels to add.	add_logistics = 1	Adds logistics skill to the current unit leader.		1.5
add_planning	int> How many skill levels to add.	add_planning = 1	Adds planning skill to the current unit leader.		1.5
add_defense	(int) How many skill levels to add.	add_defense = 1	Adds defense skill to the current unit leader.		1.5
add_attack	int> How many skill levels to add.	add_attack = 1	Adds attack skill to the current unit leader.		1.5
add_coordination	int> How many skill levels to add.	add_coordination = 1	Adds coordination skill to the current navy leader.		1.5
add_maneuver	int> How many skill levels to add.	add_maneuver = 1	Adds maneuver skill to the current navy leader.		1.5
add_temporary_buff_to_units	combat_offense = <float> The bonus to grant. Optional. combat_breakthrough = <float> The bonus to grant. Optional. combat_defense = <float> The bonus to grant. Optional. combat_defense = <float> The bonus to grant. Optional. combat_entrenchment = <float> The bonus to grant. Optional. org_damage_multiplier = <float> The bonus to grant. Optional. str_damage_multiplier = <float> The bonus to grant. Optional. war_support_reduction_on_damage = <float> The bonus to grant. Optional. cannot_retreat_while_attacking = <float> The bonus to grant. Optional. cannot_retreat_while_defending = <float> The bonus to grant. Optional. cannot_retreat_while_defending = <float> The bonus to grant. Optional. cannot_retreat_while_defending = <float> The duration of the buff. Optional. tooltip = <string> The tooltip to display for the buff.</string></float></float></float></float></float></float></float></float></float></float></float></float>	add_temporary_buff_to_units = {     combat_offense = 0.25     combat_breakthrough = 0.25     org_damage_multiplier = -1.0     str_damage_multiplier = 0.25     war_support_reduction_on_damage = 0.2     cannot_retreat_while_attacking = 1.0  days = 7     tooltip = ABILITY_FORCE_ATTACK_TOOLTIP }	Adds the specified combat buff to the current unit leader.		1.5

## Operatives[<u>编辑</u> | <u>编辑源代码</u>]

### Operative-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
add_nationality	Ctag> The country to set the nationality to.	add_nationality = GER	Adds the nationality to the current operative.		1.9
capture_operative	captured_by = <tag> By which country to get captured. ignore_death_chance = <bool> Whether to ignore the death chance on capture (no by default).</bool></tag>	<pre>capture_operative = {   captured_by = POL   ignore_death_chance = yes }</pre>	Makes the current operative be captured by a specific country.		1.9
force_operative_leader_into_hiding	<bool></bool>	force_operative_leader_into_hiding = yes	Forces the current operative into hiding.		1.9
free_operative	captured_by = <tag> The country that captured the operative.</tag>	free_operative = { captured_by = POL }	Frees the current operative.		1.9
harm_operative_leader	How much to harm the operative.	harm_operative_leader = 12	Harms the current operative.	The value is subject to modifiers.	1.9
kill_operative	killed_by = <tag> The country that'll kill the operative.</tag>	kill_operative = { killed_by = POL }	Kills the current operative.		1.9
turn_operative	turned_by = <tag> The country to which the operative defects.</tag>	turn_operative = {    turned_by = PREV }	Turns the current operative against their own country, transferring them to the specified country.	This counts as the operative dying and will trigger the corresponding On action. Logs an error if used against your own operative.	1.9
operative_leader_event	id = <event> The event to fire. days = <int> / <variable> Fires the event in the specified number of days. Optional. hours = <int> / <variable> Fires the event in the specified number of hours. Optional. random = <int> / <variable> Adds a random number (between o and random, inclusive) of hours to the scheduled fire time. Optional. random_days = <int> / <variable> Adds a random number (between o and random_days, inclusive) of days to the scheduled fire time. Optional. originator = <tag> The originator of the event. Optional, defaults to owner of operative. recipient = <tag> The recipient = <tag> The recipient of the event. Optional, defaults to owner of operative.</tag></tag></tag></variable></int></variable></int></variable></int></variable></int></event>	operative_leader_event = {     id = my_event.1         originator = POL         recipient = GER     days = 10     random = 50     random_days = 10     set_from = ENG     set_from = FRA }	Fires the specified event for the operative.	Uses a special interface displaying the current operative portrait. Where triggers do not need to be repeatedly checked random can be a performance light alternative to mean_time_to_happen for scheduling events.	1.9

第33页 共37页 2023/5/9 5:58

Name	Parameters	Examples	Description	Notes	Version Added
	set_from = <tag> Sets the scope of FROM in scripted localization. Optional. set_from_from = <tag> Sets the scope of FROM.FROM in scripted localization. Optional. set_root = <tag> Sets the scope of ROOT in scripted localization. Optional.</tag></tag></tag>				

### Division scope[编辑 | 编辑源代码]

The effects here must be used within a division scope.

#### Division-scoped effects: 折叠

Name	Parameters	Examples	Description	Notes	Version Added
destroy_unit	<pre></pre>	destroy_unit = yes	Destroys the currently-scoped division.		1.12
add_history_entry	key = <localisation key=""> The name of the entry. subject = "<string>" Logged entry. Never shown to the player. allow = <bool> Whether a medal can be awarded to the division over the history entry.</bool></string></localisation>	add_history_entry = {     key = my_history_entry     subject = "Test entry"     allow = no }	Creates an entry within the command history of a decision.		1.12
change_division_template	<pre></pre>	change_division_template = "New template"	Changes the template of the division to the specified one.		1.12
add_random_valid_trait_from_unit	<pre><character> Character to grant the trait to.</character></pre>	add_random_valid_trait_from_unit = FROM	Adds a random valid unit trait to a unit leader.	Only possible to use if the division scope is the same as the ROOT scope.	1.12
add_unit_medal_to_latest_entry	unit_medals = <medal id=""> The medal to add.</medal>	add_unit_medal_to_latest_entry = {     unit_medals = my_medal }	Adds the specified medal to the latest entry within the unit's history.		1.12
add_divisional_commander_xp	<decimal> Experience to add.</decimal>	add_divisional_commander_xp = 10	Adds the specified amount of experience to the divisional commander.		1.12
reseed_division_commander	<int> The seed to use.</int>	reseed_division_commander = 760	Re-randomises the division commander using the given seed.	Does not have a tooltip.	1.12

### Other scopes[<u>编辑 | 编辑源代码</u>]

The effects here must be used within a scope that's specified within the notes.

### Otherwise-scoped effects:

Name	Parameters	Examples	Description	Notes	Version Added
execute_operation_coordinated_strike	amount = <int> How many times the operation will get executed within the days set in the operation.</int>	<pre>execute_operation_coordinated_strike = {    amount = 12 }</pre>	Bombing in the target region will execute	Can only be used within operations.	1.9

### Flow control[编辑 | 编辑源代码]

These scopes are used within effect scopes to control the execution of effects.

### If statements[编辑 | 编辑源代码]

An if statement allows an execution of effects to only be done if certain triggers are met. This is done with the if = { ... } block. This serves as an effect block with an additional limit = { ... } argument, which is a trigger block where each trigger must be met for the scope being checked.

```
if = {
    limit = {
        has_political_power > 0
        stability < 0.9
    }
    add_stability = 0.1
}</pre>
```

If the limit is not met, then none of the effects inside will be executed. If it is, then each one will be. If the limit is omitted, it defaults to being always true.

Optionally, else\_if = { ... } (with limit = { ... } serving in a similar fashion) and else = { ... } can be added. If the initial limit within if = { ... } is false, it moves on to the next else\_if = { ... }, checking the limit there. If the limit there is false, then it moves on to the next one, until hitting an end or an else = { ... }.

Two variants exist: nested and unnested. In the first case, the else\_if or else is put directly inside of the preceding if or else\_if, while in the second case it's put right after. In case of overlap, unnested if statements are preferred. Here is an example using unnested if statements:

```
if = {
    limit = {
        stability < 0.3 # If stability is below 30%, add 30%.
    }
    add_stability = 0.3
}
else_if = {
    limit = {
        stability < 0.6 # Otherwise, if it's below 60% (i.e. 30-59%), add 20%</pre>
```

第34页 共37页 2023/5/9 5:58

```
}
  add_stability = 0.2
else = {
 add_stability = 0.1 # If there's 60-100% stability, add 10%
}
```

Within the tooltip, only effects that would be executed are shown. The effects within an unfulfilled if statement (or an else/else\_if that's not read due to the if statement being met) will be hidden from the player, and so will the trigger. In order to avoid player confusion, custom effect tooltips can be used to tell the player what this effect block would do, such as being used within an else.

#### Random effects[编辑 | 编辑源代码]

If you want an effect to have a random chance to be done or have nothing happen otherwise, the random = { ... } block is the simplest way to accomplish that:

```
random = \{
 chance = 80
  add_stability = 0.4
 add war support = 0.3
```

This in particular will have an 80% chance to add 40% stability and 30% war support and, accordingly, a 20% chance to do nothing. The chance here is on the scale from 0 to 100.

If you want the game to choose between effect blocks, random\_list can be used instead. For example, if you wanted an effect to randomly given the player one out of four bonuses, you'd do the following:

```
random list = {
 10 = {
   add_stability = 0.5
 10 = {
   add manpower = 10000
 }
 10 = {
    add\_war\_support = 0.5
 }
 10 = {
    army_experience = 100
 }
}
```

The number is not the chance, but the weight for each option, as they don't have to add up to 100 or any number. An option with the weight of 20 is twice as likely to be picked as the option with the chance of 10, for instance. In total, the probability for an option to be picked is equal to the weight of the option divided by the sum of all weights.

It is also possible to use modifiers (akin to MTTH blocks) to affect the weight of each possible random effect or to use variables as chances.

```
random_list = {
 30 = {
   modifier = {
     has_country_flag = inward_perfect_flag
    add_stability = 0.5
  25 = {
   add manpower = 10000
 20 = {
   add_war_support = 0.5
 my_variable = { # Taking "my_variable" as the variable's name, both "var:my_variable" and "my_variable" are valid options, left up to the developer's preference.
 }
}
```

If the country flag inward\_perfect\_flag is set, it'll multiply the above chance of 30 by 1.3 to get 39. Meanwhile, my\_variable will take the value of the according temp variable or the current scope's

Note that if you want to create a repeatable decision including a random list, by default the same decision will pick the same random result every time it is triggered in a game. You can reverse this behaviour by including the following line in the decision block:

fixed\_random\_seed = no

This is only for decisions. Elsewhere, random seed is unfixed by default, making this argument unnecessary to set to "no".

## Tooltip manipulation[<u>编辑</u> | <u>编辑源代码</u>]

```
See also: Localisation
```

The "tooltip" in this case refers to the text shown to the player in-game that explains what the effect block changes within the game, such as "+50 🛋 Political Power".

```
There are 3 ways to edit the tooltip within an effect block:
hidden_effect = { ... } is used in order to hide the effects within, making their execution not get shown to the player.
effect_tooltip = { ... } is, instead, used in order to put the effects into the tooltip without actually executing them.
custom_effect_tooltip = my_localisation_key is used in order to put an arbitrary paragraph of text as an effect that will get executed.
```

For example, this sample  $\underline{\text{focus'}}$  completion  $\underline{\text{reward}}$  utilises all three:

```
completion reward = {
 hidden_effect = {
```

第35页 共37页 2023/5/9 5:58

which will give you 10 artillery\_equipment\_2.

```
every_subject_country = { country_event = my_event.1 }
    custom_effect_tooltip = send_event_to_subjects_tt
    effect_tooltip = {
       add_political_power = 100
   custom_effect_tooltip = reject_war_tt
}
In this case, send event to subjects tt and reject war tt are localisation keys defined within any /Hearts of Iron IV/localisation/english/* 1 english, yml file encoded with UTF-8-BOM, assuming
the English language.
 reject_war_tt: "If they reject the demand, we gain a wargoal against them."
In-game, this will appear as such:
Effect:
Sends a demand to our every subject.
If they agree, we get the following for each subject:
If they reject the demand, we gain a wargoal against them.
Noticably, the effect that fires the country event gets hidden from the tooltip. After completing the focus, the only thing that happens is that every subject country receives an event with the ID of
{\tt my\_event.1}, the country does not immediately gain 100 political power.
Meta effects[编辑 | 编辑源代码]
Meta effects allow you to use non-dynamic effects (the ones that do not accept modifiers and can only use static tokens or constant values) as if they were accepting variables.
add_equipment_to_stockpile = {
   type = infantry equipment 2
    amount = eq_amount
}
In the effect shown above, amount of equipment added is dynamic and can be set using the variable "eq_amount". However, this effect does not let you use a variable as equipment type. You can not
store "infantry_equipment_2" in a variable and use it here.
However, meta effects will let you use variables and scripted localization within them to build effects as if they were texts and run them. Let's make previous effect accept equipment type and
equipment level as variables stored in "eq_type" and "eq_level".
set\_variable = \{\ eq\_type = 1\ \} \ \# \ Sets \ the \ equipment \ type \ to \ "1", which \ determines \ the \ equipment \ given \ using \ scripted \ localisation, included \ below \ properties of \ properties \ pr
set_variable = { eq_amount = 10 } # Sets the amount of equipment given to 10
set_variable = { eq_level = 2 } # Sets the equipment level to 2, which is used directly in the meta effect, no scripted localisation required
meta_effect = { # The actual meta effect. This can go anywhere you need it: in a decision, in a scripted effect, in a scripted GUI click effect, etc...
   text = {
        add_equipment_to_stockpile = {
           type = [EQ_TYPE]_[EQ_LEVEL]
            amount = eq_amount
    \label{eq:eq_level} \begin{tabular}{ll} EQ\_LEVEL = "[?eq\_level|.o]" \# Gets the "eq\_level" variable and saves it as "EQ\_LEVEL" for the meta effect to use the same statement of the same statement of
   EQ_TYPE = "[This.GetEquipmentName]" # Gets the equipment type from scripted localisation, included below, based on the "eq_type" variable, and saves it as "EQ_TYPE" for the meta effect to
}
{\tt\#\,The\,scripted\,localization\,for\,the\,"eq\_type"\,variable, which\,goes\,in\,a\,scripted\,localisation\,file}
defined_text = { # Since the "eq_type" variable in this example is equal to 1, the equipment given by the effect is "artillery_equipment"
    name = GetEquipmentName
   text = {
       trigger = {
            check_variable = { eq_type = o }
       localization_key = "infantry_equipment"
   }
    text = {
       trigger = {
           check_variable = { eq_type = 1 }
       localization_key = "artillery_equipment"
}
As you can see, we have created a meta_effect that takes two arguments. These arguments will be used replacing the parameters [EQ_TYPE] and [EQ_LEVEL] inside the meta effect. EQ_LEVEL will
be replaced by [?eq_level].o] which is the integer value of eq_level (in this case 2.000 becomes 2). EQ_TYPE is a bit more complicated, it is being replaced by a scripted localization. This scripted
localization will check eq_type variable and depending on its value it will return the key token for the equipment. If it is 0, it will return "infantry_equipment". If it is 1, it will return
So the final result is [EQ_TYPE] is being replaced by "artillery_equipment" and [EQ_LEVEL] is being replaced by "2" and in the end our effect will be built as:
add_equipment_to_stockpile = {
   type = artillery_equipment_2
    amount = eq_amount
```

第36页 共37页 2023/5/9 5:58

debug = yes can be added to meta effects. Which will print the final effect to game.log when the effect is executed and make debugging easier.

### Scripted effects[编辑 | 编辑源代码]

Scripted effects serve a similar purpose to functions in that they can be defined in /Hearts of Iron IV/common/scripted\_effects/\*.txt and then used elsewhere as a shortened version. Alongside that, the game allows the creation of custom console commands, which are scripted effects.

A scripted effect is defined simply as

```
scripted_effect_name = {
     <effects>
}
```

This example can be used as an effect in regular code as scripted\_effect\_name = yes.

Scripted effects can be accessed in console by typing e scripted\_effect\_name to run them.

To create a custom console command, the scripted effect's name should begin with d\_. The console command itself does not include d\_, so d\_test\_command would be run in console as test\_command

In custom console commands, the country running the command is FROM, while ROOT is the selected country, state, or character. Anything entered after the console command, separated by spaces like test\_command 123 321 GER is added to the 'args' temp array. An example of a scripted effect which will transfer every state entered as an argument to the country that runs the console command is

```
d_transfer_states = {
    for_each_scope_loop = {
        array = args
        FROM = {
            transfer_state = PREV
        }
    }
}
```

used like transfer\_states 123 321