# Commercial Real-Time Operating Systems Real-Time Systems Design (CS 6414)

#### Sumanta Pyne

Assistant Professor
Computer Science and Engineering Department
National Institute of Technology Rourkela
pynes@nitrkl.ac.in

March 10, 2021

#### Overview

- Ensures every real-time task meets timeliness requirements
- Use appropriate task scheduling techniques
- Provide flexibilty to programmers to select a scheduling policy
- Sharing critical resources and handling task dependencies
- Can general purpose OS (Unix or Windows) extended to RTOS?
- Fundamental problems associated with traditional OS
- Commercially available RTOS and their limitations
- Examine POSIX standard for RTOS and its implications
- Time service supports provided by RTOS
- Accurate and high precision clocks are important for RTOS
- Survey important features of commercially used RTOS
- Identify parameters on which RTOS can be benchmarked

#### Time services

- Clocks and time services basic facility to programmers
- Provided by OS based on software (system) clock
- System clock by OS kernel receiving interrupt from hardware clock
- Clock resolution time granularity by system clock
- Resolution duration of time between two clock ticks
- Fine resolution for hard real-time systems
- Fine resolution system clock difficult in RTOS
- Presently resolution of hardware clocks finer than 1 nsec (> 3GHz)
- Clock resolution modern RTOS order of several msec

## Why fine resolution of system clock difficult in RTOS?


- Hardware clocks periodically generate time service interrupts
- After an interrupt kernel updates software clock
- A thread gets system clock time by system call (like clock-gettime())
- Finer resolution, more interrupts, higher kernel respond time
- This overhead is a limitation on fine resolution of system clock
- Response time of clock-gettime() is not deterministic due to jitter
- Since interrupts have higher priority than system calls

## Why fine resolution of system clock difficult in RTOS?

- Processing of system call stalled during interrupt
- Worsens further
- System call preemption time vary as OS disable interrupts
- Jitter introduces error in accuracy of time value
- Calling thread gets inaccurate time value from kernel
- System call jitter in commercial OS can be several msec
- Jitter introduces error in time read by program
- Software clock resolution finer than this error not meaningful

## Clock interrupt Processing

- Each clock interrupt
  - Incrementing software clock
  - Three handler routine activities
- Process timer events



- RTOS timer queue per-process or single system-wide
- All timers in queue arranged in order of expiration times
- A handler routine for each timer invoked when timer expires
- At each interrupt kernel checks timer data structures for timer event
- If event occurs, then it queues handler routine in ready queue

## Clock interrupt Processing

- Update ready list
  - Since last clock event, some tasks arrive or become ready after waiting
  - Tasks in wait queue waits for some events like page fetch or semaphore
  - Tasks in wait queue are checked if any task has become ready
  - Tasks found ready are queued in ready queue
  - If a task found ready has higher priority than currently running task
    - Currently running task is preempted
    - Scheduler is invoked
- Update execution budget
  - At each clock interrupt, scheduler decrements task time slice (budget)
  - If remaining budget becomes zero and task incomplete
    - Task preempted
    - Scheduler invoked to select another task

## Providing High Clock Resolution

- Two main difficulties in providing a resolution timer
  - clock interrupt processing overhead excessive with finer resolution
  - jitter for lookup system call in order of several msec
- Not useful to provide clock resolution finer than several msec
- Some real-time applications deal time constraints of order of few nsec
- Is it possible to support measurement with nsec resolution?
- Fine resolution mapping hardware clock to application address space
- An application can read hardware clock from memory, no system call
- On Pentium processor user thread reads Pentium time stamp counter
- Counter starts at 0 when system powered on
- Increments after each hardware clock interrupt
- Making hardware clock readable reduces portibilty of application
- An application running on Pentium ported to different process
- New processor may not have high resolution counter
- Memory address map and resolution would differ

#### **Timers**

- Periodic Timers
  - Used for sampling events at regular intervals or periodic activities
  - Once a periodic timer is set, it expires periodically
  - Implemented using timer queues
    - Each time periodic timer expires, handler routine is invoked
    - Timer data structure inserted back into timer queue
  - For example
    - A periodic timer may be set to 100 msec
    - Its handler set to poll temperature sensor after every 100 msec interval

#### **Timers**

- Aperiodic (or One Shot) Timers
  - Set expire only once
  - Watchdog timers are popular example of one shot timers
  - Watchdog timers in real-time programs to detect if task misses deadline
  - Initiate exception handling process upon a deadline miss
  - For example

- If f() does not complete after t1 time units have elapsed
- Then the watchdog timer expires, indicating deadline missed
- Exception handling procedure is initiated
- Incase task completes before watchdog timer expires (within deadline)
- Watchdog timer is reset using wd\_tickle() call

#### Features of an RTOS

- Clock and Timer Support
  - With adequate resolution required in real-time programming
  - Hard real-time application requires time services in order of few msec
  - Finer resolutions required for certain applications
  - Clock and timer vitsl part of every RTOS
  - Traditional OS do not provide time services with high resolution
- Real-Time Priority Levels
  - RTOS must support static priority levels or real-time priority levels
  - Once programmer assigns priority value to a task, OS doesn't change it
  - Traditional OS priority levels change dynamically to max. throughput
- Faster Task Preemtion
  - Higher priority critical task arrives, preempnt low priority task for CPU
  - Duration higher priority task waits for execution task preemption time
  - Contemporary RTOS have task preemption time in order of few  $\mu$ sec
  - Traditional OS have task preemption time in order of a second
  - Significantly large latency caused by a non-preemptive kernel
  - RTOS needs preemptive kernel, task preemption time order of few  $\mu$ ms

#### Features of RTOS

- Predictable and Fast interrupt Latency
  - Interrupt latency delay between interrupt occurrence and running ISR
  - ullet Upper bound of interrupt latency in RTOS less than a few  $\mu {
    m sec}$
  - Low latency by bulk ISR activities in Deffered Procedure Call (DPC)
  - DPC performs most of ISR, executes after ISR completes at low priority
  - Support for nested interrupts desired
  - RTOS be preemptive during execution of kernel routines and ISR
  - ullet Important for hard real-time applications with sub- $\mu$ sec requirements
- Support for Resource Sharing Among Real-Time Tasks
  - Traditional critical resource sharing unbouned leading deadline misses
  - RTOS provide basic priority inheritance mechanism
  - Support of Priority Ceiling Protocol (PCP) desirable
  - PCP for large and medium sized applications

#### Features of RTOS

- Requirements on Memory Management
  - General purpose OS virtual memory and memory protection
  - Embedded RTOS never support these features
  - Meant for large and complex applications
  - RTOS for large and medium-sized applications need virtual memory
  - Virtual memory reduces average memory access time
  - Degrades worst-case memory access time
  - Penalty storing address in translation table and address translation
  - Fetching pages from secondary memory page fault latency significant
  - Control paging (memory locking) for RTOS virtual memory support
  - Memory locking a page from being swapped from memory to hard disk
  - Large jitter due to absence of memory locking
  - Lack of memory protection single address space for all tasks
  - Single address space simple, save memory bits, lightweight sys calls
  - Small embedded applications few kB/process overhead unacceptable
  - No memory protection high cost of developing and testing program
  - Change in a module req retesting entire sys high maintainance cost

## Requirements on Memory Management

- Embedded RTOS do not support virtual memory
- Creates physically contiguous blocks of memory for an application
- Memory fragmentation and protection problems
- In many embedded sys kernel and user program run in same space
- System and function calls in an application indistinguishable
- Makes debugging applications difficult
- A runaway pointer can corrupt OS code, making system 'freeze'

#### Features of RTOS


- Support for Asynchronous I/O
  - Non-blocking I/O
  - read() and write() system calls synchronous I/O
  - Synchronous I/O Process needs to wait until hardware completes I/O
  - aio\_read() and aio\_write() system calls asynchronous I/O
  - System call will return immediately I/O request passed down
  - Execution of process not blocked, no need to wait for system call result
  - Continue execution, receive I/O results later when available
- Additional Requirements for Embedded RTOS
  - Cost, size and power consumption
  - Diskless systems
  - Flash memory or ROM
  - ROM or RAM

#### Unix as an RTOS

- Unix popular general purpose OS originally developed for mainframe
- Unix and its variants used in desktop and handheld computers
- Shorcomings of traditional Unix used for real-time applications
  - non-preemptive Unix kernel
  - dynamically changing priorities of tasks
- All dicussions on Unix are based on original Unix System V

## Non-preemptive Kernel

- Unix kernel cannot be preempted
- All interrupts disabled when any OS system routine runs
- Application programs invoke OS system service through system calls
- System calls create process, interprocess comm, I/O operations
- After a system call invoked, arguments by application are checked
- A software interrupt called trap is executed
- Trap changes processor state from user to kernel (supervisor) mode



## Non-preemptive Kernel


- Creating process, file operations in kernel mode only
- Application programs prevented, need to request OS by system calls
- In Unix running process in kernel mode cannot be preempted by others
- Unix system does preempt processes running in user mode
- System call of low priority process, high priority process waits
- For real-time applications this causes priority inversion
- Longest system calls may take several hundreds of msec to complete
- Worst case preemption times several hundreds of msec
- Higher priority tasks with few msec deadlines
- System call make higher priority tasks to miss deadlines

#### Why non-preemptive Unix kernel?

- When Unix kernel runs, all interrupts disabled
- Interrupts enabled only after OS routine completes
- Very efficient way of preserving integrity of kernel data structures
- Save overheads setting-releasing locks
- Low average task preemption time
- Non-preemptive kernel worst case response time 1 sec acceptable
- Unix designers didn't foresee usage of Unix in real-time applications
- Correct kernel data structures use locks instead disabling interrupts
- Increases average task preemption time

#### **Dynamic Priority Levels**

- Traditional Unix systems no static priority value for real-time tasks
- Programmer sets priority value, OS alters it during task execution
- Difficult to schedule real-time tasks using RMA or EDF
- RMA and EDF consider static task priority
- Why Unix needs to dynamically change priority values of tasks?
- Unix uses round-robin scheduling with multilevel feedback
- Scheduler arranges tasks in multilevel queues



Fask Queues

## **Dynamic Priority Levels**

- At every preemption point, scheduler scans from top
- Selects task at head of first non-empty queue
- Each task allowed to run for a fixed time quantum (or slice) at time
- Unix normally uses one second time slice by default reconfigurable
- If blocked or not completed within time slice, a process preempted
- Scheduler selects next task for dispatching
- Kernel recomputes preempted task's priority
- Inserts back it to one of priority queues
- Priority of task Ti at end of jth time slice pri(Ti,j) = Base(Ti) + CPU(Ti,j)+nice(Ti)
  - Base(Ti) base priority of Ti
  - CPU(Ti,j) weighted history of CPU utilization of Ti
    - Maximum weightage for activity of task in immediate concluded interval
       (CDL) (CDL
    - If Tj uses CPU for full duration of j CPU(Ti,j) has a high value
    - High value of CPU(Ti,j) lowering priority of Ti
  - nice(Ti) non-negative nice value associated with Ti

#### Dynamic Priority Levels

- $CPU(Ti,j) = U(Ti,j-1)/2 + CPU(Ti,j-1)/2 + \cdots$ 
  - U(Ti,j) utilization of Ti for its jth time slice
- Recursively,  $CPU(Ti,j) = U(Ti,j-1)/2 + CPU(Ti,j-2)/4 + \cdots$
- $pri(Ti,j) = Base(Ti) + U(Ti,j-1)/2 + U(Ti,j-2)/4 + \cdots + nice(Ti)$
- I/O transfer rate responsible for slow response time
- Processors much faster than I/O devices
- Delay of I/O transfer a bottle neck
- A solution keep I/O channels as busy as possible
- Achieved by assigning higher priority to I/O bound tasks
- In Unix set of priority bands assigned to different tasks
- Tasks in decreasing order of priority
  - Swapper
  - block I/O during page fault, uses DMA, efficient use of I/O channel
  - file manupulation
  - character I/O mouse and keyboard transfers
  - device control
  - user processes

## **Dynamic Priority Values**

- Priority bands provide most effective use of I/O channels
- Any task performing I/O must not wait too long for CPU
- So as soon as a task blocks for I/O, its priority increased
- If a task makes full use of las assigned time slice
- Task is computation-bound, its priority is reduced
- In Unix interactive tasks have higher priority levels
- Processed at earliest gives good response time
- Accepted for scheduling soft real-time tasks in general purpose OS
- Like Microsoft's Windows

## **Dynamic Priority Values**

- Unix is very appropriate for maximizing average task throughput
- Provide good average response time to interactive soft real-time tasks
- Almost every modern OS does dynamic recomputation of task prioritie
- Maximize overall system throughput, good average response time
- Dynamic priority inappropriate for hard real-time tasks
- Prevents tasks being constanlty scheduled at higher priority levels
- Prevents real-time task scheduling using EDF and RMA

#### Insufficient Device Driver Support

- Unix device drivers run in kernel mode
- To support a new device driver module is linked to kernel modules
- Providing such support in already deployed application is cumbersome

#### Lack of Real-Time File Services


- File blocks allocated on request by an application
- While writing to a file a task may encounter disk out of space error
- No guarantee given for disk space available when task writes in file
- Traditional approaches result in slow writes
- Since required space has to be allocated before writing a block
- Blocks of a file block may not be contiguously located on disk
- Result unpredictable times for read operations jitter in data access
- Real-time file systems store files contiguously on disk
- Achieves significant improvement in performance
- File system preallocates space
- Times for read and write operations more predictable

#### Inadequate Timer Services Support

- Insufficient timer support for hard real-time applications
- Clock resolution 10 msec too coarse for hard real-time applications

#### Unix-based RTOS

- Extensions to the traditional Unix Kernel
  - Adding some real-time capabilities over basic kernel
  - Include real-time timer and task scheduler built over Unix scheduler
  - Extensions do not address fundamental problems
- Host-Target Approach



Target Board

- Host-target OS popular in embedded applications
- Commercial examples PSOS, VxWorks, VRTX

## Host-Target Approach

- Real-time application developed on host machine with traditional OS
- Application downloaded on target board embedding real-time system
- ROM-resident small real-time kernel in target board
- OS on target board is as small and simple as possible
- No virtual memory, compilers, program editors required
- Processor on target board run RTOS
- Host Unix/Windows with editors, cross-compilers, library, debuggers
- Require virtual memory support
- Host connected to target using serial port or TCP/IP
- RTOS developed at host, cross-compiled for target processor code
- Executable module downloaded to target board
- Tasks run on target board, ctrld at host using symb. cross-debugger
- On success, RTOS fused on ROM or flash memory, ready to work

## Preemption Point Approach


- Unix V mask interrupts during system call unacceptable for RTS
- Improve real-time performance of non-preemptive kernel
- Introduce preemption points in execution of system routines
- Preemption points instants at kernel data structures consistent
- Kernel safely preempted to run any waiting higher priority task
- Without corrupting any kernel data structures
- When execution of system call reaches a preemption point
- Kernel checks any higher priority tasks have become ready
- If atleast one, it preempts processing of kernel routine
- Dispatches waiting highest priority task immediately
- Worst-case preemption time
  - longest time between two consecutive preemption points
  - improves several folds compared to traditional OS
- Preemption point-based OS suitable for hard real-time applications
- Not for hard real-time applications with preemption latency  $< \mu sec$
- Requires minor changes to kernel code
- Past OSs like HP-UX and Windows CE taken preemption point

## Self-host systems

- Real-time application developed on same OS on which it will run
- OS modules not needed excluded to minimize embedded system OS
- Minimize OS size for lesser cost, size and power consumption
- Application runs on host, fused to target board ROM or flash memory
- Current self-host OS based on micro-kernel architecture
- In a micro-kernel architecture
  - kernel mode routines interrupt handler and process management
  - user mode modules memory, file and device management
- Add-on modules easily excluded when not required
- Easy to configure OS, resulting in a small-sized system
- Monolithic drivers, file system, kernel process same address space
- Single programming error cause fatal kernel fault
- Micro-kernel OS components memory-protected
- Rare system crashes, very reliable

#### Problems overcome in Self-host systems


- Non-Preemptive Kernel
  - Kernel-level and spin locks for fully preemptive Unix systems
  - When a task waits for kernel-level lock held by another task
  - It is blocked and undergoes context switch, ready after lock available
  - $\bullet$  Inefficient if duration critical resources needed < context switching time



- A critical resource protected by spin lock
- $\bullet$  Needed by T1 and T2 for very short times wrt context switching time
- Suppose T1 acquires spin lock, meanwhile T2 requests resource
- Since T1 has locked resource, T2 can't access it and busy waits
- T2 is not blocked, no context switch occur
- T2 gets resource as soon as T1 relinquishes resource
- Spin lock in multiprocessor system using cache coherence protocol
- Uniprocessor mutual exclusion critical resource needs very short time

#### Problems overcome in Self-host systems


Real-time Priorities



- Unix-based RTOS has three addition priority levels
- Idle (Non-Migrating) Priorities
  - Lowest priority level
  - Tasks run at this level when there are no other tasks to run
  - Idle tasks are static and are not recomputed periodically
- Dynamic Priorities
  - Recomputed periodically
  - To improve average response time of soft-real time (interactive) tasks
  - Ensures higher priority for I/O bound tasks, lower for CPU-bound tasks
- Real-Time Priorities
  - Static priorities, not recomputed during runtime
  - Hard real-time tasks operate at these levels

#### Windows as an RTOS

Genealogy MS Windows




## Windows NT for real-time applications

- Priority-driven preemptive scheduler
- Real-time threads precedence over all including kernel threads

Real-time

- Shortcomings
  - Interrupt Processing
  - Support for Resource Sharing Protocols



critical

31

#### Windows NT vs Unix

Real-Time Feature	Windows NT	Unix V
DPCs	Yes	No
Real-time priorities	Yes	No
Locking virtual memory	Yes	Yes
Timer precision	1 milli Sec	10 milli Sec
Asynchronous I/O	Yes	No

## POSIX - Portable Operating System Interface

- Important standard for OS and RTOS
- Open software movement and emergence of POSIX
- Open Software catagories
  - Open Source portibilty at source code level
  - Open Object portability of unlinked objects
  - Open Binary portability at executable level
- POSIX provides portibilty at source code level
- Originally developed by AT&T Bell Labs in early 70s
- UCB earliest recipients of Unix source code free of cost
- AT&T came up with Unix V
- UCB incorporated TCP/IP with Unix using DARPA grant
- UCB's Unix version Berkeley Software Distribution (BSD)
- Rapid growth in commercial importantance of Unix
- Extensions of Unix
  - IBM AIX, HP HP-UX, Sun Solaris, Digital Ultrix, SCO SCO-Unix
- To solve portibilty problem ANSI/IEEE yielded POSIX

#### POSIX standard

- Defines only interfaces to OS and semantics of these services
- Does not specify how exactly services are implemented
- Source-code level portability POSIX specifies
  - System calls needed by OS
  - Exact parameters of system calls
  - Semantics of system calls
- Leaves OS vendors freedom to implement system calls
- Does not specify
  - OS kernel single-threaded or multithreaded
  - Priority level at kernel services are executed
  - Programming language to be used
- POSIX standard parts
  - POSIX.1: system interfaces and system call parameters
  - POSIX.2: shells and utilities
  - POSIX.3: test methods for verifying conformance to POSIX
  - POSIX.4: real-time extensions


#### Real-time POSIX Standard

- POSIX.4 real-time extensions of POSIX also called POSIX-RT
- Requirements for OS to be POSIX-RT compliant
  - Execution scheduling Support for real-time (static) priorities
  - Performance requirements on system calls Worst-case execution time
  - Priority levels atleast 32
  - Periodic and one shot timers CLOCK\_REALTIME for RT-POSIX
  - Real-time files Stored in contiguous blocks on disk
  - Memory locking deterministic memory access
    - mlockall()/munlockall() lock/unlock all pages of a process
    - mlock()/munlock() lock/unlock a range of pages
    - mlockpage()/munlockpage() lock/unlock only current page
  - Multithreading Real-time threads schedulable with time constraints

## A Survey of Contemporary RTOS

#### PSOS

- A RTOS for embedded applications from Wind River Systems
- Host-target type RTOS
- Used in commercial embedded systems
- Example- PSOS in base stations of cell phone systems
- Host desktop Unix/Windows
- Target board embedded processor, RAM, ROM




### **VRTX**

- POSIX-RT compliant OS from Mentor Graphics
- Certified by US FAA for use in life-critical applications like avionics
- Available in two multitasking kernels: VRTXsa and VRTXmc
- VRTXsa
  - Large and medium-sized applications
  - Support virtual memory, POSIX-compliant library, priority inheritance
- VRTXmc
  - Optimized for power consumption, ROM and RAM sizes
  - Kernel 4-8 KBytes of ROM and 1 kb RAM
  - No virtual memory support
  - Cell phones and handheld devices


#### **VxWorks**

## QNX



 $\mu \text{C/OS-II}$ 

## RT Linux



## Lynx

### Windows CE

## Benchmarking Real-time Systems



# Thank you