# Thermodynamics with Complications

A pocket dictionary for students and unstudents

With bonus illustrations about Susskind's Cat.

These notes are meant as a refresher on classical thermodynamics, but we also re-interpret the usual variables in terms of computational complexity and uncomplexity in the context of ideas from Susskind and others.

We explore a "dictionary" that maps thermodynamic quantities to their complexity analogues. We see how familiar thermodynamic tools — Maxwell relations, heat capacities, and equations of state — look when translated into these languages.

All work done is basically renaming variables in classical thermo plus spelling out the interpretations. We also include an exposition of a "graded second law" in spirit of Munson et al, 2025.

# The Dictionary

#### Caveats

The correspondence between the quantities in the left and in the right column does not mean equivalence in a single (left or right) context. Don't get confused:  $S \neq C$ ! (Entropy counts states; complexity "measures depth"). These are *two distinct extensive variables* that matter for black holes: **Entropy** — proportional to the *horizon area*. Counts the number of microstates. It grows only until equilibrium, then saturates. **Complexity** — proportional to the *interior volume*. Measures the depth or circuit length needed to prepare the state. It keeps growing long after entropy saturates, up to an enormous maximum. S grows fast and then stops. C grows slowly but keeps going for doubly-exponential in S long times.

Complexity and Uncomplexity

Complexity C is bounded above by a maximum  $C_{max}$  which is of order the Hilbert space dimension (doubly-exponential in S). Once  $C = C_{max}$ , the state is "fully scrambled. **Uncomplexity** is defined as  $U = C_{max} - C$ 

This is the resource that allows useful computation (analogous to free energy).

Thus U is the **analogue** of free energy, while C plays the **analogue** of entropy.

A Note on Coarse Complexity

Exact circuit complexity is *path dependent*: the number of gates needed to reach a state depends on its precise history.

To treat complexity like entropy, we must coarse-grain: define a smoothed complexity  $C_{\rm coarse}$  that ignores microscopic fluctuations.

This is analogous to thermodynamics itself: entropy is only well-defined after averaging over microstates.

All formulas below apply to coarse complexity.

### Standard (Susskind's) Dictionary: Complexity = Volume

Thermodynamics: Complexity Analogue:

Entropy S (Area) Complexity  $C_{\text{coarse}}$ 

Temperature T Complexity temperature  $T_C$  (scrambling rate)

Volume V Interior volume  $\sim C$ 

Pressure P Complexity pressure  $P_C$  (resistance/cost to changing

volume), negative inside blackholes

Free energy F Uncomplexity  $U = C_{max} - C$ , available interior volume

Heat  $\delta Q$  Uncontrolled scrambling

Work  $\delta W$  Useful computation

#### Carathéodory / integrating factor view:

In ordinary thermo,  $\delta Q$  has an integrating factor 1/T so that  $\delta Q/T=dS$ . Here, we're defining  $\delta Q_C\equiv T_CdC$ , i.e. the integrating factor is  $1/T_C$  and the state function is C. This encodes the coarse-grained assumption: on the equilibrium manifold complexity is a state function and  $\delta Q_C/T_C$  is exact.

"Complexity free energy"  $F \equiv E - T_C dC$ ,  $dF = -C dT_C - P_C dV$ .

### First and Second Laws

In terms of complexity:

$$dC = \delta Q + \delta W$$

In terms of uncomplexity:

$$dU = -(\delta Q + \delta W)$$

Heat: uncontrolled complexity growth.

Work: directed, useful computation.

Second law of complexity:

 $\delta Q \ge 0 \implies \text{complexity tends to increase.}$ 

#### Maxwell Relations

Start from:

$$dE = T_C dC - P_C dV$$

Take exterior derivative:

$$0 = -dT_C \wedge dC + dP_C \wedge dV$$

This gives:

$$\left(\frac{\partial T_C}{\partial V}\right)_C = -\left(\frac{\partial P_C}{\partial C}\right)_V$$

Other potentials yield the family:

$$(\partial \mathcal{C}/\partial V)_{T_C} = (\partial P_C/\partial T_C)_V, (\partial T_C/\partial P_C)_C = (\partial V/\partial \mathcal{C})_{P_C}, (\partial \mathcal{C}/\partial P_C)_{T_C} = -(\partial V/\partial T_C)_{P_C}$$

These are consistency conditions: the scrambling rate, volume, complexity, and complexity pressure can't vary independently.

## **Heat Capacities**

At fixed volume: 
$$C_{\mathcal{V}} = T_C \left(\frac{\partial C}{\partial T_C}\right)_V$$
, At fixed pressure:  $C_{\mathcal{P}} = T_C \left(\frac{\partial C}{\partial T_C}\right)_{P_C}$ 

As in ordinary thermodynamics.

Interpretation:

Heat capacity tells us how much extra complexity the system absorbs per unit change in scrambling rate, under different constraints.

 $\mathcal{C}_{\mathcal{V}}$ : "rigid" interior geometry (volume locked).

 $\mathcal{C}_{\mathcal{P}}$ : "relaxed" geometry (volume free to shift to keep pressure constant).

By the stability relation

$$C_{\mathcal{P}} - C_{\mathcal{V}} = T_C \frac{\left[ (\partial P_C / \partial T_C)_V \right]^2}{(\partial P_C / \partial V)_{T_C}}$$

we know  $\mathcal{C}_{\mathcal{P}} \geq \mathcal{C}_{\mathcal{V}}$  if the system is stable.

So, the system can absorb more complexity growth if the interior is allowed to adjust than if it is frozen.

# Toy Manifolds for two equations of state

We can visualize the state space as a surface in  $(T_C, V, P_C)$ .

# Ideal Gas

Equation of state:


$$P_C V = \kappa T_C$$
,  $C = \alpha \ln T_C + \beta \ln V$ .

Isotherms: hyperbolae ( $P_{C} \propto 1/V$ ).


Heat capacities:  $\mathcal{C}_{\mathcal{V}}=\alpha$ ,  $\mathcal{C}_{\mathcal{P}}=\alpha+\kappa\beta$ .

Mechanically stable:  $(\partial P_{C}/\partial V)_{T_{C}} < 0$ .


EOS surface:



#### Isotherms:



### Isocomplexity contours:



### Fast Scrambler

Equation of state:

$$P_C(T_C, V) = \frac{A \tanh(BT_C)}{V}$$

At small  $T_C$ : linear in  $T_C$  (like ideal gas).

At large  $T_C$ : saturates (tanh  $\rightarrow$  1).

At small V: diverges like 1/V.


Interpretation:

High  $T_C$ : saturation — complexity growth capped (fast scrambling).


Low V: divergence — small interiors resist compression; young black holes are highly sensitive.

Large *V*: pressure falls, mature black hole interior grows smoothly.

# EOS surface:



Isotherms (zoomed to highlight divergence and saturation):



# Black Hole Analogy

Complexity, Volume: interior volume growth matches complexity increase.

Pressure: conjugate to interior volume, interpreted as "resistance/cost of expansion."

Heat: scrambling, random gate growth.

Work: harnessed uncomplexity for useful computation.

Saturation: black holes are fast scramblers, complexity growth caps at maximal rate.

Small volume divergence: newborn black holes are hypersensitive, interiors hard to "compress."

Black holes keep growing inside even when equilibrium is reached outside. Their effective complexity pressure is negative (like cosmological constant): the system wants to expand volume/complexity. By contrast, an integrable system with constrained state space exploration might have a positive complexity pressure: pushing it into new computational territory is costly.  $P_{C}$  measures how costly it is (in terms of "computational energy") to increase the interior volume (complexity) at fixed coarse complexity.

# Complexity of complexity, but different complexity

It is worth repeating that thermodynamics in its standard form distinguishes two modes of energy transfer:

Work (W): ordered transfer of energy, ideally reversible.

Heat (Q): disordered transfer of energy, intrinsically associated with entropy growth.

Free Energy F = E - TS: the maximum extractable work from a system in equilibrium with a reservoir at T. Energy splits into "usable" (free) and "unusable" (heat/entropy) components. The partition is sharp: reversible vs. irreversible. Real processes differ not just in *whether* they are reversible, but in how difficult it is to reverse them.

So, we can consider a ladder of energy modes:

Work *F* (reversible, efficient).

Ordered energy transfer; in principle and in practice, fully recoverable.

Polynomial Free Energy  $F^{\text{poly}}$ .

Energy stored in a state that is reversible with polynomial overhead. Still feasible in practice, but not "frictionless."

Exponential Free Energy  $F^{\text{exp}}$ .

Energy theoretically recoverable (unitary dynamics ensures reversibility), but only by procedures requiring exponential time or resources. Effectively lost to finite agents.

Heat TS.

Energy randomized beyond recovery, even in principle at the coarse-grained level.

The total energy decomposes as

$$E = F + F^{\text{poly}} + F^{\text{exp}} + TS$$

Processes tend to push energy downward along the ladder:

$$F \rightarrow F^{\text{poly}} \rightarrow F^{\text{exp}} \rightarrow TS$$

Munson et al., 2025 introduced the idea of complexity entropy — the amount of work cost that appears when erasure or transformation must be done by a complexity-bounded agent.

E.g. If the agent is limited to polynomial algorithms, then  $F^{\rm exp}$  behaves as if it were already heat. Thermodynamics of agents: what is free energy to a demon is partly entropy to a complexity-bounded observer.

#### A Graded Second Law

For any computational class D ("difficulty"),

$$\frac{d}{dt}F^D \leq 0$$

The amount of energy accessible as work to a complexity-bounded observer cannot increase. There is a family of second laws indexed by computational power.

#### **Black Hole Connections**

Hayden–Preskill 2007 showed that in principle, information thrown into an old black hole can be recovered from Hawking radiation after the scrambling time.

Harlow–Hayden 2013 argued that decoding Hawking radiation requires exponential time in the entropy of the hole. That shifts most of the would-be free energy into  $F^{\rm exp}$ . It is reversible in principle, but not in practice: information is locked in exponentially hard work.

The flow down the ladder is the physics of scrambling:

directed work (smooth states)  $\rightarrow$  polynomially inaccessible states (scrambled radiation)  $\rightarrow$  exponentially inaccessible states (deep interior correlations)  $\rightarrow$  thermal entropy.

### Literature:

Thermodynamics of Information. Juan Parrondo, 2023, arXiv:2306.12447

The Second Law of Quantum Complexity. Brown, Susskind, 2017, arXiv:1701.01107V2

Complexity-constrained quantum thermodynamics. Munson et al, 2025, <a href="mailto:arXiv:2403.04828v2">arXiv:2403.04828v2</a>

The Organization of Intrinsic Computation: Complexity-Entropy Diagrams and the Diversity of Natural Information Processing. Feldman et al., 2008, <a href="mailto:arXiv:0806.4789">arXiv:0806.4789</a>

Revisiting thermodynamics in computation and information theory. Chattopadhyay, Paul, 2024, arXiv:2102.09981v2

# Appendix A: The Carnot Cycle dictionary

High-complexity reservoir (scrambled system): provides "randomness" / complexity growth.

Low-complexity reservoir (clean qubits): provides uncomplexity, like free energy.

Engine: a quantum computer that uses the uncomplexity.

Work W: useful, directed computation (solving a problem, extracting information).

Heat Q: uncontrolled growth of complexity (scrambling).

A Carnot engine takes in heat  $Q_{hot}$  from a hot reservoir at temperature  $T_{hot}$ , releases heat  $Q_{cold}$  to a cold reservoir at temperature  $T_{cold}$ , and produces net work  $W=Q_{hot}-Q_{hot}$ . The cycle is reversible, and efficiency is  $\eta=1-T_{cold}/T_{hot}$ .

- 1. Isothermal complexity increase (at "high T"):
  - The system couples to a high-complexity reservoir (maximally mixed/scrambled environment).
  - Complexity C increases, volume grows.
  - o Some of this growth is controlled, yielding useful computation.
  - $\circ$  Analogous to absorbing  $Q_{hot}$
- 2. Adiabatic complexity compression:
  - o System is isolated, but you reorganize gates without contacting reservoirs.
  - o No "heat" (random complexity) flows, only volume rearrangement.
  - o Analogous to entropy-conserving expansion/compression.
- 3. Isothermal complexity decrease (at "low T"):
  - o The system couples to a low-complexity ancilla (a fresh clean gubit register).
  - You dump excess complexity into it, thereby refreshing uncomplexity.
  - $\circ$  Analogous to releasing  $Q_{cold}$

#### 4. Adiabatic reset:

o Isolated reconfiguration back to the initial circuit structure.

After this closed loop, you've consumed uncomplexity and extracted useful work or computation.

Computation powered by uncomplexity is only possible when there is a gradient in scrambling environments.

Appendix C: Bonus illustrations about Susskind's Cat

Susskind's Cat spends precious uncomplexity to play:



Susskind's Cat looks small outside... but its interior volume grows forever:

